1. QueueMetrix Gatekeeper	2
1.1 Building MQ Gatekeeper	4
1.2 QueueMetrix Gatekeeper Properties file	6

QueueMetrix Gatekeeper

Overview

Gatekeeper is a security plugin for MQ and provides a secure way for clients to connect to an MQ queue manager. It uses a client authentication exit module to extend the functionality of MQ to provide a method for JMS and other types of client connections to be authenticated using standard LDAP Simple authentication.


The module itself is called a 'security channel exit' and is named *libMQGatekeeper*. The module is deployed to an MQ server and is used to protect client MQ connections by providing username and password authentication against an enterprises single sign-on (SSO) such as LDAPS or Microsoft's Active Directory.

Client passwords are protected during channel authentication by using standard MQ one way SSL encryption.

The module provides a number of key security features such as,

- Username/password authentication performed using LDAP/S simple authentication.
- Every channel can employ a different security profile
- Auto fail-over to alternate LDAP/S server when one is not available
- Supports Microsoft Active Directory (AD) LDAP
- One, or two way SSL on the connecting MQ client channel to protect the password on the wire.
- Supports LDAP group memberships such as an AD group
- IP address filtering (backward compatible with BlockIP2 rules file)
- Client user id translation/pass-through for object level authorisation (OAM)
- Multiple client API support

Diagram showing how the connection is established



Source Code

Located in GitHub: https://github.com/queuemetrix/mqgatekeeper.git

- Building MQ Client LDAP Authentication Exit
- MQ LDAP Properties file Idap.properties

Examples

WebSphere MQ base Java

```
MQEnvironment.hostname = "10.10.10.10(1414)";
MQEnvironment.channel = "LAMAXU_CHANNEL";
MQEnvironment.userID = "lamaxu";
MQEnvironment.password = "mypswd";
MQQueueManager _qMgr = new
MQQueueManager("DEMO");
```

WebSphere MQ base JMS

```
mqQCF = new MQQueueConnectionFactory();
mqQCF.setQueueManager("DEMO");
mqQCF.setHostName("10.10.10.10(1414)");
mqQCF.setChannel("LAMAXU.CHANNEL");
mqQCF.setTransportType(JMSC.MQJMS_TP_CLIENT_MQ_TCPIP);
conn = mqQCF.createQueueConnection("lamaxu",
"mypswd");
```

C# .Net

```
MQEnvironment.Hostname = "10.10.10.10(1414)";
MQEnvironment.Channel = "LAMAXU.CHANNEL";
MQEnvironment.UserId = "lamaxu";
MQEnvironment.Password = "mypswd";
MQQueueManager _qMgr = new
MQQueueManager("DEMO");
```

```
char QMName[MQ_Q_MGR_NAME_LENGTH+1|MQ_Q_MGR_NAME_LENGTH+1] = "TESTQM";
char UserId[64] = "lamaxu";
char Password[64] = "mypswd";
strncpy(ClientConn.ConnectionName, "192.168.1.1(1414)",
MQ_CONN_NAME_LENGTH);
strncpy(ClientConn.ChannelName, "LAMAXU.CHANNEL",
MQ CHANNEL NAME LENGTH);
mqCSP.AuthenticationType = MQCSP_AUTH_USER_ID_AND_PWD;
mqCSP.CSPUserIdPtr = &UserId;
mqCSP.CSPUserIdLength = strlen(UserId);
mqCSP.CSPPasswordPtr = &Password;
mqCSP.CSPPasswordLength = strlen(Password);
ConnectOptions.SecurityParmsPtr = &mqCSP;
ConnectOptions.ClientConnPtr = &ClientConn;
ConnectOptions.Version = MQCNO_VERSION_2;
MQCONNX (QMName, &ConnectOptions, &HConn, &CompCode, &Reason);
```

C++

```
pchannel = new ImqChannel;
pchannel -> setConnectionName("10.10.10.10(1414)");
pchannel -> setChannelName("LDAPAUTH_CHANNEL");
pchannel -> setTransportType( MQXPT_TCP );
pchannel -> setUserId( "matt" );
pchannel -> setPassword( "mypswd" );
mgr.setName(QMName);
mgr.setChannelReference( pchannel );
if ( mgr.connect( ) ) { }
```

Related articles

QueueMetrix Gatekeeper

Building MQ Gatekeeper

- Build Instructions
 - · Linux Example;
- Dependencies
 - Build and Install OpenSSL
 - LINUX Example
 - Solaris SPARC-64 Example
 - AIX 64-bit version with IBM XL C

- Build and Install OpenLdap
 - LINUX Example
 - Solaris x86-64 Example
 - AIX Example

Build Instructions

First check out the code from GitHub, https://github.com/queuemetrix/mqgatekeeper.git

Build the dependencies first

Note, you will need to adjust the Make files to enter the correct paths for the dependency include and lib directories.

Linux Example;

```
bash-4.1$ pwd
/opt/mqm/src/c/libMQAuthLdap
bash-4.1$ make clean
/bin/rm -f libMQAuthLdap
/bin/rm -f .o *.tar *.tar.Z *.ba core x *.uu *.trc *.log
bash-4.1$ make
qcc -DLINUX -m64 -shared -fPIC -DANSI PROTOTYPES -D REENTRANT -l/opt/mgm/inc/
 -l/opt/mqm/scripts/linux64/openssl/include/ -l/opt/mqm/scripts/linux64/openIdap/include -WI,-rpath=/opt/mqm/lib64
 -WI,-rpath=/opt/mqm/scripts/linux64/openIdap/lib -WI,-rpath=/opt/mqm/scripts/linux64/openssl/lib -WI,-rpath=/usr/lib64 -c
libMQAuthLdap.c
gcc -DLINUX -m64 -shared -fPIC -DANSI_PROTOTYPES -D_REENTRANT -I/opt/mgm/inc/
 -l/opt/mgm/scripts/linux64/openssl/include/ -l/opt/mgm/scripts/linux64/openIdap/include -WI,-rpath=/opt/mgm/lib64
 -WI,-rpath=/opt/mqm/scripts/linux64/openIdap/lib -WI,-rpath=/opt/mqm/scripts/linux64/openssl/lib -WI,-rpath=/opt/mqm/scripts/lib -WI,-rpath=/o
LdapAuthenticateUser.c
acc -DLINUX -m64 -shared -fPIC -DANSI PROTOTYPES -D REENTRANT -l/opt/mam/inc/
  -l/opt/mgm/scripts/linux64/openssl/include/ -l/opt/mgm/scripts/linux64/openIdap/include -WI,-rpath=/opt/mgm/lib64
 -WI,-rpath=/opt/mqm/scripts/linux64/openIdap/lib -WI,-rpath=/opt/mqm/scripts/linux64/openssl/lib -WI,-rpath=/openssl/lib -WI,-
 gcc -DLINUX -m64 -shared -fPIC -DANSI_PROTOTYPES -D_REENTRANT -l/opt/mgm/inc/
 -l/opt/mgm/scripts/linux64/openssl/include/ -l/opt/mgm/scripts/linux64/openldap/include -WI,-rpath=/opt/mgm/lib64
 -WI,-rpath=/opt/mqm/scripts/linux64/openIdap/lib -WI,-rpath=/opt/mqm/scripts/linux64/openssl/lib -WI,-rpath=/openssl/lib -WI,-
 CheckIPAddress.c
 gcc -DLINUX -m64 -shared -fPIC -DANSI_PROTOTYPES -D REENTRANT -l/opt/mam/inc/
  -
-l/opt/mqm/scripts/linux64/openssl/include/ -l/opt/mqm/scripts/linux64/openIdap/include -WI,-rpath=/opt/mqm/lib64
 -WI,-rpath=/opt/mqm/scripts/linux64/openIdap/lib -WI,-rpath=/opt/mqm/scripts/linux64/openssl/lib -WI,-rpath=/opt/mqm/scripts/lib -WI,-rpath=/o
 -L/opt/mqm/lib64 -L/opt/mqm/scripts/linux64/openssl/lib -L/opt/mqm/scripts/linux64/openldap/lib -Imqm_r -Imqmcs_r -lssl -lcrypt
 -lldap_r libMQAuthLdap.o -o libMQAuthLdap \
 LdapAuthenticateUser.o \
 GetProperties.o \
 ChecklPAddress.o
bash-4.1$ make install
cp libMQAuthLdap /var/mqm/exits64
```

Dependencies

The LDAP authentication exit libMQAuthLdap has a number of dependencies that need to be built, or available, when the exit is compiled.

These are:

- OpenLdap
- OpenSSL

Build and Install OpenSSL

LINUX Example

mkdir /opt/mqm/scripts/linux64/openssl cd /opt/mqm/scripts/linux64/openssl-1.0.1c ./config --prefix=/opt/mqm/scripts/linux64/openssl enable-tlsext shared make make install

Solaris SPARC-64 Example

mkdir /opt/mqm/scripts/sparc/openssl cd /opt/mqm/scripts/linux64/openssl-1.0.1c ./Configure solaris64-sparcv9-cc --prefix=/opt/mqm/scripts/sparc/openssl enable-tlsext shared make make install

AIX 64-bit version with IBM XL C

./Configure threads --prefix=/usr/local/security/openssl aix64-cc shared make make install

Build and Install OpenLdap

LINUX Example

mkdir /opt/mqm/scripts/linux64/openldap
cd /opt/mqm/scripts/linux64/openldap-2.4.32
env CPPFLAGS="-l/opt/mqm/scripts/linux64/openssl/include LDFLAGS="-L/opt/mqm/scripts/linux64/openssl/lib
-L/opt/mqm/scripts/linux64/berkeley_db/lib" \
./configure --with-tls=openssl --enable-shell --prefix=/opt/openldap --disable-bdb --disable-hdb --disable-static --enable-dynamic
--disable-slapd --disable-debug
make depend
make install

Solaris x86-64 Example

mkdir /opt/mqm/scripts/solx86/openldap-2.4.32
cd /opt/mqm/scripts/solx86/src-openldap-2.4.32
export LDFLAGS="-m64 -L/opt/mqm/scripts/solx86/openssl/lib"
export CFLAGS="-m64 -l/opt/mqm/scripts/solx86/openssl/include"
export CPPFLAGS="-m64 -l/opt/mqm/scripts/solx86/openssl/include"
./configure --with-tls=openssl --enable-shell --prefix=/opt/openldap --disable-bdb --disable-hdb --disable-static --enable-dynamic
--disable-slapd --disable-debug
make depend
make install

AIX Example

```
mkdir /opt/openldap-2.4.42
cd /opt/src-openldap-2.4.42
export LDFLAGS="-q64 -L/opt/openssl/lib"
export CPPFLAGS="-q64 -l/opt/openssl/include"
export OBJECT_MODE=64
./configure --with-tls=openssl --enable-shell --prefix=/opt/openldap --disable-bdb --disable-hdb AR="ar -X64" --disable-static
--enable-dynamic --disable-slapd --disable-debug
make depend
make install
```

QueueMetrix Gatekeeper Properties file

Properties file

Defining the Exit

The *Idap.properties* file is used by the MQ *IibMQAuthLdap* security exit library to specify the security options for a particular channel. A common *Idap.properties* file can be used for all channels or a new one created per channel. The property file is specified as part of the MQ channel definition.

Example;

Channel security exit user data (SCYDATA)	ldap.properties
Channel security exit name (SCYEXTT)	libMQAuthLdap(MQAuthLdap)

Example Idap.properties file

- QMGR
- CHANNEL
- LogFilePath
- LogFileTag
- PROP_AUTHENTICATE_USER
- Debug
- PROP_CHECK_HOST_ADDRESS
- PROP_HOST_ADDRESS_RULE_FILE_FORMAT
- PROP_HOST_ADDRESS_RULE_FILE_NAME
- PROP_LDAP_AUTH_METHOD
- PROP_LDAP_VERSION
- PROP_LDAP_SCOPE
- PROP_LDAP_SCOPE_SUBTREE
- PROP_LDAP_SERVER_URL
- PROP_LDAP_PRINCIPAL_PREFIX
- PROP_LDAP_PRINCIPAL_SUFFIX
- PROP_LDAP_BASE_DN
- PROP_LDAP_GROUP_SEARCH_FILTER
- PROP_LDAP_USER_SEARCH_ATTRIBUTE
- PROP_LDAP_OPT_X_TLS_CACERTFILE
- PROP_LDAP_OPT_X_TLS_CACERTDIR
- PROP_LDAP_OPT_X_TLS_REQUIRE_CERT
- PROP_LDAP_OPT_REFERRALS
- PROP_LDAP_OPT_TIMELIMIT
- PROP_LDAP_OPT_NETWORK_TIMEOUT

Example Properties file

```
# Authenticate against the AD Domain controllers

QMGR=QM1
CHANNEL=LAMAXU.CHANNEL
LogFilePath=/var/mqm/errors/
LogFileTag=AD

PROP_AUTHENTICATE_USER=TRUE
PROP_CHECK_HOST_ADDRESS=TRUE
PROP_HOST_ADDRESS_RULE_FILE_FORMAT=BIP2
PROP_HOST_ADDRESS_RULE_FILE_NAME=/var/mqm/exits/QM1

PROP_LDAP_AUTH_METHOD=LDAP_AUTH_SIMPLE
PROP_LDAP_VERSION=LDAP_VERSION3
PROP_LDAP_SCOPE=LDAP_SCOPE_SUBTREE
PROP_LDAP_SCOPE=LDAP_SCOPE_SUBTREE
PROP_LDAP_SERVER_URL=ldaps://server123 ldaps://server456
PROP_LDAP_PRINCIPAL_PREFIX=NTDOMAIN\
PROP_LDAP_PRINCIPAL_SUFFIX=
```

```
PROP_LDAP_BASE_DN=DC=pc, DC=internal, DC=queuemetrix, DC=com
PROP_LDAP_GROUP_SEARCH_FILTER=(|(memberOf=CN=QueueMetrix
Team,OU=Groups,OU=Exchange,DC=pc,DC=internal,DC=queuemetrix,DC=com))
PROP_LDAP_USER_SEARCH_ATTRIBUTE=sAMAccountName
PROP LDAP OPT X TLS CACERTFILE=
PROP_LDAP_OPT_X_TLS_CACERTDIR=/etc/ssl/certs/
PROP_LDAP_OPT_X_TLS_REQUIRE_CERT=LDAP_OPT_X_TLS_NEVER
PROP LDAP OPT REFERRALS=LDAP OPT OFF
PROP_LDAP_OPT_TIMELIMIT=3
PROP_LDAP_OPT_NETWORK_TIMEOUT=30
# Authenticate against the LDS server
QMGR=QM1
CHANNEL=LAMAXU1.CHANNEL
LogFilePath=/var/mqm/errors/
LogFileTag=LDS
PROP_AUTHENTICATE_USER=TRUE
PROP_CHECK_HOST_ADDRESS=TRUE
PROP_HOST_ADDRESS_RULE_FILE_FORMAT=BIP2
PROP_HOST_ADDRESS_RULE_FILE_NAME=/var/mqm/exits/QM1
PROP_LDAP_AUTH_METHOD=LDAP_AUTH_SIMPLE
PROP LDAP VERSION=LDAP VERSION3
PROP LDAP SCOPE=LDAP SCOPE SUBTREE
PROP LDAP SERVER URL=ldaps://server123
PROP_LDAP_PRINCIPAL_PREFIX=CN=
PROP_LDAP_PRINCIPAL_SUFFIX=,OU=userProxy,DC=LDS,DC=Internal,DC=queuemetrix
,DC=com
PROP_LDAP_BASE_DN=OU=Users, DC=LDS, DC=Internal, DC=queuemetrix, DC=com
PROP_LDAP_GROUP_SEARCH_FILTER=(|(memberOf=CN=QueueMetrix
Team,OU=ADGroups,DC=LDS,DC=Internal,DC=queuemetrix,DC=com))
PROP_LDAP_USER_SEARCH_ATTRIBUTE=sAMAccountName
PROP_LDAP_OPT_X_TLS_CACERTFILE=
PROP_LDAP_OPT_X_TLS_CACERTDIR=/etc/ssl/certs/
PROP_LDAP_OPT_X_TLS_REQUIRE_CERT=LDAP_OPT_X_TLS_TRY
PROP_LDAP_OPT_REFERRALS=LDAP_OPT_OFF
PROP_LDAP_OPT_TIMELIMIT=3
PROP_LDAP_OPT_NETWORK_TIMEOUT=30
# Another Channel without IP filtering
OMGR=OM1
CHANNEL=LAMAXU2.CHANNEL
LogFilePath=/var/mqm/errors/
LogFileTag=Multigroup
PROP AUTHENTICATE USER=TRUE
PROP_CHECK_HOST_ADDRESS=FALSE
PROP_HOST_ADDRESS_RULE_FILE_FORMAT=BIP2
PROP HOST ADDRESS RULE FILE NAME=/var/mgm/exits/QM1
PROP_LDAP_AUTH_METHOD=LDAP_AUTH_SIMPLE
PROP_LDAP_VERSION=LDAP_VERSION3
PROP_LDAP_SCOPE=LDAP_SCOPE_SUBTREE
```

```
PROP_LDAP_SERVER_URL=ldaps://server123
PROP_LDAP_PRINCIPAL_PREFIX=CN=
PROP_LDAP_PRINCIPAL_SUFFIX=,OU=userProxy,DC=LDS,DC=Internal,DC=queuemetrix,DC=com
PROP_LDAP_BASE_DN=OU=Users,DC=LDS,DC=Internal,DC=queuemetrix,DC=com
PROP_LDAP_GROUP_SEARCH_FILTER=(|(memberOf=CN=Queuemetrix,DC=com)(memberOf=CN=Queuemetrix admin,OU=ADGroups,DC=LDS,DC=Internal,DC=queuemetrix,DC=com)(memberOf=CN=Queuemetrix admin,OU=ADGroups,DC=LDS,DC=Internal,DC=queuemetrix,DC=com))
PROP_LDAP_USER_SEARCH_ATTRIBUTE=sAMAccountName
PROP_LDAP_OPT_X_TLS_CACERTFILE=
PROP_LDAP_OPT_X_TLS_CACERTDIR=/etc/ssl/certs/
PROP_LDAP_OPT_X_TLS_REQUIRE_CERT=LDAP_OPT_X_TLS_TRY
PROP_LDAP_OPT_REFERRALS=LDAP_OPT_OFF
PROP_LDAP_OPT_TIMELIMIT=3
PROP_LDAP_OPT_NETWORK_TIMEOUT=30
```

And another Channel
QMGR=QM1
CHANNEL=OTHER.CHANNEL
LogFilePath=/var/mqm/errors/
LogFileTag=IP_Only
PROP_AUTHENTICATE_USER=FALSE
PROP_CHECK_HOST_ADDRESS=TRUE

```
PROP_HOST_ADDRESS_RULE_FILE_FORMAT=BIP2
PROP_HOST_ADDRESS_RULE_FILE_NAME=/var/mqm/exits/QM1
```

QMGR

This is the name of the queue manager that the subsequent config will be used for.

Example

QMGR=QM1

CHANNEL

This is the name of the channel that the subsequent config will be used for.

Example;

CHANNEL=LAMAXU.CHANNEL

LogFilePath

This is the directory where the error logs will be written to.

Example;

LogFilePath=/var/mqm/error/

LogFileTag

This is the name tagged to the error log after the channel name.

Example;

LogFileTag=mylogfile

PROP_AUTHENTICATE_USER

If this is set to FALSE then the username & password of connecting client will NOT be authenticated on the LDAP. If any other value is set then the default option is TRUE.

Example;

PROP_AUTHENTICATE_USER=FALSE

Debug

This value determines whether debug messages will be written to the exit log.

Valid options

```
0 = Minimal messages
1 = Full debug logging
```

PROP_CHECK_HOST_ADDRESS

If this is set to TRUE then the IP address of the connecting client will be checked. If any other value is set then the option is disabled.

Example;

PROP_CHECK_HOST_ADDRESS=TRUE

PROP_HOST_ADDRESS_RULE_FILE_FORMAT

This specifies the format of the IP address rules file. At present only the BIP2 (BlockIP2) file is supported to provide compatibility with the existing IP filter rule files.

Example;

PROP_HOST_ADDRESS_RULE_FILE_FORMAT=BIP2

PROP_HOST_ADDRESS_RULE_FILE_NAME

This option sets the location and name of the IP address rules file.

Example;

PROP_HOST_ADDRESS_RULE_FILE_NAME=/var/mqm/exits/QM1

PROP_LDAP_AUTH_METHOD

This value is always set as LDAP_AUTH_SIMPLE

Valid Options

LDAP_AUTH_SIMPLE

PROP_LDAP_VERSION

This sets the LDAP version to use and should generally be set to LDAP_VERSION3

Valid Options

LDAP_VERSION1 LDAP_VERSION2 LDAP_VERSION3

PROP_LDAP_SCOPE

Not used yet'

PROP_LDAP_SCOPE_SUBTREE

Not used yet

PROP_LDAP_SERVER_URL

This is the Idap: or Ipdaps: server URL

Note that multiple servers can be specified for redundancy purposes delimited by a space char.

Example:

On the LDS

PROP_LDAP_SERVER_URL=Idaps://server123.queuemetrix.com

and for the AD domain controller

PROP_LDAP_SERVER_URL=Idaps://server123 ldaps://server456

PROP_LDAP_PRINCIPAL_PREFIX

This is the prefix of the connecting user

Example;

On the LDS

PROP_LDAP_PRINCIPAL_PREFIX=CN=

and for the AD domain controller

PROP_LDAP_PRINCIPAL_PREFIX=NTDOMAIN\

PROP_LDAP_PRINCIPAL_SUFFIX

This is the base DN of the connecting user

Example;

On the LDS

PROP_LDAP_PRINCIPAL_SUFFIX=, OU=userProxy, DC=LDS, DC=Internal, DC=queuemetrix, DC=com

and for the AD domain controller

PROP_LDAP_PRINCIPAL_SUFFIX=

PROP_LDAP_BASE_DN

This is the base DN used when searching for user group memberships

Example;

On the LDS

PROP_LDAP_BASE_DN=OU=Users,DC=LDS,DC=Internal,DC=queuemetrix,DC=com

and for the AD domain controller

PROP_LDAP_BASE_DN=DC=pc,DC=internal,DC=queuemetrix,DC=com

PROP_LDAP_GROUP_SEARCH_FILTER

This value contains an LDAP filter string and is used to check for membership of one or more AD groups or any other valid LDAP search options.

Example;

(||(memberOf=CN=QueueMetrix Team,OU=ADGroups,DC=LDS,DC=Internal,DC=queuemetrix,DC=com)(memberOf=CN=QueueMetrix Team,OU=ADGroups,DC=LDS,DC=Internal,DC=queuemetrix,DC=com))

PROP_LDAP_USER_SEARCH_ATTRIBUTE

This is the Idap attribute that contains the user name to be filtered on. The sAMAccountName is for AD (Active Directory) authentication.

Example;

PROP_LDAP_USER_SEARCH_ATTRIBUTE=sAMAccountName

PROP_LDAP_OPT_X_TLS_CACERTFILE

This is the path to the CA Certificate .pem file

Example;

PROP_LDAP_OPT_X_TLS_CACERTFILE=/etc/ssl/certs/root.pem

PROP_LDAP_OPT_X_TLS_CACERTDIR

This is the path to the CA Certificate directory store

Example;

PROP_LDAP_OPT_X_TLS_CACERTDIR=/etc/ssl/certs/

PROP_LDAP_OPT_X_TLS_REQUIRE_CERT

This option determines how the certificate from the lpdaps: service is handled

Valid options are;

```
LDAP_OPT_X_TLS_NEVER
LDAP_OPT_X_TLS_HARD
LDAP_OPT_X_TLS_DEMAND
LDAP_OPT_X_TLS_ALLOW
LDAP_OPT_X_TLS_TRY
```

PROP_LDAP_OPT_REFERRALS

This option sets whether to follow LDAP referals during searches. It MUST be set to LDAP_OPT_OFF when authenticating against the AD domain controllers.

Valid options are;

```
LDAP_OPT_OFF
LDAP_OPT_ON
```

PROP_LDAP_OPT_TIMELIMIT

This option sets the LDAP search timeout in seconds

Example;

```
PROP_LDAP_OPT_TIMELIMIT=3
```

PROP_LDAP_OPT_NETWORK_TIMEOUT

This option sets the network timeout in seconds

Example;

```
PROP_LDAP_OPT_NETWORK_TIMEOUT=30
```