Network Working Group Request for Comments: 3812 Category: Standards Track C. Srinivasan
Bloomberg L.P.
A. Viswanathan
Force10 Networks, Inc.
T. Nadeau
Cisco Systems, Inc.
June 2004

Multiprotocol Label Switching (MPLS) Traffic Engineering (TE)

Management Information Base (MIB)

#### Status of this Memo

This document specifies an Internet standards track protocol for the Internet community, and requests discussion and suggestions for improvements. Please refer to the current edition of the "Internet Official Protocol Standards" (STD 1) for the standardization state and status of this protocol. Distribution of this memo is unlimited.

### Copyright Notice

Copyright (C) The Internet Society (2004).

#### Abstract

This memo defines a portion of the Management Information Base (MIB) for use with network management protocols in the Internet community. In particular, it describes managed objects for Multiprotocol Label Switching (MPLS) based traffic engineering (TE).

### Table of Contents

1.	Introduction	2
2.	Terminology	2
3.	The Internet-Standard Management Framework	3
4.	Feature List	3
5.	Outline	3
	5.1. Summary of Traffic Engineering MIB Module	4
6.	Brief Description of MIB Objects	4
	6.1. mplsTunnelTable	4
	6.2. mplsTunnelResourceTable	5
	6.3. mplsTunnelHopTable	5
	6.4. mplsTunnelARHopTable	5
	6.5. mplsTunnelCHoptable	5
	6.6. mplsTunnelPerfTable	6
	6.7. mplsTunnelCRLDPResTable	6
7.	Use of 32-bit and 64-bit Counters	6

Srinivasan, et al.

Standards Track

[Page 1]

8.	Application of the Interface Group to MPLS Tunnels	6
	8.1. Support of the MPLS Tunnel Interface by ifTable	7
9.	Example of Tunnel Setup	8
10.	The Use of RowPointer	11
11.	MPLS Traffic Engineering MIB Definitions	11
12.	Security Considerations	63
13.	Acknowledgments	64
14.	IANA Considerations	64
	14.1. IANA Considerations for MPLS-TE-STD-MIB	65
15.	References	65
	15.1. Normative References	65
	15.2. Informative References	66
16.	Authors' Addresses	67
17.	Full Copyright Statement	68

#### 1. Introduction

This memo defines a portion of the Management Information Base (MIB) for use with network management protocols in the Internet community. In particular, it describes managed objects for modeling a Multiprotocol Label Switching (MPLS) [RFC3031] based traffic engineering. This MIB module should be used in conjunction with the companion document [RFC3813] for MPLS based traffic engineering configuration and management.

The key words "MUST", "MUST NOT", "REQUIRED", "SHALL", "SHALL NOT", "SHOULD", "SHOULD NOT", "RECOMMENDED", "MAY", and "OPTIONAL" in this document are to be interpreted as described in BCP 14, RFC 2119, reference [RFC2119].

# 2. Terminology

This document uses terminology from the MPLS architecture document [RFC3031] and MPLS Label Switch Router MIB [RFC3813]. Some frequently used terms are described next.

An explicitly routed LSP (ERLSP) is referred to as an MPLS tunnel. It consists of in-segment(s) and/or out-segment(s) at the egress/ingress LSRs, each segment being associated with one MPLS interface. These are also referred to as tunnel segments. Additionally, at an intermediate LSR, we model a connection as consisting of one or more in-segments and/or one or more out-segments. The binding or interconnection between in-segments and out-segments is performed using a cross-connect. These objects are defined in the MPLS Label Switch Router MIB [RFC3813].

# 3. The Internet-Standard Management Framework

For a detailed overview of the documents that describe the current Internet-Standard Management Framework, please refer to section 7 of RFC 3410 [RFC3410].

Managed objects are accessed via a virtual information store, termed the Management Information Base or MIB. MIB objects are generally accessed through the Simple Network Management Protocol (SNMP). Objects in the MIB are defined using the mechanisms defined in the Structure of Management Information (SMI). This memo specifies a MIB module that is compliant to the SMIv2, which is described in STD 58, RFC 2578 [RFC2578], STD 58, RFC 2579 [RFC2579] and STD 58, RFC 2580 [RFC2580].

#### 4. Feature List

The MPLS traffic engineering MIB module is designed to satisfy the following requirements and constraints:

- The MIB module supports configuration of point-to-point unidirectional tunnels.
- MPLS tunnels need not be interfaces, but it is possible to configure a tunnel as an interface.
- The MIB module supports tunnel establishment via an MPLS signalling protocol wherein the tunnel parameters are specified using this MIB module at the head end of the LSP, and end-to-end tunnel LSP establishment is accomplished via signalling. The MIB module also supports manually configured tunnels, i.e., those for which label associations at each hop of the tunnel LSP are provisioned by the administrator via the LSR MIB [RFC3813].
- The MIB module supports persistent, as well as non-persistent tunnels.

### 5. Outline

Traffic engineering support for MPLS tunnels requires the following configuration:

- Setting up MPLS tunnels along with appropriate configuration parameters.
- Configuring tunnel for loose and strict source routed hops.

These actions may need to be accompanied by corresponding actions using [RFC3813] to establish and configure tunnel segments, if this is done manually. Also, the in-segment and out-segment performance tables, mplsInSegmentPerfTable, and mplsOutSegmentPerfTable [RFC3813], should be used to determine performance of the tunnels and tunnel segments, in addition to mplsTunnelPerfTable in this MIB module.

### 5.1. Summary of Traffic Engineering MIB Module

The MIB module objects for performing these actions consist of the following tables:

- Tunnel table (mplsTunnelTable) for setting up MPLS tunnels.
- Resource table (mplsTunnelResourceTable) for setting up the tunnel resources.
- Tunnel specified, actual, and computed hop tables (mplsTunnelHopTable, mplsTunnelARHopTable, and mplsTunnelCHopTable) for strict and loose source routed MPLS tunnel hops.
- Tunnel performance table (mplsTunnelPerfTable) for measuring tunnel performance.
- CRLDP resource table (mplsTunnelCRLDPResTable) for specifying resource objects applicable to tunnels signaled using CRLDP.

These tables are described in the subsequent sections.

# 6. Brief Description of MIB Objects

The objects described in this section support the functionality described in documents [RFC3209] and [RFC3212]. The tables support both manually configured and signaled tunnels.

### 6.1. mplsTunnelTable

The mplsTunnelTable allows new MPLS tunnels to be created between an MPLS LSR and a remote endpoint, and existing tunnels to be reconfigured or removed. Note that we only support point-to-point tunnels, although multipoint-to-point and point-to-multipoint connections are supported by an LSR acting as a cross-connect. Each MPLS tunnel can thus have one out-segment originating at an LSR and/or one in-segment terminating at that LSR.

mplsTunnelTable does not define the in and out segments forming the tunnel. Instead, these are defined by creating rows in the insegment and out-segment tables, defining relationships in the cross-connect table, and referring to these rows in the mplsTunnelTable using a cross-connect index, mplsTunnelXCIndex. These segment and cross-connect related objects are defined in [RFC3813].

### 6.2. mplsTunnelResourceTable

mplsTunnelResourceTable is used to indicate the resources required for a tunnel. Multiple tunnels may share the same resources by pointing to the same entry in this table. Tunnels that do not share resources must point to separate entries in this table.

### 6.3. mplsTunnelHopTable

mplsTunnelHopTable is used to indicate the hops, strict or loose, for an MPLS tunnel defined in mplsTunnelTable, when it is established via signalling. Multiple tunnels may share the same hops by pointing to the same entry in this table. Each row also has a secondary index, mplsTunnelHopIndex, corresponding to the next hop of this tunnel. The scalar mplsTunnelMaxHops indicates the maximum number of hops that can be specified on each tunnel supported by this LSR.

At transit LSRs, this table contains the hops, strict or loose, that apply to the downstream part of this tunnel only. This corresponds to the requested path received through the signaling protocol.

# **6.4.** mplsTunnelARHopTable

mplsTunnelARHopTable is used to indicate the actual hops traversed by a tunnel as reported by the MPLS signalling protocol after the tunnel is setup. The support of this table is optional since not all MPLS signalling protocols may support this feature.

At transit LSRs, this table contains the actual hops traversed by the tunnel along its entire length if that information is available. This corresponds to the recorded path reported by the MPLS signalling protocol, possibly derived from multiple signaling messages.

### 6.5. mplsTunnelCHoptable

mplsTunnelCHopTable lists the actual hops computed by a constraint-based routing algorithm based on the mplsTunnelHopTable for the MPLS signalling protocol in use. The support of this table is optional since not all implementations may support computation of hop lists using a constraint-based routing protocol.

At transit LSRs, this table contains the hops computed to apply to the downstream part of this tunnel. This corresponds to the requested path signaled from this LSR through the signaling protocol.

### 6.6. mplsTunnelPerfTable

mplsTunnelPerfTable provides several counters to measure the
performance of the MPLS tunnels. This table augments
mplsTunnelTable.

### 6.7. mplsTunnelCRLDPResTable

mplsTunnelCRLDPResTable contains resource information for those tunnels that are signaled using CRLDP [RFC3212]. This is a sparse extension to mplsTunnelResourceTable and is also indexed by mplsTunnelResourceIndex. As with mplsTunnelResourceTable, multiple tunnels may share the same resources by pointing to the same entry in this table. Tunnels that do not share resources must point to separate entries in this table. The mplsTunnelCRLDPResTable may be supported only by implementations that support the CR-LDP signaling protocol.

#### 7. Use of 32-bit and 64-bit Counters

64-bit counters are provided in this MIB module for high-speed interfaces where the use of 32-bit counters might be impractical. The requirements on the use of 32-bit and 64-bit counters (copied verbatim from [RFC2863]) are as follows:

For interfaces that operate at 20,000,000 (20 million) bits per second or less, 32-bit byte and packet counters MUST be supported. For interfaces that operate faster than 20,000,000 bits/second, and slower than 650,000,000 bits/second, 32-bit packet counters MUST be supported and 64-bit octet counters MUST be supported. For interfaces that operate at 650,000,000 bits/second or faster, 64-bit packet counters AND 64-bit octet counters MUST be supported.

### 8. Application of the Interface Group to MPLS Tunnels

The Interfaces Group of MIB II defines generic managed objects for managing interfaces. This memo contains the media-specific extensions to the Interfaces Group for managing MPLS Tunnels as logical interfaces.

This memo assumes the interpretation of the Interfaces Group to be in accordance with [RFC2863] which states that the interfaces table (ifTable) contains information on the managed resource's interfaces and that each sub-layer below the internetwork layer of a network

interface is considered an interface. Thus, the MPLS interface is represented as an entry in the ifTable. The inter-relation of entries in the ifTable is defined by the Interfaces Stack Group defined in [RFC2863].

When using MPLS Tunnels as interfaces, the interface stack table might appear as follows:

In the above diagram, "Underlying Layer" refers to the ifIndex of any interface type for which MPLS internetworking has been defined. Examples include ATM, Frame Relay, and Ethernet.

### 8.1. Support of the MPLS Tunnel Interface by ifTable

Some specific interpretations of the ifTable for those MPLS tunnels represented as interfaces follow:

Object Use for the MPLS tunnel. ifIndex Each MPLS tunnel is represented by an ifEntry. Description of the MPLS tunnel. ifDescr ifType The value that is allocated for the MPLS tunnel is 150. ifSpeed The total bandwidth in bits per second for use by the MPLS tunnel. ifPhysAddress Unused. ifAdminStatus See [RFC2863]. This value reflects the actual ifOperStatus operational status of the MPLS tunnel. Assumes the value down(2) if the MPLS tunnel is down. See [RFC2863]. ifLastChange

Srinivasan, et al. Standards Track [Page 7]

RFC 3812 MPLS-TE-STD-MIB June 2004

ifInOctets The number of octets received over the

MPLS tunnel.

the MPLS tunnel.

ifInErrors The number of labeled packets dropped

due to uncorrectable errors.

ifInUnknownProtos The number of received packets

discarded during packet header validation, including packets with

unrecognized label values.

ifOutErrors See [RFC2863].

ifName Textual name (unique on this system) of

the MPLS tunnel or an octet string of

zero length.

ifLinkUpDownTrapEnable

Default is disabled (2).

ifConnectorPresent Set to false (2).

ifHighSpeed See [RFC2863].

ifHCInOctets The 64-bit version of ifInOctets;

supported if required by the compliance

statements in [RFC2863].

ifHCOutOctets The 64-bit version of ifOutOctets;

supported if required by the compliance

statements in [RFC2863].

ifAlias The non-volatile 'alias' name for the

MPLS tunnel as specified by a network

manager.

### 9. Example of Tunnel Setup

This section contains an example of which MIB objects should be modified if one would like to create a best effort, loosely routed, unidirectional traffic engineered tunnel, which spans two hops of a simple network. Note that these objects should be created on the "head-end" LSR. Those objects relevant to illustrating the relationships amongst different tables are shown here. Other objects may be needed before conceptual row activation can happen.

The RowStatus values shown in this section are those to be used in the set request, typically createAndGo(4) which is used to create the conceptual row and have its status immediately set to active. A subsequent retrieval operation on the conceptual row will return a different value, such as active(1). Please see [RFC2579] for a detailed discussion on the use of RowStatus.

```
In mplsTunnelResourceTable:
```

The next two instances of mplsTunnelHopEntry are used to denote the hops this tunnel will take across the network.

The following denotes the beginning of the tunnel, or the first hop. We have used the fictitious LSR identified by "192.168.100.1" as our example head-end router.

```
In mplsTunnelHopTable:
```

```
mplsTunnelHopListIndex
 mplsTunnelPathOptionIndex
                         = 1,
 mplsTunnelHopIndex
                         = 1,
                         = ipv4 (1),
 mplsTunnelHopAddrType
                         = "192.168.100.1",
 mplsTunnelHopIpAddr
                      = 32,
 mplsTunnelHopIpPrefixLen
 mplsTunnelHopType
                         = strict (2),
 -- Mandatory parameters needed to activate the row go here
                     = createAndGo (4)
 mplsTunnelHopRowStatus
}
```

```
The following denotes the end of the tunnel, or the last hop in our
example. We have used the fictitious LSR identified by
"192.168.101.1" as our end router.
In mplsTunnelHopTable:
 mplsTunnelHopListIndex
 mplsTunnelPathOptionIndex
                              = 1,
 mplsTunnelHopIndex
                              = 2,
                             = ipv4 (1),
 mplsTunnelHopAddrType
 mplsTunnelHopIpAddr
                              = "192.168.101.1",
 -- Mandatory parameters needed to activate the row go here
 mplsTunnelHopRowStatus = createAndGo (4)
}
The following denotes the configured tunnel "head" entry:
In mplsTunnelTable:
 mplsTunnelIndex
mplsTunnelInstance
                           = 1,
                          = 0,
= 192.168.100.1,
 mplsTunnelIngressLSRId
                           = 192.168.101.1,
 mplsTunnelEgressLSRId
                           = "My first tunnel",
 mplsTunnelName
                        = "Here to there",
 mplsTunnelDescr
 mplsTunnelIsIf
                            = true (1),
-- RowPointer MUST point to the first accessible column
 mplsTunnelXCPointer = 0.0,
 mplsTunnelSignallingProto = none (1),
 mplsTunnelSetupPrio = 0,
mplsTunnelHoldingPrio = 0,
 mplsTunnelSessionAttributes = 0,
 mplsTunnelLocalProtectInUse = false (0),
-- RowPointer MUST point to the first accessible column
 mplsTunnelResourcePointer = mplsTunnelResourceMaxRate.5,
 mplsTunnelInstancePriority = 1,
 mplsTunnelHopTableIndex = 1,
 mplsTunnelIncludeAnyAffinity = 0,
 mplsTunnelIncludeAllAffinity = 0,
 mplsTunnelExcludeAnyAffinity = 0,
 mplsTunnelPathInUse
                            = 1,
```

```
mplsTunnelRole = head (1),
-- Mandatory parameters needed to activate the row go here
mplsTunnelRowStatus = createAndGo (4)
}
```

Note that any active or signaled instances of the above tunnel would appear with the same primary mplsTunnelIndex, but would have values greater than 0 for mplsTunnelInstance. They would also have other objects such as the mplsTunnelXCPointer set accordingly.

#### 10. The Use of RowPointer

RowPointer is a textual convention used to identify a conceptual row in a conceptual table in a MIB by pointing to the first accessible object. In this MIB module, in mplsTunnelTable, the objects mplsTunnelXCPointer and mplsTunnelResourcePointer are of type RowPointer. The object mplsTunnelXCPointer points to a specific entry in the mplsXCTable [RFC3813]. This entry in the mplsXCTable is the associated LSP for the given MPLS tunnel entry. The object mplsTunnelResourcePointer points to a specific entry in a traffic parameter table. An example of such a traffic parameter table is mplsTunnelResourceTable. It indicates a specific instance of a traffic parameter entry that is associated with a given MPLS tunnel entry. These RowPointer objects MUST point to the first instance of the first accessible columnar object in the appropriate conceptual row in order to allow the manager to find the appropriate corresponding entry in either MPLS-LSR-STD-MIB [RFC3813] or MPLS-TE-STD-MIB. If object mplsTunnelXCPointer returns zeroDotZero, it implies that there is no LSP associated with that particular instance of tunnel entry. If object mplsTunnelResourcePointer returns zeroDotZero, it implies that there is no QoS resource associated with that particular instance of tunnel entry.

# 11. MPLS Traffic Engineering MIB Definitions

```
MPLS-TE-STD-MIB DEFINITIONS ::= BEGIN
```

```
IMPORTS
```

```
MODULE-IDENTITY, OBJECT-TYPE, NOTIFICATION-TYPE,
Integer32, Unsigned32, Counter32, Counter64, TimeTicks,
zeroDotZero
   FROM SNMPv2-SMI -- [RFC2578]
MODULE-COMPLIANCE, OBJECT-GROUP, NOTIFICATION-GROUP
   FROM SNMPv2-CONF -- [RFC2580]
TruthValue, RowStatus, RowPointer, StorageType,
TimeStamp
   FROM SNMPv2-TC -- [RFC2579]
InterfaceIndexOrZero, ifGeneralInformationGroup,
```

```
ifCounterDiscontinuityGroup
      FROM IF-MIB
                                                         -- [RFC2863]
   mplsStdMIB, MplsBitRate, MplsBurstSize, MplsLSPID,
   MplsTunnelIndex, MplsTunnelInstanceIndex,
   MplsTunnelAffinity, MplsExtendedTunnelId, MplsPathIndex,
   MplsPathIndexOrZero, MplsOwner, TeHopAddressType,
   TeHopAddress, TeHopAddressAS, TeHopAddressUnnum
      FROM MPLS-TC-STD-MIB
                                                          -- [RFC3811]
   SnmpAdminString
      FROM SNMP-FRAMEWORK-MIB
                                                         -- [RFC3411]
   IndexIntegerNextFree
      FROM DIFFSERV-MIB
                                                         -- [RFC3289]
   InetAddressPrefixLength
      FROM INET-ADDRESS-MIB
                                                         -- [RFC3291]
mplsTeStdMIB MODULE-IDENTITY
   LAST-UPDATED
      "200406030000Z" -- June 3, 2004
      "Multiprotocol Label Switching (MPLS) Working Group"
   CONTACT-INFO
                Cheenu Srinivasan
                 Bloomberg L.P.
         Email: cheenu@bloomberg.net
                 Arun Viswanathan
                 Force10 Networks, Inc.
         Email: arunv@force10networks.com
                 Thomas D. Nadeau
                 Cisco Systems, Inc.
         Email: tnadeau@cisco.com
                Comments about this document should be emailed
                directly to the MPLS working group mailing list at
                mpls@uu.net."
   DESCRIPTION
         "Copyright (C) The Internet Society (2004). The
         initial version of this MIB module was published
         in RFC 3812. For full legal notices see the RFC
         itself or see: http://www.ietf.org/copyrights/ianamib.html
         This MIB module contains managed object definitions
         for MPLS Traffic Engineering (TE) as defined in:
         1. Extensions to RSVP for LSP Tunnels, Awduche et
         al, RFC 3209, December 2001
         2. Constraint-Based LSP Setup using LDP, Jamoussi
```

```
(Editor), RFC 3212, January 2002
          3. Requirements for Traffic Engineering Over MPLS,
           Awduche, D., Malcolm, J., Agogbua, J., O'Dell, M.,
           and J. McManus, [RFC2702], September 1999"
   -- Revision history.
   REVISION
       "200406030000Z" -- June 3, 2004
   DESCRIPTION
        "Initial version issued as part of RFC 3812."
   ::= { mplsStdMIB 3 }
-- Top level components of this MIB module.
-- traps
mplsTeNotifications OBJECT IDENTIFIER ::= { mplsTeStdMIB 0 }
-- tables, scalars
\begin{array}{llll} \texttt{mplsTeScalars} & \texttt{OBJECT IDENTIFIER ::= \{ mplsTeStdMIB 1 \} } \\ \texttt{mplsTeObjects} & \texttt{OBJECT IDENTIFIER ::= \{ mplsTeStdMIB 2 \} } \\ \end{array}
-- conformance
mplsTeConformance    OBJECT IDENTIFIER ::= { mplsTeStdMIB 3 }
-- MPLS Tunnel scalars.
mplsTunnelConfigured OBJECT-TYPE
   SYNTAX Unsigned32
   MAX-ACCESS read-only
                 current
   STATIIS
   DESCRIPTION
         "The number of tunnels configured on this device. A
           tunnel is considered configured if the
           mplsTunnelRowStatus is active(1)."
   ::= { mplsTeScalars 1 }
mplsTunnelActive OBJECT-TYPE
   SYNTAX Unsigned32
   MAX-ACCESS read-only
   STATUS
                  current
   DESCRIPTION
         "The number of tunnels active on this device. A
           tunnel is considered active if the
           mplsTunnelOperStatus is up(1)."
   ::= { mplsTeScalars 2 }
mplsTunnelTEDistProto OBJECT-TYPE
```

```
SYNTAX
               BITS {
        other (0),
         ospf (1),
         isis (2)
  MAX-ACCESS
               read-only
   STATUS
                current
   DESCRIPTION
        "The traffic engineering distribution protocol(s)
         used by this LSR. Note that an LSR may support more
         than one distribution protocol simultaneously."
   ::= { mplsTeScalars 3 }
mplsTunnelMaxHops OBJECT-TYPE
  SYNTAX Unsigned32
  MAX-ACCESS read-only
   STATUS
                current
  DESCRIPTION
       "The maximum number of hops that can be specified for
         a tunnel on this device."
   ::= { mplsTeScalars 4 }
mplsTunnelNotificationMaxRate OBJECT-TYPE
  SYNTAX Unsigned32
  MAX-ACCESS
             read-write
   STATUS current
  DESCRIPTION
       "This variable indicates the maximum number of
         notifications issued per second. If events occur
         more rapidly, the implementation may simply fail to
         emit these notifications during that period, or may
         queue them until an appropriate time. A value of 0
         means no throttling is applied and events may be
         notified at the rate at which they occur."
  DEFVAL { 0 }
   ::= { mplsTeScalars 5 }
-- End of MPLS Tunnel scalars.
-- MPLS tunnel table.
mplsTunnelIndexNext OBJECT-TYPE
  SYNTAX IndexIntegerNextFree (0..65535)
  MAX-ACCESS read-only
  STATUS
               current
   DESCRIPTION
       "This object contains an unused value for
```

mplsTunnelIndex, or a zero to indicate
that none exist. Negative values are not allowed,
as they do not correspond to valid values of
mplsTunnelIndex.

Note that this object offers an unused value for an mplsTunnelIndex value at the ingress side of a tunnel. At other LSRs the value of mplsTunnelIndex SHOULD be taken from the value signaled by the MPLS signaling protocol.

::= { mplsTeObjects 1 }

mplsTunnelTable OBJECT-TYPE

SYNTAX SEQUENCE OF MplsTunnelEntry

MAX-ACCESS not-accessible

STATUS current

DESCRIPTION

"The mplsTunnelTable allows new MPLS tunnels to be created between an LSR and a remote endpoint, and existing tunnels to be reconfigured or removed. Note that only point-to-point tunnel segments are supported, although multipoint-to-point and point-to-multipoint connections are supported by an LSR acting as a cross-connect. Each MPLS tunnel can thus have one out-segment originating at this LSR and/or one in-segment terminating at this LSR."

::= { mplsTeObjects 2 }

mplsTunnelEntry OBJECT-TYPE

SYNTAX MplsTunnelEntry MAX-ACCESS not-accessible

STATUS current

DESCRIPTION

"An entry in this table represents an MPLS tunnel.

An entry can be created by a network administrator or by an SNMP agent as instructed by an MPLS signalling protocol. Whenever a new entry is created with mplsTunnelIsIf set to true(1), then a corresponding entry is created in ifTable as well (see RFC 2863). The ifType of this entry is mplsTunnel(150).

A tunnel entry needs to be uniquely identified across a MPLS network. Indices mplsTunnelIndex and mplsTunnelInstance uniquely identify a tunnel on the LSR originating the tunnel. To uniquely identify a tunnel across an MPLS network requires

```
index mplsTunnelIngressLSRId. The last index
          mplsTunnelEgressLSRId is useful in identifying all
          instances of a tunnel that terminate on the same
          egress LSR."
   REFERENCE
        "1. RFC 2863 - The Interfaces Group MIB, McCloghrie,
          K., and F. Kastenholtz, June 2000 "
   INDEX { mplsTunnelIndex,
            mplsTunnelInstance,
            mplsTunnelIngressLSRId,
            mplsTunnelEgressLSRId
   ::= { mplsTunnelTable 1 }
MplsTunnelEntry ::= SEQUENCE {
      mplsTunnelIndex
                                   MplsTunnelIndex,
     mplsTunnelInstance
                                   MplsTunnelInstanceIndex,
                                   MplsExtendedTunnelId,
      mplsTunnelIngressLSRId
      mplsTunnelEgressLSRId
                                   MplsExtendedTunnelId,
      mplsTunnelName
                                   SnmpAdminString,
      mplsTunnelDescr
                                   SnmpAdminString,
     mplsTunnelIsIf
                                   TruthValue,
      mplsTunnelIfIndex
                                   InterfaceIndexOrZero,
      mplsTunnelOwner
                                   MplsOwner,
      mplsTunnelRole
                                   INTEGER,
      mplsTunnelXCPointer
                                   RowPointer,
      mplsTunnelSignallingProto INTEGER,
      mplsTunnelSetupPrio
                                  Integer32,
      mplsTunnelHoldingPrio
                                  Integer32,
      mplsTunnelSessionAttributes BITS,
      mplsTunnelLocalProtectInUse TruthValue,
      mplsTunnelResourcePointer
                                   RowPointer,
      mplsTunnelPrimaryInstance
                                   MplsTunnelInstanceIndex,
      mplsTunnelInstancePriority
                                   Unsigned32,
      mplsTunnelHopTableIndex
                                   MplsPathIndexOrZero,
      mplsTunnelPathInUse
                                   MplsPathIndexOrZero,
      mplsTunnelARHopTableIndex
                                   MplsPathIndexOrZero,
      mplsTunnelCHopTableIndex
                                   MplsPathIndexOrZero,
      mplsTunnelIncludeAnyAffinity MplsTunnelAffinity,
      mplsTunnelIncludeAllAffinity MplsTunnelAffinity,
      mplsTunnelExcludeAnyAffinity MplsTunnelAffinity,
      mplsTunnelTotalUpTime
                                   TimeTicks,
      mplsTunnelInstanceUpTime
                                   TimeTicks,
      mplsTunnelPrimaryUpTime
                                   TimeTicks,
      mplsTunnelPathChanges
                                   Counter32,
      mplsTunnelLastPathChange
                                   TimeTicks,
      mplsTunnelCreationTime
                                   TimeStamp,
      mplsTunnelStateTransitions Counter32,
```

```
mplsTunnelAdminStatus
                                 INTEGER,
     mplsTunnelOperStatus
                                 INTEGER,
     mplsTunnelRowStatus
                                RowStatus,
     mplsTunnelStorageType
                                StorageType
   }
mplsTunnelIndex OBJECT-TYPE
              MplsTunnelIndex
  SYNTAX
               not-accessible
  MAX-ACCESS
  STATUS
               current
  DESCRIPTION
        "Uniquely identifies a set of tunnel instances
         between a pair of ingress and egress LSRs.
         Managers should obtain new values for row
         creation in this table by reading
         mplsTunnelIndexNext. When
         the MPLS signalling protocol is rsvp(2) this value
         SHOULD be equal to the value signaled in the
         Tunnel Id of the Session object. When the MPLS
         signalling protocol is crldp(3) this value
         SHOULD be equal to the value signaled in the
         LSP ID."
   ::= { mplsTunnelEntry 1 }
mplsTunnelInstance OBJECT-TYPE
  SYNTAX MplsTunnelInstanceIndex
              not-accessible
  MAX-ACCESS
  STATUS
               current
  DESCRIPTION
        "Uniquely identifies a particular instance of a
         tunnel between a pair of ingress and egress LSRs.
         It is useful to identify multiple instances of
         tunnels for the purposes of backup and parallel
         tunnels. When the MPLS signaling protocol is
         rsvp(2) this value SHOULD be equal to the LSP Id
         of the Sender Template object. When the signaling
         protocol is crldp(3) there is no equivalent
         signaling object."
   ::= { mplsTunnelEntry 2 }
mplsTunnelIngressLSRId OBJECT-TYPE
  SYNTAX MplsExtendedTunnelId
               not-accessible
  MAX-ACCESS
               current
  STATUS
  DESCRIPTION
        "Identity of the ingress LSR associated with this
         tunnel instance. When the MPLS signalling protocol
         is rsvp(2) this value SHOULD be equal to the Tunnel
```

```
Sender Address in the Sender Template object and MAY
         be equal to the Extended Tunnel Id field in the
         SESSION object. When the MPLS signalling protocol is
         crldp(3) this value SHOULD be equal to the Ingress
         LSR Router ID field in the LSPID TLV object."
  REFERENCE
        "1. RSVP-TE: Extensions to RSVP for LSP Tunnels,
         Awduche et al, RFC 3209, December 2001
        2. Constraint-Based LSP Setup using LDP, Jamoussi
         (Editor), RFC 3212, January 2002"
   ::= { mplsTunnelEntry 3 }
mplsTunnelEgressLSRId OBJECT-TYPE
  SYNTAX MplsExtendedTunnelId
  MAX-ACCESS not-accessible
                current
  STATUS
  DESCRIPTION
        "Identity of the egress LSR associated with this
         tunnel instance."
   ::= { mplsTunnelEntry 4 }
mplsTunnelName OBJECT-TYPE
  SYNTAX
              SnmpAdminString
  MAX-ACCESS
               read-create
  STATUS
                current
  DESCRIPTION
        "The canonical name assigned to the tunnel. This name
         can be used to refer to the tunnel on the LSR's
         console port. If mplsTunnelIsIf is set to true
         then the ifName of the interface corresponding to
         this tunnel should have a value equal to
         mplsTunnelName. Also see the description of ifName
         in RFC 2863."
  REFERENCE
        "RFC 2863 - The Interfaces Group MIB, McCloghrie, K.,
         and F. Kastenholtz, June 2000"
  DEFVAL {""}
   ::= { mplsTunnelEntry 5 }
mplsTunnelDescr OBJECT-TYPE
  SYNTAX SnmpAdminString
  MAX-ACCESS
                read-create
  STATUS
                current
  DESCRIPTION
        "A textual string containing information about the
         tunnel. If there is no description this object
         contains a zero length string. This object is may
         not be signaled by MPLS signaling protocols,
```

```
consequentally the value of this object at transit
         and egress LSRs MAY be automatically generated or
         absent."
  DEFVAL {""}
   ::= { mplsTunnelEntry 6 }
mplsTunnelIsIf OBJECT-TYPE
              TruthValue
  SYNTAX
               read-create
  MAX-ACCESS
  STATUS
               current
  DESCRIPTION
        "Denotes whether or not this tunnel corresponds to an
         interface represented in the interfaces group
         table. Note that if this variable is set to true
         then the ifName of the interface corresponding to
         this tunnel should have a value equal to
         mplsTunnelName. Also see the description of ifName
         in RFC 2863. This object is meaningful only at the
         ingress and egress LSRs."
  REFERENCE
        "RFC 2863 - The Interfaces Group MIB, McCloghrie, K.,
         and F. Kastenholtz, June 2000"
  DEFVAL { false }
   ::= { mplsTunnelEntry 7 }
mplsTunnelIfIndex OBJECT-TYPE
  SYNTAX InterfaceIndexOrZero
  MAX-ACCESS
               read-only
  STATUS
               current
  DESCRIPTION
        "If mplsTunnelIsIf is set to true, then this value
         contains the LSR-assigned if Index which corresponds
         to an entry in the interfaces table. Otherwise
         this variable should contain the value of zero
         indicating that a valid if Index was not assigned to
         this tunnel interface."
  REFERENCE
        "RFC 2863 - The Interfaces Group MIB, McCloghrie, K.,
         and F. Kastenholtz, June 2000"
  DEFVAL { 0 }
   ::= { mplsTunnelEntry 8 }
mplsTunnelOwner OBJECT-TYPE
  SYNTAX MplsOwner
  MAX-ACCESS read-only
  STATUS
               current
  DESCRIPTION
        "Denotes the entity that created and is responsible
```

```
for managing this tunnel. This column is
          automatically filled by the agent on creation of a
          row."
   ::= { mplsTunnelEntry 9 }
mplsTunnelRole OBJECT-TYPE
   SYNTAX
                INTEGER \{ \text{ head}(1), 
                           transit(2),
                           tail(3),
                           headTail(4) }
   MAX-ACCESS
                read-create
   STATUS
                 current
   DESCRIPTION
        "This value signifies the role that this tunnel
          entry/instance represents. This value MUST be set
          to head(1) at the originating point of the tunnel.
          This value MUST be set to transit(2) at transit
          points along the tunnel, if transit points are
          supported. This value MUST be set to tail(3) at the
          terminating point of the tunnel if tunnel tails are
          supported.
         The value headTail(4) is provided for tunnels that
          begin and end on the same LSR."
   DEFVAL { head }
   ::= { mplsTunnelEntry 10 }
mplsTunnelXCPointer OBJECT-TYPE
   SYNTAX RowPointer
   MAX-ACCESS read-create
   STATUS
                current
   DESCRIPTION
        "This variable points to a row in the mplsXCTable.
          This table identifies the segments that compose
          this tunnel, their characteristics, and
          relationships to each other. A value of zeroDotZero
          indicates that no LSP has been associated with this
          tunnel yet."
   REFERENCE
        "Srinivasan, C., Viswanathan, A., and T. Nadeau,
          Multiprotocol Label Switching (MPLS) Label Switching
          Router (LSR) Management Information Base (MIB), RFC 3813,
          June 2004"
                { zeroDotZero }
   ::= { mplsTunnelEntry 11 }
mplsTunnelSignallingProto OBJECT-TYPE
   SYNTAX INTEGER {
```

```
none(1),
                    rsvp(2),
                    crldp(3),
                    other(4)
                    }
  MAX-ACCESS
               read-create
   STATUS
                current
   DESCRIPTION
        "The signalling protocol, if any, used to setup this
         tunnel."
  DEFVAL
          { none }
   ::= { mplsTunnelEntry 12 }
mplsTunnelSetupPrio OBJECT-TYPE
  SYNTAX Integer32 (0..7)
  MAX-ACCESS
               read-create
   STATUS
                current
  DESCRIPTION
       "Indicates the setup priority of this tunnel."
   REFERENCE
        "1. RSVP-TE: Extensions to RSVP for LSP Tunnels,
         Awduche et al, RFC 3209, December 2001
        2. Constraint-Based LSP Setup using LDP, Jamoussi
         (Editor), RFC 3212, January 2002"
   DEFVAL { 0 }
   ::= { mplsTunnelEntry 13 }
mplsTunnelHoldingPrio OBJECT-TYPE
  SYNTAX Integer32 (0..7)
  MAX-ACCESS read-create
  STATUS
                current
  DESCRIPTION
       "Indicates the holding priority for this tunnel."
  REFERENCE
        "1. RSVP-TE: Extensions to RSVP for LSP Tunnels,
         Awduche et al, RFC 3209, December 2001
        2. Constraint-Based LSP Setup using LDP, Jamoussi
         (Editor), RFC 3212, January 2002"
  DEFVAL { 0 }
   ::= { mplsTunnelEntry 14 }
mplsTunnelSessionAttributes OBJECT-TYPE
              BITS {
   SYNTAX
                 fastReroute (0),
                 mergingPermitted (1),
                 isPersistent (2),
                 isPinned (3),
```

```
recordRoute(4)
  MAX-ACCESS
                read-create
   STATUS
                current
  DESCRIPTION
        "This bit mask indicates optional session values for
          this tunnel. The following describes these bit
          fields:
        fastRerouteThis flag indicates that the any tunnel
         hop may choose to reroute this tunnel without
          tearing it down. This flag permits transit routers
          to use a local repair mechanism which may result in
          violation of the explicit routing of this tunnel.
          When a fault is detected on an adjacent downstream
          link or node, a transit router can re-route traffic
          for fast service restoration.
        mergingPermitted This flag permits transit routers
          to merge this session with other RSVP sessions for
          the purpose of reducing resource overhead on
          downstream transit routers, thereby providing
          better network scaling.
        isPersistent Indicates whether this tunnel should
         be restored automatically after a failure occurs.
        isPinned
                  This flag indicates whether the loose-
          routed hops of this tunnel are to be pinned.
        recordRouteThis flag indicates whether or not the
          signalling protocol should remember the tunnel path
          after it has been signaled."
   REFERENCE
        "1. RSVP-TE: Extensions to RSVP for LSP Tunnels,
         Awduche et al, RFC 3209, December 2001."
   ::= { mplsTunnelEntry 15 }
mplsTunnelLocalProtectInUse OBJECT-TYPE
   SYNTAX TruthValue
  MAX-ACCESS
                read-create
   STATUS
                current
   DESCRIPTION
        "Indicates that the local repair mechanism is in use
          to maintain this tunnel (usually in the face of an
          outage of the link it was previously routed over)."
  DEFVAL { false }
   ::= { mplsTunnelEntry 16 }
```

```
mplsTunnelResourcePointer OBJECT-TYPE
   SYNTAX RowPointer
  MAX-ACCESS read-create
   STATUS
                current
  DESCRIPTION
        "This variable represents a pointer to the traffic
         parameter specification for this tunnel. This
         value may point at an entry in the
         mplsTunnelResourceEntry to indicate which
         mplsTunnelResourceEntry is to be assigned to this
         LSP instance. This value may optionally point at
         an externally defined traffic parameter
         specification table. A value of zeroDotZero
         indicates best-effort treatment. By having the
         same value of this object, two or more LSPs can
         indicate resource sharing."
  DEFVAL
           { zeroDotZero }
   ::= { mplsTunnelEntry 17 }
mplsTunnelPrimaryInstance OBJECT-TYPE
               MplsTunnelInstanceIndex
  MAX-ACCESS
               read-only
  STATUS
                current
  DESCRIPTION
        "Specifies the instance index of the primary instance
         of this tunnel. More details of the definition of
         tunnel instances and the primary tunnel instance
         can be found in the description of the TEXTUAL-CONVENTION
         MplsTunnelInstanceIndex."
  DEFVAL { 0 }
   ::= { mplsTunnelEntry 18 }
mplsTunnelInstancePriority OBJECT-TYPE
   SYNTAX Unsigned32
  MAX-ACCESS read-create
   STATUS
                current
  DESCRIPTION
        "This value indicates which priority, in descending
         order, with 0 indicating the lowest priority,
         within a group of tunnel instances. A group of
          tunnel instances is defined as a set of LSPs with
          the same mplsTunnelIndex in this table, but with a
         different mplsTunnelInstance. Tunnel instance
         priorities are used to denote the priority at which
         a particular tunnel instance will supercede
         another. Instances of tunnels containing the same
         mplsTunnelInstancePriority will be used for load
         sharing."
```

```
DEFVAL
               { 0 }
   ::= { mplsTunnelEntry 19 }
mplsTunnelHopTableIndex OBJECT-TYPE
  SYNTAX MplsPathIndexOrZero
  MAX-ACCESS
               read-create
  STATUS
                current
  DESCRIPTION
        "Index into the mplsTunnelHopTable entry that
         specifies the explicit route hops for this tunnel.
         This object is meaningful only at the head-end of
         the tunnel."
  DEFVAL { 0 }
   ::= { mplsTunnelEntry 20 }
mplsTunnelPathInUse OBJECT-TYPE
           MplsPathIndexOrZero
  SYNTAX
  MAX-ACCESS read-create
  STATUS
               current
  DESCRIPTION
        "This value denotes the configured path that was
         chosen for this tunnel. This value reflects the
         secondary index into mplsTunnelHopTable. This path
         may not exactly match the one in
         mplsTunnelARHopTable due to the fact that some CSPF
         modification may have taken place. See
         mplsTunnelARHopTable for the actual path being
         taken by the tunnel. A value of zero denotes that
         no path is currently in use or available."
  DEFVAL { 0 }
   ::= { mplsTunnelEntry 21 }
mplsTunnelARHopTableIndex OBJECT-TYPE
  SYNTAX MplsPathIndexOrZero
  MAX-ACCESS read-only
  STATUS
                current
  DESCRIPTION
        "Index into the mplsTunnelARHopTable entry that
         specifies the actual hops traversed by the tunnel.
         This is automatically updated by the agent when the
         actual hops becomes available."
  DEFVAL { 0 }
   ::= { mplsTunnelEntry 22 }
mplsTunnelCHopTableIndex OBJECT-TYPE
  SYNTAX MplsPathIndexOrZero
  MAX-ACCESS read-only
  STATUS
               current
```

```
DESCRIPTION
       "Index into the mplsTunnelCHopTable entry that
         specifies the computed hops traversed by the
         tunnel. This is automatically updated by the agent
         when computed hops become available or when
         computed hops get modified."
  DEFVAL { 0 }
   ::= { mplsTunnelEntry 23 }
mplsTunnelIncludeAnyAffinity OBJECT-TYPE
  SYNTAX MplsTunnelAffinity
  MAX-ACCESS read-create
  STATUS
               current
  DESCRIPTION
        "A link satisfies the include-any constraint if and
         only if the constraint is zero, or the link and the
         constraint have a resource class in common."
  REFERENCE
       "1. RSVP-TE: Extensions to RSVP for LSP Tunnels,
         Awduche et al, RFC 3209, December 2001."
   ::= { mplsTunnelEntry 24 }
mplsTunnelIncludeAllAffinity OBJECT-TYPE
  SYNTAX MplsTunnelAffinity
              read-create
  MAX-ACCESS
               current
  STATUS
  DESCRIPTION
        "A link satisfies the include-all constraint if and
         only if the link contains all of the administrative
         groups specified in the constraint."
  REFERENCE
       "1. RSVP-TE: Extensions to RSVP for LSP Tunnels,
         Awduche et al, RFC 3209, December 2001."
   ::= { mplsTunnelEntry 25 }
mplsTunnelExcludeAnyAffinity OBJECT-TYPE
  SYNTAX MplsTunnelAffinity
  MAX-ACCESS read-create
  STATUS
               current
  DESCRIPTION
        "A link satisfies the exclude-any constraint if and
         only if the link contains none of the
         administrative groups specified in the constraint."
        "1. RSVP-TE: Extensions to RSVP for LSP Tunnels,
         Awduche et al, RFC 3209, December 2001."
  DEFVAL { 0 }
   ::= { mplsTunnelEntry 26 }
```

```
mplsTunnelTotalUpTime OBJECT-TYPE
   SYNTAX TimeTicks
  MAX-ACCESS read-only
  STATUS
               current
  DESCRIPTION
        "This value represents the aggregate up time for all
          instances of this tunnel, if available. If this
         value is unavailable, it MUST return a value of 0."
      ::= { mplsTunnelEntry 27 }
mplsTunnelInstanceUpTime OBJECT-TYPE
              TimeTicks
  MAX-ACCESS read-only STATUS current
  DESCRIPTION
        "This value identifies the total time that this
         tunnel instance's operStatus has been Up(1)."
      ::= { mplsTunnelEntry 28 }
mplsTunnelPrimaryUpTime OBJECT-TYPE
   SYNTAX
               TimeTicks
  MAX-ACCESS
               read-only
  STATUS
                current
  DESCRIPTION
        "Specifies the total time the primary instance of
         this tunnel has been active. The primary instance
         of this tunnel is defined in
         mplsTunnelPrimaryInstance."
   ::= { mplsTunnelEntry 29 }
mplsTunnelPathChanges OBJECT-TYPE
  SYNTAX
               Counter32
  MAX-ACCESS read-only
   STATUS
                current
  DESCRIPTION
       "Specifies the number of times the actual path for
        this tunnel instance has changed."
   ::= { mplsTunnelEntry 30 }
mplsTunnelLastPathChange OBJECT-TYPE
  SYNTAX TimeTicks
  MAX-ACCESS
                read-only
                current
   STATUS
   DESCRIPTION
        "Specifies the time since the last change to the
        actual path for this tunnel instance."
   ::= { mplsTunnelEntry 31 }
```

```
mplsTunnelCreationTime OBJECT-TYPE
   SYNTAX TimeStamp
  MAX-ACCESS read-only
  STATUS
                current
  DESCRIPTION
        "Specifies the value of SysUpTime when the first
          instance of this tunnel came into existence.
          That is, when the value of mplsTunnelOperStatus
          was first set to up(1)."
   ::= { mplsTunnelEntry 32 }
mplsTunnelStateTransitions OBJECT-TYPE
  SYNTAX Counter32
  MAX-ACCESS read-only
  STATUS
                current
  DESCRIPTION
        "Specifies the number of times the state
          (mplsTunnelOperStatus) of this tunnel instance has
          changed."
   ::= { mplsTunnelEntry 33 }
mplsTunnelAdminStatus OBJECT-TYPE
   SYNTAX
             INTEGER {
                  -- ready to pass packets
                  up(1),
                  down(2),
                  -- in some test mode
                  testing(3)
  MAX-ACCESS
                read-create
   STATUS
                current
  DESCRIPTION
        "Indicates the desired operational status of this
         tunnel."
   ::= { mplsTunnelEntry 34 }
mplsTunnelOperStatus OBJECT-TYPE
   SYNTAX
             INTEGER {
              -- ready to pass packets
              up(1),
              down(2),
              -- in some test mode
              testing(3),
              -- status cannot be determined
              unknown(4),
              dormant(5),
              -- some component is missing
              notPresent(6),
```

```
-- down due to the state of
              -- lower layer interfaces
              lowerLayerDown(7)
               read-only
  MAX-ACCESS
  STATIIS
                current
  DESCRIPTION
        "Indicates the actual operational status of this
         tunnel, which is typically but not limited to, a
         function of the state of individual segments of
         this tunnel."
   ::= { mplsTunnelEntry 35 }
mplsTunnelRowStatus OBJECT-TYPE
  SYNTAX RowStatus
  MAX-ACCESS read-create
  STATUS
                current
  DESCRIPTION
       "This variable is used to create, modify, and/or
         delete a row in this table. When a row in this
         table is in active(1) state, no objects in that row
         can be modified by the agent except
         mplsTunnelAdminStatus, mplsTunnelRowStatus and
         mplsTunnelStorageType."
   ::= { mplsTunnelEntry 36 }
mplsTunnelStorageType OBJECT-TYPE
  SYNTAX StorageType
  MAX-ACCESS read-create
  STATUS
               current
  DESCRIPTION "The storage type for this tunnel entry.
                Conceptual rows having the value 'permanent'
                need not allow write-access to any columnar
                objects in the row."
  DEFVAL { volatile }
   ::= { mplsTunnelEntry 37 }
-- End of mplsTunnelTable
mplsTunnelHopListIndexNext OBJECT-TYPE
  SYNTAX MplsPathIndexOrZero
  MAX-ACCESS
               read-only
  STATUS
                current
  DESCRIPTION
        "This object contains an appropriate value to be used
         for mplsTunnelHopListIndex when creating entries in
         the mplsTunnelHopTable. If the number of
         unassigned entries is exhausted, a retrieval
```

operation will return a value of 0. This object may also return a value of 0 when the LSR is unable to accept conceptual row creation, for example, if the mplsTunnelHopTable is implemented as read-only. To obtain the value of mplsTunnelHopListIndex for a new entry in the mplsTunnelHopTable, the manager issues a management protocol retrieval operation to obtain the current value of mplsTunnelHopIndex.

When the SET is performed to create a row in the mplsTunnelHopTable, the Command Responder (agent) must determine whether the value is indeed still unused; Two Network Management Applications may attempt to create a row (configuration entry) simultaneously and use the same value. If it is currently unused, the SET succeeds and the Command Responder (agent) changes the value of this object, according to an implementation-specific algorithm. If the value is in use, however, the SET fails. The Network Management Application must then re-read this variable to obtain a new usable value."

::= { mplsTeObjects 3 }

mplsTunnelHopTable OBJECT-TYPE

SYNTAX SEQUENCE OF MplsTunnelHopEntry

MAX-ACCESS not-accessible

STATUS current

DESCRIPTION

"The mplsTunnelHopTable is used to indicate the hops, strict or loose, for an instance of an MPLS tunnel defined in mplsTunnelTable, when it is established via signalling, for the outgoing direction of the tunnel. Thus at a transit LSR, this table contains the desired path of the tunnel from this LSR onwards. Each row in this table is indexed by mplsTunnelHopListIndex which corresponds to a group of hop lists or path options. Each row also has a secondary index mplsTunnelHopIndex, which indicates a group of hops (also known as a path option). Finally, the third index, mplsTunnelHopIndex indicates the specific hop information for a path option. In case we want to specify a particular interface on the originating LSR of an outgoing tunnel by which we want packets to exit the LSR, we specify this as the first hop for this tunnel in mplsTunnelHopTable."

::= { mplsTeObjects 4 }

```
mplsTunnelHopEntry OBJECT-TYPE
  SYNTAX MplsTunnelHopEntry
  MAX-ACCESS not-accessible
  STATUS
               current
  DESCRIPTION
       "An entry in this table represents a tunnel hop. An
         entry is created by a network administrator for
         signaled ERLSP set up by an MPLS signalling
         protocol."
   INDEX {
     mplsTunnelHopListIndex,
     mplsTunnelHopPathOptionIndex,
     mplsTunnelHopIndex
   }
   ::= { mplsTunnelHopTable 1 }
MplsTunnelHopEntry ::= SEQUENCE {
     mplsTunnelHopListIndex
                                   MplsPathIndex,
     mplsTunnelHopIndex
                                   MplsPathIndex,
     mplsTunnelHopAddrType
                                   TeHopAddressType,
                                   TeHopAddress,
     mplsTunnelHopIpAddr
                                  InetAddressPrefixLength,
     mplsTunnelHopIpPrefixLen
     mplsTunnelHopAsNumber
                                   TeHopAddressAS,
     mplsTunnelHopAddrUnnum
                                   TeHopAddressUnnum,
     mplsTunnelHopLspId
                                   MplsLSPID,
                                   INTEGER,
     mplsTunnelHopType
     mplsTunnelHopInclude
                                   TruthValue,
     mplsTunnelHopPathOptionName
                                  {\tt SnmpAdminString},
     mplsTunnelHopEntryPathComp
                                  INTEGER,
     mplsTunnelHopRowStatus
                                   RowStatus,
     mplsTunnelHopStorageType
                                   StorageType
   }
mplsTunnelHopListIndex OBJECT-TYPE
  SYNTAX MplsPathIndex
  MAX-ACCESS not-accessible
  STATUS
               current
  DESCRIPTION
       "Primary index into this table identifying a
         particular explicit route object."
   ::= { mplsTunnelHopEntry 1 }
mplsTunnelHopPathOptionIndex OBJECT-TYPE
  SYNTAX
              MplsPathIndex
  MAX-ACCESS not-accessible
  STATUS
                current
  DESCRIPTION
```

```
"Secondary index into this table identifying a
         particular group of hops representing a particular
         configured path. This is otherwise known as a path
         option."
   ::= { mplsTunnelHopEntry 2 }
mplsTunnelHopIndex OBJECT-TYPE
              MplsPathIndex
  SYNTAX
              not-accessible
  MAX-ACCESS
  STATUS
               current
  DESCRIPTION
        "Tertiary index into this table identifying a
         particular hop."
   ::= { mplsTunnelHopEntry 3 }
mplsTunnelHopAddrType OBJECT-TYPE
   SYNTAX
            TeHopAddressType
   MAX-ACCESS read-create
   STATUS
                current
   DESCRIPTION "The Hop Address Type of this tunnel hop.
                 The value of this object cannot be changed
                 if the value of the corresponding
                 mplsTunnelHopRowStatus object is 'active'.
                 Note that lspid(5) is a valid option only
                 for tunnels signaled via CRLDP.
                 { ipv4 }
   ::= { mplsTunnelHopEntry 4 }
mplsTunnelHopIpAddr OBJECT-TYPE
   SYNTAX TeHopAddress
   MAX-ACCESS read-create
   STATUS
                 current
   DESCRIPTION "The Tunnel Hop Address for this tunnel hop.
                 The type of this address is determined by the
                 value of the corresponding mplsTunnelHopAddrType.
                 The value of this object cannot be changed
                 if the value of the corresponding
                 mplsTunnelHopRowStatus object is 'active'.
                { '00000000'h } -- IPv4 address 0.0.0.0
   DEFVAL
    ::= { mplsTunnelHopEntry 5 }
mplsTunnelHopIpPrefixLen OBJECT-TYPE
```

InetAddressPrefixLength

```
MAX-ACCESS read-create
    STATUS
                current
   DESCRIPTION "If mplsTunnelHopAddrType is set to ipv4(1) or
                 ipv6(2), then this value will contain an
                 appropriate prefix length for the IP address in
                 object mplsTunnelHopIpAddr. Otherwise this value
                 is irrelevant and should be ignored.
    DEFVAL
                   { 32 }
    ::= { mplsTunnelHopEntry 6 }
mplsTunnelHopAsNumber OBJECT-TYPE
   SYNTAX
              TeHopAddressAS
  MAX-ACCESS
               read-create
   STATUS
                current
   DESCRIPTION
        "If mplsTunnelHopAddrType is set to asnumber(3), then
          this value will contain the AS number of this hop.
         Otherwise the agent should set this object to zero-
          length string and the manager should ignore this."
   ::= { mplsTunnelHopEntry 7 }
mplsTunnelHopAddrUnnum OBJECT-TYPE
                TeHopAddressUnnum
   SYNTAX
  MAX-ACCESS
                read-create
   STATUS
                current
  DESCRIPTION
        "If mplsTunnelHopAddrType is set to unnum(4), then
          this value will contain the interface identifier of
          the unnumbered interface for this hop. This object
         should be used in conjunction with
         mplsTunnelHopIpAddress which would contain the LSR
         Router ID in this case. Otherwise the agent should
         set this object to zero-length string and the
         manager should ignore this."
   ::= { mplsTunnelHopEntry 8 }
mplsTunnelHopLspId OBJECT-TYPE
   SYNTAX
              MplsLSPID
  MAX-ACCESS
                read-create
   STATUS
                current
   DESCRIPTION
        "If mplsTunnelHopAddrType is set to lspid(5), then
          this value will contain the LSPID of a tunnel of
          this hop. The present tunnel being configured is
          tunneled through this hop (using label stacking).
         This object is otherwise insignificant and should
```

SYNTAX

```
contain a value of 0 to indicate this fact."
   ::= { mplsTunnelHopEntry 9 }
mplsTunnelHopType OBJECT-TYPE
   SYNTAX
                 INTEGER {
                      strict(1),
                      loose(2)
   MAX-ACCESS
                read-create
   STATUS
                current
   DESCRIPTION
        "Denotes whether this tunnel hop is routed in a
          strict or loose fashion. The value of this object
         has no meaning if the mplsTunnelHopInclude object
          is set to 'false'."
   ::= { mplsTunnelHopEntry 10 }
mplsTunnelHopInclude OBJECT-TYPE
   SYNTAX
              TruthValue
   MAX-ACCESS read-create
   STATUS
                current
   DESCRIPTION
        "If this value is set to true, then this indicates
          that this hop must be included in the tunnel's
          path. If this value is set to 'false', then this hop
          must be avoided when calculating the path for this
          tunnel. The default value of this object is 'true',
          so that by default all indicated hops are included
          in the CSPF path computation. If this object is set
          to 'false' the value of mplsTunnelHopType should be
          ignored."
   DEFVAL { true }
   ::= { mplsTunnelHopEntry 11 }
mplsTunnelHopPathOptionName OBJECT-TYPE
   SYNTAX SnmpAdminString
   MAX-ACCESS
               read-create
   STATUS
                current
   DESCRIPTION
        "The description of this series of hops as they
          relate to the specified path option. The
          value of this object SHOULD be the same for
          each hop in the series that comprises a
          path option."
   ::= { mplsTunnelHopEntry 12 }
mplsTunnelHopEntryPathComp OBJECT-TYPE
   SYNTAX
                INTEGER {
```

```
explicit(2) -- strict hop
                 }
  MAX-ACCESS
               read-create
   STATUS
                current
   DESCRIPTION
        "If this value is set to dynamic, then the user
         should only specify the source and destination of
         the path and expect that the CSPF will calculate
         the remainder of the path. If this value is set to
         explicit, the user should specify the entire path
         for the tunnel to take. This path may contain
         strict or loose hops. Each hop along a specific
         path SHOULD have this object set to the same value"
   ::= { mplsTunnelHopEntry 13 }
mplsTunnelHopRowStatus OBJECT-TYPE
  SYNTAX RowStatus
  MAX-ACCESS read-create
   STATUS
               current
   DESCRIPTION
        "This variable is used to create, modify, and/or
         delete a row in this table. When a row in this
         table is in active(1) state, no objects in that row
         can be modified by the agent except
         mplsTunnelHopRowStatus and
         mplsTunnelHopStorageType."
   ::= { mplsTunnelHopEntry 14 }
mplsTunnelHopStorageType OBJECT-TYPE
  SYNTAX StorageType
  MAX-ACCESS
               read-create
   STATUS
                current
   DESCRIPTION
        "The storage type for this Hop entry. Conceptual
        rows having the value 'permanent' need not
        allow write-access to any columnar objects
        in the row."
  DEFVAL { volatile }
   ::= { mplsTunnelHopEntry 15 }
-- End of mplsTunnelHopTable
-- Begin of mplsTunnelResourceTable
mplsTunnelResourceIndexNext OBJECT-TYPE
           Unsigned32 (0.. 2147483647)
  MAX-ACCESS read-only
```

STATUS current DESCRIPTION

"This object contains the next appropriate value to be used for mplsTunnelResourceIndex when creating entries in the mplsTunnelResourceTable. If the number of unassigned entries is exhausted, a retrieval operation will return a value of 0. This object may also return a value of 0 when the LSR is unable to accept conceptual row creation, for example, if the mplsTunnelTable is implemented as read-only. To obtain the mplsTunnelResourceIndex value for a new entry, the manager must first issue a management protocol retrieval operation to obtain the current value of this object.

When the SET is performed to create a row in the mplsTunnelResourceTable, the Command Responder (agent) must determine whether the value is indeed still unused; Two Network Management Applications may attempt to create a row (configuration entry) simultaneously and use the same value. If it is currently unused, the SET succeeds and the Command Responder (agent) changes the value of this object, according to an implementation-specific algorithm. If the value is in use, however, the SET fails. The Network Management Application must then re-read this variable to obtain a new usable value."

::= { mplsTeObjects 5 }

mplsTunnelResourceTable OBJECT-TYPE

SYNTAX SEQUENCE OF MplsTunnelResourceEntry

MAX-ACCESS not-accessible

STATUS current

DESCRIPTION

"The mplsTunnelResourceTable allows a manager to specify which resources are desired for an MPLS tunnel. This table also allows several tunnels to point to a single entry in this table, implying that these tunnels should share resources."

::= { mplsTeObjects 6 }

mplsTunnelResourceEntry OBJECT-TYPE

SYNTAX MplsTunnelResourceEntry

MAX-ACCESS not-accessible

STATUS current

DESCRIPTION

"An entry in this table represents a set of resources for an MPLS tunnel. An entry can be created by a

```
network administrator or by an SNMP agent as
         instructed by any MPLS signalling protocol.
        An entry in this table referenced by a tunnel instance
         with zero mplsTunnelInstance value indicates a
         configured set of resource parameter. An entry
         referenced by a tunnel instance with a non-zero
         mplsTunnelInstance reflects the in-use resource
         parameters for the tunnel instance which may have
         been negotiated or modified by the MPLS signaling
         protocols."
                { mplsTunnelResourceIndex }
   INDEX
   ::= { mplsTunnelResourceTable 1 }
MplsTunnelResourceEntry ::= SEQUENCE {
     mplsTunnelResourceIndex
                                            Unsigned32,
     mplsTunnelResourceMaxRate
                                           MplsBitRate,
     mplsTunnelResourceMeanRate
                                           MplsBitRate,
     mplsTunnelResourceMaxBurstSize
                                          MplsBurstSize,
     mplsTunnelResourceMeanBurstSize
                                          MplsBurstSize,
     mplsTunnelResourceExBurstSize
                                          MplsBurstSize,
     mplsTunnelResourceFrequency
                                           INTEGER,
     mplsTunnelResourceWeight
                                          Unsigned32,
     mplsTunnelResourceRowStatus
                                           RowStatus,
     mplsTunnelResourceStorageType
                                           StorageType
mplsTunnelResourceIndex OBJECT-TYPE
  SYNTAX Unsigned32 (1..2147483647)
  MAX-ACCESS not-accessible
  STATUS
                current
  DESCRIPTION
        "Uniquely identifies this row."
   ::= { mplsTunnelResourceEntry 1 }
mplsTunnelResourceMaxRate OBJECT-TYPE
  SYNTAX MplsBitRate
  UNITS
                "kilobits per second"
  MAX-ACCESS read-create
  STATUS
                current
  DESCRIPTION
        "The maximum rate in bits/second. Note that setting
         mplsTunnelResourceMaxRate,
         mplsTunnelResourceMeanRate, and
         mplsTunnelResourceMaxBurstSize to 0 indicates best-
         effort treatment."
   ::= { mplsTunnelResourceEntry 2 }
mplsTunnelResourceMeanRate OBJECT-TYPE
```

```
SYNTAX MplsBitRate
               "kilobits per second"
  UNITS
  MAX-ACCESS read-create
  STATUS
               current
  DESCRIPTION
       "This object is copied into an instance of
         mplsTrafficParamMeanRate in the
         mplsTrafficParamTable. The OID of this table entry
         is then copied into the corresponding
         mplsInSegmentTrafficParamPtr."
   ::= { mplsTunnelResourceEntry 3 }
mplsTunnelResourceMaxBurstSize OBJECT-TYPE
  SYNTAX MplsBurstSize
  UNITS
               "bytes"
  MAX-ACCESS read-create
  STATUS
                current
  DESCRIPTION
       "The maximum burst size in bytes."
   ::= { mplsTunnelResourceEntry 4 }
mplsTunnelResourceMeanBurstSize OBJECT-TYPE
  SYNTAX MplsBurstSize
              "bytes"
  UNITS
  MAX-ACCESS read-create
  STATUS current
  DESCRIPTION
       "The mean burst size in bytes. The implementations
         which do not implement this variable must return
         a noSuchObject exception for this object and must
         not allow a user to set this object."
   ::= { mplsTunnelResourceEntry 5 }
mplsTunnelResourceExBurstSize OBJECT-TYPE
  SYNTAX MplsBurstSize
  UNITS
              "bytes"
  MAX-ACCESS read-create
  STATUS
              current
  DESCRIPTION
       "The Excess burst size in bytes. The implementations
         which do not implement this variable must return
         noSuchObject exception for this object and must
         not allow a user to set this value."
  REFERENCE
       "CR-LDP Specification, Section 4.3."
   ::= { mplsTunnelResourceEntry 6 }
mplsTunnelResourceFrequency OBJECT-TYPE
```

```
SYNTAX
               INTEGER { unspecified(1),
                         frequent(2),
                         veryFrequent(3)
  MAX-ACCESS
              read-create
  STATUS
               current
  DESCRIPTION
        "The granularity of the availability of committed
         rate. The implementations which do not implement
         this variable must return unspecified(1) for this
         value and must not allow a user to set this value."
        "CR-LDP Specification, Section 4.3."
   ::= { mplsTunnelResourceEntry 7 }
mplsTunnelResourceWeight
                          OBJECT-TYPE
  SYNTAX Unsigned32(0..255)
  MAX-ACCESS read-create
  STATUS
               current
  DESCRIPTION
        "The relative weight for using excess bandwidth above
         its committed rate. The value of 0 means that
         weight is not applicable for the CR-LSP."
  REFERENCE
        "CR-LDP Specification, Section 4.3."
   ::= { mplsTunnelResourceEntry 8 }
mplsTunnelResourceRowStatus OBJECT-TYPE
  SYNTAX RowStatus
  MAX-ACCESS read-create
  STATUS
                current
  DESCRIPTION
        "This variable is used to create, modify, and/or
         delete a row in this table. When a row in this
         table is in active(1) state, no objects in that row
         can be modified by the agent except
         mplsTunnelResourceRowStatus and
         mplsTunnelResourceStorageType."
   ::= { mplsTunnelResourceEntry 9 }
mplsTunnelResourceStorageType OBJECT-TYPE
  SYNTAX StorageType
               read-create
  MAX-ACCESS
                current
  STATUS
  DESCRIPTION
        "The storage type for this Hop entry. Conceptual
        rows having the value 'permanent' need not
        allow write-access to any columnar objects
```

"The mplsTunnelARHopTable is used to indicate the hops for an MPLS tunnel defined in mplsTunnelTable, as reported by the MPLS signalling protocol. Thus at a transit LSR, this table (if the table is supported and if the signaling protocol is recording actual route information) contains the actual route of the whole tunnel. If the signaling protocol is not recording the actual route, this table MAY report the information from the mplsTunnelHopTable or the mplsTunnelCHopTable.

Each row in this table is indexed by mplsTunnelARHopListIndex. Each row also has a secondary index mplsTunnelARHopIndex, corresponding to the next hop that this row corresponds to.

Please note that since the information necessary to build entries within this table is not provided by some MPLS signalling protocols, implementation of this table is optional. Furthermore, since the information in this table is actually provided by the MPLS signalling protocol after the path has been set-up, the entries in this table are provided only for observation, and hence, all variables in this table are accessible exclusively as readonly.

Note also that the contents of this table may change while it is being read because of re-routing activities. A network administrator may verify that the actual route read is consistent by reference to the mplsTunnelLastPathChange object."

::= { mplsTeObjects 7 }

```
mplsTunnelARHopEntry OBJECT-TYPE
   SYNTAX MplsTunnelARHopEntry
  MAX-ACCESS not-accessible
  STATUS
               current
  DESCRIPTION
        "An entry in this table represents a tunnel hop. An
         entry is created by the agent for signaled ERLSP
         set up by an MPLS signalling protocol."
   INDEX { mplsTunnelARHopListIndex, mplsTunnelARHopIndex }
   ::= { mplsTunnelARHopTable 1 }
MplsTunnelARHopEntry ::= SEQUENCE {
     mplsTunnelARHopListIndex
                                      MplsPathIndex,
     mplsTunnelARHopIndex
                                      MplsPathIndex,
     mplsTunnelARHopAddrType
                                      TeHopAddressType,
      mplsTunnelARHopIpAddr
                                      TeHopAddress,
     mplsTunnelARHopAddrUnnum
                                      TeHopAddressUnnum,
     mplsTunnelARHopLspId
                                      MplsLSPID
mplsTunnelARHopListIndex OBJECT-TYPE
  SYNTAX MplsPathIndex
  MAX-ACCESS not-accessible
  STATUS
                current
   DESCRIPTION
        "Primary index into this table identifying a
         particular recorded hop list."
   ::= { mplsTunnelARHopEntry 1 }
mplsTunnelARHopIndex OBJECT-TYPE
  SYNTAX MplsPathIndex
  MAX-ACCESS
               not-accessible
   STATUS
                current
   DESCRIPTION
        "Secondary index into this table identifying the
         particular hop."
   ::= { mplsTunnelARHopEntry 2 }
mplsTunnelARHopAddrType OBJECT-TYPE
               TeHopAddressType
   SYNTAX
  MAX-ACCESS
               read-only
   STATUS
                current
   DESCRIPTION
        "The Hop Address Type of this tunnel hop.
        Note that lspid(5) is a valid option only
        for tunnels signaled via CRLDP."
   DEFVAL
               { ipv4 }
```

```
::= { mplsTunnelARHopEntry 3 }
mplsTunnelARHopIpAddr OBJECT-TYPE
  SYNTAX
               TeHopAddress
  MAX-ACCESS
               read-only
  STATUS
                current
  DESCRIPTION
        "The Tunnel Hop Address for this tunnel hop.
        The type of this address is determined by the
        value of the corresponding mplsTunnelARHopAddrType.
        If mplsTunnelARHopAddrType is set to unnum(4),
         then this value contains the LSR Router ID of the
         unnumbered interface. Otherwise the agent SHOULD
         set this object to the zero-length string and the
         manager should ignore this object."
   DEFVAL { '00000000'h } -- IPv4 address 0.0.0.0
   ::= { mplsTunnelARHopEntry 4 }
mplsTunnelARHopAddrUnnum OBJECT-TYPE
  SYNTAX TeHopAddressUnnum
  MAX-ACCESS
               read-only
  STATUS
                current
  DESCRIPTION
        "If mplsTunnelARHopAddrType is set to unnum(4), then
          this value will contain the interface identifier of
         the unnumbered interface for this hop. This object
         should be used in conjunction with
         mplsTunnelARHopIpAddr which would contain the LSR
         Router ID in this case. Otherwise the agent should
         set this object to zero-length string and the
         manager should ignore this."
   ::= { mplsTunnelARHopEntry 5 }
mplsTunnelARHopLspId OBJECT-TYPE
  SYNTAX MplsLSPID
  MAX-ACCESS read-only
                current
  DESCRIPTION
        "If mplsTunnelARHopAddrType is set to lspid(5), then
          this value will contain the LSP ID of this hop.
         This object is otherwise insignificant and should
         contain a value of 0 to indicate this fact."
   ::= { mplsTunnelARHopEntry 6 }
-- End of mplsTunnelARHopTable
```

```
-- Tunnel Computed Hop table.
```

```
mplsTunnelCHopTable OBJECT-TYPE
```

SYNTAX SEQUENCE OF MplsTunnelCHopEntry

MAX-ACCESS not-accessible

STATUS current

DESCRIPTION

"The mplsTunnelCHopTable is used to indicate the hops, strict or loose, for an MPLS tunnel defined in mplsTunnelTable, as computed by a constraintbased routing protocol, based on the mplsTunnelHopTable for the outgoing direction of the tunnel. Thus at a transit LSR, this table (if the table is supported) MAY contain the path computed by the CSPF engine on (or on behalf of) this LSR. Each row in this table is indexed by mplsTunnelCHopListIndex. Each row also has a secondary index mplsTunnelCHopIndex, corresponding to the next hop that this row corresponds to. In case we want to specify a particular interface on the originating LSR of an outgoing tunnel by which we want packets to exit the LSR, we specify this as the first hop for this tunnel in mplsTunnelCHopTable.

Please note that since the information necessary to build entries within this table may not be supported by some LSRs, implementation of this table is optional. Furthermore, since the information in this table describes the path computed by the CSPF engine the entries in this table are read-only."

```
::= { mplsTeObjects 8 }
```

```
mplsTunnelCHopEntry OBJECT-TYPE
```

SYNTAX MplsTunnelCHopEntry

MAX-ACCESS not-accessible

STATUS current

DESCRIPTION

"An entry in this table represents a tunnel hop. An entry in this table is created by a path computation engine using CSPF techniques applied to the information collected by routing protocols and the hops specified in the corresponding mplsTunnelHopTable."

INDEX { mplsTunnelCHopListIndex, mplsTunnelCHopIndex }
::= { mplsTunnelCHopTable 1 }

```
MplsTunnelCHopEntry ::= SEQUENCE {
      mplsTunnelCHopListIndex
                                      MplsPathIndex,
      mplsTunnelCHopIndex
                                      MplsPathIndex,
      mplsTunnelCHopAddrType
                                      TeHopAddressType,
      mplsTunnelCHopIpAddr
                                      TeHopAddress,
                                      InetAddressPrefixLength,
      mplsTunnelCHopIpPrefixLen
      mplsTunnelCHopAsNumber
                                      TeHopAddressAS,
      mplsTunnelCHopAddrUnnum
                                      TeHopAddressUnnum,
      mplsTunnelCHopLspId
                                      MplsLSPID,
      mplsTunnelCHopType
                                      INTEGER
   }
mplsTunnelCHopListIndex OBJECT-TYPE
   SYNTAX MplsPathIndex
   {\tt MAX-ACCESS} \qquad {\tt not-accessible}
   STATUS
                current
   DESCRIPTION
        "Primary index into this table identifying a
         particular computed hop list."
   ::= { mplsTunnelCHopEntry 1 }
mplsTunnelCHopIndex OBJECT-TYPE
   SYNTAX MplsPathIndex
   MAX-ACCESS
                not-accessible
   STATUS
                current
   DESCRIPTION
        "Secondary index into this table identifying the
         particular hop."
   ::= { mplsTunnelCHopEntry 2 }
mplsTunnelCHopAddrType OBJECT-TYPE
               TeHopAddressType
   SYNTAX
   MAX-ACCESS
                read-only
   STATUS
                current
   DESCRIPTION
        "The Hop Address Type of this tunnel hop.
         Note that lspid(5) is a valid option only
        for tunnels signaled via CRLDP."
                { ipv4 }
   DEFVAL
   ::= { mplsTunnelCHopEntry 3 }
mplsTunnelCHopIpAddr OBJECT-TYPE
   SYNTAX TeHopAddress
   MAX-ACCESS read-only
   STATUS
                current
   DESCRIPTION
        "The Tunnel Hop Address for this tunnel hop.
```

```
The type of this address is determined by the
         value of the corresponding mplsTunnelCHopAddrType.
        If mplsTunnelCHopAddrType is set to unnum(4), then
         this value will contain the LSR Router ID of the
         unnumbered interface. Otherwise the agent should
         set this object to the zero-length string and the
         manager SHOULD ignore this object."
                { '00000000'h } -- IPv4 address 0.0.0.0
   ::= { mplsTunnelCHopEntry 4 }
mplsTunnelCHopIpPrefixLen OBJECT-TYPE
  SYNTAX InetAddressPrefixLength
  MAX-ACCESS
               read-only
                current
  STATUS
  DESCRIPTION
        "If mplsTunnelCHopAddrType is set to ipv4(1) or
          ipv6(2), then this value will contain an
          appropriate prefix length for the IP address in
          object mplsTunnelCHopIpAddr. Otherwise this value
          is irrelevant and should be ignored.
   DEFVAL
                   { 32 }
   ::= { mplsTunnelCHopEntry 5 }
mplsTunnelCHopAsNumber OBJECT-TYPE
  SYNTAX TeHopAddressAS
  MAX-ACCESS read-only
  STATUS
                current
  DESCRIPTION
        "If mplsTunnelCHopAddrType is set to asnumber(3),
         then this value will contain the AS number of this
         hop. Otherwise the agent should set this object to
         zero-length string and the manager should ignore
         this."
   ::= { mplsTunnelCHopEntry 6 }
mplsTunnelCHopAddrUnnum OBJECT-TYPE
  SYNTAX
               TeHopAddressUnnum
  MAX-ACCESS
               read-only
  STATUS
                current
  DESCRIPTION
        "If mplsTunnelCHopAddrType is set to unnum(4), then
          this value will contain the unnumbered interface
          identifier of this hop. This object should be used
         in conjunction with mplsTunnelCHopIpAddr which
         would contain the LSR Router ID in this case.
```

```
Otherwise the agent should set this object to zero-
         length string and the manager should ignore this."
   ::= { mplsTunnelCHopEntry 7 }
mplsTunnelCHopLspId OBJECT-TYPE
  SYNTAX
               MplsLSPID
  MAX-ACCESS
               read-only
  STATUS
                current
  DESCRIPTION
        "If mplsTunnelCHopAddrType is set to lspid(5), then
         this value will contain the LSP ID of this hop.
         This object is otherwise insignificant and should
         contain a value of 0 to indicate this fact."
   ::= { mplsTunnelCHopEntry 8 }
mplsTunnelCHopType OBJECT-TYPE
  SYNTAX
               INTEGER { strict(1),
                          loose(2)
  MAX-ACCESS
               read-only
  STATUS
                current
  DESCRIPTION
        "Denotes whether this is tunnel hop is routed in a
         strict or loose fashion."
   ::= { mplsTunnelCHopEntry 9 }
-- End of mplsTunnelCHopTable
-- MPLS Tunnel Performance Table.
mplsTunnelPerfTable OBJECT-TYPE
  SYNTAX SEQUENCE OF MplsTunnelPerfEntry
  MAX-ACCESS not-accessible
  STATUS
               current
  DESCRIPTION
       "This table provides per-tunnel instance MPLS
         performance information."
   ::= { mplsTeObjects 9 }
mplsTunnelPerfEntry OBJECT-TYPE
  SYNTAX MplsTunnelPerfEntry
              not-accessible
  MAX-ACCESS
  STATUS
               current
  DESCRIPTION
        "An entry in this table is created by the LSR for
         every tunnel. Its is an extension to
         mplsTunnelEntry."
```

```
AUGMENTS { mplsTunnelEntry }
   ::= { mplsTunnelPerfTable 1 }
MplsTunnelPerfEntry ::= SEQUENCE {
     mplsTunnelPerfBytes
mplsTunnelPerfBytes
mplsTunnelPerfBytes
mplsTunnelPerfBytes
mplsTunnelPerfBytes
     mplsTunnelPerfHCBytes Counter32
mplsTunnelPerfHCBytes Counter64
   }
mplsTunnelPerfPackets OBJECT-TYPE
  SYNTAX Counter32
  MAX-ACCESS read-only
   STATUS
                current
   DESCRIPTION
        "Number of packets forwarded by the tunnel.
         This object should represents the 32-bit
         value of the least significant part of the
         64-bit value if both mplsTunnelPerfHCPackets
         is returned."
   ::= { mplsTunnelPerfEntry 1 }
mplsTunnelPerfHCPackets OBJECT-TYPE
   SYNTAX Counter64
  MAX-ACCESS read-only
  STATUS
                current
  DESCRIPTION
        "High capacity counter for number of packets
        forwarded by the tunnel. "
   ::= { mplsTunnelPerfEntry 2 }
mplsTunnelPerfErrors OBJECT-TYPE
   SYNTAX Counter32
  MAX-ACCESS read-only
   STATUS
                current
  DESCRIPTION
        "Number of packets dropped because of errors or for
        other reasons."
   ::= { mplsTunnelPerfEntry 3 }
mplsTunnelPerfBytes OBJECT-TYPE
  SYNTAX Counter32
  MAX-ACCESS read-only
   STATUS
               current
   DESCRIPTION
        "Number of bytes forwarded by the tunnel.
         This object should represents the 32-bit
```

```
value of the least significant part of the
        64-bit value if both mplsTunnelPerfHCBytes
        is returned."
   ::= { mplsTunnelPerfEntry 4 }
mplsTunnelPerfHCBytes OBJECT-TYPE
   SYNTAX Counter64
  MAX-ACCESS
                read-only
   STATUS
                current
   DESCRIPTION
        "High capacity counter for number of bytes forwarded
         by the tunnel."
   ::= { mplsTunnelPerfEntry 5 }
-- End of mplsTunnelPerfTable
-- CR-LDP Tunnel Resource Table
mplsTunnelCRLDPResTable OBJECT-TYPE
               SEQUENCE OF MplsTunnelCRLDPResEntry
  MAX-ACCESS
               not-accessible
  STATUS
                current
  DESCRIPTION
        "The mplsTunnelCRLDPResTable allows a manager to
          specify which CR-LDP-specific resources are desired
         for an MPLS tunnel if that tunnel is signaled using
         CR-LDP. Note that these attributes are in addition
         to those specified in mplsTunnelResourceTable. This
         table also allows several tunnels to point to a
         single entry in this table, implying that these
         tunnels should share resources."
   ::= { mplsTeObjects 10 }
mplsTunnelCRLDPResEntry OBJECT-TYPE
   SYNTAX MplsTunnelCRLDPResEntry
  MAX-ACCESS not-accessible
   STATUS
                current
  DESCRIPTION
        "An entry in this table represents a set of resources
          for an MPLS tunnel established using CRLDP
          (mplsTunnelSignallingProto equal to crldp (3)). An
         entry can be created by a network administrator or
         by an SNMP agent as instructed by any MPLS
         signalling protocol."
   INDEX { mplsTunnelResourceIndex }
   ::= { mplsTunnelCRLDPResTable 1 }
```

```
MplsTunnelCRLDPResEntry ::= SEQUENCE {
       mplsTunnelCRLDPResMeanBurstSize MplsBurstSize,
      mplsTunnelCRLDPResExBurstSize MplsBurstSize,
mplsTunnelCRLDPResFrequency INTEGER,
mplsTunnelCRLDPResWeight Unsigned32,
mplsTunnelCRLDPResFlags Unsigned32,
mplsTunnelCRLDPResRowStatus RowStatus,
mplsTunnelCRLDPResStorageType StorageType
   }
mplsTunnelCRLDPResMeanBurstSize OBJECT-TYPE
   SYNTAX MplsBurstSize
   UNITS
                   "bytes"
   MAX-ACCESS read-create
   STATUS
                   current
   DESCRIPTION
         "The mean burst size in bytes."
   ::= { mplsTunnelCRLDPResEntry 1 }
mplsTunnelCRLDPResExBurstSize OBJECT-TYPE
   SYNTAX
             MplsBurstSize
   UNITS
                  "bytes"
   MAX-ACCESS read-create
   STATUS
                   current
   DESCRIPTION
      "The Excess burst size in bytes."
   REFERENCE
     "CR-LDP Specification, Section 4.3."
   ::= { mplsTunnelCRLDPResEntry 2 }
mplsTunnelCRLDPResFrequency OBJECT-TYPE
   SYNTAX INTEGER {
          unspecified(1),
          frequent(2),
          veryFrequent(3)
   MAX-ACCESS
                  read-create
                   current
   DESCRIPTION
         "The granularity of the availability of committed
           rate."
   REFERENCE
         "CR-LDP Specification, Section 4.3."
   ::= { mplsTunnelCRLDPResEntry 3 }
mplsTunnelCRLDPResWeight OBJECT-TYPE
   SYNTAX Unsigned32(0..255)
   MAX-ACCESS read-create
```

```
STATUS
               current
  DESCRIPTION
       "The relative weight for using excess bandwidth above
         its committed rate. The value of 0 means that
         weight is not applicable for the CR-LSP."
  REFERENCE
       "CR-LDP Specification, Section 4.3."
  DEFVAL { 0 }
   ::= { mplsTunnelCRLDPResEntry 4 }
mplsTunnelCRLDPResFlags OBJECT-TYPE
  SYNTAX Unsigned32 (0..63)
  MAX-ACCESS read-create
              current
  STATUS
  DESCRIPTION
       "The value of the 1 byte Flags conveyed as part of
         the traffic parameters during the establishment of
         the CRLSP. The bits in this object are to be
         interpreted as follows.
         +--+--+
         Res | F6 | F5 | F4 | F3 | F2 | F1 |
         +--+--+--+
       Res - These bits are reserved. Zero on transmission.
         Ignored on receipt.
       F1 - Corresponds to the PDR.
       F2 - Corresponds to the PBS.
       F3 - Corresponds to the CDR.
       F4 - Corresponds to the CBS.
       F5 - Corresponds to the EBS.
       F6 - Corresponds to the Weight.
       Each flag if is a Negotiable Flag corresponding to a
         Traffic Parameter. The Negotiable Flag value zero
         denotes Not Negotiable and value one denotes
         Negotiable."
   REFERENCE
        "1. Section 4.3, Constraint-Based LSP Setup using
         LDP, Jamoussi (Editor), RFC 3212, January 2002"
   DEFVAL { 0 }
    ::= { mplsTunnelCRLDPResEntry 5 }
mplsTunnelCRLDPResRowStatus OBJECT-TYPE
  SYNTAX RowStatus
  MAX-ACCESS read-create
  STATUS current
  DESCRIPTION
```

```
"This variable is used to create, modify, and/or
          delete a row in this table. When a row in this
          table is in active(1) state, no objects in that row
          can be modified by the agent except
          mplsTunnelCRLDPResRowStatus and
          mplsTunnelCRLDPResStorageType."
   ::= { mplsTunnelCRLDPResEntry 6 }
mplsTunnelCRLDPResStorageType OBJECT-TYPE
   SYNTAX StorageType
   MAX-ACCESS read-create
   STATUS
                current
   DESCRIPTION
        "The storage type for this CR-LDP Resource entry.
         Conceptual rows having the value 'permanent'
         need not allow write-access to any columnar
         objects in the row."
   DEFVAL { volatile }
   ::= { mplsTunnelCRLDPResEntry 7 }
-- Notifications.
mplsTunnelNotificationEnable OBJECT-TYPE
               TruthValue
   SYNTAX
                read-write
   MAX-ACCESS
                current
   STATUS
   DESCRIPTION
        "If this object is true, then it enables the
          generation of mplsTunnelUp and mplsTunnelDown
          traps, otherwise these traps are not emitted."
   DEFVAL { false }
   ::= { mplsTeObjects 11 }
mplsTunnelUp NOTIFICATION-TYPE
   OBJECTS
      mplsTunnelAdminStatus,
      mplsTunnelOperStatus
   STATUS
              current
   DESCRIPTION
        "This notification is generated when a
          mplsTunnelOperStatus object for one of the
          configured tunnels is about to leave the down state
          and transition into some other state (but not into
          the notPresent state). This other state is
          indicated by the included value of
          mplsTunnelOperStatus."
```

```
::= { mplsTeNotifications 1 }
mplsTunnelDown NOTIFICATION-TYPE
   OBJECTS
      mplsTunnelAdminStatus,
      mplsTunnelOperStatus
   STATUS
              current
   DESCRIPTION
        "This notification is generated when a
          mplsTunnelOperStatus object for one of the
          configured tunnels is about to enter the down state
          from some other state (but not from the notPresent
          state). This other state is indicated by the
          included value of mplsTunnelOperStatus."
   ::= { mplsTeNotifications 2 }
mplsTunnelRerouted NOTIFICATION-TYPE
   OBJECTS
      mplsTunnelAdminStatus,
      mplsTunnelOperStatus
   STATUS
               current
   DESCRIPTION
        "This notification is generated when a tunnel is
          rerouted. If the mplsTunnelARHopTable is used, then
          this tunnel instance's entry in the
          mplsTunnelARHopTable MAY contain the new path for
          this tunnel some time after this trap is issued by
          the agent."
    ::= { mplsTeNotifications 3 }
mplsTunnelReoptimized NOTIFICATION-TYPE
   OBJECTS
      mplsTunnelAdminStatus,
      mplsTunnelOperStatus
   STATUS
               current
   DESCRIPTION
        "This notification is generated when a tunnel is
          reoptimized. If the mplsTunnelARHopTable is used,
          then this tunnel instance's entry in the
          mplsTunnelARHopTable MAY contain the new path for
          this tunnel some time after this trap is issued by
          the agent."
    ::= { mplsTeNotifications 4 }
-- End of notifications.
```

```
-- Module compliance.
mplsTeGroups
   OBJECT IDENTIFIER ::= { mplsTeConformance 1 }
mplsTeCompliances
   OBJECT IDENTIFIER ::= { mplsTeConformance 2 }
-- Compliance requirement for fully compliant implementations.
mplsTeModuleFullCompliance MODULE-COMPLIANCE
   STATUS current
   DESCRIPTION
        "Compliance statement for agents that provide full
          support the MPLS-TE-STD-MIB module."
   MODULE IF-MIB -- The Interfaces Group MIB, RFC 2863.
      MANDATORY-GROUPS {
        ifGeneralInformationGroup,
         ifCounterDiscontinuityGroup
   MODULE -- this module
      -- The mandatory group has to be implemented by all
      -- LSRs that originate/terminate ESLSPs/tunnels.
      -- In addition, depending on the type of tunnels
      -- supported, other groups become mandatory as
      -- explained below.
      MANDATORY-GROUPS
         mplsTunnelGroup,
         mplsTunnelScalarGroup
      GROUP mplsTunnelManualGroup
      DESCRIPTION
          "This group is mandatory for devices which support
           manual configuration of tunnels."
      GROUP mplsTunnelSignaledGroup
      DESCRIPTION
          "This group is mandatory for devices which support
           signaled tunnel set up."
      GROUP mplsTunnelIsNotIntfcGroup
      DESCRIPTION
          "This group is mandatory for devices which support
```

```
tunnels that are not interfaces."
      GROUP mplsTunnelIsIntfcGroup
      DESCRIPTION
          "This group is mandatory for devices which support
           tunnels that are interfaces."
      GROUP mplsTunnelCRLDPResOptionalGroup
      DESCRIPTION
          "Objects in this group are required by
           implementations supporting the CR-LDP protocol for
           signalling of TE tunnels."
      GROUP mplsTeNotificationGroup
      DESCRIPTION "This group is mandatory for those implementations
                   which can implement the notifications
                   contained in this group."
      OBJECT
                 mplsTunnelRowStatus
                 RowStatus { active(1), notInService(2) }
      WRITE-SYNTAX RowStatus { active(1), notInService(2),
                              createAndGo(4), destroy(6)
      DESCRIPTION "Support for createAndWait and notReady is not
                  required."
      OBJECT
                mplsTunnelHopRowStatus
      SYNTAX
                  RowStatus { active(1), notInService(2) }
      WRITE-SYNTAX RowStatus { active(1), notInService(2),
                              createAndGo(4), destroy(6)
      DESCRIPTION "Support for createAndWait and notReady is not
                  required."
      OBJECT
                mplsTunnelCRLDPResRowStatus
      SYNTAX
                  RowStatus { active(1), notInService(2) }
      WRITE-SYNTAX RowStatus { active(1), notInService(2),
                               createAndGo(4), destroy(6)
      DESCRIPTION "Support for createAndWait and notReady is
                   not required."
   ::= { mplsTeCompliances 1 }
-- Compliance requirement for read-only implementations.
mplsTeModuleReadOnlyCompliance MODULE-COMPLIANCE
   STATUS current
```

# DESCRIPTION "Compliance requirement for implementations that only provide read-only support for MPLS-TE-STD-MIB. Such devices can then be monitored but cannot be configured using this MIB modules." MODULE -- this module -- mplsTunnelTable MANDATORY-GROUPS mplsTunnelGroup, mplsTunnelScalarGroup GROUP mplsTunnelManualGroup DESCRIPTION "This group is mandatory for devices which support manual configuration of tunnels." GROUP mplsTunnelSignaledGroup DESCRIPTION "This group is mandatory for devices which support signaled tunnel set up." GROUP mplsTunnelIsNotIntfcGroup DESCRIPTION "This group is mandatory for devices which support tunnels that are not interfaces." GROUP mplsTunnelIsIntfcGroup DESCRIPTION "This group is mandatory for devices which support tunnels that are interfaces." GROUP mplsTunnelCRLDPResOptionalGroup DESCRIPTION "Objects in this group are required by implementations supporting the CR-LDP protocol for signalling of TE tunnels." GROUP mplsTeNotificationGroup DESCRIPTION "This group is mandatory for those implementations which can implement the notifications contained in this group."

-- mplsTunnelTable

OBJECT mplsTunnelName MIN-ACCESS read-only

DESCRIPTION

"Write access is not required."

OBJECT mplsTunnelDescr

MIN-ACCESS read-only

DESCRIPTION

"Write access is not required."

OBJECT mplsTunnelIsIf MIN-ACCESS read-only

DESCRIPTION

"Write access is not required."

OBJECT mplsTunnelIfIndex

DESCRIPTION

"Write access is not required."

OBJECT mplsTunnelXCPointer

MIN-ACCESS read-only

DESCRIPTION

"Write access is not required."

OBJECT mplsTunnelSignallingProto

MIN-ACCESS read-only

DESCRIPTION

"Write access is not required."

OBJECT mplsTunnelSetupPrio

MIN-ACCESS read-only

DESCRIPTION

"Write access is not required."

OBJECT mplsTunnelHoldingPrio

MIN-ACCESS read-only

DESCRIPTION

"Write access is not required."

OBJECT mplsTunnelSessionAttributes

MIN-ACCESS read-only

DESCRIPTION

"Write access is not required."

OBJECT mplsTunnelLocalProtectInUse

MIN-ACCESS read-only

DESCRIPTION

"Write access is not required."

OBJECT mplsTunnelResourcePointer MIN-ACCESS read-only

DESCRIPTION

"Write access is not required."

OBJECT mplsTunnelInstancePriority

MIN-ACCESS read-only

DESCRIPTION

"Write access is not required."

OBJECT mplsTunnelHopTableIndex

MIN-ACCESS read-only

DESCRIPTION

"Write access is not required."

OBJECT mplsTunnelIncludeAnyAffinity

MIN-ACCESS read-only

DESCRIPTION

"Write access is not required."

OBJECT mplsTunnelIncludeAllAffinity

MIN-ACCESS read-only

DESCRIPTION

"Write access is not required."

OBJECT mplsTunnelExcludeAnyAffinity

MIN-ACCESS read-only

DESCRIPTION

"Write access is not required."

OBJECT mplsTunnelPathInUse

MIN-ACCESS read-only

DESCRIPTION

"Write access is not required."

OBJECT mplsTunnelRole

MIN-ACCESS read-only

DESCRIPTION

"Write access is not required."

OBJECT mplsTunnelAdminStatus

SYNTAX INTEGER { up (1), down (2) }

MIN-ACCESS read-only

DESCRIPTION

"Only up and down states must be supported. Write access is not required."

OBJECT mplsTunnelRowStatus

```
SYNTAX RowStatus { active(1) }
MIN-ACCESS read-only
DESCRIPTION "Write access is not required."
-- mplsTunnelHopTable
        mplsTunnelHopAddrType
SS read-only
OBJECT
MIN-ACCESS
DESCRIPTION "Write access is not required."
OBJECT mplsTunnelHopIpAddr
MIN-ACCESS read-only
DESCRIPTION "Write access is not required."
OBJECT
          mplsTunnelHopIpPrefixLen
MIN-ACCESS read-only
DESCRIPTION
    "Write access is not required."
OBJECT
          mplsTunnelHopAddrUnnum
MIN-ACCESS read-only
DESCRIPTION
    "Write access is not required."
          mplsTunnelHopAsNumber
OBJECT
MIN-ACCESS read-only
DESCRIPTION
    "Write access is not required."
OBJECT mplsTunnelHopLspId
MIN-ACCESS read-only
DESCRIPTION
    "Write access is not required."
OBJECT mplsTunnelHopType
          INTEGER { strict(1) }
SYNTAX
MIN-ACCESS read-only
DESCRIPTION
    "loose(2) need not be supported. Write access is
    not required."
OBJECT
          mplsTunnelHopInclude
MIN-ACCESS read-only
DESCRIPTION "Write access is not required."
          mplsTunnelHopPathOptionName
MIN-ACCESS read-only
DESCRIPTION "Write access is not required."
```

OBJECT mplsTunnelHopEntryPathComp

MIN-ACCESS read-only

DESCRIPTION "Write access is not required."

OBJECT mplsTunnelHopRowStatus SYNTAX RowStatus { active(1) }

MIN-ACCESS read-only

DESCRIPTION "Write access is not required."

OBJECT mplsTunnelHopStorageType

MIN-ACCESS read-only

DESCRIPTION "Write access is not required."

-- mplsTunnelResourceTable

OBJECT mplsTunnelResourceMaxRate

MIN-ACCESS read-only

DESCRIPTION "Write access is not required."

OBJECT mplsTunnelResourceMeanRate

MIN-ACCESS read-only

DESCRIPTION "Write access is not required."

OBJECT mplsTunnelResourceMaxBurstSize

MIN-ACCESS read-only

DESCRIPTION "Write access is not required."

OBJECT mplsTunnelResourceMeanBurstSize

MIN-ACCESS read-only

DESCRIPTION "Write access is not required."

OBJECT mplsTunnelResourceExBurstSize

MIN-ACCESS read-only

DESCRIPTION

"Write access is not required."

OBJECT mplsTunnelResourceFrequency

MIN-ACCESS read-only

DESCRIPTION "Write access is not required."

OBJECT mplsTunnelResourceWeight

MIN-ACCESS read-only

DESCRIPTION "Write access is not required."

OBJECT mplsTunnelResourceRowStatus SYNTAX RowStatus { active(1) }

MIN-ACCESS read-only

DESCRIPTION "Write access is not required."

OBJECT mplsTunnelResourceStorageType

```
MIN-ACCESS read-only
     DESCRIPTION "Write access is not required."
     -- mplsTunnelCRLDPResTable
                 mplsTunnelCRLDPResMeanBurstSize
     MIN-ACCESS read-only
     DESCRIPTION "Write access is not required."
              mplsTunnelCRLDPResExBurstSize
     OBJECT
     MIN-ACCESS read-only
     DESCRIPTION "Write access is not required."
     OBJECT
                mplsTunnelCRLDPResFrequency
     MIN-ACCESS read-only
     DESCRIPTION "Write access is not required."
     OBJECT
              mplsTunnelCRLDPResWeight
     MIN-ACCESS read-only
     DESCRIPTION "Write access is not required."
                mplsTunnelCRLDPResFlags
     OBJECT
     MIN-ACCESS read-only
     DESCRIPTION "Write access is not required."
                mplsTunnelCRLDPResRowStatus
     OBJECT
                RowStatus { active(1) }
     SYNTAX
     MIN-ACCESS read-only
     DESCRIPTION "Write access is not required."
                mplsTunnelCRLDPResStorageType
     OBJECT
     MIN-ACCESS
                 read-only
     DESCRIPTION "Write access is not required."
   ::= { mplsTeCompliances 2 }
-- Units of conformance.
mplsTunnelGroup OBJECT-GROUP
  OBJECTS {
     mplsTunnelIndexNext,
     mplsTunnelName,
     mplsTunnelDescr,
     mplsTunnelOwner,
     mplsTunnelXCPointer,
     mplsTunnelIfIndex,
```

```
mplsTunnelHopTableIndex,
mplsTunnelARHopTableIndex,
mplsTunnelCHopTableIndex,
mplsTunnelAdminStatus,
mplsTunnelOperStatus,
mplsTunnelRowStatus,
mplsTunnelNotificationEnable,
mplsTunnelStorageType,
mplsTunnelConfigured,
mplsTunnelActive,
mplsTunnelPrimaryInstance,
mplsTunnelPrimaryUpTime,
mplsTunnelPathChanges,
mplsTunnelLastPathChange,
mplsTunnelCreationTime,
mplsTunnelStateTransitions,
mplsTunnelIncludeAnyAffinity,
mplsTunnelIncludeAllAffinity,
mplsTunnelExcludeAnyAffinity,
mplsTunnelPerfPackets,
mplsTunnelPerfHCPackets,
mplsTunnelPerfErrors,
mplsTunnelPerfBytes,
mplsTunnelPerfHCBytes,
mplsTunnelResourcePointer,
mplsTunnelInstancePriority,
mplsTunnelPathInUse,
mplsTunnelRole,
mplsTunnelTotalUpTime,
mplsTunnelInstanceUpTime,
mplsTunnelResourceIndexNext,
mplsTunnelResourceMaxRate,
mplsTunnelResourceMeanRate,
mplsTunnelResourceMaxBurstSize,
mplsTunnelResourceMeanBurstSize,
mplsTunnelResourceExBurstSize,
mplsTunnelResourceFrequency,
mplsTunnelResourceWeight,
mplsTunnelResourceRowStatus,
mplsTunnelResourceStorageType,
mplsTunnelARHopAddrType,
mplsTunnelARHopIpAddr,
mplsTunnelARHopAddrUnnum,
mplsTunnelARHopLspId,
mplsTunnelCHopAddrType,
mplsTunnelCHopIpAddr,
mplsTunnelCHopIpPrefixLen,
mplsTunnelCHopAsNumber,
```

```
mplsTunnelCHopAddrUnnum,
      mplsTunnelCHopLspId,
      mplsTunnelCHopType
   STATUS current
   DESCRIPTION
        "Necessary, but not sufficient, set of objects to
          implement tunnels. In addition, depending on the
          type of the tunnels supported (for example,
          manually configured or signaled, persistent or non-
          persistent, etc.), the following other groups
          defined below are mandatory: mplsTunnelManualGroup
          and/or mplsTunnelSignaledGroup,
          mplsTunnelIsNotIntfcGroup and/or
          mplsTunnelIsIntfcGroup."
   ::= { mplsTeGroups 1 }
mplsTunnelManualGroup OBJECT-GROUP
   OBJECTS { mplsTunnelSignallingProto }
   STATUS current
   DESCRIPTION
        "Object(s) needed to implement manually configured
          tunnels."
   ::= { mplsTeGroups 2 }
mplsTunnelSignaledGroup OBJECT-GROUP
   OBJECTS {
      mplsTunnelSetupPrio,
      mplsTunnelHoldingPrio,
      mplsTunnelSignallingProto,
      mplsTunnelLocalProtectInUse,
      mplsTunnelSessionAttributes,
      mplsTunnelHopListIndexNext,
      mplsTunnelHopAddrType,
      mplsTunnelHopIpAddr,
      mplsTunnelHopIpPrefixLen,
      mplsTunnelHopAddrUnnum,
      mplsTunnelHopAsNumber,
      mplsTunnelHopLspId,
      mplsTunnelHopType,
      mplsTunnelHopInclude,
      mplsTunnelHopPathOptionName,
      mplsTunnelHopEntryPathComp,
      mplsTunnelHopRowStatus,
      mplsTunnelHopStorageType
   STATUS current
  DESCRIPTION
```

```
"Objects needed to implement signaled tunnels."
   ::= { mplsTeGroups 3 }
mplsTunnelScalarGroup OBJECT-GROUP
   OBJECTS {
      mplsTunnelConfigured,
      mplsTunnelActive,
      mplsTunnelTEDistProto,
      mplsTunnelMaxHops,
      mplsTunnelNotificationMaxRate
   }
   STATUS current
   DESCRIPTION
        "Scalar object needed to implement MPLS tunnels."
   ::= { mplsTeGroups 4 }
mplsTunnelIsIntfcGroup OBJECT-GROUP
   OBJECTS { mplsTunnelIsIf }
   STATUS current
   DESCRIPTION
        "Objects needed to implement tunnels that are
          interfaces."
   ::= { mplsTeGroups 5 }
mplsTunnelIsNotIntfcGroup OBJECT-GROUP
   OBJECTS { mplsTunnelIsIf }
   STATUS current
   DESCRIPTION
        "Objects needed to implement tunnels that are not
          interfaces."
   ::= { mplsTeGroups 6 }
mplsTunnelCRLDPResOptionalGroup OBJECT-GROUP
   OBJECTS {
      mplsTunnelCRLDPResMeanBurstSize,
      mplsTunnelCRLDPResExBurstSize,
      mplsTunnelCRLDPResFrequency,
      mplsTunnelCRLDPResWeight,
      mplsTunnelCRLDPResFlags,
      mplsTunnelCRLDPResRowStatus,
      mplsTunnelCRLDPResStorageType
   STATUS current
   DESCRIPTION
        "Set of objects implemented for resources applicable
          for tunnels signaled using CR-LDP."
   ::= { mplsTeGroups 7 }
```

```
mplsTeNotificationGroup NOTIFICATION-GROUP
  NOTIFICATIONS {
      mplsTunnelUp,
      mplsTunnelDown,
      mplsTunnelRerouted,
      mplsTunnelReoptimized
  }
  STATUS current
  DESCRIPTION
      "Set of notifications implemented in this module.
      None is mandatory."
  ::= { mplsTeGroups 8 }
```

# 12. Security Considerations

It is clear that this MIB module is potentially useful for the monitoring of MPLS TE tunnels. This MIB module can also be used for the configuration of certain objects, and anything that can be configured can be incorrectly configured, with potentially disastrous results.

There are a number of management objects defined in this MIB module with a MAX-ACCESS clause of read-write and/or read-create. Such objects may be considered sensitive or vulnerable in some network environments. The support for SET operations in a non-secure environment without proper protection can have a negative effect on network operations. These are the tables and objects and their sensitivity/vulnerability:

- the mplsTunnelTable, mplsTunnelHopTable, mplsTunnelResourceTable, and mplsTunnelCRLDPResTable collectively contain objects to provision MPLS tunnels, tunnel hops, and tunnel resources.

Unauthorized access to objects in these tables, could result in disruption of traffic on the network. This is especially true if a tunnel has been established. The use of stronger mechanisms, such as SNMPv3 security, should be considered where possible. Specifically, SNMPv3 VACM and USM MUST be used with any v3 agent which implements this MIB. Administrators should consider whether read access to these objects should be allowed, since read access may be undesirable under certain circumstances.

Some of the readable objects in this MIB module (i.e., objects with a MAX-ACCESS other than not-accessible) may be considered sensitive or vulnerable in some network environments. It is thus important to control even GET and/or NOTIFY access to these objects and possibly

to even encrypt the values of these objects when sending them over the network via SNMP. These are the tables and objects and their sensitivity/vulnerability:

- the mplsTunnelTable, mplsTunnelHopTable, mplsTunnelResourceTable, mplsTunnelARHopTable, mplsTunnelCHopTable, mplsTunnelPerfTable, and mplsTunnelCRLDPResTable collectively show the MPLS-TE tunnel network topology and its performance characteristics. If an Administrator does not want to reveal this information, then these tables should be considered sensitive/vulnerable.

SNMP versions prior to SNMPv3 did not include adequate security. Even if the network itself is secure (for example by using IPSec), even then, there is no control as to who on the secure network is allowed to access and GET/SET (read/change/create/delete) the objects in this MIB module.

It is RECOMMENDED that implementers consider the security features as provided by the SNMPv3 framework (see [RFC3410], section 8), including full support for the SNMPv3 cryptographic mechanisms (for authentication and privacy).

Further, deployment of SNMP versions prior to SNMPv3 is NOT RECOMMENDED. Instead, it is RECOMMENDED that SNMPv3 be deployed and cryptographic security enabled. It is then a customer/operator responsibility to ensure that the SNMP entity giving access to an instance of this MIB module is properly configured to give access to only those principals (users) that have legitimate rights to those objects.

# 13. Acknowledgments

We wish to thank Adrian Farrel, Bert Wijnen, Eric Gray, Joan Cucchiara, Patrick Kerharo, Paul Langille, Marcus Brunner, Mike MacFaden, and Mike Piecuch for their comments on this document.

Comments should be made directly to the MPLS mailing list at mpls@uu.net.

## 14. IANA Considerations

As described in [MPLSMGMT] and as requested in the MPLS-TC-STD-MIB [RFC3811], MPLS related standards track MIB modules should be rooted under the mplsStdMIB subtree. There are 4 MPLS MIB Modules contained in this document, each of the following "IANA Considerations" subsections requests IANA for a new assignment under the mplsStdMIB subtree. New assignments can only be made via a Standards Action as specified in [RFC2434].

#### 14.1. IANA Considerations for MPLS-TE-STD-MIB

The IANA has assigned { mplsStdMIB 3 } to the MPLS-TE-STD-MIB module specified in this document.

# 15. References

#### 15.1. Normative References

- [RFC2119] Bradner, S., "Key Words for use in RFCs to Indicate Requirement Levels", BCP 14, RFC 2119, March 1997.

- [RFC2863] McCloghrie, K. and F. Kastenholtz, "The Interfaces Group MIB ", RFC 2863, June 2000.
- [RFC3031] Rosen, E., Viswanathan, A., and R. Callon, "Multiprotocol Label Switching Architecture", RFC 3031, January 2001.
- [RFC3209] Awduche, D., Berger, L., Gan, D., Li, T., Srinivasan, V.,
  and G. Swallow, "RSVP-TE: Extensions to RSVP for LSP
  Tunnels", RFC 3209, December 2001.
- [RFC3212] Jamoussi, B., Ed., Andersson, L., Callon, R, Dantu, R.,
  Wu, L., Doolan, P., Worster, T., Feldman, N., Fredette,
  A., Girish, M., Gray, E., Heinanen, J., Kilty, T., and A.
  Malis, "Constraint-Based LSP Setup using LDP", RFC 3212,
  January 2002.
- [RFC3289] Baker, F., Chan, K., and A. Smith, "Management Information Base for the Differentiated Services Architecture", RFC 3289, May 2002.

- [RFC3291] Daniele, M., Haberman, B., Routhier, S., and J. Schoenwaelder, "TextualConventions for Internet Network Addresses", RFC 3291, May 2002.
- [RFC3411] Harrington, D., Presuhn, R., and B. Wijnen, "An Architecture for Describing Simple Network Management Protocol (SNMP) Management Frameworks", STD 62, RFC 3411, December 2002.
- [RFC3811] Nadeau, T. and J. Cucchiara, "Definition of Textual Conventions and for Multiprotocol Label Switching (MPLS) Management", RFC 3811, June 2004.
- [RFC3813] Srinivasan, C., Viswanathan, A., and T. Nadeau,
  "Multiprotocol Label Switching (MPLS) Label Switching
  (LSR) Router Management Information Base (MIB)", RFC 3813,
  June 2004.

## 15.2. Informative References

- [MPLSMGMT] Nadeau, T., Srinivasan, C., and A. Farrel, "Multiprotocol Label Switching (MPLS) Management Overview", Work in Progress, September 2003.
- [RFC2434] Narten, T. and H. Alvestrand., "Guidelines for Writing an IANA Considerations Section in RFCs", BCP 26, RFC 2434, October 1998.
- [RFC3410] Case, J., Mundy, R., Partain, D., and B. Stewart,
  "Introduction and Applicability Statement for Internet
  Standard Management Framework", RFC 3410, December 2002.

# 16. Authors' Addresses

Cheenu Srinivasan Bloomberg L.P. 499 Park Ave., New York, NY 10022

Phone: +1-212-893-3682 EMail: cheenu@bloomberg.net

Arun Viswanathan Force10 Networks, Inc. 1440 McCarthy Blvd Milpitas, CA 95035

Phone: +1-408-571-3516

EMail: arunv@force10networks.com

Thomas D. Nadeau Cisco Systems, Inc. 300 Apollo Drive Chelmsford, MA 01824

Phone: +1-978-244-3051 EMail: tnadeau@cisco.com

# 17. Full Copyright Statement

Copyright (C) The Internet Society (2004). This document is subject to the rights, licenses and restrictions contained in BCP 78, and except as set forth therein, the authors retain all their rights.

This document and the information contained herein are provided on an "AS IS" basis and THE CONTRIBUTOR, THE ORGANIZATION HE/SHE REPRESENTS OR IS SPONSORED BY (IF ANY), THE INTERNET SOCIETY AND THE INTERNET ENGINEERING TASK FORCE DISCLAIM ALL WARRANTIES, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO ANY WARRANTY THAT THE USE OF THE INFORMATION HEREIN WILL NOT INFRINGE ANY RIGHTS OR ANY IMPLIED WARRANTIES OF MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE.

# Intellectual Property

The IETF takes no position regarding the validity or scope of any Intellectual Property Rights or other rights that might be claimed to pertain to the implementation or use of the technology described in this document or the extent to which any license under such rights might or might not be available; nor does it represent that it has made any independent effort to identify any such rights. Information on the procedures with respect to rights in RFC documents can be found in BCP 78 and BCP 79.

Copies of IPR disclosures made to the IETF Secretariat and any assurances of licenses to be made available, or the result of an attempt made to obtain a general license or permission for the use of such proprietary rights by implementers or users of this specification can be obtained from the IETF on-line IPR repository at http://www.ietf.org/ipr.

The IETF invites any interested party to bring to its attention any copyrights, patents or patent applications, or other proprietary rights that may cover technology that may be required to implement this standard. Please address the information to the IETF at ietf-ipr@ietf.org.

# Acknowledgement

Funding for the RFC Editor function is currently provided by the Internet Society.