

Outline

Chapter 5: Inference for a single population

Introductory Statistics for Engineering Experimentation

Peter R. Nelson, Marie Coffin and Karen A.F. Copeland

Slides by Douglas Bates

4.1 Central Limit Theorem

4.2 A confidence interval for μ

The Central Limit Theorem

- ▶ The central limit theorem is one of the most important results in mathematical statistics. It says that the sample means from a *random sample* (meaning independent samples from a stable process) will be normally distributed, regardless of what the original distribution was, when n is sufficiently large.
- ▶ Formally, if $\mathcal{Y}_1, \mathcal{Y}_2, \dots, \mathcal{Y}_n$ is a random sample from a distribution with $\sigma^2 < \infty$ then for large samples, $\bar{\mathcal{Y}}$ is approximately normally distributed.
- ▶ This is a remarkably powerful result; first, because it is very general and secondly because it is a description of the asymptotic or “limiting” distribution but it holds for quite small values of n .

Other properties of the distribution of the sample mean

- ▶ If the random variables $\mathcal{Y}_1, \mathcal{Y}_2, \dots, \mathcal{Y}_n$ are a random sample (sometimes also described as a “independent and identically distributed” or i.i.d. sample) from a distribution with mean μ and variance σ^2 then $E(\bar{\mathcal{Y}}) = \mu$ and $\text{Var}(\bar{\mathcal{Y}}) = \sigma^2/n$.
- ▶ So the central limit theorem states that, for large n ,

$$\bar{\mathcal{Y}} \sim \mathcal{N}\left(\mu, \frac{\sigma^2}{n}\right)$$

- ▶ Exactly how large n must be depends on the form of the original distribution. If it is continuous and reasonably symmetric then $n = 15$ may be large enough. If it is skewed but continuous we may need $n = 30$ or more. For discrete and skewed we may need as much as $n = 100$.
- ▶ Although in practice we only have one sample and one average, \bar{y} we can use computer simulation to consider the sorts of samples we could have gotten and the distribution of the statistic.


Conducting a simulation study (not part of the course)

- ▶ Suppose we wish to simulate the value of a statistic (e.g. mean or median or variance or standard deviation) from samples of size n drawn from a certain distribution. Let K be the number of replicates we want to obtain.
- ▶ The **sample size**, n , is typically small. The number of replicates, K , can be very large. The larger the value of K , the more accurately we can determine the distribution of the statistic. With modern computers we can afford to use values of K in the hundreds of thousands or more.
- ▶ First determine how to evaluate the statistic from a single sample of size n then use the **replicate** function to repeat the process K times.

Mean of samples of size 5 from $U(-1,1)$

What is the shape of the distribution of the mean of a sample of size $n = 5$ from a $U(-1, 1)$ distribution?

```
> mns5 <- replicate(50000, mean(runif(5, min = -1, max = 1)))
> histogram(~mns5, breaks = seq(-1, 1, len = 40))
```



Sampling densities of statistics

- ▶ The idiom

```
replicate(K, <statfn>(r<distab>(n, <pars>)))
```

produces K replicates of the statistic calculated by **<statfn>** (examples are **mean**, **median**, **var** and **sd**) on samples of size **n** from distribution **<distab>** with parameter(s) **<pars>**.

- ▶ Typically K is large and n is small. Values of 10,000 or 100,000 are used for K on modern computers. The larger the value of K the smoother the approximation to the sampling density. n is the size of the actual sample you can afford to collect.

Effect of changing the sample size, n

- ▶ Performing multiple simulations allows us to see how characteristics of the distribution of \bar{Y} depends on n .


```
> mns1 <- runif(50000, -1, 1)
> mns10 <- replicate(50000, mean(runif(10, -1, 1)))
> mns20 <- replicate(50000, mean(runif(20, -1, 1)))
> sapply(list(mns1, mns5, mns10, mns20), mean)
[1] 4.165144e-03 -5.644363e-04 7.089158e-05 -1.551859e-04
```

```
> sapply(list(mns1, mns5, mns10, mns20), var)
[1] 0.33132808 0.06633685 0.03335722 0.01669940
```


- ▶ As n increases the expected value of the sample mean stays near 0.
- ▶ As n increases the variance of the sample mean decreases. Roughly, $V(\bar{X}_n) = \frac{1}{3} \cdot \frac{1}{n}$

Shape of distribution of \bar{X}_n

- As n increases, the shape of the distribution of \bar{X}_n tends to the “bell-curve” or Gaussian shape and it has less variability. That is, it tends to a “central limit”.




Overlaid normal probability plots for \bar{Y}_n



The conclusion is that the distribution of means from an i.i.d. sample of a uniform distribution is very close to a normal, even for $n = 5$.


More detail on the shape of the distribution of \bar{Y}

- In addition to the histogram we can use normal probability plots to evaluate the deviations of the distribution of \bar{Y} from normality.



Sample means from an exponential distribution

```
> emns01 <- replicate(50000, mean(rexp(1, rate = 1/7)))
> emns05 <- replicate(50000, mean(rexp(5, rate = 1/7)))
> emns15 <- replicate(50000, mean(rexp(15, rate = 1/7)))
> emns50 <- replicate(50000, mean(rexp(50, rate = 1/7)))
```



Even for $n = 50$ there is noticeable skewness in the distribution (although we would not be far wrong in assuming normality at $n = 50$).

Elementary uses of the C.L.T.

- If we have plausible values of the variance of our process, perhaps from a pilot study, we can use the normal distribution and the Central Limit Theorem (C.L.T.) to evaluate probabilities regarding the sample mean.
- Example 5.1.3 discusses product lifetimes that have an unknown mean and a variance of approximately 8 years. The number of products to sample so that we are 95% certain that \bar{y} will be within 1 year of the true mean is derived from

$$0.95 = P(|\bar{Y} - \mu| < 1)$$

The distribution of \bar{Y} will be approximately normal with mean μ and standard deviation σ/\sqrt{n} . For a standard normal, 95% of the probability is within “2” standard deviations of the mean (the actual multiple is `qnorm(0.025) = -1.95996`) so we want $1 = qnorm(0.025)^2 \frac{8}{n}$. That is, $n >$

```
> 8 * qnorm(0.025)^2
```

```
[1] 30.73167
```

Confidence intervals

- Our “best guess” at a parameter is called a *point estimate*. For example, we usually use the sample mean, \bar{y} , as the point estimate of μ .
- An *interval estimate* or *confidence interval* is an interval of plausible values for the parameter. Values outside the interval are “unreasonable” and values inside are “not unreasonable”.
- To calibrate the meaning of “unreasonable” we assign a value α to the probability of getting data like we did or even more extreme when the parameter is outside. This corresponds to the “p-value” in a hypothesis test.
- The *coverage probability* or *confidence level* is $1 - \alpha$. Typically we set $\alpha = 0.05$ or $\alpha = 0.01$ resulting in 95% or 99% confidence intervals.
- Formally, the coverage probability is the probability that an interval constructed in this way will cover the true parameter value.

Approximations for binomial or Poisson distributions

- The text describes approximations of the probabilities for a binomial or Poisson distribution based on the normal distribution.
- These are interesting from the point of view of understanding that these distributions will tend to have a “bell-curve” shape when n is large and p is moderate for the binomial or λt is large for the Poisson.
- In practice, though, you can evaluate probabilities for such distributions exactly so there is no need to use approximations.

A confidence interval on μ

- In the unlikely event that someone were to tell us what the standard deviation, σ , of the population was but somehow not know much about the mean, μ , we could create a $(1 - \alpha)$ confidence interval as

$$\bar{y} \pm z(\alpha/2) \frac{\sigma}{\sqrt{n}}$$

where $z(\alpha/2)$ is the **upper** $\alpha/2$ quantile of the standard normal distribution.

- For example, the upper 0.025 quantile of the standard normal is

```
> qnorm(0.025, low = FALSE)
```

`[1] 1.959964`
so a 95% confidence interval on μ for this artificial, “known sigma” case is

$$\bar{y} \pm 1.959964 \frac{\sigma}{\sqrt{n}}$$

Use of Student's T distribution

- ▶ In the real world no one tells us what σ is and we must estimate it as s . A statistician named William Gossett, who wrote under the pseudonym "A Student", derived the distribution of the shifted, scaled sample mean when the scale is based on the estimate, s , not the theoretical value σ .
- ▶ This distribution is called the "Student's t distribution". It is similar to the standard normal distribution but a bit more spread out. The spreading depends on the number of "degrees of freedom" in the estimate of σ^2 . The degrees of freedom are written as ν . For a single sample $\nu = n - 1$.
- ▶ As ν increases the T distribution approaches the standard normal. If we were using tables we would call anything with $\nu > 30$ a standard normal. When using a computer we don't bother.
- ▶ Notation: the t distribution with ν degrees of freedom is written $t(\nu)$. The corresponding R functions are `dt`, `pt`, `qt` and `rt`. The upper α quantile is written $t(\alpha; \nu)$.


General form of the confidence interval

- ▶ The general form of the confidence interval on μ is

$$\bar{y} \pm t\left(\frac{\alpha}{2}, n - 1\right) \frac{s}{\sqrt{n}}$$

- ▶ We can use this formula for any values of n . If n is large we don't need strong assumptions on the shape of the original distribution. If n is small we must assume that the original distribution is close to the normal (but, of course, we can't check this with a small sample - a "Catch 22" situation).
- ▶ The R function to create this interval is `t.test`. The name comes from the corresponding hypothesis test, which we will discuss later.

Graphical comparison of $t(\nu)$ and Z



Example 5.2.2

The example provides (probably fictitious) discharge times for a particular electric vehicle

```
> charge <- c(5.11, 2.1, 4.27, 5.04, 4.47, 3.73, 5.96, 6.21)
> c(summary(charge), sd = sd(charge))
```

Min.	1st Qu.	Median	Mean	3rd Qu.	Max.	sd
2.1000	4.1400	4.7600	4.6100	5.3200	6.2100	1.3108

```
> t.test(charge)
```

One Sample t-test

data: charge

t = 9.9502, df = 7, p-value = 2.211e-05

alternative hypothesis: true mean is not equal to 0

95 percent confidence interval:

3.5154 5.7071


sample estimates:

mean of x

4.6113

Example 5.2.2 (cont'd)


Because the degrees of freedom, $\nu = 7$, are quite small we should check for normality.



Sample sizes

- ▶ The half-width of a confidence interval, also called the *margin of error* depends on
 - The **confidence level** Higher confidence levels require wider intervals
 - The **standard deviation** More variability in the original distribution results in wider intervals.
 - The **sample size** Larger samples produce narrower intervals.
- ▶ Given a working value for σ we can determine the sample size needed to attain a given margin of error.
- ▶ If we are willing to assume that n is large we can use $z(\alpha/2)$ in the calculation. For small n it gets tricky because $\nu = n - 1$ determines the multiplier when, in turn, affects the sample size. We must solve a nonlinear equation but computers are good at that.

Clear-coat thickness (example 5.2.4)



```
> with(ccthickn, c(summary(thickness), sd = sd(thickness)))
   Min. 1st Qu. Median Mean 3rd Qu. Max. sd
58.2000 62.3000 64.4000 64.3000 66.2000 71.3000 2.7176

> with(ccthickn, t.test(thickness, mu = 65, conf = 0.9))
One Sample t-test
data: thickness
t = -1.7221, df = 39, p-value = 0.09297
alternative hypothesis: true mean is not equal to 65
90 percent confidence interval:
 63.536 64.984
sample estimates:
mean of x
```

Sample size calculations

- ▶ Example 5.2.5 shows calculations for the sample size from the formula $n = \left[\frac{t(\alpha/2;\infty)s}{d} \right]^2$ when the desired margin of error, d , is 0.2, the working value of s is 0.4 and α is 5% and we round the answer to the next largest integer.

```
> ceiling((qnorm(0.025)*0.4/0.2)^2)
```

[1] 16

- ▶ Because this is a small value of n we should instead solve for n in $n = \left[\frac{t(\alpha/2;n-1)s}{d} \right]^2$

```
> ceiling(uniroot(function(x) x-(qt(.025,x-1)*0.4/0.2)^2,
+ c(2,100))$root)
```

[1] 18