R documentation

of 'ldexpdose.Rd'

February 26, 2013

ldexpdose

Locally D-optimal designs for Exponential dose-response model

Description

Finds Locally D-optimal designs for Exponential dose-response model which is defined as $E(y) = a + b \exp(x/c)$ with $Var(y) = \sigma^2$, where a, b and σ are unknown parameters.

Usage

```
ldexpdose(a, b, c, lb, ub, user.points = NULL, user.weights = NULL,
..., n.restarts = 1, n.sim = 1, tol = 1e-8, prec = 53)
```

Arguments

a	initial value for paremeter a , must be greater or equal to 0 .
b	initial value for parameter b , must be greater or equal to 0 .
С	initial value for parameter c , must be greater or equal to 0 .
1b	lower bound of design interval, must be greater than or equal to 0.
ub	upper bound of design interval.
user.points	(optional) vector of user design points which calculation of its D-efficiency is aimed. Each element of user.points must be within the design interval.
user.weights	(optional) vector of weights which its elements correspond to user.points elements. The sum of weights should be 1; otherwise they will be normalized.
	(optional) additional parameters will be passed to function curve.
prec	(optional) a number, the maximal precision to be used for D-efficiency calculation, in bite. Must be at least 2 (default 53), see 'Details'.
n.restarts	(optional optimization parameter) number of solver restarts required in optimization process (default 1), see 'Details'.
n.sim	(optional optimization parameter) number of random parameters to generate for every restart of solver in optimization process (default 1), see 'Details'.
tol	(optional optimization parameter) relative tolerance on feasibility and optimality in optimization process (default $1e-8$).

2 ldexpdose

Details

While D-efficiency is NaN, an increase in prec can be beneficial to achieve a numeric value, however, it can slow down the calculation speed.

Values of n. restarts and n. sim should be chosen according to the length of design interval.

Value

plot of derivative function, see 'Note'. a list containing the following values:

points obtained design points

weights corresponding weights to the obtained design points

det.value value of Fisher information matrix determinant at the obtained design

user.eff D-efficeincy of user design, if user.design and user.weights are not NULL.

Note

To verify optimality of obtained design, derivate function (symmetry of Frechet derivative with respect to the x-axis) will be plotted on the design interval. Based on the equivalence theorem (Kiefer, 1974), a design is optimal if and only if its derivative function are equal or less than 0 on the design interval. The equality must be achieved just at the obtained points.

Author(s)

Ehsan Masoudi, Majid Sarmad and Hooshang Talebi

References

Masoudi, E., Sarmad, M. and Talebi, H. 2012, An Almost General Code in R to Find Optimal Design, In Proceedings of the 1st ISM International Statistical Conference 2012, 292-297.

Dette, H., Kiss, C., Bevanda, M. and Bretz, F. (2010), Optimal designs for the emax, log-linear and exponential models. Biometrika, 97 513-518.

Kiefer, J. C. (1974), General equivalence theory for optimum designs (approximate theory). Ann. Statist., 2, 849-879.

See Also

```
cfisher, cfderiv and eff.
```

Examples

```
ldexpdose(a = 1, b = 2, c = 3, lb = 0, ub = 9) ## $points: 0.000000 6.471562 9.000000
## D-effecincy computation|:
ldexpdose(a = 1, b = 2, c = 3, lb = 0, ub = 9, user.points = c(1, 5, 4),
user.weights = rep(.33, 3))## $user.eff: 0.07392
```

Index

```
*Topic Exponential
1dexpdose, 1
*Topic equivalence theorem
1dexpdose, 1
*Topic optimal design
1dexpdose, 1

cfderiv, 2
cfisher, 2
curve, 1

eff, 2

ldexpdose, 1
```