# GRADIENT, DIVERGENCE, CURL, AND FLUID FLOW

#### I. VECTOR CALCULUS

#### A. Scalar and vector fields

- Physical quantities generally vary systematically from point to point. They are functions of the coordinates, such as (x, y, z).
- A scalar field is a function of the form:  $V(x, y, z) = V(\vec{r})$ . A scalar field associates a scalar with each point in space. Gravitational potential in a region is an example of a scalar field.
- A vector field is a vector function of the form:  $\vec{F}(x,y,z) = \vec{F}(\vec{r})$ . It has three components  $F_i(x,y,z)$ , where i=1,2,3. A vector field associates a vector with each point in space. Gravitational field in a region is an example of a vector field.
- Since a scalar field f depends on all three coordinates, there are three independent first derivatives  $\frac{\partial f}{\partial x}$ ,  $\frac{\partial f}{\partial y}$  and  $\frac{\partial f}{\partial x}$  at each point (x, y, z). These three quantities form the components of a vector field. This is called the gradient of the scalar field.

### B. A generic set of orthogonal coordinates

Consider a generic orthogonal coordinate system  $(q_1, q_2, q_3)$ . The line element  $d\vec{r}$  of displacement from  $q_1, q_2, q_3$  to  $q_1 + dq_1, q_2 + dq_2, q_3 + dq_3$  is:

$$d\vec{r} = \sum_{i}^{3} \frac{\partial \vec{r}}{\partial q_{i}} dq_{i} = \sum_{i=1}^{3} \left| \frac{\partial \vec{r}}{\partial q_{i}} \right| dq_{i} \, \hat{q}_{i} = \sum_{i=1}^{3} h_{i} \, dq_{i} \, \hat{q}_{i}$$

$$\tag{1}$$

The surface area element dS and volume element dV are

$$dS = h_1 h_2 \delta q_1 \delta q_2, \qquad dV = h_1 h_2 h_3 \delta q_1 \delta q_2 \delta q_3 \tag{2}$$

1. The gradient operator

The change in a scalar field f as we move from a point  $\vec{r}$  to a neighbouring point  $\vec{r} + d\vec{r}$  can be written in this coordinate as:

$$df = \vec{\nabla}f \cdot d\vec{r} = \frac{\partial f}{\partial q_1} dq_1 + \frac{\partial f}{\partial q_2} dq_2 + \frac{\partial f}{\partial q_3} dq_3$$
(3)

From the definition of the gradient  $df = \vec{\nabla} f \cdot d\vec{r}$ , and the expression of line element given in Eq.(1), we can identify the Gradient operator in spherical coordinates:

$$\vec{\nabla}f = \frac{1}{h_1} \frac{\partial f}{\partial q_1} + \frac{1}{h_2} \frac{\partial f}{\partial q_2} + \frac{1}{h_3} \frac{\partial f}{\partial q_3} = \frac{1}{h_1} \partial_{q_1} f + \frac{1}{h_2} \partial_{q_1} f + \frac{1}{h_3} \partial_{q_1} f \tag{4}$$

2. Divergence of a vector field

The divergence of a vector field in arbitrary orthogonal coordinate is given in:

$$\vec{\nabla} \cdot \vec{A} = \frac{1}{h_1 h_2 h_3} \left[ \partial_{q_1} (h_2 h_3 A_1) + \partial_{q_2} (h_1 h_3 A_2) + \partial_{q_3} (h_1 h_2 A_3) \right] \tag{5}$$

A derivation of the above is given subsection IG

#### 3. Curl of a vector field

The divergence of a vector field in arbitrary orthogonal coordinate is given in:

$$\vec{\nabla} \times \vec{A} = \frac{1}{h_1 h_2 h_3} \begin{vmatrix} \hat{q}_1 h_1 & \hat{q}_2 h_2 & \hat{q}_3 h_3 \\ \partial_{q_1} & \partial_{q_2} & \partial_{q_3} \\ A_1 h_1 & A_2 h_2 & A_3 h_3 \end{vmatrix}$$
(6)

A derivation of the above is given subsection IJ.

## 4. Connection to other coordinates

- Cartesian coordinates. Here  $q_1 = x$ ,  $q_2 = y$ , and  $q_3 = z$ . We also have  $h_1 = h_2 = h_3 = 1$ .
- Cylindrical coordinates. Here  $q_1 = \rho$ ,  $q_2 = \phi$ , and  $q_3 = z$ . We also have  $h_1 = 1$ .  $h_2 = \rho$ ,  $h_3 = 1$ .
- Spherical coordinates. Here  $q_1 = r$ ,  $q_2 = \theta$ , and  $q_3 = \phi$ . We also have  $h_1 = 1$ ,  $h_2 = r$ , and  $h_3 = r \sin \theta$ .

#### C. 2D plane polar coordinates

The position vector is

$$|\vec{r} = \rho \hat{\rho}| \tag{7}$$

Line element is the change  $d\vec{r}$  in the position vector as one moves from  $(\rho, \phi)$  to  $(\rho + d\rho, \phi + d\phi)$ . There are two ways to find it: (a) geometrically (graphically) or (b) algebraically. In Fig.1, we show this graphically. The line element is:

$$d\vec{r} = d\rho \,\hat{\rho} + \rho \,d\phi \,\hat{\phi} \tag{8}$$

We can also define the area element dS as

$$dS = \rho \, d\rho \, d\phi \tag{9}$$

## 1. Velocity and kinetic energy

The velocity follows from the line element expression given in Eq.(8). The expression of the velocity  $\vec{v}$  is:

$$\vec{v} = \dot{\vec{r}} = \dot{\rho}\,\hat{\rho} + \rho\dot{\phi}\,\hat{\phi} \tag{10}$$

Having obtained the velocity, the expression of the kinetic energy is:

$$T = \frac{1}{2}m(\vec{v}\cdot\vec{v}) = \frac{1}{2}m(\dot{\rho}^2 + \rho^2\dot{\phi}^2). \tag{11}$$

In the above, we note that the  $\hat{\rho} \cdot \hat{\phi} = 0$ .

## $2. \quad The \ gradient \ operator \ in \ 2D \ polar \ coordinates$

The change in a scalar field f as we move from a point  $\vec{r}$  to a neighbouring point  $\vec{r} + d\vec{r}$  can be written in polar coordinates as:

$$df = \frac{\partial f}{\partial \rho} \delta \rho + \frac{\partial f}{\partial \phi} \delta \phi \tag{12}$$

From the definition of the gradient  $df = \vec{\nabla} f \cdot d\vec{r}$ , and the expression of line element given in Eq.(8), we can identify the Gradient operator in 2D polar coordinates:

$$\vec{\nabla} = \hat{\rho} \frac{\partial}{\partial \rho} + \hat{\phi} \frac{1}{\rho} \frac{\partial}{\partial \phi} \tag{13}$$




Figure 1. Line element of the two-dimensional (2D) polar coordinates  $(\rho, \phi)$ .

#### D. Cylindrical coordinates

The cylindrical coordinate system is one of many three-dimensional coordinate systems. The following can be used to convert them to Cartesian coordinates

$$x = \rho \cos \phi, \qquad y = \rho \sin \phi, \qquad z = z.$$
 (14)

The position vector is

$$\vec{r} = \rho \hat{\rho} + z\hat{z} \tag{15}$$

- $\rho = \sqrt{x^2 + y^2}$  is the distance in xy-plane
- $\phi = \tan^{-1}(y/x)$  is the angle measured up from the x-axis.
  - 1. Line element, Velocity and kinetic energy in cylindrical coordinates

The line element  $d\vec{r}$  for an infinitesimal displacement from  $(\rho, \phi, z)$  to  $(\rho + d\rho, \phi + d\phi, z + dz)$  is given as:

$$d\vec{r} = d\rho \,\hat{\rho} + \rho d\phi \,\hat{\phi} + dz \,\hat{z}. \tag{16}$$

See Fig.2 for a graphical representation of the line element. Using the above expression of line element, we can write the velocity as:

$$\vec{v} = \dot{\vec{r}} = \dot{\rho}\hat{\rho} + \rho\dot{\phi}\hat{\phi} + \dot{z}\hat{z} \tag{17}$$

The corresponding expression of kinetic energy is

$$T = \frac{1}{2} (\vec{v} \cdot \vec{v}) = \frac{1}{2} m \left( \dot{\rho}^2 + \rho^2 \dot{\phi}^2 + \dot{z}^2 \right)$$
 (18)

In the above, we note that the unit vectors are orthonormal  $\hat{\rho} \cdot \hat{\phi} = 0$ ,  $\hat{\rho} \cdot \hat{z} = 0$ , and  $\hat{\phi} \cdot \hat{z} = 0$  along with the fact that  $\hat{\rho} \cdot \hat{\rho} = 1$ ,  $\hat{\phi} \cdot \hat{\phi} = 1$ , and  $\hat{z} \cdot \hat{z} = 1$ .




Figure 2. The cylindrical coordinates  $(\rho, \phi, z)$ .

2. The gradient operator in cylindrical coordinates

The change in a scalar field f as we move from a point  $\vec{r}$  to a neighbouring point  $\vec{r} + d\vec{r}$  can be written in cylindrical polar coordinates as:

$$df = \frac{\partial f}{\partial \rho} \delta \rho + \frac{\partial f}{\partial \phi} \delta \phi + \frac{\partial f}{\partial z} \delta z \tag{19}$$

From the definition of the gradient  $df = \vec{\nabla} f \cdot d\vec{r}$ , and the expression of line element given in Eq.(16), we can identify the Gradient operator in cylindrical coordinates:

$$\vec{\nabla} = \hat{\rho} \frac{\partial}{\partial \rho} + \hat{\phi} \frac{1}{\rho} \frac{\partial}{\partial \phi} + \hat{z} \frac{\partial}{\partial z}$$
 (20)

## E. Spherical coordinates

The spherical coordinate system is one of many three-dimensional coordinate systems. They are useful in problems with spherical symmetry. The position vector is


$$\vec{r} = r\,\hat{r} \tag{21}$$

The following can be used to convert them to Cartesian coordinates

$$x = \rho \cos \phi = r \cos \phi \sin \theta, \qquad y = \rho \sin \phi = r \sin \phi \sin \theta, \quad z = r \cos \theta$$
 (22)

(23)

A careful observation of Fig.3 reveals that the line element  $d\vec{r}$  for an infinitesimal displacement from  $r, \theta, \phi$  to






Figure 3. The spherical coordinates  $(r, \theta, \phi)$ .

r + dr,  $\theta + d\theta$ ,  $\phi + d\phi$  is

$$d\vec{r} = dr\,\hat{r} + r\,d\theta\,\hat{\theta} + r\sin\theta\,d\phi\,\hat{\phi} \tag{24}$$

The velocity is then

$$\vec{v} = \dot{r}\,\hat{r} + r\,\dot{\theta}\,\hat{\theta} + r\sin\theta\,\dot{\phi}\,\hat{\phi} \tag{25}$$

The kinetic energy is:

$$T = \frac{1}{2}mv^2 = \frac{1}{2}m\left(\dot{r}^2 + r^2\dot{\theta}^2 + r^2\sin^2\theta\dot{\phi}^2\right)$$
 (26)

1. The gradient operator in spherical coordinates

The change in a scalar field f as we move from a point  $\vec{r}$  to a neighbouring point  $\vec{r} + d\vec{r}$  can be written in spherical polar coordinates as:

$$df = \frac{\partial f}{\partial r}dr + \frac{\partial f}{\partial \theta}d\theta + \frac{\partial f}{\partial \phi}d\phi \tag{27}$$

From the definition of the gradient  $df = \vec{\nabla} f \cdot d\vec{r}$ , and the expression of line element given in Eq.(16), we can identify the Gradient operator in spherical coordinates:

$$\vec{\nabla} = \hat{r}\frac{\partial}{\partial r} + \hat{\theta}\frac{1}{r}\frac{\partial}{\partial \theta} + \hat{\phi}\frac{1}{r\sin\theta}\frac{\partial}{\partial \phi}$$
 (28)

## F. Additive property of the flux

The flux of a vector field  $\vec{A}$  over a surface S with the normal vector  $\hat{n}$  is defined as:

$$\Phi = \oint_{S} \vec{A} \cdot d\vec{S} = \oint_{S} \vec{A} \cdot \hat{n} \, dS \tag{29}$$

Consider three closed surface: S,  $S_1$  and  $S_2$ . The surface  $S_1$  and  $S_2$  can be combined to form the surface S along with an internal region which is shared by the two surfaces  $S_1$  and  $S_2$ . Note that the normal vector is in opposite

directions on the internal surface. By convention, the normal vector  $\hat{n}$  is outward normal from the volume of a closed surface. Thus, we have:

$$\oint_{S} \vec{A} \cdot d\vec{S} = \oint_{S_1} \vec{A} \cdot d\vec{S} + \oint_{S_2} \vec{A} \cdot d\vec{S}$$
(30)

Note that the contribution from the interior surface vanishes identically as the normal vectors are in opposite directions.

#### G. Derivation of divergence in an orthogonal coordinate system

The divergence of a vector field at any point is its flux per unit volume at that point. Divergence of a vector field  $\vec{A}$  can then be explicitly written as:

$$\vec{\nabla} \cdot \vec{A} = \operatorname{div} \vec{A} = \lim_{\delta V \to 0} \frac{\oint_{\delta S} \vec{A} \cdot d\vec{S}}{\delta V}$$
 (31)




Figure 4. A volume element in an orthogonal set of coordinates. The coordinates are:  $(q_1, q_2, q_3)$ .

- Draw a very small cube of volume  $\delta V$  and compute the flux through it  $\Phi = \oint_S \vec{A} \cdot d\vec{S} = \oint_S \vec{A} \cdot \hat{n} \, dS$ .
- First compute flux of face with sides  $h_2dq_2$  and  $h_3dq_3$ . See Fig.(4).
- The normal vector is  $-\hat{q}_1$
- The flux is:  $-(A_1h_2h_3) dq_2dq_3$
- What is the flux through the opposite side? Please note that  $A_1$  and  $h_2, h_3$  all vary with q, so the flux will be:

$$\left[ (A_1 h_2 h_3) + \frac{\partial (A_1 h_2 h_3)}{\partial q_1} dq_1 \right] dq_2 dq_3 \tag{32}$$

• Flux through planes normal to  $\hat{q}_1$  direction:

$$\Phi_1 = \frac{1}{h_1 h_2 h_3} \left( \frac{\partial (h_2 h_3 A_1)}{\partial q_1} \right) dV \tag{33}$$

• Flux through planes normal to  $\hat{q}_2$  direction:

$$\Phi_2 = \frac{1}{h_1 h_2 h_3} \left( \frac{\partial (h_1 h_3 A_2)}{\partial q_2} \right) dV \tag{34}$$

• Flux through planes normal to  $\hat{q}_3$  direction:

$$\Phi_3 = \frac{1}{h_1 h_2 h_3} \left( \frac{\partial (h_1 h_2 A_3)}{\partial q_3} \right) dV \tag{35}$$

• The divergence of a vector field at any point is its flux per unit volume at that point. Divergence of vector field  $\vec{A}$  is then given as:

$$\vec{\nabla} \cdot \vec{A} = \lim_{dV \to 0} \frac{\oint_{\delta S} \vec{A} \cdot d\vec{S}}{dV} = \frac{1}{h_1 h_2 h_3} \left[ \frac{\partial (h_2 h_3 A_1)}{\partial q_1} + \frac{\partial (h_1 h_3 A_2)}{\partial q_2} + \frac{\partial (h_1 h_2 A_3)}{\partial q_3} \right]$$
(36)

This completes the derivation of Eq.(5).

#### H. Gauss divergence theorem

• The divergence is defined as:

$$\operatorname{div} \vec{A} = \vec{\nabla} \cdot \vec{A} = \lim_{\delta V \to 0} \frac{\oint_{\delta S} \vec{A} \cdot d\vec{S}}{\delta V}$$

• The definition of divergence implies that

$$\left(\vec{\nabla} \cdot \vec{A}\right) \, \delta V = \oint_{\delta S} \vec{A} \cdot d\vec{S}$$

• Sum over small volume elements:

$$\sum_{i} \left( \vec{\nabla} \cdot \vec{A} \right) \, \delta V_{i} = \sum_{i} \oint_{\delta S_{i}} \vec{A} \cdot d\vec{S}$$

• In the limit of  $\delta V_i \to 0$ , we have (using additive nature of the flux):

$$\int_{V} \left( \vec{\nabla} \cdot \vec{A} \right) dV = \oint_{S} \vec{A} \cdot d\vec{S} \tag{37}$$

• Thus, we obtain the Gauss's divergence theorem which enables us to write the surface integral of any vector field  $\vec{A}$  over a closed surface S as the volume integral of the div  $\vec{A}$  over the volume of space enclosed by S.

#### I. The continuity equation

- Consider the flow of a fluid or of electric charge.
- $\rho(\vec{r},t)$  is charge density (or mass density of the fluid).
- $\vec{J}(\vec{r},t)$  is the corresponding current density (of mass or charge) crossing unit area per unit time.
- The flux of  $\vec{J}$  over a closed surface equals the rate at which charge (or mass) leaves the volume enclosed by surface.

$$-\frac{d}{dt}\int\rho\,dV = \int\vec{J}\cdot d\vec{S} \tag{38}$$

• We now use the Gauss's divergence theorem on the RHS to obtain:

$$-\frac{d}{dt} \int \rho \, dV = \int \vec{\nabla} \cdot \vec{J} \, dV \implies \int \left(\frac{\partial \rho}{\partial t} + \vec{\nabla} \cdot \vec{J}\right) dV = 0 \tag{39}$$

• The continuity equation is then:

$$\frac{\partial \rho}{\partial t} + \vec{\nabla} \cdot \vec{J} = 0. \tag{40}$$

The conservation law of a physical quantity is expressed as a continuity equation. Equation of continuity is 'local' statement of conservation. Equation of continuity is the basic relationship, the associated global conservation laws being a consequence that follows from it.

• The global statement for the total mass [or charge] in the region concerned satisfies

$$\frac{d}{dt} \int_{V} \rho \, dV = 0.$$

The total mass (or charge) is constant in time, if the volume is so large, that the current vanishes on the surface.

## J. Derivation of curl in an orthogonal coordinate system

• Consider an open surface S whose boundary is the closed curve C. The line integral of a vector field Aâ over the closed path C :

$$\oint_C \vec{A} \cdot d\vec{r} \tag{41}$$

• The curl of a vector field  $\vec{A}$  is defined as:

$$\left(\vec{\nabla} \times \vec{A}\right) \cdot \hat{n} = \lim_{\delta S \to 0} \frac{\oint_C \vec{A} \cdot d\vec{r}}{\delta S} \tag{42}$$

Here  $\hat{n}$  is the outward normal.

- Consider the integral  $\oint_C \vec{A} \cdot d\vec{r}$  along boundary of the rectangle PQRSP shown in Fig.5.
- On the curves, PQ and RS the line integral is:  $\mp A_1\left(q_1,q_2\pm\frac{h_2\delta q_2}{2},q_3\right)\,h_1\delta q_1$
- On the curves, QR and SP the line integral is:  $\pm A_2 \left(q_1 \pm \frac{h_1 \delta q_1}{2}, q_2, q_3\right) h_2 \delta q_2$
- Thus, we have

$$\oint_{C} \vec{A} \cdot d\vec{l} = [\partial_{q_{1}} (h_{2} A_{2}) - \partial_{q_{2}} (h_{1} A_{1})] \delta q_{1} \delta q_{2}$$
(43)

- Note that  $dS = h_1 h_2 \, \delta q_1 \delta q_2$
- Thus, we have

$$\frac{\oint_{C} \vec{A} \cdot d\vec{l}}{dS} = \left[\partial_{q_{1}} (h_{2} A_{2}) - \partial_{q_{2}} (h_{1} A_{1})\right] \frac{h_{3}}{h_{1} h_{2} h_{3}} = \left(\vec{\nabla} \times \vec{A}\right) \cdot \hat{q}_{3}$$
(44)

• Finally, we identify the curl of a vector field as:

$$\operatorname{curl} \vec{A} = \vec{\nabla} \times \vec{A} = \frac{1}{h_1 h_2 h_3} \begin{vmatrix} \hat{q}_1 h_1 & \hat{q}_2 h_2 & \hat{q}_3 h_3 \\ \partial_{q_1} & \partial_{q_2} & \partial_{q_3} \\ A_1 h_1 & A_2 h_2 & A_3 h_3 \end{vmatrix}$$
(45)




Figure 5. An area element in an orthogonal set of coordinates. The coordinates are:  $(q_1, q_2, q_3)$ .

#### K. The Stokes theorem

• For a path  $\delta C$  that bounds an infinitesimal area element  $\delta S$ , we have:

$$\left(\vec{\nabla} \times \vec{A}\right) \cdot \hat{n} = \lim_{\delta S \to 0} \frac{\oint_C \vec{A} \cdot d\vec{r}}{\delta S} \tag{46}$$

• A finite area S bounded by a curve C can be broken into infinitesimal area elements  $\delta S_1, \delta S_2, \ldots, \delta S_n$  bounded by curves  $\delta C_1, \delta C_2, \ldots, \delta C_n$ , respectively such that

$$\oint_{C} \vec{A} \cdot d\vec{r} = \sum_{i=1}^{n} \oint_{\delta C_{i}} \vec{A} \cdot d\vec{r}$$
(47)

• We know that the RHS equals the surface integral of the  $\nabla \times \vec{A}$  over the finite area S. Thus, we obtain the Stokes' Theorem:

$$\oint_{C} \vec{A} \cdot d\vec{r} = \int (\vec{\nabla} \times \vec{A}) \cdot \hat{n} \, dS = \int (\operatorname{curl} \vec{A}) \cdot \hat{n} \, dS \tag{48}$$

• Stokes' theorem: The circulation of a vector field  $\vec{A}$  over a closed curve C equals the surface integral of curl  $\vec{A}$  over a surface S that is bounded by C.

## II. FUNDAMENTAL EQUATIONS OF FLUID DYNAMICS

The state of the fluid at any instant of time is described by a scalar field  $\rho(\vec{r},t)$ , which is the mass density of the fluid (or mass per unit volume) and a vector field  $\vec{r}(\vec{r},t)$ , which is the fluid velocity.

Convective derivative (also called material or total derivative) is the rate of change of a quantity - that can be temperature T or fluid velocity  $\vec{v}$  - belonging to certain moving particle. It is defined as:

$$\frac{d}{dt}\vec{v} = \left(\frac{\partial}{\partial t} + \vec{v} \cdot \vec{\nabla}\right)\vec{v} \tag{49}$$

Conservation of matter and continuity equation In a given volume element dV, the mass of the fluid is

$$\int \rho \, dV.$$

Here  $\rho$  is the mass density of the fluid (or mass per unit volume). The mass of the fluid in a volume can change if there is a flux of fluid into or away from the volume. Clearly, the total flux of the fluids into (or away) from this volume element

$$\int \rho \, \vec{v} \cdot d\vec{S} = \int \rho \, \vec{v} \cdot \hat{n} \, dS.$$

Finally, we can combine the rate of change of mass with flux by rewriting the above as a continuity equation (see also section II on how to Gauss divergence theorem to convert the above to a volume integral):

$$\frac{\partial \rho}{\partial t} = -\vec{\nabla} \cdot \vec{J}, \qquad \vec{J} = \rho \vec{v} \tag{50}$$

We know that the density of the fluid is constant for an incompressible, homogeneous fluid. Thus, the continuity equations reduces to:

$$\nabla \cdot \vec{v} = 0. \tag{51}$$

#### A. Navier-Stokes equations

We now apply Newton's law to a volume element dV located at the position vector  $\vec{r}$  at time t. The force per unit volume on a static volume element of the fluid is:

$$-\vec{\nabla}P + \vec{f}_{ext} \tag{52}$$

Here P is the fluid pressure, while  $f_{ext}$  is external force per unit volume in the fluid. For example, in case of gravity  $f_{ext} = \rho \vec{g}_{ext}$ . In addition, there is also a dissipative force, due to viscosity (coming from relative motion between layers of the fluid). It is of the form:

$$\eta \nabla^2 \vec{v}$$
 (53)

Here  $\eta$  is the viscosity of the fluid. The Navier-Stokes equations are then

$$\rho \frac{d\vec{v}}{dt} = -\vec{\nabla}P + \eta \nabla^2 \vec{v} + \vec{f}_{ext} \tag{54}$$

Using, Eq.(49), we can rewrite the Navier-Stokes equations as:

$$\rho \left[ \frac{\partial \vec{v}}{\partial t} + (\vec{v} \cdot \nabla) \vec{v} \right] = -\vec{\nabla} P + \eta \nabla^2 \vec{v} + \vec{f}_{ext}$$
 (55)

In case of conservative external force, we can write  $\vec{f}_{ext} = -\rho \vec{\nabla} \Psi$ . The Navier-Stokes equation is then:

$$\frac{\partial \vec{v}}{\partial t} + (\vec{v} \cdot \nabla)\vec{v} = -\frac{1}{\rho}\vec{\nabla}P - \vec{\nabla}\Psi + \frac{\eta}{\rho}\nabla^2\vec{v}$$
 (56)

## B. Euler's equation

In certain cases (at very high Reynolds numbers), the viscous effects can be ignored, the Navier-Stokes equation then reduces to the Euler's equation

$$\frac{\partial \vec{v}}{\partial t} + (\vec{v} \cdot \nabla)\vec{v} = -\frac{1}{\rho}\vec{\nabla}P - \vec{\nabla}\Psi \tag{57}$$

The above equation was obtained by L. Euler in 1755. The Euler equation can be rewritten as:

$$\frac{\partial \vec{v}}{\partial t} - \vec{v} \times \left( \vec{\nabla} \times \vec{v} \right) = -\frac{1}{\rho} \vec{\nabla} P - \vec{\nabla} \left[ \Psi + \frac{v^2}{2} \right]$$
 (58)

Here, we have used:

$$(\vec{v} \cdot \nabla)\vec{v} = \vec{\nabla}\left(\frac{v^2}{2}\right) - \vec{v} \times \left(\vec{\nabla} \times \vec{v}\right) \tag{59}$$

To prove the above, we note

$$\left(\vec{a} \times \vec{b}\right)_i = \epsilon_{ijk} \ a_j \ b_k, \qquad \epsilon_{ijk} \ \epsilon_{ilm} = \delta_{jl} \ \delta_{km} - \delta_{jm} \ \delta_{kl}.$$

Thus, we have

$$\left[\vec{v}\times\left(\vec{\nabla}\times\vec{v}\right)\right]_{i}=\epsilon_{ijk}v_{j}\epsilon_{klm}\nabla_{l}v_{m}=\delta_{il}\delta_{jm}v_{j}\nabla_{l}v_{m}-\delta_{im}\delta_{jl}v_{j}\nabla_{l}v_{m}=v_{j}\nabla_{i}v_{j}-v_{j}\nabla_{j}v_{i}=v_{j}\left(\nabla_{i}v_{j}-\nabla_{j}v_{i}\right)$$

Finally, note that

$$\frac{1}{2}\vec{\nabla}(\vec{v}\cdot\vec{v}) = \frac{1}{2}\nabla_i(v_jv_j) = v_j\left(\nabla_iv_j - \nabla_jv_i\right) + v_j\nabla_jv_i = \vec{v}\times(\nabla\times\vec{v}) + (\vec{v}\cdot\nabla)\vec{v}.$$

#### C. Streamlines and lines of flow

- Streamlines are a family of curves whose tangent vectors constitute the velocity vector field of the flow
  - streamlines are the field lines of the velocity vector field  $\vec{v}(\vec{r},t)$  at any given instant of time
  - Streamlines give instantaneous velocities at all points in space.
- Since the streamline is line with its tangent at any point in a fluid parallel to the instantaneous velocity of the fluid at that point, it must follow  $d\vec{r} \times \vec{v} = 0$ . Thus, the equation of streamlines follow:

1. 
$$dx v_y - dy v_x = 0$$
, which implies,  $\frac{dy}{v_y} = \frac{dx}{v_x}$ 

2. 
$$dx v_z - dz v_x = 0$$
, which implies,  $\frac{dz}{v_z} = \frac{dx}{v_x}$ 

3. 
$$dy v_z - dz v_y = 0$$
, which implies,  $\frac{dy}{v_y} = \frac{dz}{v_z}$ 

- For a steady flow, the streamlines in a fluid will remain unchanged in time.
- For non-steady flows, the streamline pattern will evolve with time.
- A line of flow is the actual path traced by an infinitesimal element of the moving fluid as time progresses.
- In a steady flow, lines of flow and streamlines coincide. However, for non-steady flow, lines of flow and streamlines are in general distinct from each other.

## D. Barotropic flows and Bernoulli's principle

We now consider steady conditions such that

$$\frac{\partial \vec{v}}{\partial t} = 0.$$

The Euler equation of Eq.(58) is then:

$$\vec{v} \times \left( \vec{\nabla} \times \vec{v} \right) = \frac{1}{\rho} \vec{\nabla} P + \vec{\nabla} \left[ \Psi + \frac{v^2}{2} \right] \tag{60}$$

At a fixed temperature the pressure P is a function of the mass density  $\rho$ . Such flows are called barotropic flows  $\rho = \rho(P)$ . Thus, the integral  $\int dP/\rho(P)$  can be written as a function  $\Lambda(P)$  of the pressure such that

$$\Lambda(P) = \int \frac{dP}{\rho} \qquad \Longrightarrow \qquad \vec{\nabla}\vec{\Lambda} = \frac{1}{\rho}\vec{\nabla}P \tag{61}$$

In the above, we have used

$$d\Lambda = \frac{dP}{\rho} \qquad \Longrightarrow \qquad \vec{\nabla}\Lambda \cdot d\vec{r} = \frac{\vec{\nabla}P \cdot d\vec{r}}{\rho} \tag{62}$$

Thus, for barotropic flows, Eq.60 becomes:

$$\vec{v} \times \left(\vec{\nabla} \times \vec{v}\right) = \vec{\nabla} \left[ \int \frac{dP}{\rho} + \Psi + \frac{v^2}{2} \right]$$
 (63)

Taking a dot product of the above equations with the fluid velocity  $\vec{v}$ , we get:

$$\vec{v} \cdot \vec{\nabla} \left[ \int \frac{dP}{\rho} + \Psi + \frac{v^2}{2} \right]. \tag{64}$$

Thus the scalar function  $\left[\int \frac{dP}{\rho} + \Psi + \frac{v^2}{2}\right]$  does not change under a displacement along the streamline. In other words,

$$\int \frac{dP}{\rho} + \Psi + \frac{v^2}{2} = C = \text{a constant along a given streamline}$$
 (65)

Here C is a constant along a streamline. This is known as Bernoulli's principle. For an incompressible fluid ( $\rho$  = constant) in a gravitational field ( $\Psi = gz$ , where z denotes vertical direction), we recover the familiar expression:

$$P + \rho gz + \frac{\rho v^2}{2} = \text{a constant along a given streamline}$$
 (66)

Note that the constant will vary on each streamline. It is useful to note that the LHS of (63) identically vanishes for irrotational flows ( $\vec{\nabla} \times \vec{v} = 0$ ). For such flows, the function  $\int \frac{dP}{\rho} + \Psi + \frac{v^2}{2}$  is a constant throughout the fluid.

$$\int \frac{dP}{\rho} + \Psi + \frac{v^2}{2} = C = \text{ a constant throughout the fluid for irrotational flows}$$
 (67)

### Appendix

Please note that the contents of this appendix are not in syllabus.

1. Dimensionless Numbers for the Navier-Stokes equations

It is useful to make the Navier-Stokes equations of Eq.(55) dimensionless using:

$$r^* = r/L, \qquad \nabla^* = L\nabla, \qquad \mathbf{v}^* = \mathbf{v}/V, \qquad t^* = t/(L/V).$$
 (68)

Here L is the typical length scale in the system, while V is the typical velocity scale.

$$\frac{\partial \vec{v}^*}{\partial t^*} + (\vec{v}^* \cdot \nabla^*) \vec{v}^* = \frac{\nabla^{*2} \vec{v}^* - \nabla^* p^*}{\text{Re}} + \frac{1}{\text{Fn}} \vec{\hat{g}}$$
(69)

Here Re is called the Reynolds number, while Fn is the Froude number and we have used  $\vec{f}_{ext} = \rho g$ , where g is acceleration due to gravity. The Reynolds number is the ratio of inertial to viscous forces. The Froude number is a ratio of inertial and gravitational forces.

$$Re = \frac{\rho VL}{\mu}, \qquad Fn = \frac{V^2}{Lg}, \tag{70}$$

The Froude number Fn deals with the relationship between gravity and inertial forces

The Reynolds number Re deals with the relationship between viscous and inertial forces