Simple Two-Way Direct Loss Measurement Procedure

draft-gandhi-ippm-simple-direct-loss-00

```
Rakesh Gandhi - Cisco Systems (<u>rgandhi@cisco.com</u>) - Presenter Clarence Filsfils - Cisco Systems (<u>cfilsfil@cisco.com</u>)
```

Daniel Voyer - Bell Canada (<u>daniel.voyer@bell.ca</u>)

Mach(Guoyi) Chen - Huawei (<u>mach.chen@huawei.com</u>)

Bart Janssens - Colt (<u>Bart.Janssens@colt.net</u>)

Stefano Salsano - Universita di Roma "Tor Vergata" (stefano.salsano@uniroma2.it)

Agenda

- Requirements and Scope
- Summary
- Next Steps

Requirements and Scope

Requirements:

- Direct Loss Measurement (DLM) for accurate data packet loss
- Support Alternate-Marking Method (AMM) [RFC 8321]
- High scale for number of sessions and faster packet loss detection interval
 - Support hardware implementation

Goals:


- Avoid provisioning and maintaining sessions on Session-Reflector
- Avoid control protocol for signaling dynamic parameters

Scope:


Follow STAMP [RFC 8762] approach

Alternate Marking Method for Packet Loss

- RFC 8321 Alternate-Marking Method for Passive and Hybrid Performance Monitoring
- RFC 8957 Synonymous Flow Label Framework



1. STAMP Test Packets with Direct Measurement TLV



| 0 1 2 2 4 5 6 7 9 9 9 1 2 2 4 5 6 7 9 9 9 1 | | | | |
|---|--|--|--|--|
| 0 1 2 3 4 5 6 7 8 9 0 1 2 3 4 5 6 7 8 9 0 1 2 3 4 5 6 7 8 9 0 1 | | | | |
| Sequence Number | | | | |
| +- | | | | |
| Timestamp | | | | |
| +++++++++++++++++++++++++++++++++++++++ | | | | |
| Error Estimate SSID +-+-+-+-+-+-+-+-+-+-+-+-+-+-+-+-+-+-+ | | | | |
| Receive Timestamp | | | | |
| +-+-+-+-+-+-+-+-+-+-+-+-+-+-+-+-+-+-+- | | | | |
| Session-Sender Sequence Number | | | | |
| +- | | | | |
| Session-Sender Timestamp | | | | |
| ' +-+-+-+-+-+-+-+-+-+-+-+-+-+-+-+-+-+-+- | | | | |
| Session-Sender Error Estimate MBZ | | | | |
| +-+-+-+-+-+-+-+-+-+-+-+-+-+-+-+-+-+-+- | | | | |
| Ses-Sender TTL MBZ2 | | | | |
| +- | | | | |
| | | | | |
| | | | | |
| STAMP TLV Flags Type Length | | | | |
| +-+-+-+-+-+-+-+-+-+-+-+-+-+-+-+-+-+-+- | | | | |
| Session-Sender Tx counter (S TxC) | | | | |
| +- | | | | |
| Session-Reflector Rx counter (R_RxC) | | | | |
| +- | | | | |
| Session-Reflector Tx counter (R_TxC) | | | | |
| +- | | | | |
| Figure: Session-Reflector Test Packet Format | | | | |

2. Direct Loss Measurement Probe Packet for Data Packet Loss Detection

- Base Direct Loss Measurement probe packet defined
 - Hardware efficient counter updating
 - Well-known locations for traffic counters
 - Block number of the counters for alternate-marking method [RFC 8321]
 - Traffic class of the counters for per class packet loss
 - DLM probe packet is also defined for authenticated mode
- User-configured destination UDP Port is used for identifying DLM probe packets (different than port 862 and the one used by STAMP)
- Sequence Number allows to monitor DLM session status
- Flags
 - X set to 1 for 64-Bit Counter, set to 0 for 32-Bit Counter
 - B set to 1 for Byte Counter, set to 0 for Packet Counter
 - T set to 1 for Sender-DSCP scoped Counter

```
\begin{smallmatrix} 0 & 1 & 2 & 3 & 4 & 5 & 6 & 7 & 8 & 9 & 0 & 1 & 2 & 3 & 4 & 5 & 6 & 7 & 8 & 9 & 0 & 1 & 2 & 3 & 4 & 5 & 6 & 7 & 8 & 9 & 0 & 1 \\ \end{smallmatrix}
 IP Header
  Source IP Address = Session-Sender IPv4 or IPv6 Address
  Destination IP Address = Session-Reflector IPv4 or IPv6 Addr .
  Protocol = UDP
 UDP Header
  Source Port = As chosen by Session-Sender
  Destination Port = User-configured Port
                  Sequence Number
Transmit Counter (C3)
Block Number | DSID
    Receive Counter (C2)
                  Session-Sender Sequence Number
Session-Sender Counter (C1)
             |Ses-Block Num | MBZ (2 octets)
|FLAGS| Ses-DSCP
    Ses-Sender TTL
Figure: Session-Reflector Direct Loss Measurement Probe Packet
```

Direct Measurement TLV vs. Direct Loss Measurement Probe Packet

| Attributes | 1. Direct Measurement TLV | Define New Direct Measurement TLV? | 2. Direct Loss Measurement Probe Packet |
|---|------------------------------|---------------------------------------|--|
| Need to write timestamp (clock sync needed for one-way delay) | Yes | Yes | No |
| Counter at fixed location in the probe packet for hardware counter writing | No (TLV-based) | No (TLV-based) | Yes |
| Reply probe packets with counter at fixed location for hardware counter-stamping | No | No | Yes |
| Need to scan for DM TLV in each received probe packet on Session-Reflector in hardware (there can be multiple TLVs) | Yes | Yes | No |
| 32-bit and 64-bit Byte counters | No | Yes | Yes |
| 64-bit packet counters | No | Yes | Yes |
| Alternate-marking method packet loss - using block number for counters (out-of-order data packet support) | No | Yes | Yes |
| Per Traffic Class Counters | No | Yes | Yes |

Data Packet Loss Calculation

- Using the Counters C1, C2, C3 and C4 as per reference topology, from the nth and (n-1)th Direct Loss Measurement probe packets.
 - Transmit Loss TxL[n-1, n] = (C1[n] C1[n-1]) (C2[n] C2[n-1])
 - Receive Loss RxL[n-1, n] = (C3[n] C3[n-1]) (C4[n] C4[n-1])
- When using Alternate-Marking Method, all Counters used for the loss calculation belongs to the same Block Number, as described in Section 3.1 of [RFC8321].

Next Steps

- Welcome your comments and suggestions
- Requesting WG adoption

Thank you