Oracle (PL/SQL)

Lesson 9: Built-in Packages in Oracle

Lesson Objectives

- To understand the following topics:
 - Testing and Debugging in PL/SQL
 - DBMS_OUTPUT
 - Enabling and Disabling output
 - Writing to the DBMS_OUTPUT Buffer
 - UTL_file
 - Handling LOB (Large Objects)





Copyright © Capgemini 2015. All Rights Reserved


9.1: Testing and Debugging in PL/SQL DBMS_OUTPUT package

- PL/SQL has no input/output capability
- However, built-in package DBMS_OUTPUT is provided to generate reports
- The procedure PUT_LINE is also provided that places the contents in the buffer

PUT_LINE (VARCHAR2 OR NUMBER OR DATE)



Copyright © Capgemini 2015. All Rights Reserved



The code will be written on SQL prompt

9.2: DBMS_OUTPUT Displaying Output

- DBMS OUTPUT:
 - DBMS_OUTPUT provides a mechanism for displaying information from the PL/SQL program on to your screen (that is your session's output device)
 - The DBMS_OUTPUT package is created when the Oracle database is installed
 - The "dbmsoutp.sql" script contains the source code for the specification of this package
 - This script is called by the "catproc.sql" script, which is normally run immediately after database creation



Copyright © Capgemini 2015. All Rights Reserved

Note:

The catproc.sql script creates the public synonym DBMS_OUTPUT for the package.

Instance-wise access to this package is provided on installation, so no additional steps should be necessary in order to use DBMS_OUTPUT

9.2: Displaying Output DBMS OUTPUT — Program Names

Table: DBMS_OUTPUT programs		
Name	Description	Use in SQL?
DISABLE	Disables output from the package; the DBMS_OUTPUT buffer will not be flushed to the screen.	Yes
ENABLE	Enables output from the package.	Yes
GET_LINE	Gets a single line from the buffer.	Yes
GET_LINE S	Gets specified number of lines from the buffer and passes them into a PL/SQL table.	Yes
NEW_LINE	Inserts an end-of-line mark in the buffer.	Yes
PUT	Puts information into the buffer.	Yes
PUT_LINE	Puts information into the buffer and appends an end-of- line marker after that data.	Yes



Convints in Consumini 2015, All Blobbs Researed

DBMS_OUTPUT Concepts:

- Each user has a DBMS_OUTPUT buffer of up to 1,000,000 bytes in size. You can write information to this buffer by calling the DBMS_OUTPUT.PUT and DBMS_OUTPUT.PUT_LINE programs.
 - ➢ If you are using DBMS_OUTPUT from within SQL*Plus, this information will be automatically displayed when your program terminates.
 - You can (optionally) explicitly retrieve information from the buffer with calls to DBMS_OUTPUT.GET and DBMS_OUTPUT.GET_LINE.
- The DBMS_OUTPUT buffer can be set to a size between 2,000 and 1,000,000 bytes with the DBMS_OUTPUT.ENABLE procedure.
 - If you do not enable the package, no information will be displayed or be retrievable from the buffer.
- The buffer stores three different types of data in their internal representations, namely VARCHAR2, NUMBER, and DATE.
 - These types match the overloading available with the PUT and PUT_LINE procedures.
 - Note that DBMS_OUTPUT does not support Boolean data in either its buffer or its overloading of the PUT procedures

DBMS OUTPUT - Example

• In this example, the following anonymous PL/SQL block uses DBMS_OUTPUT to display the name and salary of each staff member in department 10:

```
DECLARE
CURSOR emp_cur IS SELECT staff_name, staff_sal
FROM staff_master WHERE dept_code = 10
ORDER BY staff_sal DESC;
BEGIN FOR emp_rec IN emp_cur
LOOP
DBMS_OUTPUT.PUT_LINE ('Employee ' ||
emp_rec.staff_name || ' earns ' ||
TO_CHAR (emp_rec.staff_sal) || 'rupees');
END LOOP;
END;
```



Copyright C Cappernini 2015 All Rights Reserved

DBMS_OUTPUT Concepts:

The program shown in the slide generates the following output when executed in SQL*Plus:

Employee John earns 32000 rupees

Employee Mohan earns 24000 rupees

DBMS_OUTPUT Exceptions:

- DBMS_OUTPUT does not contain any declared exceptions. Instead, Oracle designed the package to rely on two error numbers in the -20 NNN range (usually reserved for Oracle customers). You may, therefore, encounter one of these two exceptions when using the DBMS_OUTPUT package (no names are associated with these exceptions).
 - The -20000 error number indicates that these packagespecific exceptions were raised by a call to RAISE_APPLICATION_ERROR, which is in the DBMS_STANDARD package.
- -20000
 - ORU-10027: buffer overflow, limit of <buf_limit> bytes.
 - If you receive the -10027 error, you should see if you can increase the size of your buffer with another call to DBMS_OUTPUT.ENABLE.
- -20000
 - ORU-10028: line length overflow, limit of 255 bytes per line.
 - If you receive the -10028 error, you should restrict the amount of data you are passing to the buffer in a single call to PUT_LINE, or in a batch of calls to PUT followed by NEW_LINE.
- You may also receive the ORA-06502 error:
 - ➤ ORA-06502
 - It is a numeric or value error.
 - If you receive the -06502 error, you have tried to pass more than 255 bytes of data to DBMS_OUTPUT.PUT_LINE. You must break up the line into more than one string.

Drawbacks of DBMS OUTPUT:

- Before learning all about the DBMS_OUPUT package, and rushing to use it, you should be aware of several drawbacks with the implementation of this functionality:
 - The "put" procedures that place information in the buffer are overloaded only for strings, dates, and numbers. You cannot request the display of Booleans or any other types of data. You cannot display combinations of data (a string and a number, for instance), without performing the conversions and concatenations yourself.
 - You will see output from this package only after your program completes its execution. You cannot use DBMS_OUTPUT to examine the results of a program while it is running. And if your program terminates with an unhandled exception, you may not see anything at all!
 - If you try to display strings longer than 255 bytes, DBMS_OUTPUT will raise a VALUE_ERROR exception.
 - DBMS_OUTPUT is not a strong choice as a report generator, because it can handle a maximum of only 1,000,000 bytes of data in a session before it raises an exception.

9.2: Displaying Output Writing to DBMS OUTPUT buffer

 You can write information to the DBMS_OUTPUT buffer with calls to the PUT, NEW_LINE, and PUT_LINE procedures.



Copyright © Caopemini 2015. All Rights Reserved

If you use DBMS_OUTPUT in SQL*Plus, you may find that any leading blanks are automatically truncated. Also, attempts to display blank or NULL lines are completely ignored.

There are workarounds for almost every one of these drawbacks. The solution invariably requires the construction of a package that encapsulates and hides DBMS_OUTPUT.

Writing to DBMS_OUTPUT buffer

- The DBMS OUTPUT.PUT procedure:
- The PUT procedure puts information into the buffer, but does not append a newline marker into the buffer.
 - Use PUT if you want to place information in the buffer (usually with more than one call to PUT), but not also automatically issue a newline marker.
 - The specification for PUT is overloaded, so that you can pass data in its native format to the package without having to perform conversions.

PROCEDURE DBMS OUTPUT.PUT (A VARCHAR2);



Writing to DBMS_OUTPUT buffer: DBMS_OUTPUT.PUT procedure:

Note:

 The specification for PUT is overloaded, so that you can pass data in its native format to the package without having to perform conversions.

PROCEDURE DBMS_OUTPUT.PUT (A VARCHAR2);
PROCEDURE DBMS_OUTPUT.PUT (A NUMBER);
PROCEDURE DBMS_OUTPUT.PUT (A DATE);

where A is the data being passed.

Example:

 In the following example, three simultaneous calls to PUT, place the employee name, department ID number, and hire date into a single line in the DBMS_OUTPUT buffer:

DBMS_OUTPUT.PUT (:employee.lname || ', ' || :employee.fname);
DBMS_OUTPUT.PUT (:employee.department_id);
DBMS_OUTPUT.PUT (:employee.hiredate);

 If you follow these PUT calls with a NEW_LINE call, that information can then be retrieved with a single call to GET_LINE

Writing to DBMS_OUTPUT buffer

- The DBMS_OUTPUT.NEW_LINE procedure:
 - The NEW LINE procedure inserts an end-of-line marker in the buffer.
 - Use NEW_LINE after one or more calls to PUT in order to terminate those entries in the buffer with a newline marker.
 - Given below is the specification for NEW_LINE:

PROCEDURE DBMS_OUTPUT.NEW_LINE;



Copyright © Capgemini 2015. All Rights Reserved

Writing to DBMS_OUTPUT buffer

- The DBMS OUTPUT.PUT LINE procedure:
 - The PUT_LINE procedure puts information into the buffer, and then appends a newline marker into the buffer
- The specification for PUT_LINE is overloaded, so that you can pass data in its native format to the package without having to perform conversions:

PROCEDURE DBMS_OUTPUT.NEW_LINE(A VARCHAR2);



Copyright © Capgemini 2015. All Rights Reserved

Writing to DBMS_OUTPUT buffer: DBMS_OUTPUT.PUT_LINE procedure:

Note:

 The specification for PUT_LINE is overloaded, so that you can pass data in its native format to the package without having to perform conversions:

PROCEDURE DBMS_OUTPUT.PUT_LINE (A VARCHAR2); PROCEDURE DBMS_OUTPUT.PUT_LINE (A NUMBER); PROCEDURE DBMS_OUTPUT.PUT_LINE (A DATE);

where A is the data being passed

- The PUT_LINE procedure is the one most commonly used in SQL*Plus to debug PL/SQL programs.
- When you use PUT_LINE in these situations, you do not need to call GET_LINE to extract the information from the buffer. Instead, SQL*Plus will automatically dump out the DBMS_OUTPUT buffer when your PL/SQL block finishes executing. (You will not see any output until the program ends.)

Writing to DBMS_OUTPUT buffer: DBMS_OUTPUT.PUT_LINE (contd.): Example:

Example:

 Suppose that you execute the following three statements in SQL*Plus:

```
SQL> exec DBMS_OUTPUT.PUT ('I am');
SQL> exec DBMS_OUTPUT.PUT (' writing');
SQL> exec DBMS_OUTPUT.PUT ('a');
```

- You will not see anything, because PUT will place the information in the buffer, but will not append the newline marker. Now suppose you issue this next PUT_LINE command, namely:
 - SQL> exec DBMS_OUTPUT.PUT_LINE ('book!');
- Then you will see the following output:
 - I am writing a book!
- All of the information added to the buffer with the calls to PUT, patiently wait to be flushed out with the call to PUT_LINE. This is the behavior you will see when you execute individual calls at the SQL*Plus command prompt to the PUT programs.
- Suppose you place these same commands in a PL/SQL block, namely:

```
BEGIN

DBMS_OUTPUT.PUT ('I am');

DBMS_OUTPUT.PUT (' writing ');

DBMS_OUTPUT.PUT ('a ');

DBMS_OUTPUT.PUT_LINE ('book');

END;

/
```

- Then the output from this script will be exactly the same as that generated by this single call:
 - SQL> exec DBMS_OUTPUT.PUT_LINE ('I am writing a book!');

9.2: Displaying Output

Retrieving Data from DBMS_OUTPUT buffer

- You can retrieve information from the DBMS_OUTPUT buffer with call to the GET_LINE procedure.
 - The DBMS OUTPUT.GET LINE procedure:
 - The GET_LINE procedure retrieves one line of information from the buffer
 - · Given below is the specification for the procedure:

PROCEDURE DBMS_OUTPUT.GET_LINE (line OUT VARCHAR2, status OUT INTEGER);



Copyright © Cappernini 2015. All Rights Reserved

Retrieving Data from the DBMS_OUTPUT buffer:

- You can use the GET_LINE and GET_LINES procedures to extract information from the DBMS_OUTPUT buffer.
- If you are using DBMS_OUTPUT from within SQL*Plus, however, you will never need to call either of these procedures. Instead, SQL*Plus will automatically extract the information and display it on the screen for you.

The DBMS_OUTPUT.GET_LINE procedure:

- The GET_LINE procedure retrieves one line of information from the buffer.
- Given below is the specification for the procedure:

PROCEDURE DBMS_OUTPUT.GET_LINE (line OUT VARCHAR2, status OUT INTEGER);R

The parameters are summarized as shown below:

Paramet er	Description
Line	Retrieved line of text
Status	GET request status

Retrieving Data from the DBMS_OUTPUT buffer (contd.): The DBMS_OUTPUT.GET_LINE procedure (contd.)

- The line can have up to 255 bytes in it, which is not very long. If GET_LINE completes successfully, then status is set to 0. Otherwise, GET_LINE returns a status of 1.
- Note that even though the PUT and PUT_LINE
 procedures allow you to place information into the buffer
 in their native representations (dates as dates, numbers
 and numbers, and so forth), GET_LINE always retrieves
 the information into a character string. The information
 returned by GET_LINE is everything in the buffer up to the
 next newline character. This information might be the data
 from a single PUT_LINE or from multiple calls to PUT.
- For example:

The following call to GET_LINE extracts the next line of information into a local PL/SQL variable:

```
FUNCTION get_next_line RETURN
VARCHAR2
IS
return_value VARCHAR2(255);
get_status INTEGER;
BEGIN
DBMS_OUTPUT.GET_LINE
(return_value, get_status);
IF get_status = 0
THEN
RETURN return_value;
ELSE
RETURN NULL;
END IF;
END;
```

UTL-FILE

- •UTL FILE package:
 - The UTL FILE package is created when the Oracle database is installed.
 - The "utlfile.sql script" (found in the built-in packages source code directory) contains the source code for the specification of this package.
 - This script is called by catproc.sql, which is normally run immediately after database creation
 - The script creates the public synonym UTL_FILE for the package, and grants EXECUTE privilege on the package to public



Copyright © Capgemini 2015. All Rights Reserved

UTL FILE: READING AND WRITING

- UTL_FILE is a package that has been welcomed warmly by PL/SQL developers. It allows PL/SQL programs to both "read from" and "write to" any operating system files that are accessible from the server on which your database instance is running.
 - You can now read ini files and interact with the operating system a little more easily than has been possible in the past.
 - You can directly load data from files into database tables while applying the full power and flexibility of PL/SQL programming.
 - You can directly generate reports from within PL/SQL without worrying about the maximum buffer restrictions of DBMS_OUTPUT.
- The UTL_FILE package is created when the Oracle database is installed. The utlfile.sql script (found in the built-in packages source code directory) contains the source code for the specification of this package. This script is called by catproc.sql, which is normally run immediately after database creation. The script creates the public synonym UTL_FILE for the package and grants EXECUTE privilege on the package to public.

	Table: UTL FILE programs	
Name	Description	Use in SQL?
FCLOSE	Closes the specified files.	NO
FCLOSE_AL L	Closes all open files.	NO
FFLUSH	Flushes all the data from the UTL_FILE buffer.	NO
FOPEN	Opens the specified file.	NO
GET_LINE	Gets the next line from the file.	NO
IS_OPEN	Returns TRUE if the file is already open.	NO
NEW_LINE	Inserts a newline mark in the file at the end of the current line.	NO
PUT	Puts text into the buffer.	NO
PUT_LINE	Puts a line of text into the file.	NO
PUTF	Puts formatted text into the buffer.	NO

File security:

- UTL_FILE lets you read and write files accessible from the server on which your database is running. So theoretically you can use UTL_FILE to write right over your tablespace data files, control files, and so on. That is of course not a very good idea.
- Server security requires the ability to place restrictions on where you can read and write your files.
- UTL_FILE implements this security by limiting access to files that reside in one of the directories specified in the INIT.ORA file for the database instance on which UTL_FILE is running.
- When you call FOPEN to open a file, you must specify both the location and the name of the file, in separate arguments. This file location is then checked against the list of accessible directories.
- Given below is the format of the parameter for file access in the INIT.ORA file:
 - utl_file_dir = <directory>
- Include a parameter for utl_file_dir for each directory you want to make accessible for UTL_FILE operations. For example: The following entries enable four different directories in UNIX:
 - utl_file_dir = /tmp
 - utl_file_dir = /ora_apps/hr/time_reporting
 - > utl file dir = /ora apps/hr/time reporting/log
 - utl_file_dir = /users/test_area
- To bypass server security and allow read/write access to all directories, you can use the special syntax given below:
 utl_file_dir = *

Specifying file locations:

- The location of the file is an operating system-specific string that specifies the directory or area in which to open the file. The location you provide must have been listed as an accessible directory in the INIT.ORA file for the database instance.
- The INIT.ORA location is a valid directory or area specification, as shown in the following examples:
 - In Windows NT: 'k:\common\debug'
 - In UNIX: '/usr/od2000/admin'
- Few examples are given below:
 - In Windows NT: file_id := UTL_FILE.FOPEN ('k:\common\debug', 'trace.lis', 'R');
 - In UNIX: file_id := UTL_FILE.FOPEN ('/usr/od2000/admin', 'trace.lis'. 'W'):
- Your location must be an explicit, complete path to the file. You
 cannot use operating system-specific parameters such as
 environment variables in UNIX to specify file locations.

UTL FILE exceptions:

- The package specification of UTL_FILE defines seven exceptions. The cause behind a UTL_FILE exception can often be difficult to understand.
- Given below are the explanations Oracle provides for each of the exceptions:

> INVALID_PATH

The file location or the filename is invalid. Perhaps the directory is not listed as a utl_file_dir parameter in the INIT.ORA file (or doesn't exist as all), or you are trying to read a file and it does not exist.

> INVALID_MODE

The value you provided for the open_mode parameter in UTL_FILE.FOPEN was invalid. It must be "A", "R", or "W".

> INVALID FILEHANDLE

The file handle you passed to a UTL_FILE program was invalid. You must call UTL_FILE.FOPEN to obtain a valid file handle.

> INVALID OPERATION

UTL_FILE could not open or operate on the file as requested. For example, if you try to write to a read-only file, you will raise this exception.

> READ_ERROR

The operating system returned an error when you tried to read from the file. (This does not occur very often.)

> WRITE ERROR

The operating system returned an error when you tried to write to the file. (This does not occur very often.)

> INTERNAL ERROR

Uh-oh. Something went wrong and the PL/SQL runtime engine couldn't assign blame to any of the previous exceptions. Better call Oracle Support!

 Programs in UTL_FILE may also raise the following standard system exceptions:

> NO DATA FOUND

It is raised when you read past the end of the file with UTL_FILE.GET_LINE.

> VALUE ERROR

It is raised when you try to read or write lines in the file which are too long.

> INVALID MAXLINEŠIZE

Oracle 8.0 and above: It is raised when you try to open a file with a maximum linesize outside of the valid range (between 1 through 32767).

9.3: UTL_FILE Process Flow

- UTL FILE process flow:
 - The following sections describe each of the UTL_FILE programs, following the process flow for working with files.
 - The flow is described for both writing and reading files.



Copyright © Capgemini 2015. All Rights Reserved

Add the notes here.

UTL FILE: Process Flow

- Write to a file: In order to "write to a file", you will (in most cases) perform the following steps:
 - Declare a file handle. This handle serves as a pointer to the file for subsequent calls to programs in the UTL_FILE package to manipulate the contents of this file
 - Open the file with a call to FOPEN, which returns a file handle to the file. You can open a file to read, replace, or append text
 - Write data to the file by using the PUT, PUTF, or PUT_LINE procedures
 - Close the file with a call to FCLOSE. This releases resources associated with the file



Copyright © Cappernini 2015. All Rights Reserved

Insertion Sort:

In Insertion Sort, if we have an array of "n" elements, then we can say that the first element is sorted, and till now we have read only 1st element.

Read the 2nd element, and find it's position is the array which is already sorted. Till now only 1st element is sorted. So check whether to add it before or after 1st element.

Accordingly, shift all elements on it's right by one location on right, and then insert the element at the appropriate location.

UTL FILE: Process Flow

- Read from a file: In order to "read data from a file", you will (in most cases) perform the following steps:
 - Declare a file handle
 - Declare a VARCHAR2 string buffer that will receive the line of data from the file.
 You can also read directly from a file into a numeric or date buffer. In this case, the data in the file will be converted implicitly, and so it must be compatible with the datatype of the buffer
 - Open the file using FOPEN in read mode

contd...



Copyright © Cappemini 2015, All Rights Reserved

Insertion Sort:

In Insertion Sort, if we have an array of "n" elements, then we can say that the first element is sorted, and till now we have read only 1st element.

Read the 2nd element, and find it's position is the array which is already sorted. Till now only 1st element is sorted. So check whether to add it before or after 1st element.

Accordingly, shift all elements on it's right by one location on right, and then insert the element at the appropriate location.

UTL FILE: Process Flow

- Use the GET_LINE procedure to read data from the file and into the buffer. To read all the lines from a file, you would execute GET_LINE in a loop
- Close the file with a call to FCLOSE



Copyright © Cappernini 2015. All Rights Reserved

Insertion Sort:

In Insertion Sort, if we have an array of "n" elements, then we can say that the first element is sorted, and till now we have read only 1st element.

Read the 2nd element, and find it's position is the array which is already sorted. Till now only 1st element is sorted. So check whether to add it before or after 1st element.

Accordingly, shift all elements on it's right by one location on right, and then insert the element at the appropriate location.

Opening Files

- You can use the FOPEN and IS_OPEN functions when you open files via UTL_FILE
- Note:
 - Using the UTL-FILE package, you can only open a maximum of ten files for each Oracle session



Copyright © Capgemini 2015. All Rights Reserved

Insertion Sort:

In Insertion Sort, if we have an array of "n" elements, then we can say that the first element is sorted, and till now we have read only 1st element.

Read the 2nd element, and find it's position is the array which is already sorted. Till now only 1st element is sorted. So check whether to add it before or after 1st element.

Accordingly, shift all elements on it's right by one location on right, and then insert the element at the appropriate location.

The UTL FILE.FOPEN Function

- UTL FILE.FOPEN function:
 - The FOPEN function opens the specified file and returns a file handle that you can then use to manipulate the file.
 - The header for the function is:

FUNCTION UTL_FILE.FOPEN (FUNCTION UTL_FILE.FOPEN (location IN VARCHAR2, location IN VARCHAR2, filename IN VARCHAR2, filename IN VARCHAR2, open_mode IN VARCHAR2) open_mode IN VARCHAR2, RETURN file_type; max_linesize IN BINARY_INTEGER) RETURN file_type;



Convight O Caopemini 2015. All Rights Reserved

UTL FILE.FOPEN Function:

Parameters for the function shown in the slide are summarized in the following table.

Paramet er	Description
location	Location of the file
filename	Name of the file
openmod e	Mode in which the file has to be opened
max_line size	The maximum number of characters per line, including the newline character, for this file. Minimum is 1, maximum is 32767.

UTL_FILE.FOPEN Function (contd.):

• You can open the file in one of the following three modes:

> R mode

Open the file read-only. If you use this mode, use UTL_FILE's GET_LINE procedure to read from the file.

➤ W mode

Open the file to read and write in replace mode. When you open in replace mode, all existing lines in the file are removed. If you use this mode, then you can use any of the following UTL_FILE programs to modify the file: PUT, PUT_LINE, NEW LINE, PUTF, and FFLUSH.

> A mode

Open the file to read and write in append mode. When you open in append mode, all existing lines in the file are kept intact. New lines will be appended after the last line in the file. If you use this mode, then you can use any of the following UTL_FILE programs to modify the file: PUT, PUT_LINE, NEW_LINE, PUTF, and fFFLUSH.

Example

The following example shows how to declare a file handle, and then open a configuration file for that handle in read-only mode:

DECLARE

config_file UTL_FILE.FILE_TYPE;

BEGIN

config_file := UTL_FILE.FOPEN
('/maint/admin', 'config.txt', 'R');

The UTL_FILE.IS_OPEN Function

- UTL FILE.IS OPEN function:
 - The IS_OPEN function returns TRUE if the specified handle points to a file that is already open. Otherwise, it returns FALSE.
 - The header for the function is:
 - where file is the file to be checked

FUNCTION UTL_FILE.IS_OPEN (file IN UTL_FILE.FILE_TYPE) RETURN BOOLEAN;



UTL FILE.FOPEN Function:

• Parameters for the function shown in the slide are summarized in the following table.

Reading from Files

 UTL_FILE provides only one program to retrieve data from a file, namely the GET_LINE procedure



Copyright © Cappernini 2015. All Rights Reserved

UTL_FILE.FOPEN Function:

Parameters for the function shown in the slide are summarized in the following table.

9.3: UTL_FILE The UTL_FILE.GET_LINE Procedure

- •UTL FILE.GET LINE procedure:
 - The GET_LINE procedure reads a line of data from the specified file, if it is open, into the provided line buffer.
 - The header for the procedure is:

PROCEDURE UTL_FILE.GET_LINE (file IN UTL_FILE.FILE_TYPE, buffer OUT VARCHAR2);



Copyright © Capgemini 2015. All Rights Reserved

UTL FILE.GET LINE procedure:

 The GET_LINE procedure reads a line of data from the specified file, if it is open, into the provided line buffer. Given below is the header for the procedure:

> PROCEDURE UTL_FILE.GET_LINE (file IN UTL_FILE.FILE_TYPE, buffer OUT VARCHAR2);

Parameters are summarized in the following table:

Paramet er	Description
File	The file handle returned by a call to FOPEN.
Buffer	The buffer into which the line of data is read.

UTL_FILE.GET_LINE procedure (contd.):

- The variable specified for the buffer parameter must be large enough to hold all the data up to the next carriage return or end-of-file condition in the file. If not, PL/SQL will raise the VALUE_ERROR exception. The line terminator character is not included in the string passed into the buffer.
- For example:
 Since GET_LINE reads data only into a string variable,
 you will have to perform your own conversions to local
 variables of the appropriate datatype if your file holds
 numbers or dates. Of course, you can call this procedure
 and directly read data into string and numeric variables,
 as well. In this case, PL/SQL will be performing a runtime,
 implicit conversion for you. In many situations, this is fine.
- It is generally recommended that you avoid implicit conversions and instead perform your own conversion.
 This approach more clearly documents the steps and dependencies.
- Here is an example:

```
DECLARE
fileID UTL_FILE.FILE_TYPE;
strbuffer VARCHAR2(100);
mynum NUMBER;
BEGIN
fileID := UTL_FILE.FOPEN ('/tmp', 'numlist.txt',
'R');
UTL_FILE.GET_LINE (fileID, strbuffer);
mynum := TO_NUMBER (strbuffer);
END;
/
```

- When GET_LINE attempts to read past the end of the file, the NO_DATA_FOUND exception is raised. This is the same exception that is raised when you:
 - a) execute an implicit (SELECT INTO) cursor that returns no rows, or
 - b) reference an undefined row of a PL/SQL (nested in PL/SQL8) table.
- If you are performing more than one of these operations in the same PL/SQL block, remember that this same exception can be caused by very different parts of your program.

Writing to Files

- In contrast to the simplicity of reading from a file, UTL_FILE offers a number of different procedures you can use to write to a file:
 - UTL FILE.PUT procedure
 - · Puts a piece of data (string, number, or date) into a file in the current line
 - UTL_FILE.NEW_LINE procedure
 - · Puts a newline or line termination character into the file at the current position



Copyright © Capgemini 2015. All Rights Reserved

Writing to Files: UTL FILE.PUT procedure

- The PUT procedure puts data out to the specified open file.
- Given below is the header for this procedure:

PROCEDURE UTL_FILE.PUT
(file IN UTL_FILE.FILE_TYPE,
buffer IN VARCHAR2); -----OUT
replace with IN

Parameters are summarized in the following table.

Parameter	Description
File	The file handle returned by a call to FOPEN.
Buffer	The buffer containing the text to be written to the file; maximum size allowed is 32K for Oracle 8.0.3 and above; for earlier versions, it is 1023 bytes.

The PUT procedure adds the data to the current line in the opened file, but
does not append a line terminator. You must use the NEW_LINE procedure to
terminate the current line or use PUT_LINE to write out a complete line with a
line termination character.

Writing to Files

- UTL_FILE.PUT_LINE procedure
 - Puts a string into a file, followed by a platform-specific line termination character
- UTL FILE.PUTF procedure
 - Puts up to five strings out to the file in a format based on a template string, similar to the printf function in C



Copyright © Cappernini 2015. All Rights Reserved

Exceptions:

PUT may raise any of the following exceptions:

UTL_FILE.INVALID_FILEHANDLE
UTL_FILE.INVALID_OPERATION
UTL_FILE.WRITE_ERROR

Note:

Besides the four procedures mentioned in the above slides there is one more procedure called UTL_FILE.FFLUSH procedure.

UTL_FILE.FFLUSH procedure makes sure that all pending data for the specified file is written physically out to a file. The header for FFLUSH is,

PROCEDURE UTL_FILE.FFLUSH (file IN UTL_FILE.FILE_TYPE);

where: file is the file handle.

One of the four procedures, namely UTL_FILE.PUT_LINE procedure, is discussed in detail in the following slide.

9.3: UTL_FILE PUT_LINE Procedure

- •UTL FILE.PUT LINE procedure:
 - This procedure writes data to a file, and then immediately appends a newline character after the text
 - The header for PUT LINE is:

PROCEDURE UTL_FILE.PUT_LINE (file IN UTL_FILE.FILE_TYPE, buffer IN VARCHAR2);



Copyright © Capgemini 2015. All Rights Reserved

<u>UTL_FILE.PUT_LINE procedure</u>:

 This procedure writes data to a file, and then immediately appends a newline character after the text. Given below is the header for PUT_LINE:

PROCEDURE UTL_FILE.PUT_LINE (file IN UTL_FILE.FILE_TYPE, buffer IN VARCHAR2);

Parameters are summarized in the following table.

Paramet er	Description
File	The file handle returned by a call to FOPEN.
Buffer	Text to be written to the file; maximum size allowed is 32K for Oracle 8.0. 3 and above; for earlier versions, it is 1023 bytes.

 Before you can call UTL_FILE.PUT_LINE, you must have already opened the file.

```
PROCEDURE emp2file
IS
fileID UTL_FILE.FILE_TYPE;
BEGIN
fileID := UTL_FILE.FOPEN ('/tmp', 'emp.dat', 'W');

/* Quick and dirty construction here! */
FOR emprec IN (SELECT * FROM emp)
LOOP
    UTL_FILE.PUT_LINE
    (TO_CHAR (emprec.empno) || ',' ||
    emprec.ename || ',' ||
    ...
    TO_CHAR (emprec.deptno));
END LOOP;

UTL_FILE.FCLOSE (fileID);
END;
```

• You can use the FCLOSE and FCLOSE_ALL procedures for closing files

Capgemini

The UTL_FILE.FCLOSE Procedure

- UTL FILE.FCLOSE procedure:
 - Use FCLOSE to close an open file.
 - The header for this procedure is:
 - where file is the file to be checked

PROCEDURE UTL_FILE.FCLOSE (file IN OUT FILE_TYPE);



Copyright © Cappernini 2015. All Rights Reserved

UTL FILE.FCLOSE procedure:

 Use FCLOSE to close an open file. The header for this procedure is:

PROCEDURE UTL_FILE.FCLOSE (file IN OUT FILE_TYPE);

where file is the file handle.

- Note that the argument to UTL_FILE.FCLOSE is an IN OUT parameter, because the procedure sets the id field of the record to NULL after the file is closed.
- If there is buffered data that has not yet been written to the file when you try to close it, UTL_FILE will raise the WRITE_ERROR exception.

UTL_FILE.FCLOSE_ALL procedure:

• FCLOSE_ALL closes all the opened files. Given below is the header for this procedure:

PROCEDURE UTL FILE.FCLOSE ALL;

- This procedure will come in handy when you have opened a variety of files and want to make sure that none of them are left open when your program terminates.
- In programs in which files have been opened, you should also call FCLOSE_ALL in exception handlers in programs. If there is an abnormal termination of the program, files will then still be closed.

```
EXCEPTION
WHEN OTHERS

THEN
UTL_FILE.FCLOSE_ALL;
... other clean up activities ...
END;
```

NOTE: When you close your files with the FCLOSE_ALL procedure, none of your file handles will be marked as closed (the id field, in other words, will still be non-NULL). The result is that any calls to IS_OPEN for those file handles will still return TRUE. You will not, however, be able to perform any read or write operations on those files (unless you reopen them).

Exceptions

 FCLOSE_ALL may raise the exception UTL_FILE.WRITE_ERROR. 9.4: Handling LOB (Large Objects)

DBMS LOB

- Handling LOBs (Large Objects)
 - Large Objects (LOBs) are a set of datatypes that are designed to hold large amounts of data.
 - LOBs are designed to support Unstructured kind of data.
 - In short:
 - · LOBs are used to store Large Objects (LOBs).
 - · LOBs support random access to data and has maximum size of 4 GB
 - · For example: Hospital database



Copyright © Capgemini 2015. All Rights Reserved

Handling LOB (Large Objects):

- Large Objects (LOBs) are a set of datatypes that are designed to hold large amounts of data.
- LOBs are designed to support Unstructured kind of data.

Unstructured Data:

- Unstructured Data cannot be decomposed into Standard Components:
 - ➤ Unstructured data cannot be decomposed into standard components. Data about an Employee can be "structured" into a Name (probably a character string), an identification (likely a number), a Salary, and so on. But if you are given a Photo, you find that the data really consists of a long stream of 0s and 1s. These 0s and 1s are used to switch pixels on or off so that you will see the Photo on a display. However, they cannot be broken down into any finer structure in terms of database storage.
- Unstructured Data is Large:
 - Also interesting is the fact that unstructured data such as text, graphic images, still video clips, full motion video, and sound waveforms tend to be large - a typical employee record may be a few hundred bytes, but even small amounts of multimedia data can be thousands of times larger.

Handling LOB (Large Objects) (contd.):

Unstructured Data (contd.):

- Unstructured Data in System Files needs Accessing from the Database:
 Finally, some multimedia data may reside on operating system files,
 and it is desirable to access them from the database.
- LOB Datatype helps support Internet Applications:
 - With the growth of the internet and content-rich applications, it has become imperative that the database supports a datatype that fulfills the following:
 - datatype should store unstructured data
 - datatype should be optimized for large amounts of such data
 - datatype should provide an uniform way of accessing large unstructured data within the database or outside

9.3: UTL FILE Writing to Files

- Two types of LOBs are supported:
- Those stored in the database either in-line in the table or in a separate segment or tablespace, such as BLOB, CLOB, and NCLOB. LOBs in the database are stored inside database tablespaces in a way that optimizes space and provides efficient access. The following SQL datatypes are supported for declaring internal LOBs: BLOB, CLOB, and NCLOB
- Those stored as operating system files, such as BFILEs.



•Given below is a summary of all the four types of LOBs :

•BLOB (Binary LOB)

BLOB stores unstructured binary data up to 4GB in length.

For example: Video or picture information

CLOB (Character LOB)

CLOB stores single-byte character data up to 4GB in length.

For example: Store document

•NCLOB (National CLOB)

NCLOB stores a CLOB column that supports multi-byte characters from National Character set defined by Oracle 8 database.

•BFILE (Binary File)

BFILE stores read-only binary data as an external file outside the database.

Internal objects store a locator in the Large


Object column of a table.

Locator is a pointer that specifies the actual location of LOB stored out-of-line.

The LOB locator for BFILE is the pointer to the location of the binary file stored in the

operating system.

Oracle supports data integrity and concurrency for all the LOBs except for BFILEs.



LOB locator:

- The value held in a LOB column or variable is not the actual binary data, but a "locator" or pointer to the physical location of the large object.
- For internal LOBs, since one LOB value can be up to four gigabytes in size, the binary data will be stored "out of line" (i.e., physically separate) from the other column values of a row (unless otherwise specified; see the next paragraph).
 - ➤ This allows the physical size of an individual row to be minimized for improved performance (the LOB column contains only a pointer to the large object).
 - ➤ Operations involving multiple rows, such as full table scans, can be more efficiently performed.
- A user can specify that the LOB value be stored in the row itself. This is usually done when working with small LOB values. This approach decreases the time needed to obtain the LOB value. However, the LOB data is migrated out of the row when it gets too big.
- For external LOBs, the BFILE value represents a filename and an operating system directory, which is also a pointer to the location of the large object.

BFILE considerations:

- There are some special considerations you should be aware of when you work with BFILEs.
 - The DIRECTORY object
 - A BFILE locator consists of a directory alias and a filename. The directory alias is an Oracle8 database object that allows references to operating system directories without hard-coding directory pathnames. This statement creates a directory:
 - → ĆREATE DIRECTORY IMAGES AS 'c:\images';
 - To refer to the c:\images directory within SQL, you can use the IMAGES alias, rather than hardcoding the actual directory pathname.
 - To create a directory, you need the CREATE DIRECTORY or CREATE ANY DIRECTORY privilege. To reference a directory, you must be granted the READ privilege, as in:
 - → GRANT READ ON DIRECTORY IMAGES TO SCOTT:

> Populating a BFILE locator

The Oracle8 built-in function BFILENAME can be used to populate a BFILE locator. BFILENAME is passed a directory alias and filename and returns a locator to the file. In the following block, the BFILE variable corporate_logo is assigned a locator for the file named ourlogo.bmp located in the IMAGES directory:

```
DECLARE
 corporate_logo
                  BFII F:
BEGÍN
 corporate_logo := BFILENAME ( 'IMAGES',
'ourlogo.bmp');
END:
The following statements populate the my book files
table; each row is associated with a file in the
BOOK TEXT directory:
INSERT INTO my_book_files ( file_descr, book_file )
  VALUES ( 'Chapter 1', BFILENAME('BOOK TEXT',
'chapter01.txt') );
UPDATE my_book_files
 SET book_file = BFILENAME( 'BOOK_TEXT',
'chapter02rev.txt')
WHERE file_descr = 'Chapter 2';
```

- Once a BFILE column or variable is associated with a physical file, read operations on the BFILE can be performed using the DBMS_LOB package.
- Remember that access to physical files via BFILEs is read-only, and that the BFILE value is a pointer. The contents of the file remain outside of the database, but on the same server on which the database resides.

9.4: Handling LOB (Large Objects) Internal LOB considerations

- Initializing and Manipulating LOB values:
 - For each LOB column, a "locator value" is stored in the table.
 - The locator points to a separate data location, which the database creates to hold the LOB data
 - Internal LOB column can have a value, null, or be empty.
 - An empty LOB stored in a table is a LOB of zero-length, which has a locator
 - You can use EMPTY_BLOB() and EMPTY_CLOB() in INSERT or UPDATE statements to initialize a NULL or non-NULL internal LOB to empty



Internal LOB considerations

- Setting the LOB to NULL or empty:
 - to set the LOB value to null use the following query:

SQL> Insert into Leave values (7900, '17-APR-98', '20-APR-98', NULL,'The LC and Amendments entry Forms have been completed. All the validations have been incorporated and passed for testing.');

1 row created.



Internal LOB considerations

- Setting the LOB to non-NULL:
 - Before writing data to an internal LOB, column must be made NON-NULL, since you cannot call the OCI or the PL/SQL DBMS_LOB functions on a NULL LOB

SQL> Insert into leave values

- 2 (7439,'12-APR-98', '17-APR-98', empty_blob(),
- 3 'The assignments regarding Oracle 8 have
- 4 been completed. I'll be back on 17th');
- 1 row created.



Internal LOB considerations: Few more points:

Given below are a few more special considerations for Internal LOBs.

- Retaining the LOB locator
 - The following statement populates the my_book_text table, which contains CLOB column chapter_text:

```
INSERT INTO my_book_text ( chapter_descr, chapter_text )
VALUES ( 'Chapter 1', 'It was a dark and stormy night.' );
```

- Programs within the DBMS_LOB package require a LOB locator to be passed as input. If you want to insert the preceding row and then call a DBMS_LOB program using the row's CLOB value, you must retain the LOB locator created by your INSERT statement.
- You can do this as shown in the following block, which inserts a row, selects the inserted LOB locator, and then calls the DBMS_LOB.GETLENGTH program to get the size of the CLOB chapter_text column. Note that the GETLENGTH program expects a LOB locator.

```
DECLARE
 chapter_loc
                 CLOB:
 chapter_length
                   INTEGER;
BEGIN
 INSERT INTO my_book_text ( chapter_descr,
chapter_text)
    VALUES ('Chapter 1', 'It was a dark and
stormy night.');
 SELECT chapter_text
  INTO chapter loc
  FROM my_book_text
  WHERE chapter_descr = 'Chapter 1';
 chapter_length := DBMS_LOB.GETLENGTH(
chapter_loc);
 DBMS_OUTPUT.PUT_LINE( 'Length of Chapter
1: ' || chapter_length );
END:
/
```

This is the output of the script: Length of Chapter 1: 31

contd.

Internal LOB considerations: Few more points (contd.):

- The RETURNING clause
 - You can avoid the second trip to the database (i.e. the SELECT of the LOB locator after the INSERT) by using a RETURNING clause in the INSERT statement.
 - By using this feature, perform the INSERT operation and the LOB locator value for the new row in a single operation.

```
DECLARE
chapter_loc CLOB;
chapter_length INTEGER;
BEGIN

INSERT INTO my_book_text ( chapter_descr, chapter_text )
VALUES ( 'Chapter 1', 'It was a dark and stormy night.')
RETURNING chapter_text INTO chapter_loc;
chapter_length := DBMS_LOB.GETLENGTH( chapter_loc );

DBMS_OUTPUT.PUT_LINE( 'Length of Chapter 1: ' || chapter_length );

END;
/
```

This is the output of the script: Length of Chapter 1: 31

The RETURNING clause can be used in both INSERT and UPDATE statements.

contd.

Internal LOB considerations: Few more points (contd.):

- NULLL LOB locators can be a problem
 - Programs in the DBMS_LOB package expect to be passed a LOB locator that is not NULL.
 - For example, the GETLENGTH program raises an exception when passed a LOB locator that is NULL.

```
DECLARE
  chapter_loc
               CLOB;
 chapter_length INTEGER;
BEGIN
   UPDATE my book text
     SET chapter text = NULL
    WHERE chapter_descr = 'Chapter 1'
 RETURNING chapter text INTO chapter loc;
 chapter_length := DBMS_LOB.GETLENGTH(
chapter_loc);
 DBMS_OUTPUT.PUT_LINE( 'Length of Chapter 1: ' ||
chapter_length);
EXCEPTION
 WHEN OTHERS
   DBMS_OUTPUT.PUT_LINE('OTHERS Exception ' ||
sqlerrm);
END:
```

This is the output of the script:
OTHERS Exception ORA-00600: internal error code,
arguments: ...

When a BLOB, CLOB, or NCLOB column is set to NULL, both the LOB binary data and its LOB locator are NULL. This NULL LOB locator should not be passed to a program in the DBMS_LOB package.

Internal LOB considerations: Few more points (contd.):

- NULL versus "empty" LOB locators
 - Oracle8 provides the built-in functions EMPTY_BLOB and EMPTY CLOB to set BLOB, CLOB, and NCLOB columns to "empty".
 - For example:

INSERT INTO my_book_text (chapter_descr, chapter_text)
VALUES ('Table of Contents', EMPTY_CLOB());

The LOB data is set to NULL. However, the associated LOB locator is assigned a valid locator value, which points to the NULL data. This LOB locator can then be passed to DBMS_LOB programs.

```
DECLARE
 chapter loc
              CLOB:
 chapter length INTEGER;
 INSERT INTO my_book_text (chapter_descr,
chapter_text)
    VALUES ( 'Table of Contents', EMPTY_CLOB() )
  RETURNING chapter_text INTO chapter_loc;
 chapter_length := DBMS_LOB.GETLENGTH(
chapter loc);
 DBMS_OUTPUT.PUT_LINE
   ('Length of Table of Contents: ' | chapter_length);
EXCEPTION
 WHEN OTHERS
   DBMS_OUTPUT.PUT_LINE( 'OTHERS Exception ' II
sqlerrm);
END;
/
```

This is the output of the script:

Length of Table of Contents: 0

- Note that EMPTY_CLOB can be used to populate both CLOB and NCLOB columns. EMPTY_BLOB and EMPTY_CLOB can be called with or without empty parentheses.
- Note: Do not populate BLOB, CLOB, or NCLOB columns with NULL values. Instead, use the EMPTY_BLOB or EMPTY_CLOB functions, which will populate the columns with a valid LOB locator and set the associated data to NULL.

9.4: Handling LOB (Large Objects) Accessing External LOBs

- The BFILENAME () function is used to associate a BFILE column with an external file.
 - To create a DIRECTORY object:
 - The first parameter to the BFILENAME () function is the directory alias, and the second parameter is the filename

SQL> alter table Leave add(b_file bfile); Table altered.



Accessing External LOBs - Examples

Example 1: Create a directory object as shown below:

SQL> Create or Replace Directory L_DIR as '\SUPRIYA_COMP\DRV_SUP_C\SUP'; Directory created.

 Example 2: In the following statement, we associate the file TEST.TXT for Empno 7900

SQL> UPDATE leave SET b_file = bfilename('L_DIR', 'TEST.TXT') WHERE EMPNO = 7900; 1 row updated.



Accessing External LOBs - Examples

- Note:
 - Read operations on the BFILE can be performed by using PL/SQL DBMS_LOB package and OCI.
 - · These files are read-only through BFILES.
 - These files cannot be updated or deleted through BFILES



9.4: Handling LOB (Large Objects) Updating LOBs

- While updating LOBs:
 - Explicitly lock the rows.
 - Use the FOR UPDATE clause in a SELECT statement.

SELECT msg FROM Leave WHERE Empno = 7439 FOR UPDATE;

UPDATE Leave

SET msg = 'The assignments regarding Oracle 8 have been completed. You can now proceed with Developer V2. I"II be back on 17th.'
WHERE Empno = 7439;

1 row updated.



Note:

- To update a column that uses the BFILE datatype, you do not have to lock the rows.
- Using a DBMS_LOB Package:
 - Provides procedures to access LOBs.
 - Allows reading and modifying BLOBs, CLOBs, and NCLOBs, and provides read-only operations on BFILEs.
- All DBMS LOB routines work based on LOB locators.

9.4: Handling LOB (Large Objects)

DBMS LOB Package Routines

Some of the procedures and functions available within DBMS_LOB package are given below:

Procedure or Function	Description	
Read	Reads data from LOB value starting at a specific offset.	
Substr	Performs SQL Substr function on a LOB value. It returns a part of a LOB value starting at a specific offset.	
Instr	Same as SQL Instr function.	
GetLength	Performs SQL length function as a LOB value.	
Compare	Compares two LOB values.	
Write	Writes data to the LOB at specified offset.	
Append	Appends the content of source LOB to the destination LOB.	
Erase	Erases all or part of LOB.	
Trim	Performs SQL Rtrim function on the LOB value.	
Сору	Copies all or part of LOB value from one LOB value to other column.	



DBMS LOB Package Routines:

The routines that can modify **BLOB**, **CLOB**, and **NCLOB** values are:

- APPEND() appends the contents of the source LOB to the destination LOB
- COPY() copies all or part of the source LOB to the destination LOB
- ERASE() erases all or part of a LOB
- LOADFROMFILE() loads BFILE data into an internal LOB
- TRIM() trims the LOB value to the specified shorter length
- WRITE() writes data to the LOB from a specified offset

The routines that read or examine **LOB** values are:

- GETLENGTH() gets the length of the LOB value
- INSTR() returns the matching position of the nth occurrence of the pattern in the LOB
- READ() reads data from the LOB starting at the specified offset
- SUBSTR() returns part of the LOB value starting at the specified offset

The read-only routines specific to **BFILEs** are:

- FILECLOSE() closes the file
- FILECLOSEÄLL()- closes all previously opened files
- FILEEXISTS() checks if the file exists on the server

- •FILEGETNAME() gets the directory alias and file name
- •FILEISOPEN() checks if the file was opened using the input BFILE
- •locators
- •FILEOPEN() opens a file

DBMS_LOB Exceptions:

A DBMS_LOB function or procedure can raise any of the named exceptions shown in the table.

Exception	Code in error msg	Meaning
INVALID_ARGVAL	21560	"argument %s is null, invalid, or out of range"
ACCESS_ERROR	22925	Attempt to read/write beyond maximum LOB size on <n>.</n>
NO_DATA_FOUN D	1403	EndofLOB indicator for looping read operations.
VALUE_ERROR	6502	Invalid value in parameter.

9.4 Handling LOB (Large Objects) BFILE Functions and Procedures

Procedure or Function	Description
FileClose	Closes an open BFILE.
FileCloseAll	Closes all the files open in a given session.
FileExists	Finds out whether the file pointed to by the locator actually exists on the server's FileSystem or not.
FileGetName	Determines only the directory alias and the filename.
FileIsOpen	Checks to see if the file is already open.
FileOpen	Opens a BFILE for the read-only access.



• To create a procedure that displays the first 30 characters of the file, refer the following example:

CREATE OR REPLACE PROCEDURE b_file(Eno in number) IS LOC BFILE;
V_FILEEXISTS INTEGER;
v_FILEISOPEN INTEGER;

NUM NUMBER; OFFSET NUMBER; LEN NUMBER; DIR_ALIAS VARCHAR2(5); NAME VARCHAR2(15);

CONTENTS LONG;

contd



BEGIN SELECT B_FILE INTO LOC FROM LEAVE WHERE EMPNO=Eno; -- Check to see if file exists V_FILEEXISTS := DBMS_LOB.FILEEXISTS(LOC); IF v_FILEEXISTS = 1 THEN DBMS_OUTPUT.PUT_LINE('The file exists'); ELSE GoTo E; END IF; -- Check if file open v_FILEISOPEN := DBMS_LOB.FILEISOPEN(LOC); contd.

Capgemini

DBMS_OUTPUT.PUT_LINE('Contents of the file: '|| CONTENTS);
END IF;
DBMS_LOB.FILEGETNAME(LOC, DIR_ALIAS, NAME);
DBMS_OUTPUT.PUT_LINE ('Opening' || dir_alias || name);
DBMS_LOB.FILECLOSE(LOC); -- Close the BFILE
<<E>>
DBMS_OUTPUT.PUT_LINE('The file cannot be found');
END; /



Test the procedure by executing it at SQL prompt as follows:

SQL> execute b_file(7900);

The file exists

Opening the file

Length of the file: 30

Contents of the file: BOSTONS MANAGEMENT CONSULTANTS

Opening L_DIR TEST.TXT

MSG: PL/SQL procedure successfully completed



DBMS_LOB.FILECLOSE() procedure:

- You can call the FILECLOSE() procedure to close a BFILE that has already been opened via the input locator.
- Note that Oracle has only read-only access to BFILEs.
 This means that BFILEs cannot be written through Oracle.

Syntax:

```
PROCEDURE FILECLOSE (
file_loc IN OUT BFILE);
```

Parameter:

Parameter Name	Meaning
File_loc	Locator for the BFILE to be closed.

Return values:

None

Pragmas:

None

Example:

```
PROCEDURE Example_5 IS
fil BFILE;
BEGIN
SELECT f_lob INTO fil FROM lob_table WHERE
key_value = 99;
DBMS_LOB.FILEOPEN(fil);
-- file operations
DBMS_LOB.FILECLOSE(fil);
EXCEPTION
WHEN some_exception
THEN handle_exception;
END;
```

Summary

- In this lesson, you have learnt about:
 - Testing and Debugging in PL/SQL
 - DBMS_OUTPUT
 - Enabling and Disabling output
 - Writing to the DBMS_OUTPUT Buffer
 - UTL file
 - Handling LOB (Large Objects)





Review Question

- Question 1: The value held in a LOB column or variable is not the actual binary data, but a "locator" or pointer to the physical location of the large object
 - True / False



- Question 2: CLOB stores a column that supports multi-byte characters from National Character set defined by Oracle.
 - True / False



Review Question

- Question 3: If the pointer to the file is already located at the last line of the file, UTL_FILE.GET_LINE does not return data.
 - True / False



- Question 4: The file can be open in one of the following three modes: ____, ___, and ___
- Question 5: The package ____ lets you read and write files accessible from the server on which your database is running.

