# 7. Deploy the Anthos Admin Workstation HCI

NetApp September 04, 2020

This PDF was generated from https://docs.netapp.com/us-en/hci-solutions/anthos\_task\_deploy\_the\_anthos\_admin\_workstation.html on November 04, 2020. Always check docs.netapp.com for the latest.



## **Table of Contents**

7. Deploy the Anthos Admir	Workstation	. 1
----------------------------	-------------	-----

## 7. Deploy the Anthos Admin Workstation

The admin workstation is a vSphere VM deployed within your NetApp HCI environment that is preinstalled with all the tools necessary to administer the Anthos on VMware solution. Follow the instructions in this section to download, deploy, and configure the Anthos admin workstation.



The admin workstation image is packaged as an OVA file and is only available for download to those users with whitelisted access service accounts. If you are unable to download the OVA from cloud storage, contact your project administrator or open a support ticket with Google Cloud support.

To deploy the Anthos admin workstation, complete the following steps:

1. Download the latest version of the virtual appliance here. You must first set your account to the whitelisted access service account that has permission to download the OVA.

```
[user@rhel7 ~]$ gcloud config set account 'access-service-account@anthos-dev.iam.gserviceaccount.com'
Updated property [core/account].
[user@rhel7 ~]$ gsutil cp gs://gke-on-prem-release/admin-appliance/1.1.1-gke.2/gke-on-prem-admin-appliance-vsphere-1.1.1-gke.2.{ova.ova.sig} ~/
Copying gs://gke-on-prem-release/admin-appliance/1.1.1-gke.2/gke-on-prem-admin-appliance-vsphere-1.1.1-gke.2.ova...
==> NOTE: You are downloading one or more large file(s), which would run significantly faster if you enabled sliced object downloads. This feature is enabled by default but requires that compiled crcmod be installed (see "gsutil help crcmod").


- [0 files][ 40.2 MiB/ 5.1 GiB]
```

2. When the OVA file is downloaded, use govc to load it into your vCenter. You need to set several environment variables for your current user that provide specific information about your VMware vSphere environment deployed on NetApp HCI.

```
[user@rhel7 ~]$ export GOVC_URL=https://anthos-vc.cie.netapp.com/sdk
[user@rhel7 ~]$ export GOVC_USERNAME=administrator@vsphere.local
[user@rhel7 ~]$ export GOVC_PASSWORD=vcpassword
[user@rhel7 ~]$ export GOVC_DATASTORE=VM_Datastore
[user@rhel7 ~]$ export GOVC_DATACENTER=NetApp-HCI-Datacenter-01
[user@rhel7 ~]$ export GOVC_RESOURCE_POOL= Anthos-Resource-Pool
[user@rhel7 ~]$ export GOVC_INSECURE=true
```

3. Because the NetApp HCI deployment uses a vDS, you need to create a custom options file that you pass as an additional argument to govc. Create a file called options\_specs, and commit the following information to the file:

4. To import the OVA file as template in VMware vSphere, enter the following command referencing the downloaded virtual appliance file, as well as the options file that you just created. The console reports upload progress, and you can also verify the upload by browsing to the Recent Tasks window in VMware vSphere.



5. With the template uploaded, we can now use Terraform to deploy the Anthos admin workstation VM. Google provides a Terraform template and variable files for environments using DHCP as well those using static IP addresses. Create a directory for these Terraform files, and copy and paste the text for both the TF and TFVARS files available here into files created with a text editor.

```
[user@rhel7 ~]$ mkdir terraform
[user@rhel7 ~]$ cd terraform
[user@rhel7 ~]$ vi terraform.tfvars
```

6.	6. See the following terraform.tfvars file contents.	

```
# vCenter Server username
vcenter_user = "administrator@vsphere.local"
# vCenter Server password
vcenter_password = "vcpassword"
# vCenter Server IP or hostname
vcenter_server = "https://anthos-vc.cie.netapp.com"
# Path in which the admin workstation's VM's public key should be saved
ssh_public_key_path = "~/.ssh/vsphere_workstation.pub"
# Hostname for the VM
vm name = "admin-workstation"
# vSphere datastore to use for storage
datastore = "VM_Datastore"
# vSphere datacenter in which to create the VM
datacenter = "NetApp-HCI-Datacenter-01"
# vSphere cluster in which to create the VM
cluster = "NetApp-HCI-Cluster-01"
# vSphere resource pool in which to create VM, if you are using a non-default resource
pool
# If you are using the default resource pool, provide a value like "CLUSTER-
NAME/Resources"
resource_pool = "Anthos-Resource-Pool"
# vSphere network to use for the VM
network = "VM_Network"
# Number of CPUs for this VM. Recommended minimum 4.
num_cpus = 4
# Memory in MB for this VM. Recommended minimum 8192.
memory = 8192
# The VM template (OVA) to clone. Change the version if you imported a different
version of the OVA.
vm_template = "gke-on-prem-admin-appliance-vsphere-1.1.1-gke.2"
[user@rhel7 ~]$ vi terraform.tf
```

7. See the following terraform.tf file contents.

```
##########################
###### VARIABLES ######
############################
# The following variables are declared in the accompanying TFVARS file
# vCenter Server username
variable "vcenter_user" { }
# vCenter Server password
variable "vcenter_password" { }
# vCenter Server address
variable "vcenter_server" { }
# Path in which the VM's public key should be saved
variable "ssh_public_key_path" { default = "~/.ssh/vsphere_workstation.pub" }
# vSphere network to use for the VM
variable "network" { default = "VM Network"}
# Hostname for the VM
variable "vm_name" { default = "vsphere-workstation" }
# vSphere datacenter in which to create the admin workstation VM
variable "datacenter" { }
# vSphere datastore to use for storage
variable "datastore" { }
# vSphere cluster in which to create the VM
variable "cluster" { }
# vSphere resource pool in which to create the VM
variable "resource_pool" { }
# Number of CPUs for this VM. Recommended minimum 4.
variable "num_cpus" { default = 4 }
# Memory in MB for this VM. Recommended minimum 8192.
variable "memory" { default = 8192 }
# The VM template (OVA) to clone
variable "vm_template" { }
```

```
provider "vsphere" {
 version = "~> 1.5"
user = "${var.vcenter_user}"
password = "${var.vcenter_password}"
 vcenter_server = "${var.vcenter server}"
 # if you have a self-signed cert
 allow unverified ssl = true
}
### vSphere Data ###
data "vsphere_datastore" "datastore" {
 name = "${var.datastore}"
 datacenter_id = "${data.vsphere_datacenter.dc.id}"
}
data "vsphere_datacenter" "dc" {
 name = "${var.datacenter}"
}
data "vsphere_compute_cluster" "cluster" {
  name = "${var.cluster}"
 datacenter_id = "${data.vsphere_datacenter.dc.id}"
data "vsphere_resource_pool" "pool" {
 name = "${var.resource pool}"
 datacenter_id = "${data.vsphere_datacenter.dc.id}"
}
data "vsphere_network" "network" {
 name = "${var.network}"
 datacenter_id = "${data.vsphere_datacenter.dc.id}"
}
data "vsphere_virtual_machine" "template_from_ovf" {
 name = "${var.vm template}"
 datacenter id = "${data.vsphere datacenter.dc.id}"
}
data "template_file" "dhcp_ip_config" {
 template = <<EOF
network:
```

```
version: 2
  ethernets:
    ens192:
      dhcp4: true
E0F
}
data "template_file" "user_data" {
  template = <<EOF
#cloud-config
apt:
 primary:
    - arches: [default]
      uri: http://us-west1.gce.archive.ubuntu.com/ubuntu/
write files:
  - path: /etc/netplan/99-dhcp.yaml
    permissions: '0644'
    encoding: base64
    content: |
      $${dhcp_ip_config}
runcmd:
  - netplan apply
  - /var/lib/gke/guest-startup.sh
E0F
  vars = {
    dhcp_ip_config = "${base64encode(data.template_file.dhcp_ip_config.rendered)}"
 }
}
### vSphere Resources ###
resource "vsphere_virtual_machine" "vm" {
                   = "${var.vm_name}"
  name
  resource_pool_id = "${data.vsphere_resource_pool.pool.id}"
 datastore_id = "${data.vsphere_datastore.id}"
num_cpus = "${var.num_cpus}"
memory = "${var.memory}"
  guest_id = "${data.vsphere_virtual_machine.template_from_ovf.guest_id}"
  enable_disk_uuid = "true"
  scsi_type = "${data.vsphere_virtual_machine.template_from_ovf.scsi_type}"
  network interface {
    network id = "${data.vsphere network.network.id}"
    adapter_type =
"${data.vsphere_virtual_machine.template_from_ovf.network_interface_types[0]}"
  wait_for_guest_net_timeout = 15
```

```
nested_hv_enabled = false
  cpu_performance_counters_enabled = false
  disk {
                   = "disk0"
   label
                    = "${max(50,
    size
data.vsphere virtual machine.template from ovf.disks.0.size)}"
    eagerly_scrub
"${data.vsphere_virtual_machine.template_from_ovf.disks.0.eagerly_scrub}"
    thin provisioned =
"${data.vsphere virtual machine.template from ovf.disks.0.thin provisioned}"
  cdrom {
   client_device = true
  }
  vapp {
    properties = {
      hostname = "${var.vm_name}"
      public-keys = "${file(var.ssh_public_key_path)}"
     user-data = "${base64encode(data.template_file.user_data.rendered)}"
   }
  }
  clone {
    template_uuid = "${data.vsphere_virtual_machine.template_from_ovf.id}"
  }
}
output "ip_address" {
  value = "${vsphere_virtual_machine.vm.default_ip_address}"
}
```



Values specific to the deployed environment have been added to the terraform.tfvars file. However, you should not modify the terraform.tf file in any manner.

8. Create an SSH public/private keypair used to log in to the admin workstation after it is deployed. Name the public key so that is matches the variable that was assigned in the terraform.tfvars file.

```
[user@rhel7 ~]$ ssh-keygen -t rsa -f ~/.ssh/vsphere_workstation -N ""
Generating public/private rsa key pair.
Your identification has been saved in /home/user/.ssh/vsphere_workstation2.
Your public key has been saved in /home/user/.ssh/vsphere_workstation2.pub.
The key fingerprint is:
SHA256:qEk8G13LhwiKqf85ekHHZkIZduX2MkZUxGNEHvFT2vw user@rhe17
The key's randomart image is:
+---[RSA 2048]----+
  oo.o+*B. .
  .0. 0 .+0 =
 ... B.o.+ o
| o ooo=B * . . |
|0..=+S.E|
. ..*
|. +.
. 0.
0+0.
+----[SHA256]----+
```

9. Navigate to the directory created to host the TF and TFVARS files. Within this directory, initialize Terraform and use it to launch the deployment of the admin workstation VM.

```
[user@rhel7 ~]$ cd terraform
[user@rhel7 terraform]$ ls
terraform.tf terraform.tfvars
[user@rhel7 terraform]$ terraform init && terraform apply -auto-approve -input=false
Initializing the backend...
Initializing provider plugins...
The following providers do not have any version constraints in configuration,
so the latest version was installed.
To prevent automatic upgrades to new major versions that may contain breaking
changes, it is recommended to add version = "..." constraints to the
corresponding provider blocks in configuration, with the constraint strings
suggested below.
* provider.template: version = "~> 2.1"
Terraform has been successfully initialized!
data.template file.dhcp ip config: Refreshing state...
data.template_file.user_data: Refreshing state...
data.vsphere_datacenter.dc: Refreshing state...
data.vsphere resource pool.pool: Refreshing state...
data.vsphere datastore.datastore: Refreshing state...
data.vsphere_virtual_machine.template_from_ovf: Refreshing state...
data.vsphere network.network: Refreshing state...
data.vsphere compute cluster.cluster: Refreshing state...
vsphere_virtual_machine.vm: Creating...
vsphere virtual machine.vm: Still creating... [10s elapsed]
vsphere_virtual_machine.vm: Still creating... [20s elapsed]
vsphere_virtual_machine.vm: Still creating... [30s elapsed]
vsphere virtual machine.vm: Still creating... [40s elapsed]
vsphere_virtual_machine.vm: Creation complete after 49s [id=42118cfa-d464-b815-f7b1-
37cd85b2943a1
Warning: "vcenter_server": [DEPRECATED] This field has been renamed to vsphere server.
Apply complete! Resources: 1 added, 0 changed, 0 destroyed.
Outputs:
ip address = 10.63.172.21
```

Next: Deploy the Admin and the First User Cluster

### **Copyright Information**

Copyright © 2020 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval systemwithout prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

#### **Trademark Information**

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.