An environment for multicolumn output*†

Frank Mittelbach Email: see top of the source file

Printed November 12, 2021

This file is maintained by the LATEX Project team. Bug reports can be opened (category tools) at https://latex-project.org/bugs.html.

Abstract

This article describes the use and the implementation of the multicols environment. This environment allows switching between one and multicolumn format on the same page. Footnotes are handled correctly (for the most part), but will be placed at the bottom of the page and not under each column. IATEX's float mechanism, however, is partly disabled in this implementation. At the moment only page-wide floats (i.e., star-forms) can be used within the scope of the environment.

Preface to version 1.8

The 1.8 release improves on the balancing approach. If due to a limited number of break points (e.g., due to large objects) the balanced columns exceed the available vertical space, then balancing is canceled and a normal page is produced first. Some overflow is allowed (controlled by the parameter \maxbalancingoverflow which defaults to 12pt). This ensures that we only cut a normal page if we get enough material carried over to next page.

Also added was support for \enlargethispage. This means it is now possible to request a page to be artificially enlarged or shortened. Note that if you enlarge pages by more than one line you may have to increase the

collectmore counter value to ensure that enough material is being picked up.

This command was used on the second page of this manual to shorten it by one line, in order to get rid of a number of widow lines on the following pages.

There are also some small enhancements to the balancing algorithm including a ways to require a minimum number of rows in the result.

Finally, version 1.8 adds the command \docolaction to help with more complicated actions that depend on the current column. This command expects 3 arguments: code that is executed if we are in the "first" column, code to execute if we end up in any "middle" column (if there are

more than two) and finally code to execute if we are in the "last" column. Thus

\docolaction{first} {middle}{last}

would typeset a different word depending the type of column this code is executed. Using it like this is probably pointless, but you can imagine applications like writing something into the nearest margin, etc.

As this feature needs at least two IATEX runs to produce correct results and as it adds to the processing complexity it is only made available if one add the option colaction when loading the package.

^{*}This file has version number v1.9b, last revised 2021/10/28.

[†]Note: This package is released under terms which affect its use in commercial applications. Please see the details at the top of the source file.

Preface to version 1.7 (right to left support)

The 1.7 release adds support for languages that are typeset right-to-left. For those languages the order of the columns on the page also need to be reversed—

something that wasn't supported before. The next paragraph demonstrates the result (as it is typeset as if we are writing in a left-to-right languageso read the rightmost column first). The change is initialized via \RLmulticolcolumns and returning to left-right (default) is done via \LRmulticolcolumns.

For example:

directions within the columns. As footnotes are typeset in full measure the footnote rule needs to be redefined as if they are below a single column, i.e., using \textwidth not \columnwidth.

Right-to-left typesetting will only reverse the column orders. Any other support needed will have to be provided by other means, e.g., using appropriate fonts and reversing the writing

Preface to version 1.5 + 1.6

The 1.5 release contains two major changes: multicols will now support up to 10 columns and two more tuning possibilities have been added to the balancing routine. The balancing rou-

tine now checks the badness of the resulting columns and rejects solutions that are larger than a certain threshold. At the same time multicols has been upgraded to run under LATEX $2_{\mathcal{E}}$.

Later changes to 1.5 include \columnbreak and multicols*.

For version 1.6 micro-spacing around the boxes produced by multicols has been improved to allow for baseline-grid typesetting.

1 Introduction

Switching between two-column and one-column layout is possible in LATEX, but every use of \twocolumn or \onecolumn starts a new page. Moreover, the last page of two-column output isn't balanced and this often results in an empty, or nearly empty, right column. When I started to write macros for doc.sty (see "The

doc-Option", *TUGboat* volume 10 #2, pp. 245–273) I thought that it would be nice to place the index on the same page as the bibliography. And balancing the last page would not only look better, it also would save space; provided of course that it is also possible to start the next article on the same page. Rewriting the index environment was compar-

atively easy, but the next goal, designing an environment which takes care of footnotes, floats, etc., was a harder task. It took me a whole weekend¹ to get together the few lines of code below and there is still a good chance that I missed something after all.

Try it and, hopefully, enjoy it; and *please* direct bug reports and suggestions back to Mainz.

2 The User Interface

To use the environment one simply says

 $\label{eq:constraints} $$ \left\{ \langle number \rangle \right\} $$ \left\{ \langle number \rangle \right\} $$ \left\{ multicolumn \ text \right\} $$ \left\{ multicols \right\} $$$

where $\langle number \rangle$ is the required number of columns and $\langle multi-column\ text \rangle$ may contain arbitrary LATEX commands, except that floats and marginpars are not allowed in the current imple-

mentation².

As its first action, the multicols environment measures the current page to determine whether there is enough room for some

¹I started with the algorithm given in the T_EXbook on page 417. Without this help a weekend would not have been enough. (This remark was made in the documentation of the initial release, since then several hundreds more hours went into improving the original code.)

²This is dictated by lack of time. To implement floats one has to reimplement the whole LATEX output routine.

portion of multicolumn output. This is controlled by the $\langle dimen \rangle$ variable \premulticols which can be changed by the user with ordinary LATEX commands. If the space is less than \premulticols, a new page is started. Otherwise, a \vskip of \multicolsep is added.³

When the end of the multicols environment is encountered, an analogous mechanism is employed, but now we test whether there is a space larger than \postmulticols available. Again we add \multicolsep or start a new page.

It is often convenient to spread some text over all columns, just before the multicolumn output, without any page break in between. To achieve this the multicols environment has an optional second argument which can be used for this purpose. For example, the text you are now reading was started with

\begin{multicols}{3}
[\section{The User
Interface}] ...

If such text is unusually long (or short) the value of \premulticols might need adjusting to prevent a bad page break. We therefore provide a third argument which can be used to overwrite the default value of \premulticols just for this occasion. So if you want to combine some longer single column text with a multicols environment you could write

\begin{multicols}{3}
 [\section{Index}
 This index contains ...]
 [6cm]
...

The space between columns is controlled by the length parameter \columnsep. The width for the individual columns is automatically calculated from this parameter and the current \linewidth. In this article a value of 18.0pt was used.

Separation of columns with vertical rules is achieved by setting the parameter \columnseprule to some positive value. In this article a value of .4pt was used.

The color of the rules separating the columns can be specified through \columnseprulecolor. The default value is \normalcolor.

Since narrow columns tend to need adjustments in interline spacing we also provide a $\langle skip \rangle$ parameter called \multicolbaselineskip which is added to the \baselineskip parameter inside the multicols environment. Please use this parameter with care or leave it alone; it is intended only for package file designers since even small changes might produce totally unexpected changes to your document.

2.1 Balancing columns

Besides the previously mentioned parameters, some others are provided to influence the layout of the columns generated.

Paragraphing in TEX is controlled by several parameters. One of the most important is called \tolerance: this controls the allowed 'looseness' (i.e. the amount of blank space between words). Its default value is 200 (the LATEX \fussy) which is too

small for narrow columns. On the other hand the \sloppy declaration (which sets \tolerance to $10000 = \infty$) is too large, allowing really bad spacing.⁴

We therefore 11se a. \multicoltolerance parameter for the \tolerance value inside the multicols environment. default value is 9999 which is less than infinity but 'bad' enough for most paragraphs in a multicolumn environment. Changing its value should be done outside the multicols environment. Since \tolerance is set to \multicoltolerance at the beginning of every multicols environment one can locally overwrite this default by assigning \tolerance_i=_i \langle desired There also exists a $value \rangle$. \multicolpretolerance rameter holding the value for \pretolerance within a multicols environment. Both parameters are usually used only by package designers.

Generation of multicolumn output can be divided into two parts. In the first part we are collecting material for a page, shipping it out, collecting material for the next page, and so on. As a second step, balancing will be done when the end of the multicols environment is reached. In the first step T_FX might consider more material whilst finding the final column content than it actually uses when shipping out the page. This might cause a problem if a footnote is encountered in the part of the input considered, but not used, on the current page. In this case the footnote might show up on the current page, while the footnotemark corresponding to this footnote

³Actually the added space may be less because we use \addvspace (see the LATEX manual for further information about this command)

⁴Look at the next paragraph, it was set with the \sloppy declaration.

might be set on the next one.⁵ Therefore the multicols environment gives a warning message⁶ whenever it is unable to use all the material considered so far.

If you don't use footnotes too often the chances of something actually going wrong are very slim, but if this happens you can help TEX by using a \pagebreak command in the final document. Another way to influence the behavior of T_EX in this respect is given by the counter variable 'collectmore'. If you use the \setcounter declaration to set this counter to $\langle number \rangle$, T_EX will consider $\langle number \rangle$ more (or less) lines before making its final decision. So a value of -1may solve all your problems at the cost of slightly less optimal columns.

In the second step (balancing columns) we have other bells and whistles. First of all you can say \raggedcolumns if you don't want the bottom lines to be aligned. The default is \flushcolumns, so TeX will normally try to make both the top and bottom baselines of all columns align.

If there is only a small amount of material available for balancing then you may end up with very few lines per column. In an extreme case there may be only one line which looks distinctly odd. In that case it might be better to have more material distributed to the earlier columns even if that means that later columns are empty or partially empty. This is controlled through the counter 'minrows' (default 1). If set to a higher value then the balancing will have at least that many rows in the first column (and also all further columns until it runs outs of material).

Additionally you can set another counter, the 'unbalance' counter, to some positive $\langle number \rangle$. This will make all but the right-most column $\langle number \rangle$ of lines longer than they would normally have been. 'Lines' in this context refer to normal text lines (i.e. one \baselineskip apart); thus, if your columns contain displays, for example, you may need a higher $\langle number \rangle$ to shift something from one column into another. A negative value can make sense if you have set minrows and want to locally adjust that.

Unlike 'collectmore,' the 'unbalance' counter is reset to zero at the end of the environment so it only applies to one multicols environment.

The two methods may be combined but I suggest using these features only when fine tuning important publications.

Two more general tuning possibilities were added with version 1.5. TEX allows to measure the badness of a column in terms of an integer value, where 0 means optimal and any higher value means a certain amount of extra white space. 10000 is considered to be infinitely bad (TEX does not distinguish any further). In addition the special value 100000 means overfull (i.e., the column contains more text than could possibly fit into it).

The new release now measures every generated column and ignores solutions where at least one column has a badness being larger than the value of the counter columnbadness. The default value for this counter is 10000, thus TEX will accept all solutions except those being over-

full. By setting the counter to a smaller value you can force the algorithm to search for solutions that do not have columns with a lot of white space.

However, if the setting is too low, the algorithm may not find any acceptable solution at all and will then finally choose the extreme solution of placing all text into the first column.

Often, when columns are balanced, it is impossible to find a solution that distributes the text evenly over all columns. If that is the case the last column usually has less text than the others. In the earlier releases this text was stretched to produce a column with the same height as all others, sometimes resulting in really ugly looking columns.

In the new release this stretching is only done if the badness of the final column is not larger than the value of the counter finalcolumnbadness. The default setting is 9999, thus preventing the stretching for all columns that TEX would consider infinitely bad. In that case the final column is allowed to run short which gives a much better result.

And there are two more parameters ofsome experimental nature, one called \multicolovershoot the other \multicolundershoot. They control the amount of space a column within the multicols environment is allowed to be "too full" or "too short" without affecting the column badness. They are set to 0pt and 2pt, respectively.

Finally, when doing the balancing at the end, columns may become higher than the remaining available space. In that case the algorithm aborts and instead generates a normal

⁵The reason behind this behavior is the asynchronous character of the TEX page_builder. However, this could be avoided by defining very complicated output routines which don't use TEX primitives like \insert but do everything by hand. This is clearly beyond the scope of a weekend problem.

 $^{^6}$ This message will be generated even if there are no footnotes in this part of the text.

page. However, if the amount is not too large, e.g., a line or so, then it might be better to keep everything on the same page instead of starting a new page with just one line after balancing. So the parameter \maxbalancingoverflow governs this process: only when the excess gets larger than its value balancing is aborted.

2.2 Not balancing the columns

Although this package was written to solve the problem of balancing columns, I got repeated requests to provide a version where all white space is automatically placed in the last column or columns. Since version v1.5q this now exists: if you use multicols* instead of the usual environment the columns on the last page are not balanced. Of course, this environment only works on top-level, e.g., inside a box one has to balance to determine a column height in absence of a fixed value.

2.3 Manually breaking columns

Another request often voiced was: "How do I tell LATEX that it should break the first column after this particular line?". The \pagebreak command (which works with the two-column option of LATEX) is of no use here since it would end the collection phase of multicols and thus all columns on that page. So with version 1.5u the \columnbreak command was added. If used within a paragraph it marks the end of the current line as the desired breakpoint. You can observe its effect on the previous page where three lines of text have been artificially forced into the second column (resulting in some white space between paragraphs in the first column).

From version 1.9 onwards \columnbreak accepts an optional argument (just like \pagebreak) in which you can specify the desirability to break the column at that point: supported values are 0 (slightly desirable) to 4 (forced). This version also adds \newcolumn which forces a column break but runs the column short (comparable to \newpage).

2.4 Floats inside a multicols environment

Within the multicols environment the usual star float commands are available but their function is somewhat different as in the twocolumn mode of standard LATEX. Stared floats, e.g., figure*, denote page wide floats that are handled in a similar fashion as normal floats outside the multicols environment. However, they will never show up on the page where they are encountered. In other words, one can influence their placement by specifying a combination of t, b, and/or p in their optional argument, but h doesn't work because the first possible place is the top of the next page. One should also note, that this means that their placement behavior is determined by the values of \topfraction, etc. rather than by \dbl....

2.5 Support for rightto-left typesetting

In right-to-left typesetting the order of the columns on the page also need to be reversed, i.e., the first column has to appear on the far right and the last column on the left. This is supported through the commands \RLmulticolcolumns (switching to right-to-left typesetting) and

\LRmulticolcolumns (switching to left-to-right typesetting) the latter being the default.

2.6 Warnings

Under certain circumstances the use of the multicols environment may result in some warnings from TEX or IATEX. Here is a list of the important ones and the possible cause:

Underfull \hbox (badness ...)

As the columns are often very narrow TeX wasn't able to find a good way to break the paragraph. Underfull denotes a loose line but as long as the badness value is below 10000 the result is probably acceptable.

Underfull \vbox ... while \output is active

If a column contains a character with an unusual depth, for example a '(', in the bottom line then this message may show up. It usually has no significance as long as the value is not more than a few points.

LaTeX Warning: I moved some lines to the next page

As mentioned above, multicols sometimes screws up the footnote numbering. As a precaution, whenever there is a footnote on a page where multicols had to leave a remainder for the following page this warning appears. Check the footnote numbering on this page. If it turns out that it is wrong, you have to manually break the page using \newpage or \pagebreak[..].

Floats and marginpars not allowed inside 'multicols' environment!

This message appears if you try to use the \marginpar command or an unstarred version of the figure or table environment. Such floats will disappear!

Very deep columns! Grid alignment might be broken

This message can only appear if the option grid was chosen. In that case it will show up if a column has a very large depth so that multicols is unable to back up to its baseline. This is only relevant if one tries to produce a document where all text lines are aligned at an invisible grid, something that requires careful adjustment of many parameters and macros, e.g., heading definitions.

2.7 Tracing the output

To understand the reasoning behind the decisions T_EX makes

when processing a multicols environment, a tracing mechanism is provided. If you set the counter 'tracingmulticols' to a positive $\langle number \rangle$ you then will get some tracing information on the terminal and in the transcript file:

 $\langle number \rangle = 1$. TEX will now tell you, whenever it enters or leaves a multicols environment, the number of columns it is working on and its decision about starting a new page before or after the environment.

⟨number⟩ = 2. In this case you also get information from the balancing routine: the heights tried for the left and right-most columns, information about shrinking if the \raggedcolumns declaration is in force and the value of the 'unbalance' counter if positive.

$\langle number \rangle = 3$. Setting

⟨number⟩ to this value will additionally trace the mark handling algorithm. It will show what marks are found, what marks are considered, etc. To fully understand this information you will probably have to read carefully trough the implementation.

$\langle number \rangle \geq 4$. Setting

⟨number⟩ to such a high value will additionally place an \hrule into your output, separating the part of text which had already been considered on the previous page from the rest. Clearly this setting should not be used for the final output. It will also activate even more debugging code for mark handling.

3 Prefaces to older versions

3.1 Preface to version 1.4

Beside fixing some bugs as mentioned in the multicol.bug file this new release enhances the multicols environment by allowing for balancing in arbitrary contexts. It is now, for example, possible to balance text within a multicols or a minipage as shown in 2 where a multicols environment within a quote environment was used. It is now even possible to nest multicols environments.

The only restriction to such inner multicols environments (nested, or within TEX's internal vertical mode) is that such vari-

ants will produce a box with the balanced material in it, so that they can not be broken across pages or columns.

Additionally I rewrote the algorithm for balancing so that it will now produce slightly better results.

I updated the source documentation but like to apologize in advance for some 'left over' parts that slipped through the revision.

A note to people who like to improve the balancing algorithm of multicols: The balancing routine is now placed into a single macro which is called \balance@columns. This means that one can easily try different balancing routines by rewriting this macro. The interface for it is explained in table 1. There are several improvements possible, one can think of integrating the \badness function of TEX3, define a faster algorithm for finding the right column height, etc. If somebody thinks he/she has an enhancement I would be pleased to learn about it. But please obey the copyright notice and don't change multicol.dtx directly!

3.2 Preface to version 1.2

After the article about the multicols environment was published in *TUGboat* 10#3, I got numerous requests for these macros. However, I also got a changed

version of my style file, together with a letter asking me if I would include the changes to get better paragraphing results in the case of narrow lines. The main dif-

ferences to my original style option were additional parameters (like \multicoladjdemerits to be used for \adjdemerits, etc.) which would influence the line

The macro \balance@columns that contains the code for balancing gathered material is a macro without parameters. It assumes that the material for balancing is stored in the box \mult@box which is a \vbox. It also "knows" about all parameters set up by the multicols environment, like \col@number, etc. It can also assume that \@colroom is the still available space on the current page.

When it finishes it must return the individual columns in boxes suitable for further processing with \page@sofar. This means that the left column should be stored in box register \mult@firstbox, the next in register \mult@firstbox + 2, ..., only the last one as an exception in register \mult@grightbox. Furthermore it has to set up the two macros \kept@firstmark and \kept@botmark to hold the values for the first and bottom mark as found in the individual columns. There are some helper functions defined in section 5.1 which may be used for this. Getting the marks right "by hand" is non-trivial and it may pay off to first take a look at the documentation and implementation of \balance@columns below before trying anew.

Table 1: Interface description for \balance@columns

breaking algorithm.

But actually resetting such parameters to zero or even worse to a negative value won't give better line breaks inside the multicols environment. TEXs line breaking algorithm will only look at those possible line breaks which can be reached without a badness higher than the current value of \tolerance (or \pretolerance in the first pass). If this isn't possible, then, as a last resort, T_EX will produce overfull boxes. All those (and only those) possible break points will be considered and finally the sequence which results in the fewest demerits will be chosen. This means that a value of -1000 for \adjdemerits instructs T_EX to prefer visibly incompatible lines instead of producing better line breaks.

However, with T_EX 3.0 it is possible to get decent line breaks

even in small columns by setting \emergencystretch to an appropriate value. I implemented a version which is capable of running both in the old and the new TeX (actually it will simply ignore the new feature if it is not available). The calculation of \emergencystretch is probably incorrect. I made a few tests but of course one has to have much more experience with the new possibilities to achieve the maximum quality.

Version 1.1a had a nice 'feature': the penalty for using the forbidden floats was their ultimate removal from LATEXs \@freelist so that after a few \marginpars inside the multicols environment floats where disabled forever. (Thanks to Chris Rowley for pointing this out.) I removed this misbehavior and at the same time decided to allow at

least floats spanning all columns, e.g., generated by the figure* environment. You can see the new functionality in table 2 which was inserted at this very point. However single column floats are still forbidden and I don't think I will have time to tackle this problem in the near future. As an advice for all who want to try: wait for T_EX 3.0. It has a few features which will make life much easier in multi-column surroundings. Nevertheless we are working here at the edge of T_FXs capabilities, really perfect solutions would need a different approach than it was done in TeXs page builder.

The text below is nearly unchanged, I only added documentation at places where new code was added.

4 The Implementation

We are now switching to two-column output to show the abilities of this environment (and bad layout decisions).

4.1 The documentation driver file

The next bit of code contains the documentation driver file for T_FX, i.e., the file that will produce the

documentation you are currently reading. It will be extracted from this file by the docstrip program.

\setemergencystretch: This is a hook for people who like to play around. It is supposed to set the \emergencystretch $\langle dimen \rangle$ register provided in the new TeX 3.0. The first argument is the number of columns and the second one is the current \hsize. At the moment the default definition is

 $4\mathtt{pt}\times \mathtt{\#1}, \text{ i.e. the } \backslash \mathtt{hsize} \text{ isn't used at all. But maybe there are better formulae.}$

\set@floatcmds: This is the hook for the experts who like to implement a full float mechanism for the multicols environment. The @ in the name should signal that this might not be easy.

Table 2: The new commands of multicol.sty version 1.2. Both commands might be removed if good solutions to these open problems are found. I hope that these commands will prevent that nearly identical style files derived from this one are floating around.

Since this is the first code in this file one can produce the documentation simply by running \LaTeX on the .dtx file.

- $_1$ $\langle *driver \rangle$
- 2 \documentclass{ltxdoc}

We use the balancingshow option when loading multicols so that full tracing is produced. This has to be done before the doc package is loaded, since doc otherwise requires multicols without any options.

- 3 \usepackage{multicol}[1999/05/25]
- 4 \usepackage{doc}

First we set up the page layout suitable for this article.

```
5 \setlength{\textwidth}{39pc}
```

- 6 \setlength{\textheight}{54pc}
- 7 \setlength{\parindent}{1em}
- 8 \setlength{\parskip}{Opt plus 1pt}
- 9 \setlength{\oddsidemargin}{Opc}
- 10 \setlength{\marginparwidth}{0pc}
- 11 \setlength{\topmargin}{-2.5pc}
- 12 \setlength{\headsep}{20pt}
- 13 $\left\lceil \frac{1.5pc}{1.5pc} \right\rceil$

We want a rule between columns.

14 \setlength\columnseprule{.4pt}

We also want to ensure that a new multicols environment finds enough space at the bottom of the page.

15 \setlength\premulticols{6\baselineskip}

When balancing columns we disregard solutions that are too bad. Also, if the last column is too bad we typeset it without stretch.

```
16 \setcounter{columnbadness}{7000}
```

17 \setcounter{finalcolumnbadness}{7000}

The index is supposed to come out in four columns. And we don't show macro names in the margin.

```
18 \setcounter{IndexColumns}{4}
```

- 19 \let\DescribeMacro\SpecialUsageIndex
- 20 \let\DescribeEnv\SpecialEnvIndex
- 21 \renewcommand\PrintMacroName[1]{}
- 22 \CodelineIndex
- 23 %\DisableCrossrefs % Partial index
- 24 \RecordChanges % Change log

Line numbers are very small for this article.

```
25 \renewcommand{\theCodelineNo}
```

- 26 {\scriptsize\rm\arabic{CodelineNo}}
- 27 \settowidth\MacroIndent{\scriptsize\rm 00\ }

28

 $29 \geq 29$

32 ^^J* Expect some Under- and overfull boxes.

33 ^^J*****************

34 \DocInput{multicol.dtx}

35 \end{document}

36 (/driver)

4.2 Identification and option processing

We start by identifying the package. Since it makes use of features only available in LATEX 2ε we ensure that this format is available. (Now this is done earlier in the file.)

```
37 (*package)
```

- 38 % \NeedsTeXFormat{LaTeX2e}
- 39 % \ProvidesPackage{multicol}[..../../..
- 40 % v... multicolumn formatting]

Next we declare options supported by multicols. Two-column mode and multicols do not work together so we warn about possible problems. How-

ever, since you can revert to \onecolumn in which case multicols does work, we don't make this an error.

```
41 \DeclareOption{twocolumn}
```

- 42 {\PackageWarning{multicol}{May not work
- 43 with the twocolumn option}}

Tracing is done using a counter. However it is also possible to invoke the tracing using the options declared below.

- 44 \newcount\c@tracingmulticols
- 45 \DeclareOption{errorshow}

```
46 {\c@tracingmulticols\z@}
47 \DeclareOption{infoshow}
48 {\c@tracingmulticols\@ne}
49 \DeclareOption{balancingshow}
50 {\c@tracingmulticols\tw@}
51 \DeclareOption{markshow}
52 {\c@tracingmulticols\thr@@}
53 \DeclareOption{debugshow}
54 {\c@tracingmulticols\relax}
```

The next option is intended for typesetting on a \baselineskip grid. Right now it doesn't do anything other than warning if it thinks that the grid got lost.

```
55 \let\mc@gridwarn\maxdimen
56 \DeclareOption{grid}
57 {\def\mc@gridwarn{\@maxdepth}}
```

Next option enables the \docolaction command. As this changes the .aux file content this is not automatically enabled.

```
58 \DeclareOption{colaction}{%
    \def\mc@col@status@write{%
59
60
           \protected@write\@auxout{}%
61
                 {\string\mc@col@status
                 {\ifmc@firstcol 1\else 2\fi}}%
62
            \mc@firstcolfalse}%
63
    \def\mc@lastcol@status@write{%
64
           \protected@write\@auxout{}%
65
66
                 {\string\mc@col@status{3}}}%
67 }
68 \let\mc@col@status@write\relax
69 \let\mc@lastcol@status@write\relax
70 \ProcessOptions
```

4.3 Starting and Ending the multicols Environment

As mentioned before, the multicols environment has one mandatory argument (the number of columns) and up to two optional ones. We start by reading the number of columns into the \col@number register.

71 \def\multicols#1{\col@number#1\relax

If the user forgot the argument, TEX will complain about a missing number at this point. The error recovery mechanism will then use zero, which isn't a good choice in this case. So we should now test whether everything is okay. The minimum is two columns at the moment.

```
72 \ifnum\col@number<\tw@
73 \PackageWarning{multicol}%
74 {Using '\number\col@number'
75 columns doesn't seem a good idea.^J
76 I therefore use two columns instead}%
77 \col@number\tw@\fi
```

We have only enough box registers for twenty columns, so we need to check that the user hasn't asked for more.

```
78 \ifnum\col@number>20
79 \PackageError{multicol}%
80 {Too many columns}%
81 {Current implementation doesn't
82 support more than 20 columns.%
83 \MessageBreak
84 I therefore use 20 columns instead}%
85 \col@number20 \fi
```

Within the environment we need a special version of the kernel \@footnotetext command since the original sets the the \hsize to \columnwidth which is not correct in the multicol environment. Here \columnwidth refers to the width of the individual column and the footnote should be in \textwidth.

Since \@footnotetext has a different definition inside a minipage environment we do not redefine it directly. Instead we locally set \columnwidth to \textwidth and call the original (current) definition stored in \orig@footnotetext. If the multicols environment is nested inside another multicols environment then the redefinition has already happened. So be better test for this situation. Otherwise, we will get a TEX stack overflow as this would generate a self-referencing definition.

```
86  \ifx\@footnotetext\mult@footnotetext
87  \else
88   \let\orig@footnotetext\@footnotetext
89   \let\@footnotetext\mult@footnotetext
90  \fi
```

Now we can safely look for the optional arguments.

91 \@ifnextchar[\mult@cols{\mult@cols[]}}

```
92 \long\def\mult@footnotetext#1{\begingroup
93 \columnwidth\textwidth
94 \orig@footnotetext{#1}\endgroup}
```

The \mult@cols macro grabs the first optional argument (if any) and looks for the second one.

```
95 \def\mult@cols[#1]{\@ifnextchar[%
```

This argument should be a $\langle dimen \rangle$ denoting the minimum free space needed on the current page to start the environment. If the user didn't supply one, we use **\premulticols** as a default.

```
96 {\mult@@cols{#1}}%
97 {\mult@@cols{#1}[\premulticols]}}
```

After removing all arguments from the input we are able to start with \mult@ccols.

```
98 \def\mult@@cols#1[#2]{%
```

First thing we do is to decide whether or not this is an unbounded multicols environment, i.e. one that may split across pages, or one that has to be typeset into a box. If we are in TEX's "inner" mode (e.g., inside a box already) then we have a boxed version of multicols therefore we set the <code>@boxedmulticols</code> switch to true. The multicols should start in vertical mode. If we are not already there we now force it with <code>\par</code> since otherwise the test for "inner" mode wouldn't show if we are in a box.

```
99 \par
100 \ifinner \@boxedmulticolstrue
```

Otherwise we check \doublecol@number. This counter is zero outside a multicols environment but positive inside (this happens a little later on). In the second case we need to process the current multicols also in "boxed mode" and so change the switch accordingly.

```
101 \else
102 \ifnum \doublecol@number>\z@
103 \@boxedmulticolstrue
104 \fi
105 \fi
```

Then we look to see if statistics are requested:

```
106 \mult@info\z@
107 {Starting environment with
108 \the\col@number\space columns%
```

In boxed mode we add some more info.

```
109 \if@boxedmulticols\MessageBreak
110 (boxed mode)\fi
111 }%
```

Then we measure the current page to see whether a useful portion of the multicolumn environment can be typeset. This routine might start a new page.

112 \enough@room{#2}%

Now we output the first argument and produce vertical space above the columns. (Note that this argument corresponds to the first optional argument of the multicols environment.) For many releases this argument was typeset in a group to get a similar effect as \twocolumn[..] where the argument is also implicitly surrounded by braces. However, this conflicts with local changes done by things like sectioning commands (which account for the majority of commands used in that argument) messing up vertical spacing etc. later in the document so that from version v1.5q on this argument is again typeset at the outer level.

113 #1\par\addvspace\multicolsep

When the last line of a paragraph had a positive depth then this depth normally taken into account by the baselineskip calculation for the next

line. However, the columns produced by a following multicol are rigid and thus the distance from the baseline of a previous text line to the first line in a multicol would differ depending on the depth of the previous line. To account for this we add a negative space unless the depth is -1000pt which signals something special to T_EX and is not supposed to be a real depth.

```
114 \ifdim \prevdepth = -\@m\p@
115 \else
```

The actual generation of this corrective space is a little bit more complicated as it doesn't make sense to always back up to the previous baseline (in case an object with a very large depth was placed there, e.g., a centered tabular). So we only back up to the extend that we are within the \baselineskip grid. We know that the box produced by multicols has \topskip at its top so that also needs to be taken into account.

```
116
         \@tempcnta\prevdepth
         \@tempcntb\baselineskip
117
        \divide\@tempcnta\@tempcntb
118
        \advance\@tempcnta\@ne
119
        \dimen@\prevdepth
120
        \advance\dimen@ -\@tempcnta\baselineskip
121
         \advance\dimen@ \topskip
122
         \kern-\dimen@
123
124
```

We start a new grouping level to hide all subsequent changes (done in \prepare@multicols for example).

```
125 \begingroup
126 \prepare@multicols
```

If we are in boxed mode we now open a box to typeset all material from the multicols body into it, otherwise we simply go ahead.

```
127 \if@boxedmulticols
128 \setbox\mult@box\vbox\bgroup
129 \color@setgroup
```

We may have to reset some parameters at this point, perhaps \@parboxrestore would be the right action but I leave it for the moment.

```
130 \fi
```

We finish by suppressing initial spaces.

```
131 \ignorespaces}
```

Here is the switch and the box for "boxed" multicols code.

```
132 \newif\if@boxedmulticols
133 \@boxedmulticolsfalse
134 \newbox\mult@box
```

The \enough@room macro used above isn't perfect but works reasonably well in this context. We measure the free space on the current page by subtracting \pagetotal from \pagegoal. This isn't entirely correct since it doesn't take the 'shrinking' (i.e. \pageshrink) into account. The 'recent contribution list' might be nonempty so we start with \par and an explicit \penalty. Actually, we use \addpenalty to ensure that a following \addvspace will 'see' the vertical space that might be present. The use of \addpenalty will have the effect that all items from the recent contributions will be moved to the main vertical list and the \pagetotal value will be updated correctly. However, the penalty will be placed in front of any dangling glue item with the result that the main vertical list may already be overfull even if T_FX is not invoking the output routine.

135 \def\enough@room#1{%

Measuring makes only sense when we are not in "boxed mode" so the routine does nothing if the switch is true.

```
136 \if@boxedmulticols\else
137 \par
```

To empty the contribution list the first release contained a penalty zero but this had the result that \addvspace couldn't detect preceding glue. So this was changed to \addpenalty. But this turned out to be not enough as \addpenalty will not add a penalty when @nobreak is true. Therefore we force this switch locally to false. As a result there may be a break between preceding text and the start of a multicols environment, but this seems acceptable since there is the optional argument for exactly this reason.

```
\label{local_local} 138 \qquad \verb|\docspin| observed has addpenalty \end{tabular} $$139 \qquad $$page@free \geq 0$
```

140 \advance \page@free -\pagetotal

To be able to output the value we need to assign it to a register first since it might be a register (default) in which case we need to use \the or it might be a plain value in which case \the would be wrong.

141 $\ensuremath{\mbox{\tt 0tempskipa\#1\relax}}$

Now we test whether tracing information is required:

142	\mult@info\z@
143	{Current page:\MessageBreak
144	height=%
145	\the\pagegoal: used \the\pagetotal
146	\space -> free=\the\page@free
147	\MessageBreak
148	needed \the\@tempskipa

⁷See the documentation of \endmulticols for further details.

```
149 \space(for #1)}%
```

Our last action is to force a page break if there isn't enough room left.

```
150 \ifdim \page@free <#1\newpage \fi 151 \fi}
```

When preparing for multicolumn output several things must be done.

152 \def\prepare@multicols{%

We start saving the current \Ototalleftmargin and then resetting the \parshape in case we are inside some list environment. The correct indentation for the multicols environment in such a case will be produced by moving the result to the right by \multicolOleftmargin later on. If we would use the value of \Ototalleftmargin directly then lists inside the multicols environment could cause a shift of the output.

```
153 \multicol@leftmargin\@totalleftmargin
```

154 \@totalleftmargin\z@

55 \parshape\z@

We also set the register \dots doublecol@number for later use. This register should contain $2 \times \col@number$. This is also an indicator that we are within a multicols environment as mentioned above.

```
156
     \doublecol@number\col@number
157
     \multiply\doublecol@number\tw@
     \advance\doublecol@number\mult@rightbox
158
159
     \if@boxedmulticols
       \let\l@kept@firstmark\kept@firstmark
160
       \let\l@kept@botmark\kept@botmark
161
       \global\let\kept@firstmark\@empty
162
       \global\let\kept@botmark\@empty
163
     \else
164
```

We add an empty box to the main vertical list to ensure that we catch any insertions (held over or inserted at the top of the page). Otherwise it might happen that the \eject is discarded without calling the output routine. Inside the output routine we remove this box again. Again this code applies only if we are on the main vertical list and not within a box. However, it is not enough to turn off interline spacing, we also have to clear \topskip before adding this box, since \topskip is always inserted before the first box on a page which would leave us with an extra space of \topskip if multicols start on a fresh sheet.

```
165 \nointerlineskip {\topskip\z@\null}%
166 \output{%
167 \global\setbox\partial@page\vbox
168 {%
```

Now we have to make sure that we catch one special situation which may result in loss of text! If the user has a huge amount of vertical material within the first optional argument that is larger then \premulticols and we are near the bottom of the page then it can happen that not the \eject is triggering this special output routine but rather the overfull main vertical list. In that case we get another breakpoint through the \eject penalty. As a result this special output routine would be called twice and the contents of \partial@page, i.e. the material before the multicols environment gets lost. There are several solutions to avoid this problem, but for now we will simply detect this and inform the user that he/she has to enlarge the \premulticols by using a suitable value for the second argument.

169 (*check) \ifvoid\partial@page\else 170 \PackageError{multicol}% 171 {Error saving partial page}% 172 {The part of the page before 173 the multicols environment was 174 nearly full with "Jthe result 175 176 that starting the environment 177 will produce an overfull page. Some "Jtext may be lost! 178 Please increase \premulticols 179 either generally or for this% 180 181 ^^Jenvironment by specifying a 182 suitable value in the second optional argument to ^ Jthe 183 multicols environment.} 184 \unvbox\partial@page 185 \box\last@line 186 187 188 (/check) 189 \unvbox\@cclv 190 \global\setbox\last@line\lastbox 191 ጉ%

Finally we need to record the marks that are present within the \partial@page so that we can construct correct first and bottom marks later on. This is done by the following code.

192 \prep@keptmarks

Finally we have to initialize \kept@topmark which should ideally be initialized with the mark that is current on "top" of this page. Unfortunately we can't use \topmark because this register will not always contain what its name promises because LATEX sometimes calls the output routine for float management. Therefore we use the second best solution by initializing it with \firstmark. In fact, for our purpose this doesn't matter as we use \kept@topmark only to initialize \firstmark and \botmark of a fol-

lowing page if we don't find any marks on the current one.

193 \global\let\kept@topmark\firstmark
194 }\eject

The next thing to do is to assign a new value to \vsize. IATEX maintains the free room on the page (i.e. the page height without the space for already contributed floats) in the register \@colroom. We must subtract the height of \partial@page to put the actual free room into this variable.

195 \advance\@colroom-\ht\partial@page

Then we have to calculate the \vsize value to use during column assembly. \set@mult@vsize takes an argument which allows to make the setting local (\relax) or global (\global). The latter variant is used inside the output routine below. At this point here we have to make a local change to \vsize because we want to get the original value for \vsize restored in case this multicols environment ends on the same page where it has started.

196 \set@mult@vsize\relax

Now we switch to a new **\output** routine which will be used to put the gathered column material together.

197 \output{\multi@column@out}%

Finally we handle the footnote insertions. We have to multiply the magnification factor and the extra skip by the number of columns since each footnote reduces the space for every column (remember that we have page-wide footnotes). If, on the other hand, footnotes are typeset at the very end of the document, our scheme still works since \cunt\footins is zero then, so it will not change. To allow even further customization the setting of the \footins parameters is done in a separate macro.

198 \init@mult@footins

For the same reason (page-wide footnotes), the $\langle dimen \rangle$ register controlling the maximum space used for footnotes isn't changed. Having done this, we must reinsert all the footnotes which are already present (i.e. those encountered when the material saved in $\operatorname{partial@page}$ was first processed). This will reduce the free space (i.e. $\operatorname{pagetotal}$) by the appropriate amount since we have changed the magnification factor, etc. above.

199 \reinsert@footnotes

Inside multicols a \clearpage is fairly useless as we aren't supporting floats. In fact, it can cause harm as it doesn't know about the \partial@page and may therefore result in making columns too long.

⁸During such a call the \botmark gets globally copied to \topmark by the TEX program.

So we change that to behave like \newpage but also check if there are any deferred floats. If so, perhaps the user tried to place them through that \clearpage (but that needs to be done before starting the multicols environment.

```
\def\clearpage{%
200
        \ifx\@deferlist\@empty\else
201
202
          \PackageError{multicol}%
203
           {Deferred floats not cleared}%
204
           {A \string\clearpage\space inside
            multicols acts like
205
206
            \string\newpage\space and doesn't
207
            clear floats.\MessageBreak
208
            Move it before the multicols
            environment if you need it.}%
209
210
        \fi
211
       \newpage}%
```

All the code above was only necessary for the unrestricted multicols version, i.e. the one that allows page breaks. If we are within a box there is no point in setting up special output routines or \vsize, etc.

```
212 \fi
```

But now we are coming to code that is necessary in all cases. We assign new values to \vbadness, \hbadness and \tolerance since it's rather hard for TeX to produce 'good' paragraphs within narrow columns.

- 213 \vbadness\@Mi \hbadness5000
- 214 \tolerance\multicoltolerance

Since nearly always the first pass will fail we ignore it completely telling TeX to hyphenate directly. In fact, we now use another register to keep the value for the multicol pre-tolerance, so that a designer may allow to use \pretolerance.

215 \pretolerance\multicolpretolerance

For use with the new TeX we set $\ensuremath{\mathtt{Venergencystretch}}$ to $\ensuremath{\mathtt{Col@number}} \times 4pt$. However this is only a guess so at the moment this is done in a macro $\ensuremath{\mathtt{Setemergencystretch}}$ which gets the current $\ensuremath{\mathtt{hsize}}$ and the number of columns as arguments. Therefore users are able to figure out their own formula.

${\tt 216} \quad \verb|\setemergencystretch| col@number| hsize$

Another hook to allow people adding their own extensions without making a new package is \set@floatcmds which handles any redefinitions of LATEXs internal float commands to work with the multicols environment. At the moment it is only used to redefine \@dblfloat and \end@dblfloat.

217 \set@floatcmds

Additionally, we advance \baselineskip by \multicolbaselineskip to allow corrections for narrow columns.

218 \advance\baselineskip\multicolbaselineskip
The \hsize of the columns is given by the formula:

```
\frac{\texttt{\linewidth} - (\texttt{\local@number} - 1) \times \texttt{\local@number}}{\texttt{\local@number}}
```

The formula above has changed from release to release. We now start with the current value of \linewidth so that the column width is properly calculated when we are inside a minipage or a list or some other environment. This will be achieved with:

- 219 \hsize\linewidth \advance\hsize\columnsep
- 220 \advance\hsize-\col@number\columnsep
- 221 \divide\hsize\col@number

We also set \linewidth and \columnwidth to \hsize In the past \columnwidth was left unchanged. This is inconsistent, but \columnwidth is used only by floats (which aren't allowed in their current implementation) and by the \footnote macro. Since we want page-wide footnotes this simple trick saved us from rewriting the \footnote macros. However, some applications referred to \columnwidth as the "width of the current column" to typeset displays (the amsmath package, for example) and to allow the use of such applications together with multicol this is now changed.

Before we change \linewidth to the new value we record its old value in some register called \full@width. This value is used later on when we package all columns together.

```
222 \full@width\linewidth
223 \linewidth\hsize
224 \columnwidth\hsize
225 }
```

This macro is used to set up the parameters associated with footnote floats. It can be redefined by applications that require different amount of spaces when typesetting footnotes.

```
226 \def\init@mult@footins{%
227 \multiply\count\footins\col@number
228 \multiply\skip \footins\col@number
229 }
```

⁹I'm not sure that I really want page-wide footnotes. But balancing of the last page can only be achieved with this approach or with a multi-path algorithm which is complicated and slow. But it's a challenge to everybody to prove me wrong! Another possibility is to reimplement a small part of the *fire_up* procedure in TEX (the program). I think that this is the best solution if you are interested in complex page makeup, but it has the disadvantage that the resulting program cannot be called TEX thereafter.

Since we have to set $\col@umber$ columns on one page, each with a height of $\colon=0$ we have to assign $\colon=0$ collect enough material before entering the $\colon=0$ collect enough material before entering the $\colon=0$ colon=0 in fact we have to add another $\colon=0$ if you think about it.

```
230 \def\set@mult@vsize#1{%
231 \vsize\@colroom
232 \@tempdima\baselineskip
233 \advance\@tempdima-\topskip
234 \advance\vsize\@tempdima
235 \vsize\col@number\vsize
236 \advance\vsize-\@tempdima
```

But this might not be enough since we use \vsplit later to extract the columns from the gathered material. Therefore we add some 'extra lines,' one for each column plus a corrective action depending on the value of the 'collectmore' counter. The final value is assigned globally if #1 is \global because we want to use this macro later inside the output routine too.

```
237 \advance\vsize\col@number\baselineskip
238 #1\advance\vsize
239 \c@collectmore\baselineskip}
```

Here is the dimen register we need for saving away the outer value of \@totalleftmargin.

```
240 \newdimen\multicol@leftmargin
```

In versions prior to 1.8r the balancing at the end of the environment was done by changing the output routine from \multi@column@out to \balance@column@out. As it turned out that this has a couple of issues when the last columns should not be balanced after all (for example because they contained several \columnbreak commands we now stay with one output routine for the environment and only signal that we reached the end of the environment by marking it with a special penalty that we can check for later.

When the end of the multicols environment is sensed we have to balance the gathered material. Depending on whether or not we are inside a boxed multicol different things must happen. But first we end the current paragraph with a \par command.

```
243 \def\endmulticols{\par 244 \if@boxedmulticols
```

In boxed mode we have to close the box in which we have gathered all material for the columns. But before we do this we need to remove any space at the end of the box as we don't want to use this in balancing. Because of the \color@endgroup this can't be done later in \balance@columns as the color command will hide it.

```
245 \remove@discardable@items
246 \color@endgroup\egroup
```

Now we call \balance@columns the routine that balances material stored in the box \mult@box.

```
247 \balance@columns
```

After balancing the result has to be returned by the command \page@sofar. But before we do this we reinsert any marks found in box \mult@box.

```
248
       \return@nonemptymark{first}%
249
                     \kept@firstmark
       \return@nonemptymark{bot}%
250
251
                      \kept@botmark
252
       \page@sofar
       \global\let\kept@firstmark
253
254
                   \l@kept@firstmark
255
       \global\let\kept@botmark
256
                \1@kept@botmark
257 (*marktrace)
258
       \mult@info\tw@
          {Restore kept marks to\MessageBreak
259
          first: \meaning\kept@firstmark
260
          \MessageBreak bot\space\space:
261
                  \meaning\kept@botmark }%
262
263 (/marktrace)
```

This finishes the code for the "boxed" case.

```
64 \else
```

If there was a \columnbreak on the very last line all material will have been moved to the \colbreak@box. Thus the galley will be empty and no output routine gets called so that the text is lost. To avoid this problem (though unlikely) we check if the current galley is empty and the \colbreak@box contains text and if so return that to the galley. If the galley is non-empty any material in \colbreak@box is added in the output routine since it needs to be put in front.

```
265 \ifdim\pagegoal=\maxdimen
266 \ifvoid\colbreak@box\else
267 \mult@info\@ne{Re-adding forced
268 break(s) for splitting}%
269 \unvbox\colbreak@box\fi
270 \fi
```

¹⁰This once caused a puzzling bug where some of the material was balanced twice, resulting in some overprints. The reason was the \eject which was placed at the end of the contribution list. Then the page_builder was called (an explicit \penalty will empty the contribution list), but the line with the \eject didn't fit onto the current page. It was then reconsidered after the output routine had ended, causing a second break after one line.

If we are in an unrestricted multicols environment we end the current paragraph above with \par but this isn't sufficient since TEXs page_builder will not totally empty the contribution list. Therefore we must also add an explicit \penalty. Now the contribution list will be emptied and, if its material doesn't all fit onto the current page then the output routine will be called before we change it. At this point we need to use \penalty not \addpenalty to ensure that a) the recent contributions are emptied and b) that the very last item on the main vertical list is a valid break point so that TEX breaks the page in case it is overfull.

271 \penalty\z@

Now it's safe to call the output routine in order to balance the columns. We do this by calling it with a special penalty.

272 \penalty-\@Mvi

If the multicols environment body was completely empty or if a multi-page multicols just ends at a page boundary we have the unusual case that the \eject will have no effect (since the main vertical list is empty)—thus no output routine is called at all. As a result the material preceding the multicols (stored in \partial@page will get lost if we don't put this back by hand.

```
273 \ifvbox\partial@page
274 \unvbox\partial@page\fi
```

After the output routine has acted we restore the kept marks to their initial value.

```
275 \global\let\kept@firstmark\@empty
276 \global\let\kept@botmark\@empty
277 \langle*marktrace\
278 \mult@info\tw@
279 \{Make kept marks empty\}\'\'
280 \/\marktrace\
281 \fi
```

The output routine above will take care of the \vsize and reinsert the balanced columns, etc. But it can't reinsert the \footnotes because we first have to restore the \footins parameter since we are returning to one column mode. This will be done in the next line of code; we simply close the group started in \multicols.

To fix an obscure bug which is the result of the current definition of the \begin ... \end macros, we check that we are still (logically speaking) in the multicols environment. If, for example, we forget to close some environment inside the multicols environment, the following \endgroup would be incorrectly considered to be the closing of this environment.

```
282 \@checkend{multicols}%
283 \endgroup
```

We also set the 'unbalance' counter to its default. This is done globally since LATEX counters are always changed this way. 11

```
284 \global\c@unbalance\z@
```

Now it's time to return any footnotes if we are in unrestricted mode. In boxed mode footnotes are kept inside, but in that case we have to write another column status into the .aux file to support \docolaction in case we have nested environments.

```
285 \if@boxedmulticols
286 \mc@col@status@write
287 \else
288 \reinsert@footnotes
```

We also take a look at the amount of free space on the current page to see if it's time for a page break. The vertical space added thereafter will vanish if \enough@room starts a new page.

But there is one catch. If the \end{multicols} is at the top of which can happen if there is a break point just before it (such as end ending environment) which was chosen. In that case we would do the next page using the internal \vsize for multicol collection which is a disaster. So we better catch this case. Fortunately we can detect it by looking at \pagegoal.

```
289 \ifdim \pagegoal=\maxdimen
290 \global\vsize\@colroom
291 \else
292 \enough@room\postmulticols
293 \fi
294 \fi
295 \addvspace\multicolsep
```

There is one more thing to do: the balanced result of the environment is supposed to have a \prevdepth of zero as we backed up by its real prevdepth within \page@sofar. However if the balancing happened in the output routine then TEX reverts to the \prevdepth that was current before the OR once the OR has finished. In short \prevdepth is something you can't set globally it is alway local to the current list being built. Thus we need to set it back to zero here to avoid incorrect spacing.

296 \prevdepth\z@

If statistics are required we finally report that we have finished everything.

```
297 \mult@info\z@
298 {Ending environment
299 \if@boxedmulticols
300 \space(boxed mode)\fi
```

 $^{^{11}}$ Actually, we are still in a group started by the **\begin** macro, so **\global** must be used anyway.

```
301 }}
```

Let us end this section by allocating all the registers used so far.

```
302 \newcount\c@unbalance
303 \newcount\c@collectmore
```

In the new IATEX release \col@number is already allocated by the kernel, so we don't allocate it again.

```
304 %\newcount\col@number
305 \newcount\doublecol@number
306 \newcount\multicoltolerance
307 \newcount\multicolpretolerance
308 \newdimen\full@width
309 \newdimen\page@free
310 \newdimen\premulticols
311 \newdimen\postmulticols
312 \newskip\multicolsep
```

The output routines

4.4

We first start with some simple macros. When type-setting the page we save the columns either in the box registers $0, 2, 4, \dots$ (locally) or $1, 3, 5, \dots$ (globally). This is PLAIN TEX policy to avoid an overflow of the save stack.

Therefore we define a \process@cols macro to help us in using these registers in the output routines below. It has two arguments: the first one is a number; the second one is the processing information. It loops starting with \count@=#1 (\count@ is a scratch register defined in Plain TeX), processes argument #2, adds two to \count@, processes argument #2 again, etc. until \count@ is higher than \doublecol@number. It might be easier to understand it through an example, so we define it now and explain its usage afterwards.

```
325 \def\process@cols#1#2{\count@#1\relax
326 \loop
327 \rangle*debug\
328 \typeout{Looking at box \the\count@}
329 \/debug\
330 #2%
331 \advance\count@\tw@
332 \ifnum\count@<\doublecol@number
333 \repeat}
```

We now define \page@sofar to give an example of the \process@cols macro. \page@sofar should output everything prepared by the balancing routine \balance@columns.

```
334 \neq \frac{\%}{2}
```

```
313 \newskip\multicolbaselineskip
314 \newbox\partial@page
315 \newbox\last@line

And here are their default values:
316 \c@unbalance = 0
317 \c@collectmore = 0
```

To allow checking whether some macro is used within the multicols environment the counter \col@number gets a default of 1 outside the environment.

```
318 %\col@number = 1
319 \multicoltolerance = 9999
320 \multicolpretolerance = -1
321 \premulticols = 50pt
322 \postmulticols= 20pt
323 \multicolsep = 12pt plus 4pt minus 3pt
324 \multicolbaselineskip=0pt
```

\balance@columns prepares its output in the even numbered scratch box registers. Now we output the columns gathered assuming that they are saved in the box registers 2 (left column), 4 (second column), ... However, the last column (i.e. the rightmost) should be saved in box register 0.¹² First we ensure that the columns have equal width. We use \process@cols for this purpose, starting with \count@ = \mult@rightbox. Therefore \count@ loops through \mult@rightbox, \mult@rightbox + 2....(to \doublecol@number).

335 \process@cols\mult@rightbox

We have to check if the box in question is void, because the operation $\mbox{\sc wd}\mbox{\sc number}\mbox{\sc on}$ a void box will not change its dimension (sigh).

```
336 {\ifvoid\count@

337 \setbox\count@\hbox to\hsize{}%

338 \else

339 \wd\count@\hsize

340 \fi}%
```

Now we give some tracing information.

```
\count@\col@number \advance\count@\m@ne
341
      \mult@info\z@
342
       {Column spec: \the\full@width\space = indent
343
344
                      + columns + sep =\MessageBreak
345
           \the\multicol@leftmargin\space
346
           + \the\col@number\space
           x \the\hsize\space
347
348
           + \the\count@\space
349
           x \the\columnsep
350
```

 $^{^{12}}$ You will see the reason for this numbering when we look at the output routines \mathbf{u} and \mathbf{b} and \mathbf{b}

At this point we should always be in vertical mode.

351 \ifvmode\else\errmessage{Multicol Error}\fi

Now we put all columns together in an \hbox of width \full@width (shifting it by \multicol@leftmargin to the right so that it will be placed correctly if we are within a list environment) and separating the columns with a rule if desired.

The box containing the columns has a large height and thus will always result in using \lineskip if the normal \baselineskip calculations are used. We therefore better cancel that process.

352 \nointerlineskip

As mentioned earlier we want to have the reference point of the box we put on the page being at the baseline of the last line of the columns but we also want to ensure that the box has no depth so that any following skip is automatically starting from that baseline. We achieve this by recording the depths of all columns and then finally backing up by the maximum. (perhaps a simpler method would be to assemble the box in a register and set the depth of that box to zero (not checked).

We need a global scratch register for this; using standard TEX conventions we choose \dimen2 and initialize it with the depth of the character "p" since that is one of the depths that compete for the maximum.

```
353 \setbox\z@\hbox{p}\global\dimen\tw@\dp\z@
354 \moveright\multicol@leftmargin
```

355 \hbox to\full@width{%

If the document is written in a language that is typeset right-to-left then, of course, the multicol columns should be also typeset right-to-left. To support this we call \mc@align@columns which with execute different code depending on the typesetting direction.

356 \mc@align@columns

The depths of the columns depend on their last lines. To ensure that we will always get a similar look as far as the rules are concerned we force the depth to be at least the depth of a letter 'p' (which is what we set \dimen2 to above).

```
357 \rlap{\phantom p}% 358 }%
```

The processed material might consist of a last line with a descender in which case the \prevdepth will be non-zero. However, this material is getting reformatted now so that this value is likely to be wrong. We therefore normalize the situation by pretending that the depth is zero. However, if \page@sofar is being called inside the OR then setting \prevdepth

here has no long-lasting effect, we therefore have to repeat this once we return to the main vertical list. Here we set it only for those cases where the command is used within a list and then followed by something else.

359 \prevdepth\z@

Now after typesetting the box we back up to its baseline by using the value stored in \dimen2 (which will hold the largest depth found on any column).

360 \kern-\dimen\tw@

However, in case one of the columns was unusually deep TEX may have tried some corrective actions in which case backing up by the saved value will not bring us back to the baseline. A good indication for this is a depth of \@maxdepth though it is not an absolute proof. If the option grid is used \mc@gridwarn will expand to this, otherwise to \maxdimen in which case this warning will not show up.

```
361 \ifdim\dimen\tw@ > \mc@gridwarn
362 \PackageWarning{multicol}%
363 {Very deep columns!\MessageBreak
364 Grid alignment might be broken}%
365 \fi
366 }
```

By default the vertical rule between columns will be in \normalcolor.

```
367 \def\columnseprulecolor{\normalcolor}
```

Before we tackle the bigger output routines we define just one more macro which will help us to find our way through the mysteries later. \reinsert@footnotes will do what its name indicates: it reinserts the footnotes present in \footinbox so that they will be reprocessed by TeX's page_builder.

Instead of actually reinserting the footnotes we insert an empty footnote. This will trigger insertion mechanism as well and since the old footnotes are still in their box and we are on a fresh page \skip footins should be correctly taken into account.

```
368 \def\reinsert@footnotes{\ifvoid\footins\else 369 \insert\footins{}\fi}
```

This curious definition is used as the space at the bottom of a column if we implement \raggedcolumns. Normally one only appends \vfill in that case but this is actually wrong for columns that are more or less full: by adding a glue at the bottom such a column doesn't have any depth any more but without it the material would be allowed a depth of \@maxdepth. So we allow shrinking by that amount. This only makes a difference if the box would otherwise become overfull and shrinking

never exceeds the specified value, so we should be fine.

```
370 \def\vfilmaxdepth{\vskip \z@ \@plus .0001fil 371 \@minus \@maxdepth}
```

Now we can't postpone the difficulties any longer. The $\mbox{multi@column@out}$ routine will be called in two situations. Either the page is full (i.e., we have collected enough material to generate all the required columns) or a float or marginpar or a $\mbox{clearpage}$ is sensed. In the latter case the $\mbox{outputpenalty}$ is less than -10000, otherwise the penalty which triggered the output routine is higher. Therefore it's easy to distinguish both cases: we simply test this register.

```
372 \def\multi@column@out{% 373 \ifnum\outputpenalty <-\@M
```

If this was a \clearpage, a float or a marginpar we call \speci@ls

```
374 \speci@ls \else
```

otherwise we construct the final page. For the next block of code see comments in section 7.2.

```
375 \ifvoid\colbreak@box\else
376 \mult@info\@ne{Re-adding forced}
377 break(s) for splitting}%
378 \setbox\@cclv\vbox{%}
379 \unvbox\colbreak@box
380 \penalty-\@Mv
381 \unvbox\@cclv}%
382 \fi
```

Let us now consider the normal case. We have to \vsplit the columns from the accumulated material in box 255. Therefore we first assign appropriate values to \splittopskip and \splitmaxdepth.

```
383 \splittopskip\topskip
384 \splitmaxdepth\@maxdepth
```

We also need to restrict \boxmaxdepth so that reboxing is not generating boxes with arbitrary depth.

385 \boxmaxdepth\@maxdepth

Then we calculate the current column height (in \dimen@). Note that the height of \partial@page is already subtracted from \@colroom so we can use its value as a starter.

386 \dimen@\@colroom

But we must also subtract the space occupied by footnotes on the current page. Note that we first have to reset the skip register to its normal value. Again, the actual action is carried out in a utility macro, so that other applications can modify it.

```
387 \divide\skip\footins\col@number
388 \ifvoid\footins \else
```

```
389 \leave@mult@footins
390 \fi
```

And there is one more adjustment that we have to make: if the user has issue a \enlargethispage command then the height the \@kludgeins box will be the negation of the size by which the page should be enlarged. If the star form of this command has been used then we also need to shrink the resulting column.

That local change will be reverted at the end of the output routine So for the next page the original state will be reestablished. However, in theory there is a possibility to sneak in a whole multicols environment into the running header definition. If that happens then it will also be affected by this change—too bad I think.

```
391 \ifvbox \@kludgeins
392 \advance \dimen@ -\ht\@kludgeins
```

The star form of \enlargethispage makes the width of the box greater than zero (sneaky isn't it?).

```
393 \ifdim \wd\@kludgeins>\z@
394 \shr@nkingtrue
395 \fi
396 \fi
```

Now we are able to \vsplit off all but the last column. Recall that these columns should be saved in the box registers 2, 4,... (plus offset).

```
397 \process@cols\mult@firstbox{%
398 \setbox\count@
399 \vsplit\@cclv to\dimen@
```

After splitting we update the kept marks.

```
400 \set@keptmarks
```

If \raggedcolumns is in force we add a vfill at the bottom by unboxing the split box. But we need to unbox anyway to ensure that at the end of the box we do not have unwanted space. This can sneak in in certain situations, for example, if two lists follow each other and we break between them. While such space is usually zero it still has an effect because it hides depth of the last line in the column and that will result in incorrect placement.

```
401 \setbox\count@
402 \vbox to\dimen@
403 \{\unvbox\count@
404 \ifshr@nking
405 \vfilmaxdepth\fi}%
406 }%
```

Then the last column follows.

```
407 \setbox\mult@rightbox
408 \vsplit\@cclv to\dimen@
409 \set@keptmarks
410 \setbox\mult@rightbox\vbox to\dimen@
411 {\unvbox\mult@rightbox
412 \ifshr@nking\vfilmaxdepth\fi}%
```

Having done this we hope that box 255 is emptied. If not, we reinsert its contents.

```
413 \ifvoid\@cclv \else
414 \unvbox\@cclv
415 \ifnum\outputpenalty=\@M
416 \else
417 \penalty\outputpenalty
418 \fi
```

In this case a footnote that happens to fall into the leftover bit will be typeset on the wrong page. Therefore we warn the user if the current page contains footnotes. The older versions of multicols produced this warning regardless of whether or not footnotes were present, resulting in many unnecessary warnings.

```
419 \ifvoid\footins\else
420 \PackageWarning{multicol}%
421 {I moved some lines to
422 the next page.\MessageBreak
423 Footnotes on page
424 \thepage\space might be wrong}%
425 \fi
```

If the 'tracingmulticols' counter is 4 or higher we also add a rule.

```
426 \ifnum \c@tracingmulticols>\thr@@
427 \hrule\allowbreak \fi
428 \fi
```

To get a correct marks for the current page we have to (locally) redefine \firstmark and \botmark. If \kept@firstmark is non-empty then \kept@botmark must be non-empty too so we can use their values. Otherwise we use the value of \kept@topmark which was first initialized when we gathered the \partical@page and later on was updated to the \botmark for the preceding page.

```
429 \ifx\@empty\kept@firstmark
430 \let\firstmark\kept@topmark
431 \let\botmark\kept@topmark
432 \else
433 \let\firstmark\kept@firstmark
434 \let\botmark\kept@botmark
435 \fi
```

We also initialize \topmark with \kept@topmark. This will make this mark okay for all middle pages of the multicols environment.

```
436 \let\topmark\kept@topmark
437 \rangle*marktrace\
438 \mult@info\tw@
439 {Use kept top mark:\MessageBreak
440 \meaning\kept@topmark
441 \MessageBreak
442 Use kept first mark:\MessageBreak
```

```
\meaning\kept@firstmark
443
            \MessageBreak
444
            Use kept bot mark:\MessageBreak
445
446
              \meaning\kept@botmark
            \MessageBreak
447
            Produce first mark:\MessageBreak
448
              \meaning\firstmark
449
            \MessageBreak
450
           Produce bot mark:\MessageBreak
451
452
              \meaning\botmark
453
             \@gobbletwo}%
454 (/marktrace)
```

With a little more effort we could have done better. If we had, for example, recorded the shrinkage of the material in \partial@page it would be now possible to try higher values for \dimen@ (i.e. the column height) to overcome the problem with the nonempty box 255. But this would make the code even more complex so I skipped it in the current implementation.

Now we use \LaTeX 's standard output mechanism. ¹³ Admittedly this is a funny way to do it.

Within the OR \boxmaxdepth needs to be unrestricted so we set it back now as it was changed above.

```
455 \boxmaxdepth\maxdimen
456 \setbox\@cclv\vbox{\unvbox\partial@page
457 \page@sofar}%
```

The macro \@makecol adds all floats assigned for the current page to this page. \@outputpage ships out the resulting box. Note that it is just possible that such floats are present even if we do not allow any inside a multicols environment.

458 \@makecol\@outputpage

After the page is shipped out we have to prepare the kept marks for the following page. \kept@firstmark and \kept@botmark reinitialized by setting them to \@empty. The value of \botmark is then assigned to \kept@topmark.

```
\global\let\kept@topmark\botmark
459
        \global\let\kept@firstmark\@empty
460
        \global\let\kept@botmark\@empty
461
462 (*marktrace)
        \mult@info\tw@
463
464
           {(Re)Init top mark:\MessageBreak
465
             \meaning\kept@topmark
466
             \@gobbletwo}%
467 (/marktrace)
```

Now we reset \@colroom to \@colht which is LaTEX's saved value of \textheight. We also have to reset the recorded position of the last \marginpar

 $^{^{13}}$ This will produce a lot of overhead since both output routines are held in memory. The correct solution would be to redesign the whole output routine used in \LaTeX

as well as the recorded size of in-text floats as we are now on a new page.

```
468 \global\@colroom\@colht
469 \global \@mparbottom \z@
470 \global \@textfloatsheight \z@
```

Then we process deferred floats waiting for their chance to be placed on the next page.

```
471 \process@deferreds
472 \@whilesw\if@fcolmade\fi{\@outputpage}
473 \global\@colroom\@colht
474 \process@deferreds}%
```

If the user is interested in statistics we inform him about the amount of space reserved for floats.

```
475 \mult@info\@ne
476 {Colroom:\MessageBreak
477 \the\@colht\space
478 after float space removed
479 = \the\@colroom \@gobble}%
```

Having done all this we must prepare to tackle the next page. Therefore we assign a new value to \vsize. New, because \partial@page is now empty and \@colroom might be reduced by the space reserved for floats.

```
480 \set@mult@vsize \global
```

The \footins skip register will be adjusted when the output group is closed.

```
481 \fi}
```

This macro is used to subtract the amount of space occupied by footnotes for the current space from the space available for the current column. The space current column is stored in \dimen@. See above for the description of the default action.

```
482 \def\leave@mult@footins{%

483 \advance\dimen@-\skip\footins

484 \advance\dimen@-\ht\footins

485}
```

We left out two macros: $\process@deferreds$ and $\process@deferreds$.

```
486 \def\speci@ls{%
487 \ifnum\outputpenalty <-\@Mi
```

If the document ends in the middle of a multicols environment, e.g., if the user forgot the \end{multicols}, TEX adds a very negative penalty to the end of the galley which is intended to signal the output routine that it is time to prepare for shipping out everything remaining. Since inside multicols the output routine of LATEX is disabled sometimes we better check for this case: if we find a very negative penalty we produce an error message and run the default output routine for this case.

```
\ifnum \outputpenalty<-\@MM
488
       \PackageError{multicol}{Document end
489
490
               inside multicols environment}\@ehd
491
       \@specialoutput
492
      \else
For the next block of code see comments in sec-
tion 7.2.
493
         \mult@info\@ne{Forced column
494
495
                           break seen}%
             \global\advance\vsize-\pagetotal
496
             \global\setbox\colbreak@box
497
               \vbox{%
498
                  \ifvoid\colbreak@box
499
                  \else
500
501
                    \unvbox\colbreak@box
502
                    \penalty-\@Mv
503
```

As this is the place of a forced break we now remove vertical white space just in front of it (or some of it at least) as it is quite likely that the break is not exactly in the right place, e.g., after a display environment (if LaTeX would break here by its own it would break before the space following the display).

Thus we rebox box 255 once (using \@maxdepth and calling \remove@discardable@items inside). The depth of 255 will then give us the depth the box would have had if it would have been a natural break. We then unbox 255 to get it into the \colbreak@box and then back up by this depth. This will position the bottom of the box at its natural baseline which is useful for balancing later on.

```
\boxmaxdepth\@maxdepth
504
                   \setbox\@cclv\vbox{%
505
                      \unvbox\@cclv
506
                      \remove@discardable@items}%
507
508
                   \dimen@\dp\@cclv
                   \unvbox\@cclv
509
                   \kern-\dimen@
510
             }%
511
512
             \reinsert@footnotes
513
         \else
```

Another special case is reaching the end of the multicols environment which is signaled by -\@Mvi.

```
514 \ifnum\outputpenalty = -\@Mvi
515 \mult@info\@ne{End penalty of
516 multicols seen}%
```

If we are at this point then we have to run the balancing code (which was previously its own output routine). First we pretend that we had a normal forced breakpoint and then call \balance@column@out. The latter may be let to \multi@column@out if we are inside multicols* in which case we would get a loop if the

\outputpenalty is not changed—this could be cleaned up in a better way; basically it is like this, because of the older code was using different ORs and I simply reused most of it.

```
517 \outputpenalty\@M % pretend we had
518 % a natural
519 % forced break
520 \balance@columns@out
521 \else
```

If we encounter a float or a marginpar in the current implementation we simply warn the user that this is not allowed. Then we reinsert the page and its footnotes.

```
522 \PackageWarningNoLine{multicol}%
523 {Floats and marginpars not
524 allowed inside 'multicols'
525 environment!}%
526 \unvbox\@cclv\reinsert@footnotes
```

Additionally we empty the \@currlist to avoid later error messages when the LATEX output routine is again in force. But first we have to place the boxes back onto the \@freelist. (\@elts default is \relax so this is possible with \xdef.)

If the penalty is -10001 it will come from a $\cline{localcolor}$ clearpage and we will execute $\cline{localcolor}$ doclearpage to get rid of any deferred floats.

```
533 \else \@doclearpage \fi 534 }
```

\process@deferreds is a simplified version of LATEX's \@startpage. We first call the macro \@floatplacement to save the current user parameters in internal registers. Then we start a new group and save the \@deferlist temporarily in the macro \@tempb.

```
535 \def\process@deferreds{%
536 \@floatplacement
537 \@tryfcolumn\@deferlist
538 \if@fcolmade\else
539 \begingroup
540 \let\@tempb\@deferlist
```

Our next action is to (globally) empty \@deferlist and assign a new meaning to \@elt. Here \@scolelt is a macro that looks at the boxes in a list to decide whether they should be placed on the next page (i.e. on \@toplist or \@botlist) or should wait for further processing.

```
541 \gdef\@deferlist{}%
```

```
542 \let\@elt\@scolelt
```

Now we call \@tempb which has the form

```
\ensuremath{\verb|Qelt|} box \ register \ensuremath{\verb|Voelt|} box \ register \ensuremath{\verb|Celt|} \ldots
```

So \@elt (i.e. \@scolelt) will distribute the boxes to the three lists.

```
543 \Qtempb \endgroup
544 \fi}
```

The \raggedcolumns and \flushcolumns declarations are defined with the help of a new \if... macro.

```
545 \newif\ifshr@nking
```

The actual definitions are simple: we just switch to true or false depending on the desired action. To avoid extra spaces in the output we enclose these changes in \Obsphack...\Oesphack.

```
546 \def\raggedcolumns{%
547 \@bsphack\shr@nkingtrue\@esphack}
548 \def\flushcolumns{%
549 \@bsphack\shr@nkingfalse\@esphack}
```

Now for the last part of the show: the column balancing output routine. Since this code is called with an explicit penalty (\epsilonject) there is no need to check for something special (eg floats). We start by balancing the material gathered.

```
550 \def\balance@columns@out{%
```

For this we need to put the contents of box 255 into \mult@box. For the next block of code see also comments in section 7.2. All forced breaks except the last are inside \colbreak@box so all we have to do is to concatenate this box with box \@cclv and put a penalty in between. Here we test if \colbreak@box is void so that the message is only generated if we really add forced breaks and the penalty.

```
551
      \setbox\mult@box\vbox{%
          \ifvoid\colbreak@box\else
552
553
             \unvbox\colbreak@box
             \penalty-\@Mv
554
             \mult@info\@ne{Re-adding
555
556
               forced break(s) in balancing}%
          \fi
557
          \unvbox\@cclv
558
```

The last column again is a forced break, so here we discard white space as well as that is normally unwanted.

```
559 \remove@discardable@items
560 }%
561 \balance@columns
```

If during balancing the columns got too long the flag \iftoo@bad is set to true.

```
562 \iftoo@bad
563 \mult@info\@ne
564 {Balancing failed ...
565 cut a normal page}%
```

In that case we put the material back in box 255 so that we can cut a normal page. The curious set of \vskips we add is necessary to cancel out the \splittopskip that got added for balancing.

```
566 \setbox\@cclv\vbox
567 {\vskip\topskip
568 \vskip\splittopskip
569 \unvbox\mult@box
```

We also have to re-add the end of environment penalty since after this page we may want balance the remaining material.

```
570 \penalty-\@Mvi
571 }%
```

We then call the standard multicol output routine which will produce a normal page for us (remember we are still within the OR so some part of the code in \multi@column@out is actually not doing anything—perhaps this should be cleaned up at some point). This also means that if there was an \enlargethispage present it will apply to this page as \multi@column@out will look at the status of \@kludgeins.

572 \multi@column@out

Because balancing made the columns too long we are sure that there will be some material remaining which was put back onto the main vertical list by \multi@column@out. This will also put the explicit \eject penalty back so the current \balance@columns@out output routine will be called again (so we better do not add another penalty or else the OR will be called twice and we may get scrambled results).

```
573 \else
```

If the balancing went ok, we are in the position to apply \page@sofar. But first we have to set \vsize to a value suitable for one column output.

```
574 \global\vsize\@colroom
575 \global\advance\vsize\ht\partial@page
```

We also have to look at \@kludgeins and generate a new \insert in case there was one present due to an \enlargethispage command.

```
576 \ifvbox\@kludgeins
577 \insert\@kludgeins
578 {\unvbox\@kludgeins}\fi
```

Then we \unvbox the \partial@page (which may be void if we are not processing the first page of this multicols environment.

```
579 \unvbox\partial@page
```

Then we return the first and bottom mark and the gathered material to the main vertical list.

```
580 \return@nonemptymark{first}%
581 \kept@firstmark
582 \return@nonemptymark{bot}\kept@botmark
583 \page@sofar
```

We need to add a penalty at this point which allows to break at this point since calling the output routine may have removed the only permissible break point thereby "glueing" any following skip to the balanced box. In case there are any weird settings for \multicolsep etc. this could produce funny results.

```
584 \penalty\z@
585 \fi
586 }
```

As we already know, reinserting of footnotes will be done in the macro \endmulticols.

This macro now does the actual balancing.

```
587 \def\balance@columns{%
```

We start by setting the kept marks by updating them with any marks from this box. This has to be done *before* we add a penalty of -10000 to the top of the box, otherwise only an empty box will be considered.

588 \get@keptmarks\mult@box

We then continue by resetting trying to remove any discardable stuff at the end of \mult@box. This is rather experimental. We also add a forced break point at the very beginning, so that we can split the box to height zero later on, thereby adding a known \splittopskip glue at the beginning.

```
589 \setbox\mult@box\vbox{%

590 \penalty-\@M

591 \unvbox\mult@box

592 }%
```

Then follow values assignments to get the \vsplitting right. We use the natural part of \topskip as the natural part for \splittopskip and allow for a bit of undershoot and overshoot by adding some stretch and shrink.

```
593 \@tempdima\topskip
594 \splittopskip\@tempdima
595 \@plus\multicolundershoot
596 \@minus\multicolovershoot
597 \splitmaxdepth\@maxdepth
```

We also have to set \boxmaxdepth which normally allows to build boxes with arbitrary depth, but as we are building text columns we really want to restrict the depth. This is necessary as we sometimes rebox the boxes generated by \vsplit and then the restriction posed by \splitmaxdepth gets lost.

```
598 \boxmaxdepth\@maxdepth
```

The next step is a bit tricky: when TeX assembles material in a box, the first line isn't preceded by interline glue, i.e. there is no parameter like \boxtopskip in TeX. This means that the baseline of the first line in our box is at some unpredictable point depending on the height of the largest character in this line. But of course we want all columns to align properly at the baselines of their first lines. For this reason we have opened \mult@box with a \penalty -10000. This will now allow us to split off from \mult@box a tiny bit (in fact nothing since the first possible break-point is the first item in the box). The result is that \splittopskip is inserted at the top of \mult@box which is exactly what we like to achieve.

599 \setbox\@tempboxa\vsplit\mult@box to\z@

Next we try to find a suitable starting point for the calculation of the column height. It should be less than the height finally chosen, but large enough to reach this final value in only a few iterations. The formula which is now implemented will try to start with the nearest value which is a multiple of \baselineskip. The coding is slightly tricky in TeX and there are perhaps better ways ...

```
600 \@tempdima\ht\mult@box
601 \advance\@tempdima\dp\mult@box
602 \divide\@tempdima\col@number
```

The code above sets \Qtempdima to the length of a column if we simply divide the whole box into equal pieces. To get to the next lower multiple of \baselineskip we convert this dimen to a number (the number of scaled points) then divide this by \baselineskip (also in scaled points) and then multiply this result with \baselineskip assigning the result to \dimenQ. This makes \dimenQ \leq to \Qtempdimena.

```
603 \count@\@tempdima
604 \divide\count@\baselineskip
605 \dimen@\count@\baselineskip
```

Next step is to correct our result by taking into account the difference between \topskip and \baselineskip. We start by adding \topskip; if this makes the result too large then we have to subtract one \baselineskip.

```
606 \advance\dimen@\topskip
607 \ifdim \dimen@ >\@tempdima
608 \advance\dimen@-\baselineskip
609 \fi
```

As a further restriction we want to see a minimum number of rows in the balanced result based on the setting of the counter minrows. If the starting value is lower we adjust.

```
610 \@tempdima\dimexpr
```

```
\topskip +\c@minrows\baselineskip
611
612
                   -\baselineskip\relax
      \ifnum\dimen@<\@tempdima
613
614
        \mult@info\@ne
615
          {Start value
              \the\dimen@ \space ->
616
              \the\@tempdima \space
617
              (corrected for minrows)}%
618
619
         \dimen@\@tempdima
```

At the user's request we start with a higher value (or lower, but this usually only increases the number of tries).

621 \advance\dimen@\c@unbalance\baselineskip We type out statistics if we were asked to do so.

```
622 \mult@info\@ne
623 {Balance columns\on@line:
624 \ifnum\c@unbalance=\z@\else
625 (off balance=\number\c@unbalance)\fi
626 \@gobbletwo}%
```

But we don't allow nonsense values for a start.

```
627 \ifnum\dimen@<\topskip
628 \mult@info\@ne
629 {Start value
630 \the\dimen@ \space ->
631 \the\topskip \space (corrected)}%
632 \dimen@\topskip
633 \fi
```

Now we try to find the final column height. We start by setting \vbadness to infinity (i.e. 10000) to suppress underfull box reports while we are trying to find an acceptable solution. We do not need to do it in a group since at the end of the output routine everything will be restored. The setting of the final columns will nearly always produce underfull boxes with badness 10000 so there is no point in warning the user about it.

634 \vbadness\@M

We also allow for overfull boxes while we trying to split the columns. They can easily happen if we have objects with unusual depth.

```
635 \vfuzz \maxdimen
```

The variable **\last@try** will hold the dimension used in the previous trial splitting. We initialize it with a negative value.

```
636 \last@try-\p@
637 \loop
```

In order not to clutter up TEX's valuable main memory with things that are no longer needed, we empty all globally used box registers. This is necessary if we return to this point after an unsuccessful trial. We use \process@cols for this purpose, starting with \mult@grightbox. Note the extra braces around this macro call. They are needed since

PLAIN TEX's \loop...\repeat mechanism cannot be nested on the same level of grouping.

```
638 {\process@cols\mult@grightbox
639 {\global\setbox\count@
640 \box\voidb@x}}%
```

The contents of box \mult@box are now copied globally to box \mult@grightbox. (This will be the right-most column, as we shall see later.)

```
641 \global\setbox\mult@grightbox
642 \copy\mult@box
```

We start with the assumption that the trial will be successful. If we end up with a solution that is too bad we set too@bad to true. We also assume that all forced breaks (if any) will be used during balancing. If this is not the case we record this in forcedbreak@leftover.

```
643 (*badness)
644 \too@badfalse
645 \forcedbreak@leftoverfalse
646 (/badness)
```

Using \vsplit we extract the other columns from box register \mult@grightbox. This leaves box register \mult@box untouched so that we can start over again if this trial was unsuccessful.

```
647 {\process@cols\mult@gfirstbox{% 648 \global\setbox\count@ 649 \vsplit\mult@grightbox to\dimen@
```

After splitting we need to ensure that there isn't any space at the bottom, so we rebox once more.

```
650 \global\setbox\count@
651 \vbox to\dimen@
652 {\unvbox\count@}%
```

After every split we check the badness of the resulting column, normally the amount of extra white in the column.

```
653 (*badness)
             \ifnum\c@tracingmulticols>\@ne
654
               \@tempcnta\count@
655
               \advance\@tempcnta-\mult@grightbox
656
657
               \divide\@tempcnta \tw@
658
               \message{^^JColumn
659
                  \number\@tempcnta\space
                   badness: \the\badness\space}%
660
             \fi
```

If this badness is larger than the allowed column badness we reject this solution by setting too@bad to true.

```
662 \ifnum\badness\c@columnbadness
663 \ifnum\c@tracingmulticols>\@ne
664 \message{too bad
665 (>\the\c@columnbadness)}%
```

```
666 \fi
667 \too@badtrue
668 \fi
669 \/badness\
670 }}%
```

There is one subtle point here: while all other constructed boxes have a depth that is determined by \splitmaxdepth and/or \boxmaxdepth the last box will get a natural depth disregarding the original setting and the value of \splitmaxdepth or \boxmaxdepth. This means that we may end up with a very large depth in box \mult@grightbox which would make the result of the testing incorrect. So we change the value by unboxing the box into itself.

```
671 \global\setbox\mult@grightbox
672 \vbox{\unvbox\mult@grightbox}%
```

We also save a copy \mult@gfirstbox at its "natural" size for later use.

```
673 \setbox\mult@nat@firstbox
674 \vbox{\unvcopy\mult@gfirstbox}%
```

After \process@cols has done its job we have the following situation:

We report the height of the first column, in brackets the natural size is given.

```
675 \ifnum\c@tracingmulticols>\@ne
676 \message{^^JFirst column
677 = \the\dimen@\space
678 (\the\ht\mult@nat@firstbox)}\fi
```

If \raggedcolumns is in force older releases of this file also shrank the first column to its natural height at this point. This was done so that the first column doesn't run short compared to later columns but it is actually producing incorrect results (overprinting of text) in boundary cases, so since version v1.5q \raggedcolumns means allows for all columns to run slightly short.

```
679 % \ifshr@nking
680 % \global\setbox\mult@gfirstbox
681 % \copy\mult@nat@firstbox
682 % \fi
```

Then we give information about the last column.¹⁴

```
683 \ifnum\c@tracingmulticols>\@ne
684 \message{<> last column =
685 \the\ht\mult@grightbox^^J}%
```

¹⁴With TEX version 3.141 it is now possible to use LATEX's \newlinechar in the \message command, but people with older TEX versions will now get ^^J instead of a new line on the screen.

Some tracing code that we don't compile into the production version unless asked for. It will produce huge listings of the boxes involved in balancing in the transcript file.

```
686 (*debug)
          \ifnum\c@tracingmulticols>4
687
688
             {\showoutput
              \batchmode
689
690
               \process@cols\mult@grightbox
                {\showbox\count@}}%
691
               \errorstopmode
692
693
          \fi
694 (/debug)
695
         \fi
```

We check whether our trial was successful. The test used is very simple: we merely compare the first and the last column. Thus the intermediate columns may be longer than the first if \raggedcolumns is used. If the right-most column is longer than the first then we start over with a larger value for \dimen@.

```
696 \ifdim\ht\mult@grightbox >\dimen@
```

If the height of the last box is too large we mark this trial as unsuccessful.

```
697 (*badness)
698 \too@badtrue
699 \ifnum\c@tracingmulticols>\@ne
700 \typeout{Rejected: last
701 column too large!}%
702 \fi
703 \else
```

To ensure that there isn't a forced break in the last column we try to split off a box of size \maxdimen from \mult@grightbox (or rather from a copy of it). This should result in a void box after the split, unless there was a forced break somewhere within the column in which case the material after the break would have stayed in the box.

```
704 \setbox\@tempboxa
705 \copy\mult@grightbox
706 \setbox\z@\vsplit\@tempboxa to\maxdimen
707 \ifvoid\@tempboxa
```

Thus if \@tempboxa is void we have a valid solution. In this case we take a closer look at the last column to decide if this column should be made as long as all other columns or if it should be allowed to be shorter. For this we first have to rebox the column into a box of the appropriate height. If tracing is enabled we then display the badness for this box.

```
708 \global\setbox\mult@grightbox
709 \vbox to\dimen@
710 \{\unvbox\mult@grightbox}\%
711 \ifnum\c@tracingmulticols>\@ne
712 \message{Final badness:
```

```
713 \the\badness}%
714 \fi
```

We then compare this badness with the allowed badness for the final column. If it does not exceed this value we use the box, otherwise we rebox it once more and add some glue at the bottom.

```
\ifnum\badness>\c@finalcolumnbadness
715
716
              \global\setbox\mult@grightbox
717
               \vbox to\dimen@
718
                  {\unvbox\mult@grightbox\vfil}%
719
               \ifnum\c@tracingmulticols>\@ne
720
                 \message{ setting natural
721
                  (> \the\c@finalcolumnbadness)}%
               \fi
722
           \fi
723
```

If \@tempboxa above was not void our trial was unsuccessful and we report this fact and try again.

```
724 \else
```

If we have unprocessed forced breaks we normally reiterate with a larger column size to fit them in eventually. However, if there are simply too many of them (e.g., 3 forced breaks but only 2 columns to balance) then this will never succeed and we would continue growing the columns until we hit the largest possible column size. So in addition we check how big the column size is compared to available room and if we exceed this by \maxbalancingoverflow we give up and instead of balancing cut another normal page. To be indicate this case we set forcedbreak@leftover to true.

```
\@tempdima\@colroom
726
          \advance\@tempdima \maxbalancingoverflow
727
          \ifdim \dimen@ < \@tempdima
728
           \too@badtrue
             \ifnum\c@tracingmulticols>\@ne
729
               \typeout{Rejected: unprocessed
730
                 forced break(s) in last column!}%
731
            \fi
732
          \else
733
             \forcedbreak@leftovertrue
734
735
             \ifnum\c@tracingmulticols>\@ne
              \typeout{Failed: columns too large
736
                with unprocessed forced break(s)!}%
737
             \fi
738
739
          \fi
740
          \fi
```

If the natural height of the first box is smaller than the current trial size but is larger than the previous trial size it is likely that we have missed a potentially better solution. (This could have happened if for some reason our first trial size was too high.) In that case we dismiss this trial and restart using the natural height for the next trial.

```
\ifdim\ht\mult@nat@firstbox<\dimen@
742
          \ifdim\ht\mult@nat@firstbox>\last@try
743
744
            \too@badtrue
745
            \ifnum\c@tracingmulticols>\@ne
               \typeout{Retry: using natural
746
                        height of first column!}%
747
            \fi
748
            \dimen@\ht\mult@nat@firstbox
749
            \last@try\dimen@
750
751
            \advance\dimen@-\p@
752
```

Finally the switch too@bad is tested. If it was made true either earlier on or due to a rightmost column being too large we try again with a slightly larger value for \dimen@.

```
754 \iftoo@bad
755 \/badness\
756 \advance\dimen@\p@
757 \repeat
```

If we come out of the loop with the switch forcedbreak@leftover set to true then balancing has failed and we should cut a normal page. We indicate this below with \too@badtrue when any of the columns get too high, so we set this flag here too in order to get the same processing logic. 15

```
758 \ifforcedbreak@leftover
759 \too@badtrue
760 \else
```

At that point \dimen@ holds the height that was determined by the balancing loop. If that height for the columns turns out to be larger than the available space (which is \@colroom) we squeeze the columns into the space assuming that they will have enough shrinkability to allow this. 16 However, this squeezing should only be done if we are balancing columns on the main galley and not if we are building a boxed multicol (in the latter case the current \@colroom is irrelevant since the produced box might be moved anywhere at a later stage).

```
761 \if@boxedmulticols\else
762 \ifdim\dimen@>\@colroom
763 \dimen@\@colroom
764 \fi
765 \fi
```

Then we move the contents of the odd-numbered box registers to the even-numbered ones, shrinking them if requested. We have to use \vbox not \vtop (as it was done in the first versions) since otherwise the resulting boxes will have no height (*TeXbook* page 81). This would mean that extra \topskip is added when the boxes are returned to the page-builder via \page@sofar.

```
766 \process@cols\mult@rightbox
767 {\@tempcnta\count@
768 \advance\@tempcnta\@ne
```

when putting the final column together we want overfull information:

```
\vfuzz\z@
769
              \setbox\count@\vbox to\dimen@
770
771
772
                  \vskip \z@
                     \@plus-\multicolundershoot
773
                     \@minus-\multicolovershoot
774
775
                  \unvbox\@tempcnta
776
                  \ifshr@nking\vfilmaxdepth\fi
                 }%
777
```

If the resulting box is overfull there was too much material to fit into the available space. The question though is how much? If it wasn't more than \maxbalancingoverflow we accept it still to avoid getting very little material for the next page (which we would then have difficulties to balance).

```
\ifnum\badness>\@M
778
                \vfuzz\maxdimen % no overfull warning
779
780
                \setbox\@tempboxa \vbox to\dimen@
781
                     {\vskip-\maxbalancingoverflow
782
                      \unvcopy\count@}%
783
                \ifnum\badness>\@M
                  \millt@info\@ne
784
785
                    {Balanced column more than
786
                      \the\maxbalancingoverflow\space
787
                      too large}%
```

Fail the balancing attempt:

```
788 \too@badtrue
789 \else
```

Otherwise report that there is a problem but within the accepted boundary.

```
790 \mult@info\@ne
791 {Balanced column
792 too large, but less than
793 \the\maxbalancingoverflow}%
794 \fi
795 \fi
796 }%
```

Finally end the \ifforcedbreak@leftover conditional.

```
797 \fi
798}
```

Amount that balancing is allowed to overflow the available column space. We default to 12pt which means about one line in most layouts.

```
799 \newdimen\maxbalancingoverflow
800 \maxbalancingoverflow=12pt
```

¹⁵Should get cleaned up as we now have two different routes to reach this part of the processing.

¹⁶This might be wrong, since the shrinkability that accounts for the amount of material might be present only in some columns. But it is better to try then to give up directly.

4.5 The box allocations

Early releases of these macros used the first box registers 0, 2, 4,... for global boxes and 1, 3, 5,... for the corresponding local boxes. (You might still find some traces of this setup in the documentation, sigh.) This produced a problem at the moment we had more than 5 columns because then officially allocated boxes were overwritten by the algorithm. The new release now uses private box registers.

There was in fact a bug in the new implementation because at one point LATEX started to use the extended registers and so jumped from below 255 to above omitting the boxes allocated for inserts and the output page box.

So nowadays we really have to check if we get the full sequence of boxes allocated without holes (i.e., $2 \times max \ cols + 1$) and if not alter the allocation registers to start allocating after 255. This is all done quite low-level by looking directly at the values of the allocation counters.

```
801 \ifnum\numexpr
802 \count20-\count14-1<40
803 % this is = 2 * 20
804 \count14=\@cclv
```

```
805 \fi
806 \newbox\mult@rightbox
807 \newbox\mult@grightbox
808 \newbox\mult@firstbox
809 \newbox\mult@gfirstbox
810 \newbox\@tempa\newbox\@tempa
811 \newbox\@tempa\newbox\@tempa
812 \newbox\@tempa\newbox\@tempa
813 \newbox\@tempa\newbox\@tempa
814 \newbox\@tempa\newbox\@tempa
815 \newbox\@tempa\newbox\@tempa
816 \newbox\@tempa\newbox\@tempa
817 \newbox\@tempa\newbox\@tempa
818 \mbox\ \mb
819 \newbox\@tempa\newbox\@tempa
820 \newbox\@tempa\newbox\@tempa
821 \newbox\@tempa\newbox\@tempa
822 \newbox\@tempa\newbox\@tempa
823 \newbox\@tempa\newbox\@tempa
824 \newbox\@tempa\newbox\@tempa
825 \newbox\@tempa\newbox\@tempa
826 \newbox\@tempa\newbox\@tempa
827 \newbox\@tempa\newbox\@tempa
```

5 New macros and hacks for version 1.2

If we don't use TEX 3.0 \emergencystretch is undefined so in this case we simply add it as an unused $\langle dimen \rangle$ register.

```
829 \@ifundefined{emergencystretch}
830 {\newdimen\emergencystretch}{}
```

My tests showed that the following formula worked pretty well. Nevertheless the \setemergencystretch macro also gets \hsize as second argument to enable the user to try different formulae.

```
831 \def\setemergencystretch#1#2{%
832 \emergencystretch 4pt
833 \multiply\emergencystretch#1}
```

Even if this should be used as a hook we use a ${\tt Q}$ in the name since it is more for experts.

```
834 \def\set@floatcmds{%

835 \let\@dblfloat\@dbflt

836 \def\end@dblfloat{\@endfloatbox
```

```
837 \@largefloatcheck
838 \outer@nobreak
```

828 \let\@tempa\relax

This is cheap (deferring the floats until after the current page) but any other solution would go deep into LaTeX's output routine and I don't like to work on it until I know which parts of the output routine have to be reimplemented anyway for LaTeX3.

```
839 \ifnum\@floatpenalty<\z@
```

We have to add the float to the \@deferlist because we assume that outside the multicols environment we are in one column mode. This is not entirely correct, I already used the multicols environment inside of IATEXs \twocolumn declaration but it will do for most applications.

```
840 \@cons\@deferlist\@currbox

841 \fi

842 \ifnum\@floatpenalty=-\@Mii

843 \@Esphack

844 \fi}}
```

5.1 Maintaining the mark registers

This section contains the routines that set the marks so that they will be handled correctly. They have been introduced with version 1.4.

First thing we do is to reserve three macro names to hold the replacement text for TEX's primitives \firstmark, \botmark and \topmark. We initialize the first two to be empty and \kept@topmark to contain two empty pair of braces. This is necessary since \kept@topmark is supposed to contain the last mark from a preceding page and in LATEX any "real" mark must contain two parts representing left and right mark information.

```
845 \def\kept@topmark{{}{}}
846 \let\kept@firstmark\@empty
847 \let\kept@botmark\@empty
```

Sometimes we want to return the value of a "kept" mark into a \mark node on the main vertical list. This is done by the function \return@nonemptymark. As the name suggests it only acts if the replacement text of the kept mark is non-empty. This is done to avoid adding an empty mark when no mark was actually present. If we would nevertheless add such a mark it would be regarded as a valid \firstmark later on.

```
848 \def\return@nonemptymark#1#2{%
849 \ifx#2\@empty
850 \else
```

For debugging purposes we take a look at the value of the kept mark that we are about to return. This code will get stripped out for production.

Since the contents of the mark may be arbitrary LATEX code we better make sure that it doesn't get expanded any further. (Some expansion have been done already during the execution of \markright or \markboth.) We therefore use the usual mechanism of a toks register to prohibit expansion.¹⁷

```
858 \toks@\expandafter{#2}%
859 \mark{\the\toks@}%
```

We don't want any breakpoint between such a returned mark and the following material (which is usually just the box where the mark came from).

```
860 \nobreak
861 \fi}
```

If we have some material in a box register we may want to get the first and the last mark out of this box. This can be done with \get@keptmarks which takes one argument: the box register number or its nick name defined by \newbox.

```
862 \def\get@keptmarks#1{%
```

For debugging purposes we take a look at the current dimensions of the box since in earlier versions of the code I made some mistakes in this area.

Now we open a new group and locally copy the box to itself. As a result any operation, i.e. \vsplit, will only have a local effect. Without this trick the box content would get lost up to the level where the last assignment to the box register was done.

```
867 \begingroup
868 \vbadness\@M
869 \setbox#1\copy#1%
```

Now we split the box to the maximal possible dimension. This should split off the full contents of the box so that effectively everything is split off. As a result \splitfirstmark and \splitbotmark will contain the first and last mark in the box respectively.

$870 \qquad \texttt{\sctbox#1\vsplit#1to\maxdimen}$

Therefore we can now set the kept marks which is a global operation and afterwards close the group. This will restore the original box contents.

```
871 \set@keptmarks
872 \endgroup
```

For debugging we take again a look at the box dimension which shouldn't have changed.

```
873 (*debug)

874 \typeout{Mark box #1 \space after:

875 ht \the\ht#1, dp \the\dp#1}%

876 (/debug)

877 }
```

The macro \set@keptmarks is responsible for setting \kept@firstmark and \kept@botmark, by checking the current values for \splitfirstmark and \splitbotmark.

```
878 \def\set@keptmarks{%
```

¹⁷ Due to the current definition of \markright etc. it wouldn't help to define the \protect command to prohibit expansion as any \protect has already vanished due to earlier expansions.

If \kept@firstmark is empty we assume that it isn't set. This is strictly speaking not correct as we loose the ability to have marks that are explicitly empty, but for standard IATEX application it is sufficient. If it is non-empty we don't change the value—within the output routines it will then be restored to \@empty.

```
879 \ifx\kept@firstmark\@empty
```

We now put the contents of \splitfirstmark into \kept@firstmark. In the case that there wasn't any mark at all \kept@firstmark will not change by that operation.

```
880 \expandafter\gdef\expandafter

881 \kept@firstmark

882 \expandafter{\splitfirstmark}%
```

When debugging we show the assignment but only when something actually happened.

```
883 (*marktrace)
884    \ifx\kept@firstmark\@empty\else
885    \mult@info\tw@
886     {Set kept first mark:\MessageBreak
887         \meaning\kept@firstmark%
888         \@gobbletwo}%
889    \fi
890 \/marktrace\
891    \fi
```

We always try to set the bottom mark to the \splitbotmark but of course only when there has been a \splitbotmark at all. Again, we assume that an empty \splitbotmark means that the split off box part didn't contain any marks at all.

```
892
      \expandafter\def\expandafter\@tempa
893
          \expandafter{\splitbotmark}%
894
      \ifx\@tempa\@empty\else
          \global\let\kept@botmark\@tempa
895
896 (*marktrace)
897
          \mult@info\tw@
            {Set kept bot mark:\MessageBreak
898
899
             \meaning\kept@botmark%
900
             \@gobbletwo}%
901 (/marktrace)
      \fi}%
902
```

The \prep@keptmarks function is used to initialize the kept marks from the contents of \partial@page, i.e. the box that holds everything from the top of the current page prior to starting the multicols environment. However, such a box is only available if we are not producing a boxed multicols.

```
903 \def\prep@keptmarks{%

904 \if@boxedmulticols \else

905 \get@keptmarks\partial@page

906 \fi}
```

There are situations when we may have some space at the end of a column and this macro here will attempt to get rid of it. The typical IATEX sequence is a series of self-canceling glues so if we remove them recursively we are usually fine.

Special care is needed with handling \vspace* as that corresponds to \penalty10000, \vskip <skip>, followed by \vskip Opt. If we see this sequence going backwards in the vertical list we assume that this is a "desired" space. We therefore stop the recursion and reinsert the spaces.

As the multicol code sometimes add an explicit penalty at the end of a column we first attempt to remove it in case it is there.

```
907 \skip0=0pt
908 \edef\the@zero@skip{\the\skip0}
909 \def\remove@discardable@items{%
910 \unpenalty
```

Save a previous skip (if there) and then remove it, we can't really tell the difference between no skip an a skip of zero but that's life.

```
911 \edef\@tempa{\the\lastskip}%
912 %\typeout{s1=\@tempa}%
913 \unskip
```

If it was a zero skip (or none) we save the next previous skip (if any).

```
914 \ifx\@tempa\the@zero@skip 915 \edef\@tempb{\the\lastskip}% 916 %\typeout{s2=\@tempb}%
```

If this one again was zero (or more likely not there in the first place) we stop.

```
917 \ifx\@tempb\the@zero@skip
918 \else
```

Otherwise we remove this "real" skip. Then we look if it was preceded by a penalty of 10000 (i.e., a \nobreak)

```
919 \unskip
920 %\typeout{p=\lastpenalty}%
921 \ifnum \lastpenalty=\@M
```

If so this was a \vspace* or something equivalent to it. Therefore we reintroduce the skips and stop. Otherwise we recurse.

```
922 \vskip\@tempb\vskip\@tempa\relax
923 \else
924 \remove@discardable@items
925 \fi
926 \fi
927 \else
```

If the first skip was a non-zero skip we recurse as well.

```
928 \remove@discardable@items
929 \fi
930 }
```

```
931 (*badness)
                                                     944
932 \newif\iftoo@bad
933 \def\too@badtrue{\global\let\iftoo@bad\iftrue}
                                                     945 \newdimen\multicolovershoot
934 \def\too@badfalse{\global\et\iftoo@bad} \et\ \newdimen\multicolundershoot
                                                     947 \multicolovershoot=0pt
935 \newif\ifforcedbreak@leftover
                                                     948 \multicolundershoot=2pt
                                                     949 \mbox\mult@nat@firstbox
                                                     950 (/badness)
936 \newcount\c@minrows
937 \c@minrows=1
                                                     A helper for producing info messages
                                                     951 \def\mult@info#1#2{%
                                                           \ifnum\c@tracingmulticols>#1%
938 \newcount\c@columnbadness
                                                     952
939 \c@columnbadness=10000
                                                     953
                                                            \GenericWarning
940 \newcount\c@finalcolumnbadness
                                                     954
                                                                {(multicol)\@spaces\@spaces}%
941 \c@finalcolumnbadness=9999
                                                     955
                                                                {Package multicol: #2}%
                                                     956
                                                           \fi
943 \newdimen\last@try
                                                     957 }
```

6 Fixing the \columnwidth

If we store the current column width in \columnwidth we have to redefine the internal \@footnotetext macro to use \textwidth for the width of the footnotes rather than using the original definition.

Starting with version v1.5r this is now done in a way that the original definition is still used, except that locally \columnwidth is set to \textwidth.

This solves two problems: first redefinitions of

\@footnotetext done by a class will correctly survive and second if multicols is used inside a minipage environment the special definition of \@footnotetext in that environment will be picked up and not the one for the main galley (the latter would result in all footnotes getting lost in that case).

See the definition of the \multicols command further up for the exact code.

7 Further extensions

This section does contain code for extensions added to this package over time. Not all of them may be active, some might sit dormant and wait for being activated in some later release.

7.1 Not balancing the columns

This is fairly trivial to implement. we just have to disable the balancing output routine and replace it by the one that ships out the other pages.

The code for this environment was suggested by Matthias Clasen.

If we are not on the main galley, i.e., inside a box of some sort, that approach will not work since we don't have a vertical size for the box so we better warn that we balance anyway.

```
960 \ifinner
961 \PackageWarning{multicol}%
```

```
962 {multicols* inside a box does
963 not make sense.\MessageBreak
964 Going to balance anyway}%
965 \else
```

Τf we aren't balancing we change \balance@columns@out to work like the normal output routine that cuts normal pages. However, there is a catch: In case the last page we cut (after seeing the end of the environment) is actually larger than a page (for example, if it contains more \columnbreak commands than columns) we end up with some leftover material that is returned to the main galley, but now the environment end penalty is missing. So we add another one here too. Of course that shouldn't be done if there is really only a single final page, but fortunately in that case we have just finished a page and any penalty on the recent contributions will be discarded, thus the extra one is harmless—puh.

```
966 \def\balance@columns@out
967 {\multi@column@out \penalty-\@Mvi }%
```

```
968 \fi
969 \begin{multicols}
970 }
```

When ending the environment we simply end the inner multicols environment, except that we better also stick in some stretchable vertical glue so that the last column still containing text is not vertically stretched out.

We do this as follows: first we ensure that we are back in vertical mode and then we cancel out \lastskip if it was positive (in case of a negative glue we assume that it was deliberate, for a deliberate positive glue one needs to use \vspace*). We can't simply use \remove@discardable@items here as this only works inside boxes but we are here on the main vertical list.

Then we back up by \prevdepth but not more than \boxmaxdepth so that a baseline of the last box is now at the bottom. This way the material will align properly in case something like \vfill spreads it out after all. Finally we append \vfil to put white space at the bottom of the column, but we only do this if we aren't anyway doing \raggedcolumns.

```
971 \ensuremath{\mbox{\tt 071}} \ensuremath{
                                                           \par
972
                                                           \ifdim\lastskip>\z@ \vskip-\lastskip \fi
973
                                                           \left\langle \right\rangle \
974
                                                                                 \vskip-\ifdim\prevdepth>\boxmaxdepth
975
976
                                                                                                                                                                                                            \boxmaxdepth
                                                                                                                                                   \else \prevdepth \fi
977
978
                                                           \fi
                                                           \ifshr@nking\else
979
980
                                                                              \vfil
981
982
                                                           \end{multicols}}
983 (/nobalance)
```

7.2 Manual column breaking

The problem with manual page breaks within multicols is the fact that during collection of material for all columns a page-forcing penalty (i.e. -10000 or higher) would stop the collecting pass which is not quite what is desired. On the other hand, using a penalty like -9999 would mean that there would be occasions where the \vspliting operations within multicols would ignore that penalty and still choose a different break point.

For this reason the current implementation uses a completely different approach. In a nutshell it extends the LATEX output routine handling by introducing an additional penalty flag (i.e., a penalty which is forcing but higher than -10000 so that the

output routine can look at this value and thus knows why it has been called).

Inside the output routine we test for this value and if it appears we do two things: save the galley up to this point in a special box for later use and reduce the \vsize by the height of the material seen. This way the forcing penalty is now hidden in that box and we can restart the collection process for the remaining columns. (This is done in \speci@ls above.)

In the output routines that do the \vsplitting either for balancing or for a full page we simply combine box 255 with the saved box thus getting a single box for splitting which now contains forcing breaks in the right positions.

\columnbreak is modeled after \pagebreak except that we generate a penalty -10005.

```
984 \mathchardef\@Mv=10005
985 \newcommand\columnbreak[1][4]{%
```

We have to ensure that it is only used within a multicols environment since if that penalty would be seen by the unmodified IATEX output routine strange things would happen.

```
986 \ifnum\col@number<\tw@
987 \PackageError{multicol}%
988 {\noexpand\columnbreak outside multicols}%
989 {This command can only be used within
990 a multicols or multicols* environment.}%
991 \else
```

Increasingly lower penalty based on argument value. This is like \pagebreak but we use other penalty values are the LATEX defaults aree rather pointless for pagination.

```
992 \edef\mc@break@pen
993 {-\ifcase#1\@m\or 3333\or 6666\or 9999\else\@Mv\fi\relax
994 \ifvmode
995 \penalty \mc@break@pen
996 \else
997 \@bsphack
998 \vadjust{\penalty \mc@break@pen}%
999 \@esphack
```

This is modeled after \newpage but for column breaks

```
1002 \newcommand\newcolumn{%
1003 \ifnum\col@number<\tw@
1004 \PackageError{multicol}%
1005 {\noexpand\newcolumn outside multicols}%
1006 {This command can only be used within
1007 a multicols or multicols* environment.}%
1008 \else
1009 \ifvmode
```

1000

1001

\fi

fi

```
1010 \nobreak\vfill\penalty -\@Mv\relax
1011 \else
1012 \@bsphack
1013 \vadjust{\nobreak\vfill\kern\z@\penalty
1014 \@esphack
1015 \fi
1016 \fi}
```

Need a box to collect the galley up to the column break.

```
1017 \newbox\colbreak@box 1018 \langle/package\rangle
```

7.3 Supporting right-to-left languages

\LR@column@boxes is called when we are assembling the columns for left to right typesetting. When we start we are inside an \hbox of full width. Left to right typesetting is fairly easy, we basically output each column box intermixed with vertical rules and proper spacing. As this happens inside a box of a defined width the rules and the columns automatically get into the right positions.

```
1019 \def\LR@column@boxes{%
```

We loop through the columns with \process@cols
1020 \process@cols\mult@firstbox{%

If the depth of the current box is larger than the maximum found so far in \dimen2 we update that register for later use.

```
1021 \ifdim\dp\count@>\dimen\tw@
1022 \global\dimen\tw@\dp\count@\fi
```

If the colaction option is given we write out status information about the current column, otherwise the next command does nothing.

```
1023 \mc@col@status@write
```

The typeset box followed by the column rule material

```
1024 \box\count@

1025 \hss{\columnseprulecolor\vrule

1026 \@width\columnseprule}\hss}%
```

As you will have noticed, we started with box register \mult@firstbox (i.e. the left column). So this time \count@ looped through 2, 4,... (plus the appropriate offset). Finally we add box \mult@rightbox and we are done. Again we may have to update \dimen\tw@.

```
1027 \ifdim\dp\mult@rightbox>\dimen\tw@
1028 \global\dimen\tw@\dp\mult@rightbox \fi
```

If the colaction option is given we write out status information about the last column, otherwise the next command does nothing.

```
1029 \mc@lastcol@status@write
1030 \box\mult@rightbox
1031 }
```

\@Mv\relax}%

Assembling the boxes for right to left typesetting is far more complicated. When I first tried to build a solution for this my thinking was that all that is necessary to do is to reverse the order of the columns. But such an approach produces a subtle bug: If we work this way then the first column put on the page will be the last column of the text to read. and this means that the order in which TEX executes write statements or assembles mark material will not happen in the order of the textual flow. So if, for example each column contains a section command then these sections will appear in reverse order in the table of content.

For this reason some amount of gymnastics is needed to add the columns in their natural flow.

1032 \def\RL@column@boxes{%

First step is to put all rules in the right place (without adding the comes which are instead represented by a space of \hsize.

```
1033 \process@cols\mult@firstbox{%
1034 \hskip\hsize
1035 \hss{\columnseprulecolor\vrule
1036 \@width\columnseprule}\hss
1037 }%
1038 \hskip\hsize
```

At this point in the code our typesetting reference point is at the right end of the rightmost column (or rather where that column should appear).

We are now typesetting all columns by first backing up by their width (which is \hsize) then typesetting the box and then backing up again, but this time further, i.e., also across the column separation. That will then enable us to typeset the next column using the same approach until we are done with all but the final column.

```
1039
         \process@cols\mult@firstbox{%
1040
           \ifdim\dp\count@>\dimen\tw@
1041
              \global\dimen\tw@\dp\count@ \fi
1042
           \hskip-\hsize
           \mc@col@status@write
1043
1044
           \box\count@
1045
           \hskip-\hsize
1046
           \hskip-\columnsep
1047
```

The approach for the final column is similar only that we do not have to back up over any column

```
gap.

1048 \ifdim\dp\mult@rightbox>\dimen\tw@
1049 \global\dimen\tw@\dp\mult@rightbox \fi
1050 \hskip-\hsize
```

```
1051 \mc@lastcol@status@write
1052 \box\mult@rightbox
1053 \hskip-\hsize
```

However we do have to move the reference point to its right place: to make the rules appear at the expected places, we should get the typesetting position to the far right again. As we at the moment at the far left we skip to the far right like this:

```
1054 \hskip\full@width 1055 }
```

Macros to switch between left-right and right-left typesetting. In LR typesetting the \LR@column@boxes is used to combine the columns. When typesetting right to left the \RL@column@boxes is used instead.

```
\begin{array}{lll} 1056 \newcommand\RLmulticolcolumns \\ 1057 & \{\let\mc@align@columns \\ 1058 & \RL@column@boxes\} \\ 1059 \newcommand\LRmulticolcolumns \\ 1060 & \{\let\mc@align@columns \\ 1061 & \LR@column@boxes\} \\ \end{array}
```

The default is left-to-right:

1062 \LRmulticolcolumns

7.4 Supporting \docolaction

Whenever we want to do something that depends on the current column we execute \docolaction. This command takes one optional and three mandatory arguments. The mandatory ones denote what to do if this is a "left", "middle", or "right" column and the optional one is simply there to say what to do if we don't know (default is to use the "left" column action in that case).

We use one counter \mc@col@check@num to generate us unique label names. Each time we execute \docolaction we increment this counter to get a new name

1063 \newcount\mc@col@check@num

The generated "labels" are named

```
\mc@col-\the\mc@col@check@num
```

and they hold as values the numbers 1, 2, or 3 denoting the current column type.

The \docolaction scans for a star and optional argument and 3 mandatory ones, but we do this in chunks (not having xparse available).

1064 \newcommand\docolaction{%

```
First check is the support is enabled.
    \ifx\mc@col@status@write\relax
         \PackageError{multicol}%
1066
          {Option 'colaction' not selected}%
1067
          {\string\docolaction\space
1068
           requires the use of the 'colaction'
1069
1070
           option on the package}%
1071 \fi
Then prepare \mc@col@type.
     \global\advance\mc@col@check@num\@ne
     \edef\mc@col@type{\expandafter\ifx
1073
       \csname mc@col-\the\mc@col@check@num
1074
1075
       \endcsname\relax
1076
1077
       \csname mc@col-\the\mc@col@check@num
1078
       \endcsname
1079
       fi}%
Finally check for a star, record this information and
then call \@docolaction to do the rest.
1081
       {\@docolactionstartrue \@docolaction}%
       {\@docolactionstarfalse\@docolaction}%
1082
```

1084 \newcommand\@docolaction[4][1]{%

1083 }

How does the column number get associated with our label? We do this by writing another line into the aux file. Here are the preparations.

```
1085 \edef\@docolactioncheck{\write\@auxout
1086 {\string\mc@set@col@status
1087 {mc@col-\the\mc@col@check@num}%
1088 {\mc@col@type}}}%
```

Where we do the actual \write depends on the whether or not we gave seen a *. If yes, we do it first and then execute the code argument, otherwise we execute that code first and check at the point after that.

1089 \if@docolactionstar \@docolactioncheck \fi We prefix with 0 so that an unknown label (that returns \relax) will result in case 0

```
1090 \ifcase \mc@col@type\relax
```

If column is unknown we use the default action or the action denoted by the optional argument (so that arg can take the value 1, 2, 3).

```
1091 \ifcase #1\or #2\or#3\or#4\fi
1092 \or
```

Otherwise we know (or think we know) that this is a first, middle, or last column:

```
1093 #2% % 1 First col

1094 \or

1095 #3% % 2 any middle col

1096 \or

1097 #4% % 3 last col

1098 \else
```

```
\ERRORwrongdefaultgiven
1100
1101 $$ \left(\frac{1}{100} \right) \Lambda EndDocument{\def\mc@set@col@status#1#2{\%}} = 1101 $$ \left(\frac{1}{100} \Lambda EndDocument{\def\mc@set@col@status#1#2{\%}} \right) $$
1102 }
```

Here is the if used above:

1103 \newif\if@docolactionstar

Because of extra data writing to the aux file the aux file will now contain something like the following after the document is processed the first time:

```
\relax
\mc@col@status{1}
\mc@set@col@status{lcol-1}{0}
\mc@col@status{2}
\mc@set@col@status{lcol-2}{0}
\mc@col@status{3}
\mc@set@col@status{lcol-3}{0}
\mc@col@status{1}
\mc@col@status{2}
\mc@col@status{3}
\mc@set@col@status{lcol-4}{0}
```

The \mc@col@status line denotes the column type and has been written out just before corresponding the column box was placed onto the The\mc@set@col@status lines have been written out as part of shipping the column boxes out, e.g., \mc@set@col@status{lcol-1}{0} was therefore somewhere within the first column as it appears between $\mbox{\em mc@col@status{1}}$ and \mc@col@status{2} The second argument in that line is the value used in the previous run (or zero if there was no previous run. We can use this to determine if a rerun is necessary.

Thus with this knowledge we can set things up to get the labels working.

When the aux file is read in \mc@col@status is used to set \mc@curr@col@status:

```
1104 \def\mc@col@status#1{%
        \gdef\mc@curr@col@status{#1}}
```

And when \mc@set@col@status is executed we can simply set up the label by associating it with the \mc@curr@col@status and ignore the second argument:

```
1106 \def\mc@set@col@status#1#2{%
      \global\expandafter\let\csname #1\endcsname
                             \mc@curr@col@status}
```

The above definition is being used when the .aux file is read in at the beginning. At the end we need a different definition to test if another typesetting run is needed. There we compare the value used in the current run (stored in the second argument) with the value used on the next run. If those two values differ we set Otempswa to false which will trigger the "Label(s) may have changed" warning.

```
\ifnum #2=\mc@curr@col@status\else
1110
1111
            \@tempswatrue
1112
         fi}%
1113 }
```

Finally, as part of determining in which column we are, we used a switch inside \mc@col@status@write to determine if we are in the first column or not.

```
1114 \newif\ifmc@firstcol
1115 \mc@firstcoltrue
```

Index

Numbers written in italic refer to the page where the corresponding entry is described; numbers underlined refer to the code line of the definition; numbers in roman refer to the code lines where the entry is used.

Symbols	\endmulticols* <u>971</u>	\mc@col@status . $\frac{1104}{}$	\page@sofar <u>334</u>
\@Mvi <u>241</u>	\enough@room 135	$\mbox{mc@firstcol} \dots \ \ \ \ \ \ \ \ \ \ \ \ \ \ \ \ \ \ $	\partial@page $\frac{301}{2}$
\@footnotetext 958		\mc@set@col@status	\postmulticols $3, \frac{301}{}$
	\mathbf{F}	<u>1106</u>	\premulticols . $2, \frac{301}{}$
В	\flushcolumns 545	\mult@@cols <u>98</u>	\prep@keptmarks . 903
\balance@columns $\frac{587}{}$		\mult@cols <u>95</u>	\prepare@multicols $\frac{152}{1}$
\balance@columns@out	G	$\mbox{mult@firstbox}$ $\mbox{801}$	\process@cols $\frac{325}{2}$
<u>550</u>	\get@keptmarks 862	\mult@footnotetext	\process@deferreds 535
\mathbf{C}	I	$\mbox{mult@gfirstbox}$. 801	\mathbf{R}
\c@collectmore 301	\if@boxedmulticols $\underline{132}$	\mult@grightbox . 801	\raggedcolumns 545
\c@columnbadness 938	\ifshr@nking 545	\mult@info 951	\reinsert@footnotes
$\c0finalcolumnbadness$	\init@mult@footins $\frac{226}{}$	\mult@rightbox 801	<u>368</u>
<u>938</u>		\multi@column@out 372	\remove@discardable@items
\c@minrows 936	\mathbf{K}	\multicol@leftmargin	<u>907</u>
\c@unbalance 302	\kept@botmark 845	<u>240</u>	\return@nonemptymark
\col@number 301	\kept@firstmark . 845	\multicolbaselineskip	
\colbreak@box 1017	\kept@topmark 845	3, 301	\RL@column@boxes 1032
\columnbreak 984		\multicolpretolerance	\RLmulticolcolumns
\columnsep \dots 3	$\mathbf L$	3, 301	<u>1056</u>
\columnseprule \dots 3	\leave@mult@footins	\multicols 71	
\columnseprulecolor		\multicols* 958	${f S}$
	\LR@column@boxes <u>1019</u>	\multicolsep $3, \overline{301}$	\set@floatcmds 834
	\LRmulticolcolumns	\multicoltolerance	\set@keptmarks 878
D	<u>1056</u>		\set@mult@vsize . 230
\docolaction 1064		,	\setemergencystretch
\doublecol@number $\frac{301}{1}$	\mathbf{M}	${f N}$	<u>829</u>
	\maxbalancingoverflow	$\verb \newcolumn \dots \underline{1002}$	\speci@ls \dots 486
${f E}$	<u>799</u>		
\emergencystretch 829	\mc@align@columns $\frac{1056}{}$	P	\mathbf{V}
\endmulticols $\underline{243}$	\mc@col@check@num $\frac{1063}{}$	\page@free \dots 301	\vfilmaxdepth $\frac{370}{}$

Change History

v1.0c	description
\enough@room: Penalty 0 added to empty the	v1.1a
contribution list	\flushcolumns: \flushedcolumns renamed to
v1.0d	\flushcolumns 21
General: All lines shortened to 72 or less 1	General: \multicolssep changed to
v1.0e	$\verb \multicolsep. $
\prepare@multicols: \textwidth changed to	v1.2a
\linewidth 13	\balance@columns: Group around main loop
Setting of \columnwidth removed 13	removed
So this file will work with the 'twocolumn'	\prepare@multicols: \pretolerance -1
command	because it nearly never succeeds 13
General: Redefinition of description env. to use	\set@floatcmds added 13
\descriptionmargin=5pt in	\setemergencystretch added 13
documentation	\vbadness 10001 now 13
v1.0f	\set@floatcmds: Macro added
General: Changed \z@ to 0pt in redefinition of	\setemergencystretch: Macro added 27

\speci@ls: Float boxes freed 21	v1.4i
v1.3a	\multi@column@out: Set \kept@topmark to
\balance@columns: Changed \vtop to \vbox 26	
v1.3b	\prepare@multicols: \kept@topmark
\endmulticols: Do \penalty with \addpenalty 14	
\enough@room: Do \penalty with \addpenalty 11	
\multicols: Minimum of two columns 9	\setemergencystretch: Setting of \emergencystretch on top removed 27
v1.3c	v1.4k
\balance@columns: \global\advance left over	\multicals: Maximum of 5 columns (temp)
from older code	v1 4l
Limit column height to \@colroom 26	\mult00cols:\0totalleftmargin now in
\endmulticols: Check closing env	\nronaro@multicole 10
\multi@column@out: \unboxing avoided 18	\page@sofar: use \multicol@leftmargin
Check if footnotes are actually present before	instead of \@totalleftmargin 16
issuing a warning	\prepare@multicols: saved
Unnecessary code removed	\@totalleftmargin 11
\prepare@multicols: \null inserted and	v1.4m
removed in output	\endmutticois: Check \partial@page being
\reinsert@footnotes: \unboxing avoided 17	emptied
v1.3d	v1.4n
\c@unbalance: \col@number set to one 16	(Tedarisionempoymark, Watte marks Tobast 20
v1.4a	v1.4o
\balance@columns: Changed to proper	\prepare@multicols: \topskip locally zeroed. 11
\endlinechar in\message	11.1p
\multi@column@out: \botmark set to	,
\splitbotmark 19	setting
\prepare@multicols: Checking for text losses. 12	
Conditional code for boxed mode added 11	77 1177
kept marks initiated	
General: Added support for multicol in inner	v1.5?
mode 1	
v1.4d	a bit long or short
\balance@columns: New algorithm for start	Do splitting to zero here
height	Initialize \last@try 23
v1.4e	Show natural size 24
\endmulticols: But ignore \@nobreak in	\endmulticols: Splitting off zero box moved to
\addpenalty 14	\balance@columns 14
\enough@room: But ignore \@nobreak in	\leave@mult@footins: Macro added 20
\addpenalty 11	\mult@@cols: Penalty moved to later point 10
\mult@@cols: Typeset optional arg inside group 10	\multi@column@out: Use \leave@mult@footins 18
\prepare@multicols: Using 13	\prepare@multicols: Use \init@mult@footins 12
v1.4f	V1.5a
\balance@columns: \on@line added to tracing	\LR@column@boxes: New box mechanism 32
info	\balance@columns: New box mechanism 24
\mult@@cols: \on@line added to tracing info . 10	\multi@column@out: New box mechanism 18 \multicols: Allow 10 columns again 9
\par added to allow for correct inner test 10	multicols. Allow to columns again
v1.4g	\prepare@multicols: Add offset to
\mult@@cols: \global was probably wrong but	\doublecolnumber
at least unnecessary 10	
\multi@column@out: Only change	\balance@columns: New badness mechanism 24
\kept@topmark if \kept@botmark	v1.5c
non-empty	
v1.4h	output routine exit
\kept@topmark: Init to double brace pair 28	
General: Added mark tracing with	\multi@column@out: Support \clearpage 18
$tracing multicols \ge 2 \dots 1$	

v1.5d	v1.5v	
\multi@column@out: reinit \topmark 19	\balance@columns: Added tracing statements	
v1.5e	for trial unsuccessful 2	25
\enough@room: Assign arg to skip register to be	Check last column if it contains forced break	
able to output value 11	and reject trial if that is the case 2	25
v1.5g	\balance@columns@out: Added debug	
\set@floatcmds: Updated since floats have	statements for column break support 2	1
changed	\multi@column@out: Added debug statements	
v1.5h	for column break support 1	8
\balance@columns: Get kept marks first 22	\speci@ls: Added debug statements for column	
\page@sofar: Check for void boxes 16	break support 2	20
v1.5i	v1.5w	
\page@sofar: But don't remove original code 16	\multicols: Make \@footnotetext long to	
v1.5j		9
\set@floatcmds: Updated since floats have	v1.5x	
changed again	\endmulticols: Detect and fix problem if a	
v1.5l	multicols ends at the top of a page 1	5
\set@floatcmds: $Added$ \@largefloatcheck 27	v1.5y	Ĭ
General: Try hard to explain unresolved	\balance@columns: Limit column height only in	
reference that happens if \OnlyDescription	unrestricted mode (pr/3212) 2	16
is used	v1.5z	·U
v1.5n		
General: Applied improvement of	\page@sofar: Ensure that column rule has always \normalcolor	c
documentation, kindly done by Robin	v1.5z1	·U
Fairbairns		
v1.5o	\c@finalcolumnbadness: Change wrong default	
\@footnotetext : Redefinition added $pr/2664$ 30	(1 / /	80
\prepare@multicols: Setting of \columnwidth	\mult@@cols: Add a kern to cancel potential	_
added again pr/2664	depth of previous line 1	.U
v1.5p	\page@sofar: Suppress interline glue at this	_
\multicols: Redefinition of \Ofootnotetext	point	.7
only within env pr/2689 9	v1.6a	
v1.5q	\LR@column@boxes: Preparing for adjusting	
\balance@columns: Do not reset	\prevdepth 3	
\mult@gfirstbox (pr2739) 24	\mult@@cols: Adjust spacing 1	.0
Removed setting \dimen@ (pr2739) 26	\page@sofar: Preparing for adjusting	
\endmulticols*: Macro added	\prevdepth 1	
\mult@@cols: And removed the group again six	General: New option grid	9
years later	v1.6b	
\multicols*: Macro added	\page@sofar: Different info display 1	.6
v1.5r	v1.6c	
\@footnotetext: Use \@footnotetext but with	\set@mult@vsize: Collect one line per column	
local change to \columnwidth 30	more 1	4
\mult@footnotetext: Macro removed again 30	v1.6d	
\multicols: Use \@footnotetext but with	\endmulticols: Catch problem with	
local change to \columnwidth 9	\columnbreak in last line 1	4
v1.5s	v1.6e	
\speci@ls: check for \stop penalty pr/2873 20	\multicols: Avoid self-referencing definition of	
v1.5t	\@footnotetext (pr/3618)	9
\return@nonemptymark: re-add \mark command	v1.6f	
which was commented out by mistake at	\balance@columns: /colbreak guard in the	
some point in 1998 (pr/2978) \dots 28	wrong position	25
v1.5u	need to use \mult@grightbox in the loop 2	
	\columnseprulecolor: Make the color of the	ں.
\balance@columns@out: Support \columnbreak 21 \colbreak@box: Macro added	rule a hook 1	7
\columnbreak: Macro added	\page@sofar: Make the color of the rule a hook 1	
		.U
\multi@column@out: Support \columnbreak 18	v1.6g	, –
\speci@ls: Support \columnbreak 20	\set@floatcmds: $Added$ \@minipagefalse 2	. (

v1.6h	v1.8i	
\set@floatcmds: Use \@endfloatbox to better	\endmulticols*: Add \null to hide the final	
support the modifications done by the float	fill and only add vertical space if not doing	
package	\raggedcolumns 3	31
v1.7a	v1.8j	
General: RL language support added 32	\balance@columns: Use \vfil in this case 2	25
v1.7b	\endmulticols*: Redesign the whole approach. 3	31
\page@sofar: RL language support fixed 17	\multi@column@out: Set \boxmaxdepth 1	18
General: RL language support fixed 32	\vfilmaxdepth: Use only '0.0001fil' for	
v1.8a	stretching 1	17
\balance@columns: Balancing concept improved 26	v1.8k	
\balance@columns@out: Balancing concept	\balance@columns: 2	26
improved 21	\remove@discardable@items removed 2	22
Support for \enlargethispage 22	Do not use \remove@discardable@items here 2	24
\maxbalancingoverflow:	Finish the new conditional	26
\maxbalancingoverflow parameter added 26	Init \ifforcedbreak@leftover 2	24
\multi@column@out: Only re-add output	Watch out for columns growing too far in	
penalty if it was explicitly set 18	case of forced breaks	25
Support for \enlargethispage 18	\balance@columns@out: Add	
v1.8b	\remove@discardable@items at the end of	
\balance@columns: Remove discardable items	the last column when balancing 2	21
at the end of split boxes	No additional penalty here 2	22
\multi@column@out: And 20odd years later	Use \@Mv and not \break in case this forced	
conclude that this was wrong and unboxing	break is not used on this page 2	21
is always needed	\endmulticols*: And a bit more redesign	
Remove discardable items at the end of split	because of the change in	
boxes	\remove@discardable@items 3	31
v1.8c	\multi@column@out:	
\endmulticols: Add \color@endgroup to	\remove@discardable@items removed 1	18
prevent color leak	\speci@ls: Remove discardable items just	
\mult@@cols: Add \color@setgroup to prevent		20
color leak	General: The new switch	30
v1.8d	v1.8l	
\multi@column@out: Reset \@mparbottom after	\balance@columns: Added additional tracing if	
page finishes		25
v1.8e	v1.8m	
\LR@column@boxes: Support \docolaction 32	\remove@discardable@items: Another rewrite	
\RL@column@boxes: Support \docolaction 32, 33	of \remove@discardable@items hopefully	
General: Support \docolaction 9, 33		29
v1.8f	v1.8n	
\endmulticols: Discard spaces before adding	\multi@column@out: Reset	10
\color@endgroup 14	\Otextfloatsheight after page finishes 1	19
v1.8g	v1.80	
\page@sofar: Now adjusting \prevdepth 17	\c@unbalance: \col@number already initialized	
Resetting \prevdepth in the right place 17	in the kernel, so not initializing it in the	
Warn if value is exceeded not when equal 17	package in case the document is in	1 6
v1.8h	two-column (pr/4435)	16
\balance@columns: All column boxes should		31
obey \maxdepth ($pr/4395$)	before using \prevdepth (pr/4448) 3)1
Do not report overfull	1	10
Use \vfilmaxdepth	\multi@column@out: Reset \boxmaxdepth 1	LÐ
\endmulticols: Set \prevdepdth for current	v1.8q	
vlist when returning from multicols	\prepare@multicols: Make \clearpage behave like \newpage (pr/4511) 1	19
environment	v1.8r	. 4
\endmulticols*: Use \vfilmaxdepth 31	\@Mvi: Macro added	14
\multi@column@out: Use \vfilmaxdepth 18	\balance@columns@out: Re-add the final	r.+
\vfilmaxdepth: Macro added (pr/4395) 17	penalty	ງາ
(ATTIMOVACE OF MACIO GOOCH (b) 4999) 11	penany	كاب

\endmulticols: Use special penalty to signal	\maxdepth $(gh/190)$
	15 \speci@ls: Use \@maxdepth not \maxdepth (gh/190)
penalty	20 \vfilmaxdepth: Use \@maxdepth not \maxdepth (gh/190)
v1.8u	v1.8y \mult@gfirstbox: Allow for 20 columns (gh/237)
\docolaction: Support star with \docolaction v1.8v \multi@column@out: Removed dead code, the case where this can go wrong is too obscure to worry about it (gh/101)	\columnbreak: Added optional argument for conditional break
\c@minrows: Provide minrows counter for	\columnbreak: Corrected error message text (gh/703)
${ m v1.8x}$ \balance@columns: Use \@maxdepth not	General: Swap names \mult@gfirstbox and \mult@firstbox (gh/701) 1