# **Boost.Chrono 1.0.0**

# Howard Hinnant Beman Dawes Vicente J. Botet Escriba

Copyright © 2008, 2006, 2009 -2011 Vicente J. Botet Escriba

Distributed under the Boost Software License, Version 1.0. (See accompanying file LICENSE\_1\_0.txt or copy at http://www.boost.org/LICENSE\_1\_0.txt)

# **Table of Contents**

Overview	1
Motivation	2
Description	2
User's Guide	3
Getting Started	3
Tutorial	5
Examples	18
External Resources	
Reference	31
Included on the C++0x Recommendation	32
Chrono I/O	54
Other Clocks	58
Appendices	
Appendix A: History	
Appendix B: Rationale	
Appendix C: Implementation Notes	
Appendix D: FAQ	
Appendix E: Acknowledgements	
Appendix F: Future plans	65

# **Overview**

"What is time, then? If nobody asks me, I know; if I have to explain it to someone who has asked me, I do not know."

-- Augustine

### **How to Use This Documentation**

This documentation makes use of the following naming and formatting conventions.

- Code is in fixed width font and is syntax-highlighted.
- Replaceable text that you will need to supply is in italics .
- Free functions are rendered in the code font followed by (), as in free\_function().
- If a name refers to a class template, it is specified like this: class\_template<>; that is, it is in code font and its name is followed by <> to indicate that it is a class template.
- If a name refers to a function-like macro, it is specified like this: MACRO(); that is, it is uppercase in code font and its name is followed by () to indicate that it is a function-like macro. Object-like macros appear without the trailing ().



Names that refer to concepts in the generic programming sense are specified in CamelCase.



### **Note**

In addition, notes such as this one specify non-essential information that provides additional background or rationale.

Finally, you can mentally add the following to any code fragments in this document:

```
// Include all of Chrono files
#include <boost/chrono.hpp>
namespace bchrono=boost::chrono;
```

# **Motivation**

#### **Time**

We all deal with time every day of our lives. We've intuitively known it since birth. Thus we are all very familiar with it and believe it to be a simple matter. The modeling of time in computer programs should be similarly simple. The unfortunate truth is that this perceived simplicity is only skin deep. Fortunately however, we do not need a terribly complicated solution to meet the bulk of our needs. However, overly simplistic solutions can be dangerous and inefficient, and won't adapt as the computer industry evolves.

**Boost.Chrono** aims to implement the new time facilities in C++0x, as proposed in **N2661 - A Foundation to Sleep On**. That document provides background and motivation for key design decisions and is the source of a good deal of information in this documentation.

### Wall clock versus system and user time

To make the timing facilities of Boost.Chrono more generally useful, the library provides a number of clocks that are thin wrappers around the operating system's process time API, thereby allowing the extraction of wall clock time, user CPU time, and system CPU time of the process. Wall clock time is the sum of CPU time and system CPU time. (On POSIX-like systems, this relies on times(). On Windows, it relies on GetProcessTimes().)

# **Description**

The **Boost.Chrono** library provides:

#### **Standard**

- A means to represent time durations: managed by the generic duration class. Examples of time durations include days, minutes, seconds and nanoseconds, which can be represented with a fixed number of clock ticks per unit. All of these units of time duration are united with a generic interface by the duration facility.
- A type for representing points in time: time\_point. A time\_point represents an epoch plus or minus a duration. The library leaves epochs unspecified. A time\_point is associated with a *clock*.
- Several clocks, some of which may not be available on a particular platform: system\_clock, steady\_clock and high\_resolution\_clock. A clock is a pairing of a time\_point and duration, and a function which returns a time\_point representing now.

### Other clocks

To make the timing facilities more generally useful, **Boost.Chrono** provides a number of clocks that are thin wrappers around the operating system's time APIs, thereby allowing the extraction of wall clock time, user CPU time, system CPU time spent by the process,

process\_real\_cpu\_clock, captures wall clock CPU time spent by the current process.



- process\_user\_cpu\_clock, captures user-CPU time spent by the current process.
- process\_system\_cpu\_clock, captures system-CPU time spent by the current process.
- A tuple-like class process\_cpu\_clock, that captures real, user-CPU, and system-CPU process times together.
- A thread\_clock thread steady clock giving the time spent by the current threrad( when supported by a platform).

Lastly, **Boost.Chrono** includes typeof registration for duration and time\_point to permit using emulated auto with C++03 compilers.

#### 1/0

It provides I/O for duration and time\_point. It builds on <boost/ratio/ratio\_io.hpp> to provide readable and flexible formatting and parsing for types in <boost/chrono.hpp>. The duration unit names can be customized through a new facet: duration\_punct.

## **Caveat Emptor**

The underlying clocks provided by operating systems are subject to many seemingly arbitrary policies and implementation irregularities. That's a polite way of saying they tend to be flakey, and each operating system or even each clock has its own cruel and unusual forms of flakiness. Don't bet the farm on their accuracy, unless you have become deeply familiar with exactly what the specific operating system is guaranteeing, which is often very little.

# **User's Guide**

# **Getting Started**

# **Installing Chrono**

### **Getting Boost.Chrono**

**Boost.Chrono** is in the latest Boost release in the folder /boost/chrono. Documentation, tests and examples folder are at boost/libs/chrono/.

You can also access the latest (unstable?) state from the Boost trunk directories boost/chrono and libs*chrono. Just go to [@ht-tp:/*svn.boost.org/trac/boost/wiki/BoostSubversion here] and follow the instructions there for anonymous SVN access.

### Where to install Boost.Chrono?

The simple way is to decompress (or checkout from SVN) the files in your BOOST\_ROOT directory.

### **Building Boost.Chrono**

**Boost.Chrono** can be configured as a header only library. When BOOST\_CHRONO\_INLINED is defined the lib is header only library. Otherwise is not a header only library and you need to compile it before use.

bjam libs/chrono/build

#### Requirements

**Boost.Chrono** depends on some new traits in **Boost.TypeTraits** which have been added on Boost 1.45.

In particular, **Boost.Chrono** depends on:

**Boost.Config** for configuration purposes, ...



**Boost.Exception** for throw\_exception, ...

**Boost.Integer** for cstdint conformance, ...

**Boost.MPL** for MPL Assert and bool, logical ...

**Boost.Operators** for operators, ...

**Boost.Ratio** for ratio, milli, micro, ...

**Boost.System** for error\_code, ...

**Boost.TypeTraits** for is\_base, is\_convertible, common\_type, ...

**Boost.Utility/EnableIf** for enable\_if, ...

### **Building an Executable that Uses Boost.Chrono**

In addition to link with the **Boost.Chrono** library you need also to link with the **Boost.System** library. Once **Boost.System** will be configurable to be a header only using BOOST\_SYSTEM\_INLINED you will no need to link with.

#### **Exception safety**

All functions in the library are exception-neutral and provide strong guarantee of exception safety as long as the underlying parameters provide it.

### **Thread safety**

All functions in the library are thread-unsafe except when noted explicitly.

As Boost.Chrono doesn't use mutable global variables the thread safety analysis is limited to the access to each instance variable. It is not thread safe to use a function that modifies the access to a user variable if another can be reading or writing it.

### **Tested compilers**

The implementation will eventually work with most C++03 conforming compilers. Current version has been tested on:

Windows with

• MSVC 10.0

Cygwin 1.5 with

GCC 3.4.4

Cygwin 1.7 with

GCC 4.3.4

MinGW with

- GCC 4.4.0
- GCC 4.5.0
- GCC 4.5.0 -std=c++0x
- GCC 4.6.0
- GCC 4.6.0 std = c + +0x

Initial versions were tested on:



MacOS with GCC 4.2.4 (Some test are needed for the specific Mac files).

Ubuntu Linux with GCC 4.2.4



### **Note**

Please let us know how this works on other platforms/compilers.



### Note

Please send any questions, comments and bug reports to boost <at> lists <dot> boost <dot> org.

## **Hello World!**

If all you want to do is to time a program's execution, here is a complete program (stopclock\_example.cpp):

```
#include <boost/chrono.hpp>
#include <cmath>

int main()
{
    bchrono::system_clock::time_point start = bchrono::system_clock::now();

    for ( long i = 0; i < 10000000; ++i )
        std::sqrt( 123.456L ); // burn some time

    bchrono::duration<double> sec = bchrono::system_clock::now() - start;
        std::cout << "took " << sec.count() << " seconds\n";
        return 0;
}</pre>
```

Output was:

```
took 0.832 seconds
```

# **Tutorial**

## **Duration**

The duration is the heart of this library. The interface that the user will see in everyday use is nearly identical to that of **Boost.DateTime** time duration's authored by Jeff Garland, both in syntax and in behavior. This has been a very popular boost library for 7 years. There is an enormous positive history with this interface.

The library consists of six units of time duration:

- hours
- minutes
- seconds
- milliseconds
- microseconds



#### nanoseconds

These units were chosen as a subset of the boost library because they are the most common units used when sleeping, waiting on a condition variable, or waiting to obtain the lock on a mutex. Each of these units is nothing but a thin wrapper around a signed integral count. That is, when you construct minutes(3), all that happens is a 3 is stored inside of minutes. When you construct microseconds(3), all that happens is a 3 is stored inside of microseconds.

The only context in which these different types differ is when being converted to one another. At this time, unit-specific compile-time conversion constants are used to convert the source unit to the target unit. Only conversions from coarser units to finer units are allowed (in boost). This restriction ensures that all conversions are always exact. That is, microseconds can always represent any value minutes has.

In **Boost.DateTime**, these units are united via inheritance. **Boost.Chrono** instead unites these units through the class template duration. That is, in **Boost.Chrono** all six of the above units are nothing but typedefs to different instantiations of duration. This change from Boost.DateTime has a far reaching positive impact, while not changing the syntax of the everyday use at all.

The most immediate positive impact is that the library can immediately generate any unit, any precision it needs. This is sometimes necessary when doing comparisons or arithmetic between duration's of differing precision, assuming one wants the comparison and arithmetic to be exactly correct.

A secondary benefit is that by publishing the class template duration interface, user code can very easily create duration's with any precision they desire. The ratio utility is used to specify the precision, so as long as the precision can be expressed by a rational constant with respect to seconds, this framework can exactly represent it (one third of a second is no problem, and neither is one third of a femto second). All of this utility and flexibility comes at no cost just by making use of the no-run-time-overhead ratio facility.

In Boost.DateTime, hours does not have the same representation as nanoseconds. The former is usually represented with a long whereas a long long is required for the latter. The reason for this is simply range. You don't need many hours to cover an extremely large range of time. But this isn't true of nanoseconds. Being able to reduce the sizeof overhead for some units when possible, can be a significant performance advantage.

**Boost.Chrono** continues, and generalizes that philosophy. Not only can one specify the precision of a duration, one can also specify its representation. This can be any integral type, or even a floating point type. Or it can be a user-defined type which emulates an arithmetic type. The six predefined units all use signed integral types as their representation. And they all have a minimum range of +/- 292 years. nanoseconds needs 64 bits to cover that range. hours needs only 23 bits to cover that range.

### So What Exactly is a duration and How Do I Use One?

A duration has a representation and a tick period (precision).

```
template <class Rep, class Period = ratio<1> > class duration;
```

The representation is simply any arithmetic type, or an emulation of such a type. The representation stores a count of ticks. This count is the only data member stored in a duration. If the representation is floating point, it can store fractions of a tick to the precision of the representation. The tick period is represented by a ratio and is encoded into the duration's type, instead of stored. The tick period only has an impact on the behavior of the duration when a conversion between different duration's is attempted. The tick period is completely ignored when simply doing arithmetic among like duration's.

### **Example:**



In the final line of code above, there is an implicit conversion from minutes to microseconds, resulting in a relatively large number of microseconds.

If you need to access the tick count within a duration, there is a member count () which simply returns the stored tick count.

```
long long tc = us4.count(); // tc is 300000005
```

These duration's have very simple, very predictable, and very observable behavior. After all, this is really nothing but the time tested interface of Jeff's boost time duration library (unified with templates instead of inheritance).

## What Happens if I Assign m3 + us3 to minutes Instead of microseconds?

```
minutes m4 = m3 + us3;
```

It won't compile. The rationale is that implicit truncation error should not be allowed to happen. If this were to compile, then m4 would hold 5, the same value as m3. The value associated with us3 has been effectively ignored. This is similar to the problem of assigning a double to an int: the fractional part gets silently discarded.

#### But What if the Truncation Behavior is What I Want to Do?

There is a duration\_cast facility to explicitly ask for this behavior:

```
minutes m4 = bchrono::duration_cast<minutes>(m3 + us3); // m4.count() == 5
```

In general, one can perform duration arithmetic at will. If duration\_cast isn't used, and it compiles, the arithmetic is exact. Any place one wants to override this exact arithmetic behavior, duration\_cast can be used to explicitly specify that desire. The duration\_cast has the same efficiency as the implicit conversion, and will even be exact as often as it can.

You can use duration\_cast<> to convert the duration into whatever units you desire. This facility will round down (truncate) if an exact conversion is not possible. For example:



```
bchrono::nanoseconds start;
bchrono::nanoseconds end;
typedef bchrono::milliseconds ms;
ms d = bchrono::duration_cast<ms>(end - start);

// d now holds the number of milliseconds from start to end.
std::cout << ms.count() << "ms\n";</pre>
```

We can convert to nanoseconds, or some integral-based duration which nanoseconds will always exactly convert to, then duration\_cast<> is unnecessary:

```
typedef bchrono::nanoseconds ns;
ns d = end - start;
std::cout << ns.count() << "ns\n";</pre>
```

If you need seconds with a floating point representation you can also eliminate the duration\_cast<>:

```
typedef bchrono::duration<double> sec; // seconds, stored with a double
sec d = end - start;
std::cout << sec.count() << "s\n";</pre>
```

If you're not sure if you need duration\_cast<> or not, feel free to try it without. If the conversion is exact, or if the destination has a floating point representation, it will compile: else it will not compile.

If you need to use duration\_cast<>, but want to round up, instead of down when the conversion is inexact, here is a handy little helper function to do so. Writing it is actually a good starter project for understanding **Boost.Chrono**:

# **Trafficking in Floating Point Durations**

I don't want to deal with writing duration\_cast all over the place. I'm content with the precision of my floating point representation

Not a problem. When the destination of a conversion has floating point representation, all conversions are allowed to happen implicitly.



```
typedef bchrono::duration<double, ratio<60> > dminutes;
dminutes dm4 = m3 + us3; // dm4.count() == 5.000000083333333
```

## How Expensive is All of this?

If you were writing these conversions by hand, you could not make it more efficient. The use of ratio ensures that all conversion constants are simplified as much as possible at compile time. This usually results in the numerator or denominator of the conversion factor simplifying to 1, and being subsequently ignored in converting the run time values of the tick counts.

### How Complicated is it to Build a Function Taking a duration Parameter?

There are several options open to the user:

• If the author of the function wants to accept any duration, and is willing to work in floating point duration's, he can simply use any floating point duration as the parameter:

```
void f(bchrono::duration<double> d) // accept floating point seconds
{
    // d.count() == 3.e-6 when passed bchrono::microseconds(3)
}
f(bchrono::microseconds(3));
```

• If the author of the function wants to traffic only in integral duration's, and is content with handling nothing finer than say nanoseconds (just as an example), he can simply specify nanoseconds as the parameter:

```
void f(bchrono::nanoseconds d)
{
    // d.count() == 3000 when passed bchrono::microseconds(3)
}
f(bchrono::microseconds(3));
```

In this design, if the client wants to pass in a floating point duration, or a duration of finer precision than nanoseconds, then the client is responsible for choosing his own rounding mode in the conversion to nanoseconds.

```
bchrono::duration<double> s(1./3); // 1/3 of a second f(bchrono::duration_cast<bchrono::nanoseconds>(s)); // round towards zero in conversion to nanoJ seconds
```

In the example above, the client of f has chosen "round towards zero" as the desired rounding mode to nanoseconds. If the client has a duration that won't exactly convert to nanoseconds, and fails to choose how the conversion will take place, the compiler will refuse the call:

```
f(s); // does not compile
```

• If the author of the function wants to accept any duration, but wants to work with integral representations and wants to control the rounding mode internally, then he can template the function:



```
template <class Rep, class Period>
void f(bchrono::duration<Rep, Period> d)
{
    // convert d to nanoseconds, rounding up if it is not an exact conversion
    bchrono::nanoseconds ns = bchrono::duration_cast<bchrono::nanoseconds>(d);
    if (ns < d)
        ++ns;
    // ns.count() == 333333334 when passed 1/3 of a floating point second
}
f(bchrono::duration<double>(1./3));
```

• If the author in the example does not want to accept floating point based duration's, he can enforce that behavior like so:

```
template <class Period>
void f(bchrono::duration<long long, Period> d)
{
    // convert d to nanoseconds, rounding up if it is not an exact conversion
    bchrono::nanoseconds ns = bchrono::duration_cast<nanoseconds>(d);
    if (ns < d)
        ++ns;
    // ns.count() == 333333334 when passed 333333333333 picoseconds
}
// About 1/3 of a second worth of picoseconds
f(bchrono::duration<long long, boost::pico>(333333333333));
```

Clients with floating point duration's who want to use f will now have to convert to an integral duration themselves before passing the result to f.

In summary, the author of f has quite a bit of flexibility and control in the interface he wants to provide his clients with, and easy options for manipulating that duration internal to his function.

### **Can Durations Overflow?**

This depend on the representation. The default typedefs uses a representation that don't handle overflows. The user can define his own representation that manage overflow as required by its application.

### **Clocks**

While duration's only have precision and representation to concern themselves, clocks and time\_point's are intimately related and refer to one another. Because clocks are simpler to explain, we will do so first without fully explaining time\_point's. Once clocks are introduced, it will be easier to then fill in what a time\_point is.

A clock is a concept which bundles 3 things:

- 1. A concrete duration type.
- 2. A concrete time\_point type.
- 3. A function called now() which returns the concrete time\_point.

The standard defines tree system-wide clocks that are associated to the computer time.

- system\_clock represents system-wide realtime clock that can be synchronized with an external clock.
- steady\_clock can not be changed explicitly and the time since the initial epoch increase in a steady way.
- high\_resolution\_clock intend to use the system-wide clock provided by the platform with the higest resolution.



**Boost.**Chrono provides them when supported by the underlying platform. A given platform may not be able to supply all three of these clocks.

The library adds some clocks that are specific to a process or a thread, that is there is a clock per process or per thread.

The user is also able to easily create more clocks.

Given a clock named Clock, it will have:

One can get the current time from Clock with:

```
Clock::time_point t1 = Clock::now();
```

And one can get the time duration between two time\_point's associated with Clock with:

```
Clock::duration d = Clock::now() - t1;
```

And one can specify a past or future time\_point with:

```
Clock::time_point t2 = Clock::now() + d;
```

Note how even if a particular clock becomes obsolete, the next clock in line will have the same API. There is no new learning curve to come up. The only source code changes will be simply changing the type of the clock. The same duration and time\_point framework continues to work as new clocks are introduced. And multiple clocks are safely and easily handled within the same program.

### **Time Point**

A time\_point represents a point in time, as opposed to a duration of time. Another way of saying the same thing, is that a time\_point represents an epoch plus or minus a duration. Examples of time\_point's include:

- 3 minutes after the computer booted.
- 03:14:07 UTC on Tuesday, January 19, 2038
- 20 milliseconds after I started that timer.

In each of the examples above, a different epoch is implied. Sometimes an epoch has meaning for several millennia. Other times the meaning of an epoch is lost after a while (such as the start of a timer, or when the computer booted). However, if two time\_point's are known to share the same epoch, they can be subtracted, yielding a valid duration, even if the definition of the epoch no longer has meaning.

In **Boost.Chrono**, an epoch is a purely abstract and unspecified concept. There is no type representing an epoch. It is simply an idea that relates (or doesn't) time\_point's to a clock, and in the case that they share a clock, time\_point's to one another. time\_point's



associated with different clocks are generally not interoperable unless the relationship between the epochs associated with each clock is known.

### So What Exactly is a time\_point and How Do I Use One?

A time\_point has a clock and a duration.

```
template <class Clock, class Duration = typename Clock::duration> class time_point;
```

The time\_point's clock is not stored. It is simply embedded into the time\_point's type and serves two purposes:

- 1. Because time\_point's originating from different clocks have different types, the compiler can be instructed to fail if incompatible time\_point's are used in inappropriate ways.
- 2. Given a time\_point, one often needs to compare that time\_point to "now". This is very simple as long as the time\_point knows what clock it is defined with respect to.

A time\_point's duration is stored as the only data member of the time\_point. Thus time\_point's and their corresponding duration have exactly the same layout. But they have very different meanings. For example, it is one thing to say I want to sleep for 3 minutes. It is a completely different thing to say I want to sleep until 3 minutes past the time I started that timer (unless you just happened to start that timer now). Both meanings (and options for sleeping) have great practical value in common use cases for sleeping, waiting on a condition variable, and waiting for a mutex's lock. These same concepts and tools are found (for example) in Ada.

A timer example:

```
void f()
{
    bchrono::steady_clock::time_point start = bchrono::steady_clock::now();
    g();
    h();
    duration<double> sec = bchrono::steady_clock::now() - start;
    cout << "f() took " << sec.count() << " seconds\n";
}</pre>
```

Note that if one is using the duration between two clock time\_point's in a way where the precision of the duration matters, it is good practice to convert the clock's duration to a known duration. This insulates the code from future changes which may be made to the clock's precision in the future. For example steady\_clock could easily be based on the clock speed of the cpu. When you upgrade to a faster machine, you do not want your code that assumed a certain tick period of this clock to start experiencing run time failures because your timing code has silently changed meaning.

A delay loop example:

```
// delay for at least 500 nanoseconds:
auto go = bchrono::steady_clock::now() + bchrono::nanoseconds(500);
while (bchrono::steady_clock::now() < go)
;</pre>
```

The above code will delay as close as possible to half a microsecond, no matter what the precision of steady\_clock is. The more precise steady\_clock becomes, the more accurate will be the delay to 500 nanoseconds.



# **Specific Clocks**

## system\_clock

system\_clock is useful when you need to correlate the time with a known epoch so you can convert it to a calendar time. Note the specific functions in the system\_clock class.

### steady\_clock

steady\_clock is useful when you need to wait for a specific amount of time. steady\_clock time can not be reset. As other steady clocks, it is usually based on the processor tick.

Next is presented a polling solution, which will however be too inefficient:

```
bchrono::steady_clock::time_point start= chrono::steady_clock::now();
bchrono::steady_clock::duration delay= chrono::seconds(5);
while (bchrono::steady_clock::now() - start <= delay) {}</pre>
```

### high\_resolution\_clock

When available, high\_resolution\_clock is usualy more expensive than the other system-wide clocks, so they are used only when the provided resolution is required to the application.

## process\_cpu\_clock

Process and thread clocks are used usualy to measure the time spent by code blocks, as a basic time-spent profiling of different blocks of code (Boost.Stopwatch is clear example of this use).

## thread\_clock

You can use thread\_clock whenever you want to measure the time spent by the current thread. For example:

```
bchrono::thread_clock::time_point start=bchrono::thread_clock::now();
//do something

typedef bchrono::milliseconds ms;
ms d = bchrono::thread_clock::now() - start;
// d now holds the number of milliseconds from start to end.
std::cout << ms.count() << "ms\n";</pre>
```

If you need seconds with a floating point representation you can do:

```
typedef bchrono::duration<double> sec; // seconds, stored with a double
sec d = end - start;
std::cout << sec.count() << "s\n";</pre>
```

If you would like to programmatically inspect thread\_clock::duration, you can get the representation type with thread\_clock::rep, and the tick period with thread\_clock::period (which should be a type ratio which has nested values ratio::num and ratio::den). The tick period of thread\_clock is thread\_clock::period::num / thread\_clock::period::den seconds: 1/10000000000 in this case (1 billionth of a second), stored in a long long.



## 1/0

Any duration can be streamed out to a basic\_ostream. The run time value of the duration is formatted according to the rules and current format settings for duration::rep. This is followed by a single space and then the compile time unit name of the duration. This unit name is built on the string returned from ratio\_string<> and the data used to construct the duration\_punct which was inserted into the stream's locale. If a duration\_punct has not been inserted into the stream's locale, a default constructed duration\_punct will be added to the stream's locale.

duration unit names come in two varieties: long and short. The default constructed duration\_punct provides names in the long format. These names are English descriptions. Other languages are supported by constructing a duration\_punct with the proper spellings for "hours", "minutes" and "seconds", and their abbreviations (for the short format). The short or long format can be easily chosen by streaming a duration\_short() or duration\_long() manipulator respectively.

A time\_point is formatted by outputting its internal duration followed by a string that describes the time\_point::clock epoch. This string will vary for each distinct clock, and for each implementation of the supplied clocks.

#### **Example:**



```
#include <iostream>
#include <boost/chrono/chrono_io.hpp>
int main()
   using namespace std;
   using namespace boost;
   namespace bchrono=boost::chrono;
   cout << "milliseconds(3) + microseconds(10) = "</pre>
         << bchrono::milliseconds(3) + bchrono::microseconds(10) << '\n';
    cout << "hours(3) + minutes(10) = "</pre>
        << bchrono::hours(3) + bchrono::minutes(10) << '\n';</pre>
    typedef bchrono::duration<long long, boost::ratio<1, 2500000000> > ClockTick;
    cout << "ClockTick(3) + bchrono::nanoseconds(10) = '</pre>
         << ClockTick(3) + bchrono::nanoseconds(10) << '\n';</pre>
    cout << "\nSet cout to use short names:\n";</pre>
    cout << bchrono::duration_short;</pre>
    cout << "milliseconds(3) + microseconds(10) = "</pre>
         << bchrono::milliseconds(3) + bchrono::microseconds(10) << '\n';</pre>
    cout << "hours(3) + minutes(10) = "</pre>
         << bchrono::hours(3) + bchrono::minutes(10) << '\n';
    cout << "ClockTick(3) + nanoseconds(10) = "</pre>
         << ClockTick(3) + bchrono::nanoseconds(10) << '\n';</pre>
    cout << "\nsystem_clock::now() = " << bchrono::system_clock::now() << '\n';</pre>
#ifdef BOOST_CHRONO_HAS_CLOCK_STEADY
   #endif
   cout << "\nSet cout to use long names:\n"</pre>
            << bchrono::duration_long
            << "high_resolution_clock::now() = "</pre>
            << bchrono::high_resolution_clock::now() << '\n';
    return 0;
}
```

The output could be



```
milliseconds(3) + microseconds(10) = 3010 microseconds
hours(3) + minutes(10) = 190 minutes
ClockTick(3) + nanoseconds(10) = 56 [1/5000000000]seconds

Set cout to use short names:
milliseconds(3) + microseconds(10) = 3010 ##s
hours(3) + minutes(10) = 190 m
ClockTick(3) + nanoseconds(10) = 56 [1/5000000000]s

system_clock::now() = 129387415616250000 [1/10000000]s since Jan 1, 1970
monotonic_clock::now() = 37297387636417 ns since boot

Set cout to use long names:
high_resolution_clock::now() = 37297387655134 nanoseconds since boot
```

Parsing a duration follows rules analogous to the duration converting constructor. A value and a unit (short or long) are read from the basic\_istream. If the duration has an integral representation, then the value parsed must be exactly representable in the target duration (after conversion to the target duration units), else failbit is set. duration's based on floating point representations can be parsed using any units that do not cause overflow.

For example a stream containing "5000 milliseconds" can be parsed into seconds, but if the stream contains "5001 milliseconds", parsing into seconds will cause failbit to be set.

#### **Example:**

```
#include <boost/chrono/chrono_io.hpp>
#include <sstream>
#include <cassert>
int main()
    using namespace std;
    namespace bchrono=boost::chrono;
    istringstream in("5000 milliseconds 4000 ms 3001 ms");
    bchrono::seconds d(0);
    in >> d;
    assert(in.good());
    assert(d == seconds(5));
    in >> d;
    assert(in.good());
    assert(d == seconds(4));
    in >> d;
    assert(in.fail());
    assert(d == seconds(4));
    return 0;
```

Note that a duration failure may occur late in the parsing process. This means that the characters making up the failed parse in the stream are usually consumed despite the failure to successfully parse.

Parsing a time\_point involves first parsing a duration and then parsing the epoch string. If the epoch string does not match that associated with time\_point::clock then failbit will be set.

#### **Example:**



```
#include <boost/chrono/chrono_io.hpp>
#include <sstream>
#include <iostream>
#include <cassert>
int main()
   using namespace std;
   namespace bchrono=boost::chrono;
   bchrono::high_resolution_clock::time_point t0 = bchrono::high_resolution_clock::now();
    stringstream io;
    io << t0;
   bchrono::high_resolution_clock::time_point t1;
   io >> t1;
   assert(!io.fail());
    cout << io.str() << '\n';
    cout << t0 << '\n';
    cout << t1 << '\n';
   bchrono::high_resolution_clock::time_point t = bchrono::high_resolution_clock::now();
    cout << t << ' n';
    cout << "That took " << t - t0 << '\n';
    cout << "That took " << t - t1 << '\n';
    return 0;
```

The output could be:

```
50908679121461 nanoseconds since boot
That took 649630 nanoseconds
```

Here's a simple example to find out how many hours the computer has been up (on this platform):

```
#include <boost/chrono/chrono_io.hpp>
#include <iostream>
int main()
{
    using namespace std;
    using namespace boost;
    namespace bchrono=boost::chrono;

    typedef bchrono::time_point<bchrono::steady_clock, bchrono::duration<double, boost::ra」
tio<3600> >> T;
    T tp = bchrono::steady_clock::now();
    std::cout << tp << '\n';
    return 0;
}</pre>
```

The output could be:



```
17.8666 hours since boot
```

# **Examples**

### **Duration**

## **How you Override the Duration's Default Constructor**

Next follows how you override the duration's default constructor to do anything you want (in this case set it to zero). All we need to do is to change the representation

```
namespace I_dont_like_the_default_duration_behavior {
template <class R>
class zero_default
public:
    typedef R rep;
private:
   rep rep_;
public:
   zero_default(rep i = 0) : rep_(i) {}
    operator rep() const {return rep_;}
   zero_default& operator+=(zero_default x) {rep_ += x.rep_; return *this;}
    zero_default& operator-=(zero_default x) {rep_ -= x.rep_; return *this;}
    zero_default& operator*=(zero_default x) {rep_ *= x.rep_; return *this;
    zero_default& operator/=(zero_default x) {rep_ /= x.rep_; return *this;}
    zero_default operator+ () const {return *this;}
    zero_default operator- () const {return zero_default(-rep_);}
                                     {++rep_; return *this;}
    zero_default& operator++()
    zero_default operator++(int)
                                    {return zero_default(rep_++);}
    zero_default& operator--()
                                    {--rep_; return *this;}
    zero_default operator--(int)
                                    {return zero_default(rep_--);}
    friend zero_default operator+(zero_default x, zero_default y) {return x += y;}
    friend zero_default operator-(zero_default x, zero_default y) {return x -= y;}
    friend zero_default operator*(zero_default x, zero_default y) {return x *= y;}
    friend zero_default operator/(zero_default x, zero_default y) {return x /= y;}
    friend bool operator==(zero_default x, zero_default y) {return x.rep_ == y.rep_;}
    friend bool operator!=(zero_default x, zero_default y) {return !(x == y);}
    friend bool operator< (zero_default x, zero_default y) {return x.rep_ < y.rep_;}</pre>
    friend bool operator<=(zero_default x, zero_default y) {return !(y < x);}</pre>
    friend bool operator> (zero_default x, zero_default y) {return y < x;}</pre>
    friend bool operator>=(zero_default x, zero_default y) {return !(x < y);}</pre>
};
typedef bchrono::duration<zero_default<long long>, boost::nano
                                                                     > nanoseconds;
```



Usage

```
using namespace I_dont_like_the_default_duration_behavior;
milliseconds ms;
std::cout << ms.count() << '\n';</pre>
```

See the source file example/i\_dont\_like\_the\_default\_duration\_behavior.cpp

## **Saturating**

A "saturating" signed integral type is developed. This type has +/- infinity and a nan (like IEEE floating point) but otherwise obeys signed integral arithmetic. This class is subsequently used as the rep in bchrono::duration to demonstrate a duration class that does not silently ignore overflow.

See the source file example/saturating.cpp

### **xtime Conversions**

Example round\_up utility: converts d to To, rounding up for inexact conversions Being able to **easily** write this function is a major feature!

Demonstrate interaction with xtime-like facility:



```
struct xtime
    long sec;
   unsigned long usec;
};
template <class Rep, class Period>
xtime
to_xtime_truncate(bchrono::duration<Rep, Period> d)
   xtime xt;
   xt.sec = static_cast<long>(bchrono::duration_cast<seconds>(d).count());
   xt.usec = static_cast<long>(bchrono::duration_cast<microseconds>(d - seconds(xt.sec)).count());
   return xt;
template <class Rep, class Period>
to_xtime_round_up(bchrono::duration<Rep, Period> d)
   xtime xt;
   xt.sec = static_cast<long>(bchrono::duration_cast<seconds>(d).count());
   xt.usec = static_cast<unsigned long>(round_up<bchrono::microJ
seconds>(d - bchrono::seconds(xt.sec)).count());
microseconds
from xtime(xtime xt)
    return bchrono::seconds(xt.sec) + bchrono::microseconds(xt.usec);
void print(xtime xt)
{
    std::cout << '{' << xt.sec << ',' << xt.usec << "}\n";
```

#### Usage

```
xtime xt = to_xtime_truncate(seconds(3) + bchrono::milliseconds(251));
print(xt);
bchrono::milliseconds ms = bchrono::duration_cast<bchrono::milliseconds>(from_xtime(xt));
std::cout << ms.count() << " milliseconds\n";
xt = to_xtime_round_up(ms);
print(xt);
xt = to_xtime_truncate(bchrono::seconds(3) + nanoseconds(999));
print(xt);
xt = to_xtime_round_up(bchrono::seconds(3) + nanoseconds(999));
print(xt);</pre>
```

See the source file here

### **Clocks**

# **Cycle count**

Users can easily create their own clocks, with both points in time and time durations which have a representation and precision of their own choosing. For example if there is a hardware counter which simply increments a count with each cycle of the cpu, one can



very easily build clocks, time points and durations on top of that, using only a few tens of lines of code. Such systems can be used to call the time-sensitive threading API's such as sleep, wait on a condition variable, or wait for a mutex lock. The API proposed herein is not sensitive as to whether this is a 300MHz clock (with a 3 1/3 nanosecond tick period) or a 3GHz clock (with a tick period of 1/3 of a nanosecond). And the resulting code will be just as efficient as if the user wrote a special purpose clock cycle counter.

```
#include <boost/chrono.hpp>
#include <boost/type_traits.hpp>
#include <iostream>
namespace bchrono=boost::chrono;
template <long long speed>
struct cycle_count
    typedef typename boost::__ratio_multiply__<boost::ratio<speed>, boost::mega>::type
        frequency; // Mhz
    typedef typename boost::__ratio_divide__<boost::ratio<1>, frequency>::type period;
    typedef long long rep;
    typedef bchrono::duration<rep, period> duration;
    typedef bchrono::time_point<cycle_count> time_point;
    static time_point now()
        static long long tick = 0;
        // return exact cycle count
        return time_point(duration(++tick)); // fake access to clock cycle count
};
template <long long speed>
struct approx_cycle_count
    static const long long frequency = speed * 1000000; // MHz
    typedef nanoseconds duration;
    typedef duration::rep rep;
    typedef duration::period period;
    static const long long nanosec_per_sec = period::den;
    typedef bchrono::time_point<approx_cycle_count> time_point;
    static time_point now()
        static long long tick = 0;
        // return cycle count as an approximate number of nanoseconds
        // compute as if nanoseconds is only duration in the std::lib
        return time_point(duration(++tick * nanosec_per_sec / frequency));
};
```

See the source file here

### xtime\_clock

This example demonstrates the use of a timeval-like struct to be used as the representation type for both <u>duraiton</u> and <u>time\_point</u>.



```
class xtime {
private:
   long tv_sec;
   long tv_usec;
   void fixup() {
        if (tv_usec < 0) {</pre>
           tv_usec += 1000000;
            --tv_sec;
public:
    explicit xtime(long sec, long usec) {
        tv_sec = sec;
        tv_usec = usec;
        if (tv_usec < 0 || tv_usec >= 1000000) {
           tv_sec += tv_usec / 1000000;
            tv_usec %= 1000000;
           fixup();
    explicit xtime(long long usec) {
        tv_usec = static_cast<long>(usec % 1000000);
        tv_sec = static_cast<long>(usec / 1000000);
        fixup();
    // explicit
    operator long long() const {return static_cast<long long>(tv_sec) * 1000000 + tv_usec;}
    xtime& operator += (xtime rhs) {
       tv_sec += rhs.tv_sec;
        tv_usec += rhs.tv_usec;
        if (tv_usec >= 1000000) {
           tv_usec -= 1000000;
            ++tv_sec;
        return *this;
   xtime& operator -= (xtime rhs) {
        tv_sec -= rhs.tv_sec;
        tv_usec -= rhs.tv_usec;
        fixup();
       return *this;
    xtime& operator %= (xtime rhs) {
        long long t = tv_sec * 1000000 + tv_usec;
        long long r = rhs.tv_sec * 1000000 + rhs.tv_usec;
        t %= r;
        tv_sec = static_cast<long>(t / 1000000);
        tv_usec = static_cast<long>(t % 1000000);
        fixup();
        return *this;
    friend xtime operator+(xtime x, xtime y) {return x += y;}
    friend xtime operator-(xtime x, xtime y) {return x -= y;}
    friend xtime operator%(xtime x, xtime y) {return x %= y;}
```



```
friend bool operator==(xtime x, xtime y)
    { return (x.tv_sec == y.tv_sec && x.tv_usec == y.tv_usec); }

friend bool operator<(xtime x, xtime y) {
    if (x.tv_sec == y.tv_sec)
        return (x.tv_usec < y.tv_usec);
    return (x.tv_sec < y.tv_sec);
}

friend bool operator!=(xtime x, xtime y) { return !(x == y); }

friend bool operator> (xtime x, xtime y) { return y < x; }

friend bool operator<=(xtime x, xtime y) { return !(y < x); }

friend bool operator>=(xtime x, xtime y) { return !(x < y); }

friend std::ostream& operator<<(std::ostream& os, xtime x)
    {return os << '{' < x.tv_sec << ',' << x.tv_usec << '}'; }
};</pre>
```

Clock based on timeval-like struct.

```
class xtime_clock
public:
    typedef xtime
                                                    rep;
    typedef boost::micro
                                                    period;
    typedef bchrono::duration<rep, period>
                                              duration;
    typedef bchrono::time_point<xtime_clock> time_point;
    static time_point now()
    #if defined(BOOST_CHRONO_WINDOWS_API)
        time_point t(duration(xtime(0)));
        gettimeofday((timeval*)&t, 0);
        return t;
    #elif defined(BOOST_CHRONO_MAC_API)
        time_point t(duration(xtime(0)));
        gettimeofday((timeval*)&t, 0);
        return t;
    #elif defined(BOOST_CHRONO_POSIX_API)
        //time_point t(0,0);
        timespec ts;
        ::clock_gettime( CLOCK_REALTIME, &ts );
        xtime xt( ts.tv_sec, ts.tv_nsec/1000);
        return time_point(duration(xt));
    #endif // POSIX
};
```

Usage of xtime\_clock



```
std::cout << "sizeof xtime_clock::time_point = " << sizeof(xtime_clock::time_point) << '\n';
std::cout << "sizeof xtime_clock::duration = " << sizeof(xtime_clock::duration) << '\n';
std::cout << "sizeof xtime_clock::rep = " << sizeof(xtime_clock::rep) << '\n';
xtime_clock::duration delay(bchrono::milliseconds(5));
xtime_clock::time_point start = xtime_clock::now();
while (xtime_clock::now() - start <= delay) {}
xtime_clock::time_point stop = xtime_clock::now();
xtime_clock::time_point stop = xtime_clock::now();
xtime_clock::duration elapsed = stop - start;
std::cout << "paused " << bchrono::::nanoseconds(elapsed).count() << " nanoseconds\n";</pre>
```

See the source file example/timeval\_demo.cpp

## **Time Point**

## min Utility

The user can define a function returning the earliest time\_point as follows:

Being able to easily write this function is a major feature!

```
BOOST_AUTO(t1, system_clock::now() + seconds(3));
BOOST_AUTO(t2, system_clock::now() + nanoseconds(3));
BOOST_AUTO(t3, min(t1, t2));
```

See the source file example/min\_time\_point.cpp



## A Tiny Program that Times How Long Until a Key is Struck

```
#include <boost/chrono.hpp>
#include <iostream>
#include <iomanip>
using namespace boost::chrono;
template< class Clock >
class timer
 typename Clock::time_point start;
public:
 timer() : start( Clock::now() ) {}
 typename Clock::duration elapsed() const
   return Clock::now() - start;
 double seconds() const
    return elapsed().count() * ((double)Clock::period::num/Clock::period::den);
};
int main()
  timer<system_clock> t1;
  timer<steady_clock> t2;
 timer<high_resolution_clock> t3;
 std::cout << "Type the Enter key: ";</pre>
 std::cin.get();
 std::cout << std::fixed << std::setprecision(9);</pre>
 std::cout << "system_clock-----: "</pre>
           << t1.seconds() << " seconds\n";
  std::cout << "steady_clock----: "</pre>
           << t2.seconds() << " seconds\n";
 std::cout << "high_resolution_clock--: "</pre>
           << t3.seconds() << " seconds\n";
 system_clock::time_point d4 = system_clock::now();
 system_clock::time_point d5 = system_clock::now();
 std::cout << "\nsystem_clock latency----- " << (d5 - d4).count() << std::endl;</pre>
 steady_clock::time_point d6 = steady_clock::now();
 steady_clock::time_point d7 = steady_clock::now();
 std::cout << "steady_clock latency-----: " << (d7 - d6).count() << std::endl;
 high_resolution_clock::time_point d8 = high_resolution_clock::now();
 high_resolution_clock::time_point d9 = high_resolution_clock::now();
 std::cout << "high_resolution_clock latency--: " << (d9 - d8).count() << std::endl;
 std::time_t now = system_clock::to_time_t(system_clock::now());
```



The output of this program run looks like this:

See the source file example/await\_keystroke.cpp

## 24 Hours Display

In the example above we take advantage of the fact that time\_point's convert as long as they have the same clock, and as long as their internal duration's convert. We also take advantage of the fact that a duration with a floating point representation will convert from anything. Finally the I/O system discovers the more readable "hours" unit for our duration<double, ratio<3600>>.

There are many other ways to format durations and time\_points. For example see ISO 8601. Instead of coding every possibility into operator<<, which would lead to significant code bloat for even the most trivial uses, this document seeks to inform the reader how to write custom I/O when desired.

As an example, the function below streams arbitrary durations to arbitrary basic\_ostreams using the format:

```
[-]d/hh:mm:ss.cc
```

#### Where:

- d is the number of days
- h is the number of hours
- m is the number of minutes
- ss.cc is the number of seconds rounded to the nearest hundreth of a second
  - 1. include <boost/chrono/chrono\_io.hpp>
  - 2. include <ostream>
  - 3. include <iostream>



```
// format duration as [-]d/hh::mm::ss.cc
template <class CharT, class Traits, class Rep, class Period>
std::basic_ostream<CharT, Traits>&
display(std::basic_ostream<CharT, Traits>& os,
       bchrono::duration<Rep, Period> d)
    using namespace std;
    using namespace boost;
    namespace bchrono=boost::chrono;
    typedef bchrono::duration<long long, boost::ratio<86400> > days;
    typedef bchrono::duration<long long, boost:centi> centiseconds;
    // if negative, print negative sign and negate
    if (d < bchrono::duration<Rep, Period>(0))
        d = -di
        os << '-';
    // round d to nearest centiseconds, to even on tie
    centiseconds cs = bchrono::duration_cast<centiseconds>(d);
    if (d - cs > bchrono::milliseconds(5)
        | | (d - cs == bchrono::milliseconds(5) && cs.count() & 1))
        ++cs;
    // separate seconds from centiseconds
    bchrono::seconds s = bchrono::duration_cast<br/>bchrono::seconds>(cs);
    // separate minutes from seconds
    bchrono::minutes m = bchrono::duration_cast<bchrono::minutes>(s);
    // separate hours from minutes
    bchrono::hours h = bchrono::duration_cast<bchrono::hours>(m);
    m -= h;
    // separate days from hours
    days dy = bchrono::duration_cast<days>(h);
    h -= dy;
    // print d/hh:mm:ss.cc
    os << dy.count() << '/';
    if (h < bchrono::hours(10))</pre>
        os << '0';
    os << h.count() << ':';
    if (m < bchrono::minutes(10))</pre>
       os << '0';
    os << m.count() << ':';
    if (s < bchrono::seconds(10))</pre>
       os << '0';
    os << s.count() << '.';
    if (cs < bchrono::centiseconds(10))</pre>
       os << '0';
    os << cs.count();
    return os;
int main()
    using namespace std;
    using namespace boost;
    namespace bchrono=boost::chrono;
```



The output could be:

```
12/06:03:22.95
-0/00:00:00.01
11/13:46:40.00
-11/13:46:40.00
```

### **Simulated Thread Interface Demonstration Program**

The C++0x standard library's multi-threading library requires the ability to deal with the representation of time in a manner consistent with modern C++ practices. Next follows a simulation of this interface.

The non-member sleep functions can be emulated as follows:

```
namespace boost { namespace this_thread {
template <class Rep, class Period>
void sleep for(const chrono::duration<Rep, Period>& d) {
    chrono::microseconds t = chrono::duration_cast<chrono::microseconds>(d);
    if (t < d)
        ++t;
    if (t > chrono::microseconds(0))
        std::cout << "sleep_for " << t.count() << " microseconds\n";</pre>
template <class Clock, class Duration>
void sleep_until(const chrono::time_point<Clock, Duration>& t) {
    using namespace chrono;
    typedef time_point<Clock, Duration> Time;
    typedef system_clock::time_point SysTime;
    if (t > Clock::now()) {
        typedef typename common_type<typename Time::duration,
                                      typename SysTime::duration>::type D;
        /* auto */ D d = t - Clock::now();
        microseconds us = duration_cast<microseconds>(d);
        if (us < d)
            ++us;
        SysTime st = system_clock::now() + us;
        std::cout << "sleep_until</pre>
        detail::print_time(st);
       std::cout << " which is " << (st - system_clock::now()).count() << " microseconds away\n";
}
} }
```

Next follows the boost::thread::timed\_mutex modified fuctions



```
namespace boost {
struct timed_mutex {
    // ...
    template <class Rep, class Period>
    bool try_lock_for(const chrono::duration<Rep, Period>& d) {
        chrono::microseconds t = chrono::duration_cast<chrono::microseconds>(d);
        if (t <= chrono::microseconds(0))</pre>
            return try_lock();
        std::cout << "try_lock_for " << t.count() << " microseconds\n";</pre>
        return true;
    template <class Clock, class Duration>
    bool try_lock_until(const chrono::time_point<Clock, Duration>& t)
        using namespace chrono;
        typedef time_point<Clock, Duration> Time;
        typedef system_clock::time_point SysTime;
        if (t <= Clock::now())</pre>
            return try_lock();
        {\tt typedef \ typename \ common\_type$<$typename \ Time$::duration,}
          typename Clock::duration>::type D;
        /* auto */ D d = t - Clock::now();
        microseconds us = duration_cast<microseconds>(d);
        SysTime st = system_clock::now() + us;
        std::cout << "try_lock_until ";</pre>
        detail::print_time(st);
        std::cout << " which is " << (st - system_clock::now()).count()</pre>
          << " microseconds away\n";
        return true;
};
```

 $\verb|boost::thread::condition_variable| time| related| function| are| modified| as| follows:$ 



```
namespace boost {
struct condition_variable
    // ...
    template <class Rep, class Period>
    bool wait_for(mutex&, const chrono::duration<Rep, Period>& d) {
        chrono::microseconds t = chrono::duration_cast<chrono::microseconds>(d);
        std::cout << "wait_for " << t.count() << " microseconds\n";</pre>
        return true;
    template <class Clock, class Duration>
    bool wait_until(mutex&, const chrono::time_point<Clock, Duration>& t) {
        using namespace boost::chrono;
        typedef time_point<Clock, Duration> Time;
        typedef system_clock::time_point SysTime;
        if (t <= Clock::now())</pre>
            return false;
        typedef typename common_type<typename Time::duration,
          typename Clock::duration>::type D;
        /* auto */ D d = t - Clock::now();
        microseconds us = duration_cast<microseconds>(d);
        SysTime st = system_clock::now() + us;
         std::cout << "wait_until</pre>
        detail::print_time(st);
        std::cout << " which is " << (st - system_clock::now()).count()</pre>
          << " microseconds away\n";
        return true;
};
```

Next follows how simple is the usage of this functions:

```
boost::mutex m;
boost::timed_mutex mut;
boost::condition_variable cv;
using namespace boost;
this_thread::sleep_for(chrono::seconds(3));
this_thread::sleep_for(chrono::nanoseconds(300));
chrono::system_clock::time_point time_limit = chrono::sys-
tem_clock::now() + chrono::__seconds_(4) + chrono::milliseconds(500);
this_thread::sleep_until(time_limit);
mut.try_lock_for(chrono::milliseconds(30));
mut.try_lock_until(time_limit);
cv.wait_for(m, chrono::minutes(1)); // real code would put this in a loop
cv.wait_until(m, time_limit); // real code would put this in a loop
// For those who prefer floating point
this_thread::sleep_for(chrono::duration<double>(0.25));
this_thread::sleep_until(chrono::system_clock::now() + chrono::duration<double>(1.5));
```

See the source file example/simulated\_thread\_interface\_demo.cpp



### 10

#### Example use of output in French

```
#include <boost/chrono/chrono_io.hpp>
#include <iostream>
#include <locale>
int main()
    using namespace std;
    using namespace boost;
    using namespace boost::chrono;
    cout.imbue(locale(locale(), new duration_punct<char>
            duration_punct<char>::use_long,
            "secondes", "minutes", "heures",
            "s", "m", "h"
        )));
    hours h(5);
    minutes m(45);
    seconds s(15);
    milliseconds ms(763);
    cout << h << ", " << m << ", " << s << " et " << ms << '\n';
```

### Output is:

```
5 heures, 45 minutes, 15 secondes et 763 millisecondes
```

See the source file example/french.cpp

# **External Resources**

C++ Standards Committee's current Working Paper

The most authoritative reference material for the library is the C++ Standards Committee's current Working Paper (WP). 20.11 Time utilities "time"

N2661 - A Foundation to Sleep On

From Howard E. Hinnant, Walter E. Brown, Jeff Garland and Marc Paterno. Is very informative and provides motivation for key design decisions

LGW 934. duration is missing operator%

From Terry Golubiewski. Is very informative and provides motivation for key design decisions

LGW 935. clock error handling needs to be specified

From Beman Dawes. This issue has been stated as NAD Future.

# Reference

As constexpr will not be supported by some compilers, it is replaced in the code by BOOST\_CHRONO\_CONSTEXPR for constexpr functions and BOOST\_CHRONO\_STATIC\_CONSTEXPR for struct/class static fields. The documentation doesn't use these macros.



# Included on the C++0x Recommendation

# Header <boost/chrono.hpp>

```
#include <boost/chrono/duration.hpp>
#include <boost/chrono/time_point.hpp>
#include <boost/chrono/system_clocks.hpp>
#include <boost/chrono/typeof/boost/chrono/chrono.hpp>
```

### **Limitations and Extensions**

Next follows limitation respect to the C++0x recomendations:

- constexpr not tested yet.
- The recently steady\_clock approved is not yet included.

The current implementation provides in addition:

- clock error handling as specified in clock error handling needs to be specified.
- · process and thread clocks.

### **Configuration Macros**

#### **How Assert Behaves?**

When BOOST\_NO\_STATIC\_ASSERT is defined, the user can select the way static assertions are reported. Define

- BOOST\_CHRONO\_USES\_STATIC\_ASSERT: define it if you want to use Boost.StaticAssert
- BOOST\_CHRONO\_USES\_MPL\_ASSERT: define it if you want to use Boost.MPL static asertions
- BOOST\_CHRONO\_USES\_ARRAY\_ASSERT: define it if you want to use internal static asertions

The default behavior is as BOOST\_CHRONO\_USES\_ARRAY\_ASSERT was defined.

When BOOST\_CHRONO\_USES\_MPL\_ASSERT is not defined the following symbols are defined as

```
#define BOOST_CHRONO_A_DURATION_REPRESENTATION_CAN_NOT_BE_A_DURATION \
    "A duration representation can not be a duration"
#define BOOST_CHRONO_SECOND_TEMPLATE_PARAMETER_OF_DURATION_MUST_BE_A_STD_RATIO \
    "Second template parameter of duration must be a boost::ratio"
#define BOOST_CHRONO_DURATION_PERIOD_MUST_BE_POSITIVE \
    "duration period must be positive"
#define BOOST_CHRONO_SECOND_TEMPLATE_PARAMETER_OF_TIME_POINT_MUST_BE_A_BOOST_CHRONO_DURATION \
    "Second template parameter of time_point must be a bchrono::duration"
```

Depending on the static assertion used system you will have an hint of the failing assertion either through the symbol or through the text.

### How to Build Boost. Chrono as a Header Only Library?

When BOOST\_CHRONO\_INLINED is defined the lib is header-only.

If in addition BOOST\_USE\_WINDOWS\_H is defined <windows.h> is included, otherwise files in boost/detail/win are used to reduce the impact of including <windows.h>.



# Header <boost/chrono/duration.hpp>

This file contains duration specific classes and non-member functions.

```
namespace boost {
 namespace chrono {
    template <class Rep, class Period = ratio<1> > class duration;
 template <class Rep1, class Period1, class Rep2, class Period2>
 struct common_type<duration<Rep1, Period1>,
                     duration<Rep2, Period2> >;
 namespace chrono {
    // customization traits
    template <class Rep> struct treat_as_floating_point;
    template <class Rep> struct duration_values;
    // duration arithmetic
    template <class Rep1, class Period1, class Rep2, class Period2>
    typename common_type<duration<Rep1, Period1>, duration<Rep2, Period2> >::type
    operator+(
        const duration<Rep1, Period1>& lhs,
        const duration<Rep2, Period2>& rhs);
    template <class Rep1, class Period1, class Rep2, class Period2>
    typename common_type<duration<Rep1, Period1>, duration<Rep2, Period2> >::type
    operator-(
        const duration<Rep1, Period1>& lhs,
        const duration<Rep2, Period2>& rhs);
    template <class Rep1, class Period, class Rep2>
    duration<typename common_type<Rep1, Rep2>::type, Period>
    operator*(
        const duration<Rep1, Period>& d,
        const Rep2& s);
    template <class Rep1, class Period, class Rep2>
    duration<typename common_type<Rep1, Rep2>::type, Period>
    operator*(
        const Rep1& s,
        const duration<Rep2, Period>& d);
    template <class Rep1, class Period, class Rep2>
    duration<typename common_type<Rep1, Rep2>::type, Period>
    operator/(
        const duration<Rep1, Period>& d,
        const Rep2& s);
    template <class Rep1, class Period1, class Rep2, class Period2>
    typename common_type<Rep1, Rep2>::type
    operator/(
        const duration<Rep1, Period1>& lhs,
        const duration<Rep2, Period2>& rhs);
    #ifdef BOOST_CHRONO_EXTENSIONS
    // Used to get frecuency of events
    template <class Rep1, class Rep2, class Period>
    double operator/(
```



```
const Rep1& s,
    const duration<Rep2, Period>& d);
#endif
// duration comparisons
template <class Rep1, class Period1, class Rep2, class Period2>
constexpr bool operator == (
    const duration<Rep1, Period1>& lhs,
    const duration<Rep2, Period2>& rhs);
template <class Rep1, class Period1, class Rep2, class Period2>
constexpr bool operator!=(
    const duration<Rep1, Period1>& lhs,
    const duration<Rep2, Period2>& rhs);
template <class Rep1, class Period1, class Rep2, class Period2>
constexpr bool operator<(
    const duration<Rep1, Period1>& lhs,
    const duration<Rep2, Period2>& rhs);
template <class Rep1, class Period1, class Rep2, class Period2>
constexpr bool operator<=(</pre>
    const duration<Rep1, Period1>& lhs,
    const duration<Rep2, Period2>& rhs);
template <class Rep1, class Period1, class Rep2, class Period2>
constexpr bool operator> (
    const duration<Rep1, Period1>& lhs,
    const duration<Rep2, Period2>& rhs);
template <class Rep1, class Period1, class Rep2, class Period2>
constexpr bool operator>=(
   const duration<Rep1, Period1>& lhs,
   const duration<Rep2, Period2>& rhs);
// duration_cast
template <class ToDuration, class Rep, class Period>
ToDuration duration_cast(const duration<Rep, Period>& d);
// convenience typedefs
typedef duration<boost::int_least64_t, nano> nanoseconds;
                                                              // at least 64 bits needed
typedef duration<boost::int_least64_t, micro> microseconds; // at least 55 bits needed
typedef duration<boost::int_least64_t, milli> milliseconds; // at least 45 bits needed
typedef duration<boost::int_least64_t> seconds;
                                                              // at least 35 bits needed
typedef duration<boost::int_least32_t, ratio< 60> > minutes; // at least 29 bits needed
typedef duration<boost::int_least32_t, ratio<3600> > hours; // at least 23 bits needed
```

#### **Time-related Traits**

#### Metafunction treat as floating point<>

```
template <class Rep> struct treat_as_floating_point
    : boost::is_floating_point<Rep> {};
```

The duration template uses the treat\_as\_floating\_point trait to help determine if a duration with one tick period can be converted to another duration with a different tick period. If treat\_as\_floating\_point<Rep>::value is true, then Rep is a floating point type and implicit conversions are allowed among duration's. Otherwise, the implicit convertibility depends on the tick periods of the duration's. If Rep is a class type which emulates a floating point type, the author of Rep can specialize



treat\_as\_floating\_point so that duration will treat this Rep as if it were a floating point type. Otherwise Rep is assumed to be an integral type, or a class emulating an integral type.

#### Class Template duration\_values

```
template <class Rep>
struct duration_values
{
public:
    static constexpr Rep zero();
    static constexpr Rep max();
    static constexpr Rep min();
};
```

The duration template uses the duration\_values trait to construct special values of the duration's representation (Rep). This is done because the representation might be a class type with behavior which requires some other implementation to return these special values. In that case, the author of that class type should specialize duration\_values to return the indicated values.

#### Static Member Function zero()

```
static constexpr Rep zero();
```

**Returns:** Rep(0). **Note:** Rep(0) is specified instead of Rep() since Rep() may have some other meaning, such as an uninitialized value.

**Remarks:** The value returned corresponds to the additive identity.

#### Static Member Function max()

```
static constexpr Rep max();
```

**Returns:** numeric\_limits<Rep>::max().

**Remarks:** The value returned compares greater than zero().

### Static Member Function min()

```
static constexpr Rep min();
```

Returns: numeric\_limits<Rep>::lowest().

**Remarks:** The value returned compares less than or equal to zero().



### common\_type Specialization

```
template <class Rep1, class Period1, class Rep2, class Period2>
struct common_type<chrono::duration<Rep1, Period1>, chrono::duration<Rep2, Period2> >
{
    typedef chrono::duration<typename common_type<Rep1, Rep2>::type, see bellow> type;
};
```

The period of the duration indicated by this specialization of common\_type is the greatest common divisor of Period1 and Period2. This can be computed by forming a ratio of the greatest common divisor of Period1::num and Period2::num, and the least common multiple of Period1::den and Period2::den.

**Note:** The typedef type is the <u>duration</u> with the largest tick period possible where both <u>duration</u> arguments will convert to it without requiring a division operation. The representation of this type is intended to be able to hold any value resulting from this conversion, with the possible exception of round-off error when floating point <u>duration</u>'s are involved (but not truncation error).

### Class Template duration<>

A duration measures time between two points in time (time\_point). A duration has a representation which holds a count of ticks, and a tick period. The tick period is the amount of time which occurs from one tick to another in units of a second. It is expressed as a rational constant using ratio.



```
namespace boost { namespace chrono {
    template <class Rep, class Period>
    class duration {
    public:
        typedef Rep rep;
        typedef Period period;
    private:
       rep rep_; // exposition only
    public:
        constexpr duration();
        template <class Rep2>
        constexpr explicit duration(const Rep2& r);
        template <class Rep2, class Period2>
        constexpr duration(const duration<Rep2, Period2>& d);
        duration& operator=(const duration&) = default;
        constexpr rep count() const;
        constexpr duration operator+();
        constexpr duration operator-();
        duration& operator++();
        duration operator++(int);
        duration& operator--();
        duration operator--(int);
        duration& operator+=(const duration& d);
        duration& operator-=(const duration& d);
        duration& operator*=(const rep& rhs);
        duration& operator/=(const rep& rhs);
        duration& operator%=(const rep& rhs);
        duration& operator%=(const duration& rhs);
        static constexpr duration zero();
        static constexpr duration min();
        static constexpr duration max();
    };
} }
```

Rep must be an arithmetic type, or a class emulating an arithmetic type, compile diagnostic otherwise. If duration is instantiated with the type of Rep being a duration, compile diagnostic is issued.

Period must be an instantiation of ratio, compile diagnostic otherwise.

Period::num must be positive, compile diagnostic otherwise.

#### Examples:

- duration<long, ratio<60> > holds a count of minutes using a long.
- duration<long long, milli> holds a count of milliseconds using a long long.
- duration<double, ratio<1, 30> > holds a count using a double with a tick period of 1/30 second (a tick frequency of 30 Hz).

The following members of duration do not throw an exception unless the indicated operations on the representations throw an exception.



#### Constructor duration(const Rep2&)

```
template <class Rep2>
constexpr explicit duration(const Rep2& r);
```

**Remarks:** Rep2 is implicitly convertible to rep, and

- treat\_as\_floating\_point<rep>::value is true, or
- !treat\_as\_floating\_point<rep>::value && !treat\_as\_floating\_point<Rep2>::value is true.

If these constraints are not met, this constructor will not participate in overload resolution. **Note:** This requirement prevents construction of an integral-based duration with a floating point representation. Such a construction could easily lead to confusion about the value of the duration.

#### **Example:**

```
duration<int, milli> d(3.5); // do not compile
duration<int, milli> d(3); // ok
```

Effects: Constructs an object of type duration.

PostConditions: count() == static\_cast<rep>(r).

#### Constructor duration(const duration&)

```
template <class Rep2, class Period2>
constexpr duration(const duration<Rep2, Period2>& d);
```

**Remarks:** treat\_as\_floating\_point<rep>::value, or ratio\_divide<Period2, period>::type::den == 1, else this constructor will not participate in overload resolution. **note** This requirement prevents implicit truncation error when converting between integral-based duration's. Such a construction could easily lead to confusion about the value of the duration.

#### **Example:**

```
duration<int, milli> ms(3);
duration<int, micro> us = ms; // ok
duration<int, milli> ms2 = us; // do not compile
```

Effects: Constructs an object of type duration, constructing rep\_from duration\_cast<duration>(d).count().

## Member Function count() const

```
constexpr rep count() const;
```

Returns: rep\_.



#### Member Function operator+() const

```
constexpr duration operator+() const;
```

Returns: \*this.

#### Member Function operator-() const

```
constexpr duration operator-() const;
```

**Returns:** duration(-rep\_).

#### Member Function operator++()

```
duration@ operator++();
```

**Effects:** ++rep\_.

Returns: \*this.

#### Member Function operator++(int)

```
duration operator++(int);
```

**Returns:** duration(rep\_++).

#### Member Function operator--()

```
duration& operator--();
```

**Effects:** --rep\_.

Returns: \*this.

### Member Function operator--(int)

```
duration operator--(int);
```

**Returns:** duration(rep\_--).

## Member Function operator+=(const duration&)

```
duration& operator+=(const duration& d);
```

Effects: rep\_ += d.count().

Returns: \*this.



## Member Function operator == (const duration&)

```
duration& operator-=(const duration& d);
```

Effects: rep\_ -= d.count().

Returns: \*this.

## Member Function operator%=(const duration&)

```
duration& operator%=(const duration& d);
```

Effects: rep\_ %= d.count().

Returns: \*this.

### Member Function operator\*=(const rep&)

```
duration& operator*=(const rep& rhs);
```

Effects: rep\_ \*= rhs.

Returns: \*this.

## Member Function operator/=(const rep&)

```
duration& operator/=(const rep& rhs);
```

Effects: rep\_ /= rhs.

Returns: \*this.

## Member Function operator%=(const rep&)

```
duration& operator%=(const rep& rhs);
```

Effects: rep\_ %= rhs.

Returns: \*this.

#### Static Member Function zero()

```
static constexpr duration zero();
```

Returns: duration(duration\_values<rep>::zero()).



#### Static Member Function min()

```
static constexpr duration min();
```

Returns: duration(duration\_values<rep>::min()).

#### Static Member Function max()

```
static constexpr duration max();
```

**Returns:** duration(duration\_values<rep>::max()).

#### duration Non-Member Arithmetic

## Non-Member Function operator+(duration,duration)

```
template <class Rep1, class Period1, class Rep2, class Period2>
typename common_type<duration<Rep1, Period1>, duration<Rep2, Period2> >::type
operator+(const duration<Rep1, Period1>& lhs, const duration<Rep2, Period2>& rhs);
```

**Returns:** CD(lhs) += rhs where CD is the type of the return value.

#### Non-Member Function operator-(duration, duration)

```
template <class Rep1, class Period1, class Rep2, class Period2>
typename common_type<duration<Rep1, Period1>, duration<Rep2, Period2> >::type
operator-(const duration<Rep1, Period1>& lhs, const duration<Rep2, Period2>& rhs);
```

**Returns:** CD(lhs) -= rhs where CD is the type of the return value.

```
template <class Rep1, class Period, class Rep2>
duration<typename common_type<Rep1, Rep2>::type, Period>
operator*(const duration<Rep1, Period>& d, const Rep2& s);
```

**Requires:** Let CR represent the common\_type of Rep1 and Rep2. This function will not participate in overload resolution unless both Rep1 and Rep2 are implicitly convertible to CR.

Returns: duration<CR, Period>(d) \*= s.

#### Non-Member Function operator\*(Rep1,duration)

```
template <class Rep1, class Period, class Rep2>
duration<typename common_type<Rep1, Rep2>::type, Period>
operator*(const Rep1& s, const duration<Rep2, Period>& d);
```

**Requires:** Let CR represent the common\_type of Rep1 and Rep2. This function will not participate in overload resolution unless both Rep1 and Rep2 are implicitly convertible to CR.

Returns: d \* s.



#### Non-Member Function operator/(duration,Rep2)

```
template <class Rep1, class Period, class Rep2>
duration<typename common_type<Rep1, Rep2>::type, Period>
operator/(const duration<Rep1, Period>& d, const Rep2& s);
```

**Requires:** Let CR represent the common\_type of Rep1 and Rep2. This function will not participate in overload resolution unless both Rep1 and Rep2 are implicitly convertible to CR, and Rep2 is not an instantiation of duration.

Returns: duration<CR, Period>(d) /= s.

#### Non-Member Function operator/(duration,duration)

```
template <class Rep1, class Period1, class Rep2, class Period2>
typename common_type<Rep1, Rep2>::type
operator/(const duration<Rep1, Period1>& lhs, const duration<Rep2, Period2>& rhs);
```

Returns: Let CD represent the common\_type of the two duration arguments. Returns CD(lhs).count() / CD(rhs).count().

#### Non-Member Function operator/(Rep1,duration)

Included only if BOOST CHRONO EXTENSIONS is defined.

This overloading could be used to get the frequency of an event counted by Rep1.

```
template <class Rep1, class Rep2, class Period> double operator/(const Rep1& s, const duration<Rep2, Period>& d);
```

**Remarks:** Let CR represent the common\_type of Rep1 and Rep2. This function will not participate in overload resolution unless both Rep1 and Rep2 are implicitly convertible to CR, and Rep1 is not an instantiation of duration.

**Returns:** CR(s)/duration<CR, Period>(d).count().

#### Non-Member Function operator%(duration,Rep2)

```
template <class Rep1, class Period, class Rep2>
duration<typename common_type<Rep1, Rep2>::type, Period>
operator%(const duration<Rep1, Period>& d, const Rep2& s);
```

**Remarks** This function will not participate in overload resolution unless Rep2 must be implicitly convertible to CR(Rep1, Rep2) and Rep2 must not be an instantiation of duration.

**Returns:** duration<CR(Rep1,Rep2), Period>(d) %= s.

#### Non-Member Function operator%(duration, duration)

Remarks This function will not participate in overload resolution unless



**Returns:** CD(lhs) %= CD(rhs)

### duration Non-Member Comparaisons

#### Non-Member Function operator==(duration,duration)

Returns: Let CD represent the common\_type of the two duration arguments. Returns CD(lhs).count() == CD(rhs).count()

#### Non-Member Function operator!=(duration,duration)

Returns: !(lhs == rhs).

#### Non-Member Function operator<(duration,duration)

Returns: Let CD represent the common\_type of the two duration arguments. Returns CD(lhs).count() < CD(rhs).count()

## Non-Member Function operator<=(duration,duration)

**Returns:** !(rhs < lhs).

#### Non-Member Function operator>(duration,duration)

Returns: rhs < lhs.

#### **Non-Member Function** operator>=(duration,duration)

**Returns:** !(lhs < rhs).



## Non-Member Function duration cast(duration)

```
template <class ToDuration, class Rep, class Period>
ToDuration duration_cast(const duration<Rep, Period>& d);
```

Requires: This function will not participate in overload resolution unless ToDuration is an instantiation of duration.

**Returns:** Forms CF which is a ratio resulting from ratio\_divide<Period, typename ToDuration::period>::type. Let CR be the common\_type of ToDuration::rep, Rep, and intmax\_t.

- If CF::num == 1 and CF::den == 1, then returns ToDuration(static\_cast<typename ToDuration::rep>(d.count()))
- else if CF::num != 1 and CF::den == 1, then returns ToDuration(static\_cast<typename ToDuration::rep>(static\_cast<CR>(d.count()) \* static\_cast<CR>(CF::num)))
- else if CF::num == 1 and CF::den != 1, then returns ToDuration(static\_cast<typename ToDuration::rep>(static\_cast<CR>(d.count()) / static\_cast<CR>(CF::den)))
- else returns ToDuration(static\_cast<typename ToDuration::rep>(static\_cast<CR>(d.count()) \* static\_cast<CR>(CF::num) / static\_cast<CR>(CF::den)))

**Remarks:** This function does not rely on any implicit conversions. All conversions must be accomplished through static\_cast. The implementation avoids all multiplications or divisions when it is known at compile time that it can be avoided because one or more arguments are 1. All intermediate computations are carried out in the widest possible representation and only converted to the destination representation at the final step.

## duration typedefs

## **Clock Requirements**

A clock represents a bundle consisting of a duration, a time\_point, and a function now() to get the current time\_point. A clock must meet the requirements in the following Table.

In this table C1 and C2 denote clock types. t1 and t2 are values returned from C1::now() where the call returning t1 happens before the call returning t2 and both of these calls happen before C1::time\_point::max().



**Table 1. Clock Requirements** 

expression	return type	operational semantics	
C1::rep	An arithmetic type or class emulating an arithmetic type.	The representation type of the duration and time_point.	
C1::period	ratio	The tick period of the clock in seconds.	
C1::duration	<pre>chrono::duration<c1::rep, c1::period=""></c1::rep,></pre>	The duration type of the clock.	
Cl::time_point	<pre>chrono::time_point<cl></cl></pre>	The time_point type of the clock. Different clocks are permitted to share a time_point definition if it is valid to compare their time_points by comparing their respective duration's. C1 and C2 must refer to the same epoch.	
C1::is_steady	constexpr bool	true if t1 <= t2 is always true, else false. <b>Note</b> : A clock that can be adjusted backwards is not steady	
C1::now()	C1::time_point	Returns a time_point representing the current point in time.	

#### Models of Clock:

- system\_clock
- steady\_clock
- high\_resolution\_clock
- process\_real\_cpu\_clock
- process\_user\_cpu\_clock
- process\_system\_cpu\_clock
- thread\_clock

# Header <boost/chrono/time\_point.hpp>

This file contains time\_point specific classes and non-member functions.



```
namespace boost {
 namespace chrono {
    template <class Clock, class Duration = typename Clock::duration> class time_point;
  template <class Clock, class Duration1, class Duration2>
 struct common_type<time_point<Clock, Duration1>,
                     time_point<Clock, Duration2> >;
 namespace chrono {
    // time_point arithmetic
    template <class Clock, class Duration1, class Rep2, class Period2>
    time_point<Clock, typename common_type<Duration1, duration<Rep2, Period2> >::type>
    operator+(const time_point<Clock, Duration1>& lhs, const duration<Rep2, Period2>& rhs);
    template <class Rep1, class Period1, class Clock, class Duration2>
    time_point<Clock, typename common_type<duration<Rep1, Period1>, Duration2>::type>
    operator+(const duration<Rep1, Period1>& lhs, const time_point<Clock, Duration2>& rhs);
    template <class Clock, class Duration1, class Rep2, class Period2>
    time_point<Clock, typename common_type<Duration1, duration<Rep2, Period2> >::type>
    operator-(const time_point<Clock, Duration1>& lhs, const duration<Rep2, Period2>& rhs);
    template <class Clock, class Duration1, class Duration2>
    typename common_type<Duration1, Duration2>::type
    operator-(const time_point<Clock, Duration1>& lhs, const time_point<Clock,
           Duration2>& rhs);
    // time_point comparisons
    template <class Clock, class Duration1, class Duration2>
    constexpr bool operator == (const time_point < Clock, Duration1 > & lhs,
                    const time_point<Clock, Duration2>& rhs);
    template <class Clock, class Duration1, class Duration2>
    constexpr bool operator!=(const time_point<Clock, Duration1>& lhs,
                    const time_point<Clock, Duration2>& rhs);
    template <class Clock, class Duration1, class Duration2>
    constexpr bool operator< (const time_point<Clock, Duration1>& lhs,
                    const time_point<Clock, Duration2>& rhs);
    template <class Clock, class Duration1, class Duration2>
    constexpr bool operator<=(const time_point<Clock, Duration1>& lhs,
                   const time_point<Clock, Duration2>& rhs);
    template <class Clock, class Duration1, class Duration2>
    constexpr bool operator> (const time_point<Clock, Duration1>& lhs,
                    const time_point<Clock, Duration2>& rhs);
    template <class Clock, class Duration1, class Duration2>
    constexpr bool operator>=(const time_point<Clock, Duration1>& lhs,
                    const time_point<Clock, Duration2>& rhs);
```



```
// time_point_cast
  template <class ToDuration, class Clock, class Duration>
  constexpr time_point<Clock, ToDuration> time_point_cast(const time_point<Clock, Duration>& t);
}
}
```

## common\_type specialization

```
template <class Clock, class Duration1, class Duration2>
struct common_type<chrono::time_point<Clock, Duration1>, chrono::time_point<Clock, Duration2> >
{
    typedef chrono::time_point<Clock, typename common_type<Duration1, Duration2>::type> type;
};
```

The common\_type of two time\_point's is a time\_point with the same clock (both have the same clock), and the common\_type of the two duration's.

## Class template time\_point<>

A time\_point represents a point in time with respect to a specific clock.

```
template <class Clock, class Duration>
class time_point {
public:
    typedef Clock
                                       clock;
    typedef Duration
                                      duration;
    typedef typename duration::rep
    typedef typename duration::period period;
private:
    duration d_; // exposition only
public:
    constexpr time_point();
    constexpr explicit time_point(const duration& d);
    // conversions
    template <class Duration2>
    time_point(const time_point<clock, Duration2>& t);
    // observer
    constexpr duration time_since_epoch() const;
    // arithmetic
    time_point& operator+=(const duration& d);
    time_point& operator-=(const duration& d);
    // special values
    static constexpr time_point min();
    static constexpr time_point max();
};
```

Clock must meet the Clock requirements.

Duration must be an instantiation of duration, compile diagnostic otherwise.



#### Constructor time\_point()

```
constexpr time_point();
```

Effects: Constructs an object of time\_point, initializing d\_ with duration::zero(). This time\_point represents the epoch.

#### Constructor time\_point(const duration&)

```
constexpr time_point(const duration& d);
```

Effects: Constructs an object of time\_point, initializing d\_ with d. This time\_point represents the epoch + d.

#### Copy Constructor time\_point(const time\_point&)

```
template <class Duration2> time_point(const time_point<clock, Duration2>& t);
```

Requires: This function will not participate in overload resolution unless Duration2 is implicitly convertible to duration.

Effects: Constructs an object of time\_point, initializing d\_ with t.time\_since\_epoch().

## Member Function time\_since\_epoch() const

```
constexpr duration time_since_epoch() const;
```

Returns: d\_.

#### Member Function operator+=

```
time_point& operator+=(const duration& d);
```

**Effects:**  $d_{-} += d$ .

Returns: \*this.

#### Member Function operator -=

```
time_point& operator-=(const duration& d);
```

Effects: d\_ -= d

Returns: \*this.

#### Static Member Function min

```
static constexpr time_point min();
```

Returns: time\_point(duration::min()).



## Static Member Function max

```
static constexpr time_point max();
```

**Returns:** time\_point(duration::max()).

#### time\_point non-member arithmetic

## Non-Member Function operator+(time\_point,duration)

**Returns:** CT(lhs) += rhs where CT is the type of the return value.

#### Non-Member Function operator+(duration,time\_point)

**Returns:** rhs + lhs.

#### Non-Member Function operator-(time\_point,duration)

**Returns:** lhs + (-rhs).

## Non-Member Function operator-(time\_point,time\_point)

Returns: lhs.time\_since\_epoch() - rhs.time\_since\_epoch().



## time\_point non-member comparisons

#### Non-Member Function operator == (time\_point, time\_point)

Returns: lhs.time\_since\_epoch() == rhs.time\_since\_epoch().

## Non-Member Function operator!=(time\_point,time\_point)

template <class Clock, class Duration1, class Duration2> bool operator!=(const time\_point<Clock, Duration1>& lhs, const time\_point<Clock, Duration2>& rhs);

Returns: !(lhs == rhs).

#### Non-Member Function operator<(time\_point,time\_point)

**Returns:** lhs.time\_since\_epoch() < rhs.time\_since\_epoch().

#### Non-Member Function operator<=(time\_point,time\_point)

Returns: ! (rhs < lhs).

## Non-Member Function operator>(time\_point,time\_point)

template <class Clock, class Duration1, class Duration2> bool operator>(const time\_point<Clock, Duration1>& lhs, const time\_point<Clock, Duration2>& rhs);

Returns: rhs < lhs.

## Non-Member Function operator>=(time\_point,time\_point)

Returns: !(lhs < rhs).



## Non-Member Function time\_point\_cast(time\_point)

```
template <class ToDuration, class Clock, class Duration>
time_point<Clock, ToDuration> time_point_cast(const time_point<Clock, Duration>& t);
```

Requires: This function will not participate in overload resolution unless ToDuration is an instantiation of duration.

 $\textbf{Returns:} \ \texttt{time\_point} < \texttt{Clock, ToDuration} > (\texttt{duration\_cast} < \texttt{ToDuration} > (\texttt{t.time\_since\_epoch())}).$ 

## Header <boost/chrono/system\_clocks.hpp>

This file contains the standard clock classes.

```
namespace boost {
  namespace chrono {

    // Clocks
    class system_clock;
    class steady_clock;
    class high_resolution_clock;
}
```

### Class system\_clock

The system\_clock class provides a means of obtaining the current wall-clock time from the system-wide real-time clock. The current time can be obtained by calling system\_clock::now(). Instances of system\_clock::time\_point can be converted to and from time\_t with the system\_clock::to\_time\_t() and system\_clock::to\_time\_point() functions. If system clock is not steady, a subsequent call to system\_clock::now() may return an earlier time than a previous call (e.g. if the operating system clock is manually adjusted, or synchronized with an external clock).

The current implementation of system\_clock is related an epoch (midnight UTC of January 1, 1970), but this is not in the contract. You need to use the static function static

```
std::time_t to_time_t(const time_point& t);
```

which returns a time\_t type that is based on midnight UTC of January 1, 1970.



```
class system_clock {
public:
    typedef see bellow
                                duration;
    typedef duration::rep
                                                 rep;
    typedef duration::period
                                                 period;
    typedef chrono::time_point<system_clock>
                                                 time_point;
    static constexpr bool is_steady =
                                                 false;
                                                      // throws on error
    static time_point now();
    static time_point now(system::error_code & ec); // never throws
    // Map to C API
    static std::time_t to_time_t(const time_point& t);
    static time_point from_time_t(std::time_t t);
};
```

system\_clock satisfy the Clock requirements:

- system\_clock::duration::min() < system\_clock::duration::zero() is true.
- The nested duration typedef has a resolution that depends on the one provided by the platform.

### Static Member Function to\_time\_t(time\_point)

time\_t to\_time\_t(const time\_point& t);

**Returns:** A time\_t such that the time\_t and t represent the same point in time, truncated to the courser of the precisions among time\_t and t.

#### Static Member Function from\_time\_t(time\_t)

```
time_point from_time_t(time_t t);
```

**Returns:** A time\_point such that the time\_point and t represent the same point in time, truncated to the coarser of the precisions among time\_point and t.

### Macro boost\_chrono\_has\_clock\_steady

Defined if the platform support steady clocks.

#### Class steady\_clock

steady\_clock satisfy the clock requirements.

steady\_clock class provides access to the system-wide steady clock. The current time can be obtained by calling
steady\_clock::now(). There is no fixed relationship between values returned by steady\_clock::now() and wall-clock time.



#### Class high\_resolution\_clock

high\_resolution\_clock satisfy the Clock requirements.

```
#ifdef BOOST_CHRONO_HAS_CLOCK_STEADY
   typedef steady_clock high_resolution_clock; // as permitted by [time.clock.hires]
#else
   typedef system_clock high_resolution_clock; // as permitted by [time.clock.hires]
#endif
```

## Header <boost/chrono/typeof/boost/chrono/chrono.hpp>

Register duration<> and time\_point<> class templates to **Boost.Typeof**.



# Chrono I/O

# Header <boost/chrono/chrono\_io.hpp>

```
namespace boost {
namespace chrono {
    template <class CharT>
    class duration_punct;
    template <class Clock, class CharT>
    struct clock_string;
    template <class CharT, class Traits>
         std::basic_ostream<CharT, Traits>&
        duration_short(std::basic_ostream<CharT, Traits>& os);
    template <class CharT, class Traits>
         std::basic_ostream<CharT, Traits>&
         duration_long(std::basic_ostream<CharT, Traits>& os);
    template <class CharT, class Traits, class Rep, class Period>
         std::basic_ostream<CharT, Traits>&
         operator<<(std::basic_ostream<CharT, Traits>& os, const duration<Rep, Period>& d);
    template <class CharT, class Traits, class Rep, class Period>
         std::basic_istream<CharT, Traits>&
         operator >> (\texttt{std}:: \texttt{basic\_istream} < \texttt{CharT}, \ \texttt{Traits} > \& \ \texttt{is}, \ \texttt{duration} < \texttt{Rep}, \ \texttt{Period} > \& \ \texttt{d})
    template <class CharT, class Traits, class Clock, class Duration>
         std::basic_ostream<CharT, Traits>&
         operator << (std::basic_ostream < CharT, Traits > & os,
                const time_point<Clock, Duration>& tp);
    template <class CharT, class Traits, class Clock, class Duration>
         std::basic_istream<CharT, Traits>&
         operator>>(std::basic_istream<CharT, Traits>& is,
                time_point<Clock, Duration>& tp);
```

## Template Class duration\_punct<>

The duration unit names can be customized through the facet: duration\_punct. duration unit names come in two varieties: long and short. The default constructed duration\_punct provides names in the long format. These names are English descriptions. Other languages are supported by constructing a duration\_punct with the proper spellings for "hours", "minutes" and "seconds", and their abbreviations (for the short format).



```
template <class CharT>
class duration_punct
    : public std::locale::facet
public:
    typedef std::basic_string<CharT> string_type;
    enum {use_long, use_short};
    static std::locale::id id;
    explicit duration_punct(int use = use_long);
    duration_punct(int use,
        const string_type& long_seconds, const string_type& long_minutes,
        \verb|const| | \verb|string_type&| | \verb|long_hours|, | \verb|const| | \verb|string_type&| | \verb|short_seconds|, | \\
        const string_type& short_minutes, const string_type& short_hours);
    duration_punct(int use, const duration_punct& d);
    template <class Period> string_type short_name() const;
    template <class Period> string_type long_name() const;
    template <class Period> string_type name() const;
    bool is_short_name() const;
    bool is_long_name() const;
};
```

## Template Class clock\_string<>

```
template <class Clock, class CharT>
struct clock_string;
```

This template must be specialized for specific clocks. The specialization must define the following functions

```
static std::basic_string<CharT> name();
static std::basic_string<CharT> since();
```

clock\_string<>::name() return the clock name, which usualy corresponds to the class name. clock\_string<>::since()
return the textual format of the clock epoch.

## clock\_string<system\_clock> Specialization

```
template <class CharT>
struct clock_string<system_clock, CharT>
{
    static std::basic_string<CharT> name();
    static std::basic_string<CharT> since();
};
```

clock\_string<>::name() returns "system\_clock".clock\_string<>::since() returns "since Jan 1, 1970"



## clock\_string<steady\_clock> Specialization

```
#ifdef BOOST_CHRONO_HAS_CLOCK_STEADY

template <class CharT>
struct clock_string<steady_clock, CharT>
{
    static std::basic_string<CharT> name();
    static std::basic_string<CharT> since();
};
#endif
```

clock\_string<>::name() returns "steady\_clock". clock\_string<>::since() returns "since boot"

## clock\_string<thread\_clock> Specialization

```
#if defined(BOOST_CHRONO_HAS_THREAD_CLOCK)
template <class CharT>
struct clock_string<thread_clock, CharT>
{
    static std::basic_string<CharT> name();
    static std::basic_string<CharT> since();
};
#endif
```

clock\_string<>::name() returns "thread\_clock".clock\_string<>::since() returns "since thread start-up"

## clock\_stringcpu\_clock Specialization

```
template <class CharT>
struct clock_stringprocess_real_cpu_clock, CharT>
{
    static std::basic_string<CharT> name();
    static std::basic_string<CharT> since();
};
```

clock\_string<>::name() returns "process\_real\_cpu\_clock".clock\_string<>::since() returns "since process start-up"

#### clock\_stringclock> Specialization

```
template <class CharT>
struct clock_stringprocess_user_cpu_clock, CharT>
{
    static std::basic_string<CharT> name();
    static std::basic_string<CharT> since();
};
```

clock\_string<>::name() returns "process\_user\_cpu\_clock". clock\_string<>::since() returns " since process start-up"



## clock\_stringcpu\_clock Specialization

```
template <class CharT>
struct clock_stringcpu_clock, CharT>
{
    static std::basic_string<CharT> name();
    static std::basic_string<CharT> since();
};
```

clock\_string<>::name() returns "process\_system\_cpu\_clock".clock\_string<>::since() returns "since process start-up"

## ${\tt clock\_string < process\_cpu\_clock>} \begin{tabular}{l} \textbf{Specialization} \\ \end{tabular}$

```
template <class CharT>
struct clock_stringprocess_cpu_clock, CharT>
{
    static std::basic_string<CharT> name();
    static std::basic_string<CharT> since();
};
```

clock\_string<>::name() returns "process\_cpu\_clock".clock\_string<>::since() returns "since process start-up"

## I/O Manipulators

The short or long format can be easily chosen by streaming a duration\_short or duration\_long manipulator respectively.

```
template <class CharT, class Traits>
    std::basic_ostream<CharT, Traits>&
    duration_short(std::basic_ostream<CharT, Traits>& os);
```

**Effects:** Set the duration\_punct facet to stream durations and time\_points as abreviations.

Returns: the output stream

```
template <class CharT, class Traits>
    std::basic_ostream<CharT, Traits>&
    duration_long(std::basic_ostream<CharT, Traits>& os);
```

**Effects:** Set the duration\_punct facet to stream durations and time\_points as long text.

Returns: the output stream

#### I/O Streams Operations

Any duration can be streamed out to a basic\_ostream. The run time value of the duration is formatted according to the rules and current format settings for duration::rep. This is followed by a single space and then the compile time unit name of the duration. This unit name is built on the string returned from ratio\_string<> and the data used to construct the duration\_punct which was inserted into the stream's locale. If a duration\_punct has not been inserted into the stream's locale, a default constructed duration\_punct will be added to the stream's locale.

A time\_point is formatted by outputting its internal duration followed by a string that describes the time\_point::clock epoch. This string will vary for each distinct clock, and for each implementation of the supplied clocks.



```
template <class CharT, class Traits, class Rep, class Period>
    std::basic_ostream<CharT, Traits>&
    operator<<(std::basic_ostream<CharT, Traits>& os, const duration<Rep, Period>& d);
```

Effects: outputs the duration as an abrevieated or long text format depending on the state of the duration\_punct facet.

Returns: the output stream

```
template <class CharT, class Traits, class Rep, class Period>
std::basic_istream<CharT, Traits>&
operator>>(std::basic_istream<CharT, Traits>& is, duration<Rep, Period>& d)
```

Effects: reads a duration from the input stream. If a format error is found, the input stream state will be set to failbit.

Returns: the input stream

```
template <class CharT, class Traits, class Clock, class Duration>
   std::basic_ostream<CharT, Traits>&
   operator<<(std::basic_ostream<CharT, Traits>& os,
        const time_point<Clock, Duration>& tp);
```

Effects: outputs the time\_point as an abrevieated or long text format depending on the state of the duration\_punct facet.

**Returns:** the output stream

```
template <class CharT, class Traits, class Clock, class Duration>
    std::basic_istream<CharT, Traits>&
    operator>>(std::basic_istream<CharT, Traits>& is,
        time_point<Clock, Duration>& tp);
```

Effects: reads a time\_point from the input stream. If a format error is found, the input stream state will be set to failbit.

Returns: the input stream

# **Other Clocks**

Header <boost/chrono/process\_cpu\_clocks.hpp>

Knowing how long a program takes to execute is useful in both test and production environments. It is also helpful if such timing information is broken down into real (wall clock) time, CPU time spent by the user, and CPU time spent by the operating system servicing user requests.

Process clocks don't include the time spent by the child process.



```
namespace boost { namespace chrono {
    class process_real_cpu_clock;
    class process_user_cpu_clock;
    class process_system_cpu_clock;
    class process_cpu_clock;
    struct process_cpu_clock::times;
    template <class CharT, class Traits>
    std::basic_ostream<CharT, Traits>&
    operator<<(std::basic_ostream<CharT, Traits>& os,
            process_cpu_clock::times const& rhs);
    template <class CharT, class Traits>
    std::basic_istream<CharT, Traits>&
    operator>>(std::basic_istream<CharT, Traits>& is,
           process_cpu_clock::times const& rhs);
    template <>
    struct duration_valuescpu_clock::times>;
} }
{\tt namespace \ std}\ \{
    template <>
    class numeric_limits<boost::chrono::process_cpu_clock::times>;
```

## Class process\_real\_cpu\_clock

process\_real\_cpu\_clock satisfy the Clock requirements.

process\_real\_cpu\_clock class provides access to the real process wall-clock steady clock, i.e. the real CPU-time clock of the calling process. The process relative current time can be obtained by calling process\_real\_cpu\_clock::now().

### Class process\_user\_cpu\_clock

process\_user\_cpu\_clock satisfy the Clock requirements.

process\_user\_cpu\_clock class provides access to the user CPU-time steady clock of the calling process. The process relative user current time can be obtained by calling process\_user\_cpu\_clock::now().



## Class process\_system\_cpu\_clock

process\_system\_cpu\_clock satisfy the Clock requirements.

process\_system\_cpu\_clock class provides access to the system CPU-time steady clock of the calling process. The process relative system current time can be obtained by calling process\_system\_cpu\_clock::now().

## Class process\_cpu\_clock

process\_cpu\_clock can be considered as a tuplecpu\_clock, process\_user\_cpu\_clock, process\_system\_cpu\_clock>.

process\_cpu\_clock provides a thin wrapper around the operating system's process time API. For POSIX-like systems, that's the times() function, while for Windows, it's the GetProcessTimes() function.

The process relative real, user and system current time can be obtained at once by calling process\_clocks::now().

#### Class process\_cpu\_clock::times

This class is the representation of the process\_cpu\_clock::duration class. As such it needs to implements the arithmetic operators.



```
struct times : arithmetic<times,</pre>
    multiplicative<times, process_real_cpu_clock::rep,</pre>
    less_than_comparable<times> > >
   process_real_cpu_clock::rep real;
                                           // real (i.e wall clock) time
    process_user_cpu_clock::rep user;
                                            // user cpu time
    process_system_cpu_clock::rep system; // system cpu time
    times();
    times(
        process_real_cpu_clock::rep r,
        process_user_cpu_clock::rep u,
        process_system_cpu_clock::rep s);
    bool operator==(times const& rhs);
    times operator+=(times const& rhs);
    times operator -= (times const& rhs);
    times operator*=(times const& rhs);
    times operator/=(times const& rhs);
    bool operator<(times const & rhs) const;</pre>
};
```

## process\_cpu\_clock::times Input/Output

```
template <class CharT, class Traits>
std::basic_ostream<CharT, Traits>&
  operator<<(std::basic_ostream<CharT, Traits>& os,
      process_cpu_clock::times const& rhs);
```

**Effect**: Output each part separated by ';' and sourrounded by '{', '}'. **Throws**: None.

```
template <class CharT, class Traits>
std::basic_istream<CharT, Traits>&
  operator>>(std::basic_istream<CharT, Traits>& is,
      process_cpu_clock::times const& rhs);
```

**Effect**: overrides the value of rhs if the input stream has the format "{r;u;s}". Otherwise, set the input stream state as failbit | eofbit. **Throws**: None.

## duration\_values Specialization for times

```
template <>
struct duration_valuescpu_clock::times>
{
    static process_cpu_clock::times zero();
    static process_cpu_clock::times max();
    static process_cpu_clock::times min();
};
```

The times specific functions zero(), max() and min() uses the relative functions on the representation of each component.



## numeric\_limits Specialization for times

```
namespace std {
    template <>
    class numeric_limits<boost::chrono::process_cpu_clock::times> {
        typedef boost::chrono::process_cpu_clock::times Rep;
        static const bool is_specialized = true;
        static Rep min();
        static Rep max();
        static Rep lowest();
        static const int digits;
        static const int digits10;
        static const bool is_signed = false;
        static const bool is_integer = true;
        static const bool is_exact = true;
        static const int radix = 0;
    };
}
```

The times specialization functions min(), max() and lowest() uses the relative functions on the representation of each component.

#### Notes

- min() returns the tuple of min's
- max() returns the tuple of max's
- lowest()' returns the tuple of lowest's \* digits' is the sum of digits's
- 'digits10' is the sum of digits10's

## Header <boost/chrono/thread\_clock.hpp>

Knowing the time a thread takes to execute is useful in both test and production environments.

```
#define BOOST_CHRONO_HAS_THREAD_CLOCK
#define BOOST_CHRONO_THREAD_CLOCK_IS_STEADY
namespace boost { namespace chrono {
   class thread_clock;
}
```

#### Macro boost\_chrono\_has\_thread\_clock

This macro is defined if the platform supports thread clocks.

## Macro boost\_chrono\_thread\_clock\_is\_steady

This macro is defined if the platform has a thread clock. Its value is true if it is steady and false otherwise.

## Class thread\_clock

thread\_clock satisfy the Clock requirements.



thread\_clock class provides access to the real thread wall-clock, i.e. the real CPU-time clock of the calling thread. The thread relative current time can be obtained by calling thread\_clock::now().

# **Appendices**

# **Appendix A: History**

# **Appendix B: Rationale**

See N2661 - A Foundation to Sleep On which is very informative and provides motivation for key design decisions. This section contains some extracts from this document.

## Is it possible for the user to pass a duration to a function with the units being ambiguous?

No. No matter which option the author of f chooses above, the following client code will not compile:

```
f(3); // Will not compile, 3 is not implicitly convertible to any __duration
```

## Why duration needs operator%

This operator is convenient for computing where in a time frame a given duration lies. A motivating example is converting a duration into a "broken-down" time duration such as hours::minutes::seconds:



```
class ClockTime
{
    typedef boost::chrono::minutes minutes;
    typedef boost::chrono::seconds seconds;

public:
    hours hours_;
    minutes minutes_;
    seconds seconds_;

template <class Rep, class Period>
    explicit ClockTime(const boost::chrono::duration<Rep, Period>& d)
    : hours_ (boost::chrono::duration_cast<hours> (d)),
        minutes_(boost::chrono::duration_cast<minutes>(d % hours(1))),
        seconds_(boost::chrono::duration_cast<seconds>(d % minutes(1)))
        {}
};
```

# **Appendix C: Implementation Notes**

## Which APIs have been chosen to implement each clock on each platform?

The following table presents a resume of which API is uused for each clock on each platform

Table 2. Clock API correspondence

Clock	Windows Platform	Posix Platform	Mac Platform
system_clock	GetSystemTimeAsFileTime	clock_gettime( CLOCK_RE-ALTIME)	gettimeofday
steady_clock	QueryPerformanceCounter and QueryPerformanceFrequency	clock_gettime(CLOCK_STEADY)	mach_timebase_info,mach_absolute_time
p r o - cess_real_cpu_clock	GetProcessTimes	times	times
process_sys- tem_cpu_clock	GetProcessTimes	times	times
p r o - cess_user_cpu_clock	GetProcessTimes	times	times
process_cpu_clock	GetProcessTimes	times	times
thread_clock	GetThreadTimes	_	c l o c k _ g e t - time(pthread_getcpuclockid)

# **Appendix D: FAQ**

## Why does process\_cpu\_clock sometimes give more cpu seconds than real seconds?

Ask your operating system supplier. The results have been inspected with a debugger, and both for Windows and Linux, that's what the OS appears to be reporting at times.



## Are integer overflows in the duration arithmetic detected and reported?

**Boost.Ratio** avoids all kind of overflow that could result of arithmetic operation and that can be simplified. The typedefs durations don't detect overflow. You will need a representation that handles with.

## Which clocks should be used to benchmarking?

Each clock has his own features. It depends on what do you need to benchmark. Most of the time, you could be interested in using a thread clock, but if you need to measure code subject to synchronization a process clock would be better. If you have a multi-process application, a system-wide clock could be needed.

## Which clocsk should be used to watching?

For trace purposes it seems better to use a system-wide clock.

# **Appendix E: Acknowledgements**

The library's code was derived from Howard Hinnant's time2\_demo prototype. Many thanks to Howard for making his code available under the Boost license. The original code was modified by Beman Dawes to conform to Boost conventions.

time2 demo contained this comment:

Much thanks to Andrei Alexandrescu, Walter Brown, Peter Dimov, Jeff Garland, Terry Golubiewski, Daniel Krugler, Anthony Williams.

The file <boost/chrono\_io.hpp> has been adapted from the experimental header <chrono\_io> from Howard Hinnant. Thanks for all Howard.

Howard Hinnant, who is the real author of the library, has provided valuable feedback and suggestions during the development of the library. In particular, The chrono\_io\_io.hpp source has been adapted from the experimental header <chrono\_io> from Howard Hinnant.

The acceptance review of Boost.Ratio took place between November 5th and 15th 2010. Many thanks to Anthony Williams, the review manager, and to all the reviewers: David Deakins, John Bytheway, Roland Bock and Paul A. Bristol.

Thanks to Ronald Bock, Andrew Chinoff, Paul A. Bristol and John Bytheway for his help polishing the documentation.

Thanks to Tom Tan for reporting some compiler issues with MSVC V10 beta and MinGW-gcc-4.4.0 and for the many pushing for an homogeneous process\_cpu\_clock clock.

Thanks to Ronald Bock for reporting Valgind issues and for the many suggestion he did concerning the documentation.

# **Appendix F: Future plans**

## For later releases

• Add chrono utilities as defined By Howard Hinnant in here.

