

Red Hat Enterprise Linux 9

Automating system administration by using RHEL system roles

Consistent and repeatable configuration of RHEL deployments across multiple hosts with Red Hat Ansible Automation Platform playbooks

Last Updated: 2024-10-10

Red Hat Enterprise Linux 9 Automating system administration by using RHEL system roles

Consistent and repeatable configuration of RHEL deployments across multiple hosts with Red Hat Ansible Automation Platform playbooks

Legal Notice

Copyright © 2024 Red Hat, Inc.

The text of and illustrations in this document are licensed by Red Hat under a Creative Commons Attribution–Share Alike 3.0 Unported license ("CC-BY-SA"). An explanation of CC-BY-SA is available at

http://creativecommons.org/licenses/by-sa/3.0/

. In accordance with CC-BY-SA, if you distribute this document or an adaptation of it, you must provide the URL for the original version.

Red Hat, as the licensor of this document, waives the right to enforce, and agrees not to assert, Section 4d of CC-BY-SA to the fullest extent permitted by applicable law.

Red Hat, Red Hat Enterprise Linux, the Shadowman logo, the Red Hat logo, JBoss, OpenShift, Fedora, the Infinity logo, and RHCE are trademarks of Red Hat, Inc., registered in the United States and other countries.

Linux ® is the registered trademark of Linus Torvalds in the United States and other countries.

Java [®] is a registered trademark of Oracle and/or its affiliates.

XFS [®] is a trademark of Silicon Graphics International Corp. or its subsidiaries in the United States and/or other countries.

MySQL ® is a registered trademark of MySQL AB in the United States, the European Union and other countries.

Node.js ® is an official trademark of Joyent. Red Hat is not formally related to or endorsed by the official Joyent Node.js open source or commercial project.

The OpenStack [®] Word Mark and OpenStack logo are either registered trademarks/service marks or trademarks/service marks of the OpenStack Foundation, in the United States and other countries and are used with the OpenStack Foundation's permission. We are not affiliated with, endorsed or sponsored by the OpenStack Foundation, or the OpenStack community.

All other trademarks are the property of their respective owners.

Abstract

The Red Hat Enterprise Linux (RHEL) system roles are a collection of Ansible roles, modules, and playbooks that help automate the consistent and repeatable administration of RHEL systems. With RHEL system roles, you can efficiently manage large inventories of systems by running configuration playbooks from a single system.

Table of Contents

PROVIDING FEEDBACK ON RED HAT DOCUMENTATION	7
CHAPTER 1. INTRODUCTION TO RHEL SYSTEM ROLES	8
CHAPTER 2. PREPARING A CONTROL NODE AND MANAGED NODES TO USE RHEL SYSTEM ROLES 2.1. PREPARING A CONTROL NODE ON RHEL 9 2.2. PREPARING A MANAGED NODE	10 10 12
CHAPTER 3. ANSIBLE VAULT	15
4.1. THE RHEL_MGMT COLLECTION 4.2. USING THE IPMI_BOOT MODULE	18 18 19 20
5.1. THE REDFISH MODULES5.2. REDFISH MODULES PARAMETERS5.3. USING THE REDFISH_INFO MODULE	22 22 23 24 25
CHAPTER 6. REQUESTING CERTIFICATES BY USING RHEL SYSTEM ROLES 6.1. THE CERTIFICATE RHEL SYSTEM ROLE 6.2. REQUESTING A NEW SELF-SIGNED CERTIFICATE BY USING THE CERTIFICATE RHEL SYSTEM ROLE	27 27
6.3. REQUESTING A NEW CERTIFICATE FROM IDM CA BY USING THE CERTIFICATE RHEL SYSTEM ROLE	28
6.4. SPECIFYING COMMANDS TO RUN BEFORE OR AFTER CERTIFICATE ISSUANCE BY USING THE CERTIFICATE RHEL SYSTEM ROLE	29
CHAPTER 7. INSTALLING AND CONFIGURING WEB CONSOLE BY USING RHEL SYSTEM ROLE 7.1. INSTALLING THE WEB CONSOLE BY USING THE COCKPIT RHEL SYSTEM ROLE	31
CHAPTER 8. SETTING A CUSTOM CRYPTOGRAPHIC POLICY BY USING RHEL SYSTEM ROLES	
9.1. RESETTING THE FIREWALLD SETTINGS BY USING THE FIREWALL RHEL SYSTEM ROLE 9.2. FORWARDING INCOMING TRAFFIC IN FIREWALLD FROM ONE LOCAL PORT TO A DIFFERENT LOCAL PORT BY USING THE FIREWALL RHEL SYSTEM ROLE	37 37 L 39 40
 10.1. VARIABLES OF THE HA_CLUSTER RHEL SYSTEM ROLE 10.2. SPECIFYING AN INVENTORY FOR THE HA_CLUSTER RHEL SYSTEM ROLE 10.2.1. Configuring node names and addresses in an inventory 10.2.2. Configuring watchdog and SBD devices in an inventory 10.3. CREATING PCSD TLS CERTIFICATES AND KEY FILES FOR A HIGH AVAILABILITY CLUSTER 10.4. CONFIGURING A HIGH AVAILABILITY CLUSTER RUNNING NO RESOURCES 10.5. CONFIGURING A HIGH AVAILABILITY CLUSTER WITH FENCING AND RESOURCES 10.6. CONFIGURING A HIGH AVAILABILITY CLUSTER WITH RESOURCE AND RESOURCE OPERATION DEFAULTS 	42 42 61 62 63 64 66 68 70

10.8. CONFIGURING A HIGH AVAILABILITY CLUSTER WITH RESOURCE CONSTRAINTS 10.9. CONFIGURING COROSYNC VALUES IN A HIGH AVAILABILITY CLUSTER 10.10. CONFIGURING A HIGH AVAILABILITY CLUSTER WITH SBD NODE FENCING 10.11. CONFIGURING A HIGH AVAILABILITY CLUSTER USING A QUORUM DEVICE 10.11.1. Configuring a quorum device 10.11.2. Configuring a cluster to use a quorum device 10.12. CONFIGURING A HIGH AVAILABILITY CLUSTER WITH NODE ATTRIBUTES 10.13. CONFIGURING AN APACHE HTTP SERVER IN A HIGH AVAILABILITY CLUSTER WITH THE HA_CLURHEL SYSTEM ROLE	72 76 78 79 80 81 82 STER 84
CHAPTER 11. CONFIGURING THE SYSTEMD JOURNAL BY USING RHEL SYSTEM ROLES	89
CHAPTER 12. CONFIGURING AUTOMATIC CRASH DUMPS BY USING RHEL SYSTEM ROLES	. 91 91
CHAPTER 13. CONFIGURING KERNEL PARAMETERS PERMANENTLY BY USING RHEL SYSTEM ROLE 13.1. INTRODUCTION TO THE KERNEL_SETTINGS RHEL SYSTEM ROLE 13.2. APPLYING SELECTED KERNEL PARAMETERS BY USING THE KERNEL_SETTINGS RHEL SYSTEM R	93 93 OLE 94
CHAPTER 14. CONFIGURING THE GRUB 2 BOOT LOADER BY USING RHEL SYSTEM ROLES 14.1. UPDATING THE EXISTING BOOT LOADER ENTRIES BY USING THE BOOTLOADER RHEL SYSTEM R	
14.2. SECURING THE BOOT MENU WITH PASSWORD BY USING THE BOOTLOADER RHEL SYSTEM ROL	E 98
14.3. SETTING A TIMEOUT FOR THE BOOT LOADER MENU BY USING THE BOOTLOADER RHEL SYSTEM ROLE	√I 100
14.4. COLLECTING THE BOOT LOADER CONFIGURATION INFORMATION BY USING THE BOOTLOADE RHEL SYSTEM ROLE	R 103
CHAPTER 15. CONFIGURING LOGGING BY USING RHEL SYSTEM ROLE 15.1. THE LOGGING RHEL SYSTEM ROLE 15.2. APPLYING A LOCAL LOGGING RHEL SYSTEM ROLE 15.3. FILTERING LOGS IN A LOCAL LOGGING RHEL SYSTEM ROLE 15.4. APPLYING A REMOTE LOGGING SOLUTION BY USING THE LOGGING RHEL SYSTEM ROLE 15.5. USING THE LOGGING RHEL SYSTEM ROLE WITH TLS 15.5.1. Configuring client logging with TLS 15.5.2. Configuring server logging with TLS 15.6. USING THE LOGGING RHEL SYSTEM ROLES WITH RELP 15.6.1. Configuring client logging with RELP 15.6.2. Configuring server logging with RELP	106 106 108 110 112 112 114 117 117
CHAPTER 16. MONITORING PERFORMANCE BY USING THE RHEL SYSTEM ROLE 16.1. INTRODUCTION TO THE METRICS RHEL SYSTEM ROLE 16.2. USING THE METRICS RHEL SYSTEM ROLE TO MONITOR YOUR LOCAL SYSTEM WITH VISUALIZAT 16.3. USING THE METRICS RHEL SYSTEM ROLE TO SET UP A FLEET OF INDIVIDUAL SYSTEMS TO MONITOR THEMSELVES 16.4. USING THE METRICS RHEL SYSTEM ROLE TO MONITOR A FLEET OF MACHINES CENTRALLY USI	123 TION 123 124
YOUR LOCAL MACHINE 16.5. SETTING UP AUTHENTICATION WHILE MONITORING A SYSTEM BY USING THE METRICS RHEL SYSTEM ROLE 16.6. USING THE METRICS RHEL SYSTEM ROLE TO CONFIGURE AND ENABLE METRICS COLLECTION	125 126 FOR
SQL SERVER	127

16.7. CONFIGURING PMIE WEBHOOKS USING THE METRICS RHEL SYSTEM ROLE	129
CHAPTER 17. CONFIGURING MICROSOFT SQL SERVER BY USING RHEL SYSTEM ROLES	132
17.1. INSTALLING AND CONFIGURING SQL SERVER WITH AN EXISTING TLS CERTIFICATE BY USING THE MICROSOFT.SQL.SERVER ANSIBLE SYSTEM ROLE	132
17.2. INSTALLING AND CONFIGURING SQL SERVER WITH A TLS CERTIFICATE ISSUED FROM IDM BY US	
THE MICROSOFT.SQL.SERVER ANSIBLE SYSTEM ROLE	134
17.3. INSTALLING AND CONFIGURING SQL SERVER WITH CUSTOM STORAGE PATHS BY USING THE MICROSOFT.SQL.SERVER ANSIBLE SYSTEM ROLE	137
17.4. INSTALLING AND CONFIGURING SQL SERVER WITH AD INTEGRATION BY USING THE MICROSOFT.SQL.SERVER ANSIBLE SYSTEM ROLE	139
CHAPTER 18. CONFIGURING NBDE BY USING RHEL SYSTEM ROLES	143
18.1. USING THE NBDE_SERVER RHEL SYSTEM ROLE FOR SETTING UP MULTIPLE TANG SERVERS	143
18.2. SETTING UP CLEVIS CLIENTS WITH DHCP BY USING THE NBDE_CLIENT RHEL SYSTEM ROLE	144
18.3. SETTING UP STATIC-IP CLEVIS CLIENTS BY USING THE NBDE_CLIENT RHEL SYSTEM ROLE	146
CHAPTER 19. CONFIGURING NETWORK SETTINGS BY USING RHEL SYSTEM ROLES	149
19.1. CONFIGURING AN ETHERNET CONNECTION WITH A STATIC IP ADDRESS BY USING THE NETWORK RHEL SYSTEM ROLE WITH AN INTERFACE NAME	(149
19.2. CONFIGURING AN ETHERNET CONNECTION WITH A STATIC IP ADDRESS BY USING THE NETWOR	
RHEL SYSTEM ROLE WITH A DEVICE PATH	151
19.3. CONFIGURING AN ETHERNET CONNECTION WITH A DYNAMIC IP ADDRESS BY USING THE NETWORK RHEL SYSTEM ROLE WITH AN INTERFACE NAME	ORK 153
19.4. CONFIGURING AN ETHERNET CONNECTION WITH A DYNAMIC IP ADDRESS BY USING THE NETWORK RHEL SYSTEM ROLE WITH A DEVICE PATH	ORK 155
19.5. CONFIGURING VLAN TAGGING BY USING THE NETWORK RHEL SYSTEM ROLE	158
19.6. CONFIGURING A NETWORK BRIDGE BY USING THE NETWORK RHEL SYSTEM ROLE	160
19.7. CONFIGURING A NETWORK BOND BY USING THE NETWORK RHEL SYSTEM ROLE	162
19.8. CONFIGURING AN IPOIB CONNECTION BY USING THE NETWORK RHEL SYSTEM ROLE	164
19.9. ROUTING TRAFFIC FROM A SPECIFIC SUBNET TO A DIFFERENT DEFAULT GATEWAY BY USING TH NETWORK RHEL SYSTEM ROLE	HE 166
19.10. CONFIGURING A STATIC ETHERNET CONNECTION WITH 802.1X NETWORK AUTHENTICATION BY USING THE NETWORK RHEL SYSTEM ROLE	171
19.11. CONFIGURING A WIFI CONNECTION WITH 802.1X NETWORK AUTHENTICATION BY USING THE NETWORK RHEL SYSTEM ROLE	173
19.12. SETTING THE DEFAULT GATEWAY ON AN EXISTING CONNECTION BY USING THE NETWORK RHE	īL.
SYSTEM ROLE	176
19.13. CONFIGURING A STATIC ROUTE BY USING THE NETWORK RHEL SYSTEM ROLE	178
19.14. CONFIGURING AN ETHTOOL OFFLOAD FEATURE BY USING THE NETWORK RHEL SYSTEM ROLE	179
19.15. CONFIGURING AN ETHTOOL COALESCE SETTINGS BY USING THE NETWORK RHEL SYSTEM ROL	.E 181
19.16. INCREASING THE RING BUFFER SIZE TO REDUCE A HIGH PACKET DROP RATE BY USING THE	
NETWORK RHEL SYSTEM ROLE	183
19.17. NETWORK STATES FOR THE NETWORK RHEL SYSTEM ROLE	185
CHAPTER 20. MANAGING CONTAINERS BY USING RHEL SYSTEM ROLES	188
20.1. CREATING A ROOTLESS CONTAINER WITH BIND MOUNT USING THE PODMAN RHEL SYSTEM ROL	_E 188
20.2. CREATING A ROOTFUL CONTAINER WITH PODMAN VOLUME USING THE PODMAN RHEL SYSTEM	
ROLE 20.3. CREATING A QUADLET APPLICATION WITH SECRETS USING THE PODMAN RHEL SYSTEM ROLE	190 192
CHAPTER 21. CONFIGURING POSTFIX MTA BY USING RHEL SYSTEM ROLES	195
21.1. USING THE POSTFIX RHEL SYSTEM ROLE TO AUTOMATE BASIC POSTFIX MTA ADMINISTRATION	195

CHAPTER 22. INSTALLING AND CONFIGURING POSTGRESQL BY USING RHEL SYSTEM ROLES	
22.1. INTRODUCTION TO THE POSTGRESQL RHEL SYSTEM ROLE	197
22.2. CONFIGURING THE POSTGRESQL SERVER BY USING THE POSTGRESQL RHEL SYSTEM ROLE	197
CHAPTER 23. REGISTERING THE SYSTEM BY USING RHEL SYSTEM ROLES	. 199
23.1. INTRODUCTION TO THE RHC RHEL SYSTEM ROLE	199
23.2. REGISTERING A SYSTEM BY USING THE RHC RHEL SYSTEM ROLE	199
23.3. REGISTERING A SYSTEM WITH SATELLITE BY USING THE RHC RHEL SYSTEM ROLE	201
23.4. DISABLING THE CONNECTION TO INSIGHTS AFTER THE REGISTRATION BY USING THE RHC RH	EL
SYSTEM ROLE	202
23.5. ENABLING REPOSITORIES BY USING THE RHC RHEL SYSTEM ROLE	203
23.6. SETTING RELEASE VERSIONS BY USING THE RHC RHEL SYSTEM ROLE	204
23.7. USING A PROXY SERVER WHEN REGISTERING THE HOST BY USING THE RHC RHEL SYSTEM RO	LE
	205
23.8. DISABLING AUTO UPDATES OF INSIGHTS RULES BY USING THE RHC RHEL SYSTEM ROLE	207
23.9. DISABLING INSIGHTS REMEDIATIONS BY USING THE RHC RHEL SYSTEM ROLE	208
23.10. CONFIGURING INSIGHTS TAGS BY USING THE RHC RHEL SYSTEM ROLE	209
23.11. UNREGISTERING A SYSTEM BY USING THE RHC RHEL SYSTEM ROLE	210
CHAPTER 24. CONFIGURING SELINUX BY USING RHEL SYSTEM ROLES	. 212
24.1 INTRODUCTION TO THE SELINUX RHEL SYSTEM ROLE	212
24.2. USING THE SELINUX RHEL SYSTEM ROLE TO APPLY SELINUX SETTINGS ON MULTIPLE SYSTEM	
24.2. OSINO THE SEEMONTHEE STOTEM NOCE TO ALL TEL SEEMON SETTINGS ON MOETH LESTOTEM	212
24.3. MANAGING PORTS BY USING THE SELINUX RHEL SYSTEM ROLE	213
CHAPTER 25. RESTRICTING THE EXECUTION OF APPLICATIONS BY USING THE FAPOLICYD RHEL	
SYSTEM ROLE	. 215
25.1. PREVENTING USERS FROM EXECUTING UNTRUSTWORTHY CODE BY USING THE FAPOLICYD RI	HEL
SYSTEM ROLE	215
CHAPTER 26. CONFIGURING SECURE COMMUNICATION BY USING RHEL SYSTEM ROLES	. 217
26.1. VARIABLES OF THE SSHD RHEL SYSTEM ROLE	217
26.2. CONFIGURING OPENSSH SERVERS BY USING THE SSHD RHEL SYSTEM ROLE	217
26.3. USING THE SSHD RHEL SYSTEM ROLE FOR NON-EXCLUSIVE CONFIGURATION	219
26.4. OVERRIDING THE SYSTEM-WIDE CRYPTOGRAPHIC POLICY ON AN SSH SERVER BY USING THE RHEL SYSTEM ROLE	221
26.5. VARIABLES OF THE SSH RHEL SYSTEM ROLE	222
26.6. CONFIGURING OPENSSH CLIENTS BY USING THE SSH RHEL SYSTEM ROLE	223
CHAPTER 27. MANAGING LOCAL STORAGE BY USING RHEL SYSTEM ROLES	226
27.1. INTRODUCTION TO THE STORAGE RHEL SYSTEM ROLE	226
27.2. CREATING AN XFS FILE SYSTEM ON A BLOCK DEVICE BY USING THE STORAGE RHEL SYSTEM F	
27.2. CREATING AN ALST ILE STSTEM ON A BLOCK DEVICE BY USING THE STORAGE RITLE STSTEM P	227
27.3. PERSISTENTLY MOUNTING A FILE SYSTEM BY USING THE STORAGE RHEL SYSTEM ROLE	228
27.4. MANAGING LOGICAL VOLUMES BY USING THE STORAGE RHEL SYSTEM ROLE	229
27.5. ENABLING ONLINE BLOCK DISCARD BY USING THE STORAGE RHEL SYSTEM ROLE	230
27.6. CREATING AND MOUNTING AN EXT4 FILE SYSTEM BY USING THE STORAGE RHEL SYSTEM ROI	_E
	231
27.7. CREATING AND MOUNTING AN EXT3 FILE SYSTEM BY USING THE STORAGE RHEL SYSTEM ROL	-E
	232
27.8. RESIZING AN EXISTING FILE SYSTEM ON LVM BY USING THE STORAGE RHEL SYSTEM ROLE	233
27.9. CREATING A SWAP VOLUME BY USING THE STORAGE RHEL SYSTEM ROLE	234
27.10. CONFIGURING A RAID VOLUME BY USING THE STORAGE RHEL SYSTEM ROLE	235
27.11. CONFIGURING AN LVM POOL WITH RAID BY USING THE STORAGE RHEL SYSTEM ROLE	236
27.12. CONFIGURING A STRIPE SIZE FOR RAID LVM VOLUMES BY USING THE STORAGE RHEL SYSTEM	1
ROLE	237

27.13. COMPRESSING AND DEDUPLICATING A VDO VOLUME ON LVM BY USING THE STORAGE RHEL SYSTEM ROLE	238
27.14. CREATING A LUKS2 ENCRYPTED VOLUME BY USING THE STORAGE RHEL SYSTEM ROLE	240
27.15. EXPRESSING POOL VOLUME SIZES AS PERCENTAGE BY USING THE STORAGE RHEL SYSTEM RO	DLE 241
CHAPTER 28. MANAGING SYSTEMD UNITS BY USING RHEL SYSTEM ROLES	243
28.1. MANAGING SERVICES BY USING THE SYSTEMD RHEL SYSTEM ROLE	243
28.2. DEPLOYING SYSTEMD DROP-IN FILES BY USING THE SYSTEMD RHEL SYSTEM ROLE	244
28.3. DEPLOYING SYSTEMD UNITS BY USING THE SYSTEMD RHEL SYSTEM ROLE	246
CHAPTER 29. CONFIGURING TIME SYNCHRONIZATION BY USING RHEL SYSTEM ROLES	248
29.1. CONFIGURING TIME SYNCHRONIZATION OVER NTP BY USING THE TIMESYNC RHEL SYSTEM ROL	E 248
29.2. CONFIGURING TIME SYNCHRONIZATION OVER NTP WITH NTS BY USING THE TIMESYNC RHEL SYSTEM ROLE	250
CHAPTER 30. CONFIGURING A SYSTEM FOR SESSION RECORDING BY USING RHEL SYSTEM ROLES	253
30.1. CONFIGURING SESSION RECORDING FOR INDIVIDUAL USERS BY USING THE TLOG	
RHEL SYSTEM ROLE	253
30.2. EXCLUDING CERTAIN USERS AND GROUPS FROM SESSION RECORDING BY USING THE THE TLOGRIED RHEL SYSTEM ROLE	G 254
CHAPTER 31. CONFIGURING VPN CONNECTIONS WITH IPSEC BY USING RHEL SYSTEM ROLES	257
31.1. CREATING A HOST-TO-HOST VPN WITH IPSEC BY USING THE VPN RHEL SYSTEM ROLE	257
31.2. CREATING AN OPPORTUNISTIC MESH VPN CONNECTION WITH IPSEC BY USING THE VPN RHEL SYSTEM ROLE	259

PROVIDING FEEDBACK ON RED HAT DOCUMENTATION

We appreciate your feedback on our documentation. Let us know how we can improve it.

Submitting feedback through Jira (account required)

- 1. Log in to the Jira website.
- 2. Click **Create** in the top navigation bar
- 3. Enter a descriptive title in the **Summary** field.
- 4. Enter your suggestion for improvement in the **Description** field. Include links to the relevant parts of the documentation.
- 5. Click **Create** at the bottom of the dialogue.

CHAPTER 1. INTRODUCTION TO RHEL SYSTEM ROLES

By using RHEL system roles, you can remotely manage the system configurations of multiple RHEL systems across major versions of RHEL.

Important terms and concepts

The following describes important terms and concepts in an Ansible environment:

Control node

A control node is the system from which you run Ansible commands and playbooks. Your control node can be an Ansible Automation Platform, Red Hat Satellite, or a RHEL 9, 8, or 7 host. For more information, see Preparing a control node on RHEL 9.

Managed node

Managed nodes are the servers and network devices that you manage with Ansible. Managed nodes are also sometimes called hosts. Ansible does not have to be installed on managed nodes. For more information, see Preparing a managed node.

Ansible playbook

In a playbook, you define the configuration you want to achieve on your managed nodes or a set of steps for the system on the managed node to perform. Playbooks are Ansible's configuration, deployment, and orchestration language.

Inventory

In an inventory file, you list the managed nodes and specify information such as IP address for each managed node. In the inventory, you can also organize the managed nodes by creating and nesting groups for easier scaling. An inventory file is also sometimes called a hostfile.

Available roles on a Red Hat Enterprise Linux 9 control node

On a Red Hat Enterprise Linux 9 control node, the **rhel-system-roles** package provides the following roles:

Role name	Role description	Chapter title
certificate	Certificate Issuance and Renewal	Requesting certificates by using RHEL system roles
cockpit	Web console	Installing and configuring web console with the cockpit RHEL system role
crypto_policies	System-wide cryptographic policies	Setting a custom cryptographic policy across systems
firewall	Firewalld	Configuring firewalld by using system roles
ha_cluster	HA Cluster	Configuring a high-availability cluster by using system roles
kdump	Kernel Dumps	Configuring kdump by using RHEL system roles

Role name	Role description	Chapter title
kernel_settings	Kernel Settings	Using Ansible roles to permanently configure kernel parameters
logging	Logging	Using the logging system role
metrics	Metrics (PCP)	Monitoring performance by using RHEL system roles
network	Networking	Using the network RHEL system role to manage InfiniBand connections
nbde_client	Network Bound Disk Encryption client	Using the nbde_client and nbde_server system roles
nbde_server	Network Bound Disk Encryption server	Using the nbde_client and nbde_server system roles
postfix	Postfix	Variables of the postfix role in system roles
postgresql	PostgreSQL	Installing and configuring PostgreSQL by using the postgresql RHEL system role
selinux	SELinux	Configuring SELinux by using system roles
ssh	SSH client	Configuring secure communication with the ssh system roles
sshd	SSH server	Configuring secure communication with the ssh system roles
storage	Storage	Managing local storage by using RHEL system roles
tlog	Terminal Session Recording	Configuring a system for session recording by using the tlog RHEL system role
timesync	Time Synchronization	Configuring time synchronization by using RHEL system roles
vpn	VPN	Configuring VPN connections with IPsec by using the vpn RHEL system role

Additional resources

- Red Hat Enterprise Linux (RHEL) system roles
- /usr/share/ansible/roles/rhel-system-roles.</re>
- /usr/share/doc/rhel-system-roles/<role_name>/ directory

CHAPTER 2. PREPARING A CONTROL NODE AND MANAGED NODES TO USE RHEL SYSTEM ROLES

Before you can use individual RHEL system roles to manage services and settings, you must prepare the control node and managed nodes.

2.1. PREPARING A CONTROL NODE ON RHEL 9

Before using RHEL system roles, you must configure a control node. This system then configures the managed hosts from the inventory according to the playbooks.

Prerequisites

- The system is registered to the Customer Portal.
- A **Red Hat Enterprise Linux Server** subscription is attached to the system.
- Optional: An **Ansible Automation Platform** subscription is attached to the system.

Procedure

- 1. Create a user named **ansible** to manage and run playbooks:
 - [root@control-node]# useradd ansible
- 2. Switch to the newly created **ansible** user:
 - [root@control-node]# su ansible

Perform the rest of the procedure as this user.

3. Create an SSH public and private key:

```
[ansible@control-node]$ ssh-keygen
Generating public/private rsa key pair.
Enter file in which to save the key (/home/ansible/.ssh/id_rsa):
Enter passphrase (empty for no passphrase): password>
Enter same passphrase again: cpassword>
...
```

Use the suggested default location for the key file.

- 4. Optional: To prevent Ansible from prompting you for the SSH key password each time you establish a connection, configure an SSH agent.
- 5. Create the ~/.ansible.cfg file with the following content:

```
[defaults]
inventory = /home/ansible/inventory
remote_user = ansible

[privilege_escalation]
become = True
```

become_method = sudo become_user = root become_ask_pass = True



NOTE

Settings in the ~/.ansible.cfg file have a higher priority and override settings from the global /etc/ansible/ansible.cfg file.

With these settings, Ansible performs the following actions:

- Manages hosts in the specified inventory file.
- Uses the account set in the remote_user parameter when it establishes SSH connections to managed nodes.
- Uses the sudo utility to execute tasks on managed nodes as the root user.
- Prompts for the root password of the remote user every time you apply a playbook. This is recommended for security reasons.
- 6. Create an ~/inventory file in INI or YAML format that lists the hostnames of managed hosts. You can also define groups of hosts in the inventory file. For example, the following is an inventory file in the INI format with three hosts and one host group named US:

managed-node-01.example.com

[US]

managed-node-02.example.com ansible_host=192.0.2.100 managed-node-03.example.com

Note that the control node must be able to resolve the hostnames. If the DNS server cannot resolve certain hostnames, add the **ansible_host** parameter next to the host entry to specify its IP address.

- 7. Install RHEL system roles:
 - On a RHEL host without Ansible Automation Platform, install the rhel-system-roles package:
 - [root@control-node]# dnf install rhel-system-roles

This command installs the collections in the /usr/share/ansible/collections/ansible_collections/redhat/rhel_system_roles/ directory, and the ansible-core package as a dependency.

- On Ansible Automation Platform, perform the following steps as the ansible user:
 - i. Define Red Hat automation hub as the primary source for content in the ~/.ansible.cfg file.
 - ii. Install the **redhat.rhel_system_roles** collection from Red Hat automation hub:

[ansible@control-node]\$ ansible-galaxy collection install redhat.rhel_system_roles

This command installs the collection in the

~/.ansible/collections/ansible_collections/redhat/rhel_system_roles/ directory.

Next step

• Prepare the managed nodes. For more information, see Preparing a managed node.

Additional resources

- Scope of support for the Ansible Core package included in the RHEL 9 and RHEL 8.6 and later AppStream repositories
- How to register and subscribe a system to the Red Hat Customer Portal using subscriptionmanager (Red Hat Knowledgebase)
- The **ssh-keygen(1)** manual page
- Connecting to remote machines with SSH keys using ssh-agent
- Ansible configuration settings
- How to build your inventory

2.2. PREPARING A MANAGED NODE

Managed nodes are the systems listed in the inventory and which will be configured by the control node according to the playbook. You do not have to install Ansible on managed hosts.

Prerequisites

- You prepared the control node. For more information, see Preparing a control node on RHEL 9.
- You have SSH access from the control node.



IMPORTANT

Direct SSH access as the **root** user is a security risk. To reduce this risk, you will create a local user on this node and configure a **sudo** policy when preparing a managed node. Ansible on the control node can then use the local user account to log in to the managed node and run playbooks as different users, such as **root**.

Procedure

1. Create a user named ansible:

[root@managed-node-01]# useradd ansible

The control node later uses this user to establish an SSH connection to this host.

2. Set a password for the **ansible** user:

[root@managed-node-01]# **passwd ansible** Changing password for user ansible. New password: **<password>** Retype new password: password
password
authentication tokens updated successfully.

You must enter this password when Ansible uses **sudo** to perform tasks as the **root** user.

- 3. Install the **ansible** user's SSH public key on the managed node:
 - a. Log in to the control node as the **ansible** user, and copy the SSH public key to the managed node:

[ansible@control-node]\$ ssh-copy-id managed-node-01.example.com

/usr/bin/ssh-copy-id: INFO: Source of key(s) to be installed:

"/home/ansible/.ssh/id_rsa.pub"

The authenticity of host 'managed-node-01.example.com (192.0.2.100)' can't be established.

ECDSA key fingerprint is

SHA256:9bZ33GJNODK3zbNhybokN/6Mq7hu3vpBXDrCxe7NAvo.

b. When prompted, connect by entering **yes**:

Are you sure you want to continue connecting (yes/no/[fingerprint])? yes

/usr/bin/ssh-copy-id: INFO: attempting to log in with the new key(s), to filter out any that are already installed

/usr/bin/ssh-copy-id: INFO: 1 key(s) remain to be installed -- if you are prompted now it is to install the new keys

c. When prompted, enter the password:

ansible@managed-node-01.example.com's password:

Number of key(s) added: 1

Now try logging into the machine, with: "ssh 'managed-node-01.example.com" and check to make sure that only the key(s) you wanted were added.

d. Verify the SSH connection by remotely executing a command on the control node:

[ansible@control-node]\$ **ssh managed-node-01.example.com whoami** ansible

- 4. Create a **sudo** configuration for the **ansible** user:
 - a. Create and edit the /etc/sudoers.d/ansible file by using the visudo command:

[root@managed-node-01]# visudo /etc/sudoers.d/ansible

The benefit of using **visudo** over a normal editor is that this utility provides basic checks, such as for parse errors, before installing the file.

- b. Configure a **sudoers** policy in the /**etc/sudoers.d/ansible** file that meets your requirements, for example:
 - To grant permissions to the **ansible** user to run all commands as any user and group on this host after entering the **ansible** user's password, use:

```
ansible ALL=(ALL) ALL
```

• To grant permissions to the **ansible** user to run all commands as any user and group on this host without entering the **ansible** user's password, use:

```
ansible ALL=(ALL) NOPASSWD: ALL
```

Alternatively, configure a more fine-granular policy that matches your security requirements. For further details on **sudoers** policies, see the **sudoers(5)** manual page.

Verification

1. Verify that you can execute commands from the control node on an all managed nodes:

The hard-coded all group dynamically contains all hosts listed in the inventory file.

2. Verify that privilege escalation works correctly by running the **whoami** utility on all managed nodes by using the Ansible **command** module:

```
[ansible@control-node]$ ansible all -m command -a whoami
BECOME password: cpassword>
managed-node-01.example.com | CHANGED | rc=0 >>
root
...
```

If the command returns root, you configured **sudo** on the managed nodes correctly.

Additional resources

- Preparing a control node on RHEL 9
- **sudoers(5)** manual page

CHAPTER 3. ANSIBLE VAULT

Sometimes your playbook needs to use sensitive data such as passwords, API keys, and other secrets to configure managed hosts. Storing this information in plain text in variables or other Ansible-compatible files is a security risk because any user with access to those files can read the sensitive data.

With Ansible vault, you can encrypt, decrypt, view, and edit sensitive information. They could be included as:

- Inserted variable files in an Ansible Playbook
- Host and group variables
- Variable files passed as arguments when executing the playbook
- Variables defined in Ansible roles

You can use Ansible vault to securely manage individual variables, entire files, or even structured data like YAML files. This data can then be safely stored in a version control system or shared with team members without exposing sensitive information.



IMPORTANT

Files are protected with symmetric encryption of the Advanced Encryption Standard (AES256), where a single password or passphrase is used both to encrypt and decrypt the data. Note that the way this is done has not been formally audited by a third party.

To simplify management, it makes sense to set up your Ansible project so that sensitive variables and all other variables are kept in separate files, or directories. Then you can protect the files containing sensitive variables with the **ansible-vault** command.

Creating an encrypted file

The following command prompts you for a new vault password. Then it opens a file for storing sensitive variables using the default editor.

ansible-vault create vault.yml

New Vault password: <vault password>

Confirm New Vault password: <vault password>

Viewing an encrypted file

The following command prompts you for your existing vault password. Then it displays the sensitive contents of an already encrypted file.

ansible-vault view vault.yml

Vault password: <vault_password>

my_secret: "yJJvPqhsiusmmPPZdnjndkdnYNDjdj782meUZcw"

Editing an encrypted file

The following command prompts you for your existing vault password. Then it opens the already encrypted file for you to update the sensitive variables using the default editor.

ansible-vault edit vault.yml

Vault password: <vault password>

Encrypting an existing file

The following command prompts you for a new vault password. Then it encrypts an existing unencrypted

ansible-vault encrypt vault.yml

New Vault password: <vault password>

Confirm New Vault password: <vault_password>

Encryption successful

Decrypting an existing file

The following command prompts you for your existing vault password. Then it decrypts an existing encrypted file.

ansible-vault decrypt vault.yml

Vault password: <vault password>

Decryption successful

Changing the password of an encrypted file

The following command prompts you for your original vault password, then for the new vault password.

ansible-vault rekey vault.yml

Vault password: <vault password> New Vault password: <vault_password>

Confirm New Vault password: <vault_password>

Rekey successful

Basic application of Ansible vault variables in a playbook

- name: Create user accounts for all servers hosts: managed-node-01.example.com vars files:

vault.yml

tasks:

- name: Create user from vault.yml file

name: "{{ username }}" password: "{{ pwhash }}"

You read-in the file with variables (vault.yml) in the vars_files section of your Ansible Playbook, and you use the curly brackets the same way you would do with your ordinary variables. Then you either run the playbook with the ansible-playbook --ask-vault-pass command and you enter the password manually. Or you save the password in a separate file and you run the playbook with the ansibleplaybook --vault-password-file /path/to/my/vault-password-file command.

Additional resources

ansible-vault(1), ansible-playbook(1) man pages on your system

- Ansible vault
- Ansible vault Best Practices

CHAPTER 4. ANSIBLE IPMI MODULES IN RHEL

4.1. THE RHEL_MGMT COLLECTION

The Intelligent Platform Management Interface (IPMI) is a specification for a set of standard protocols to communicate with baseboard management controller (BMC) devices. The **IPMI** modules allow you to enable and support hardware management automation. The **IPMI** modules are available in:

- The rhel mgmt Collection. The package name is ansible-collection-redhat-rhel mgmt.
- The RHEL 8 AppStream, as part of the new **ansible-collection-redhat-rhel_mgmt** package.

The following IPMI modules are available in the rhel_mgmt collection:

- **ipmi_boot**: Management of boot device order
- **ipmi_power**: Power management for machine

The mandatory parameters used for the IPMI Modules are:

• **ipmi_boot** parameters:

Module name	Description
name	Hostname or ip address of the BMC
password	Password to connect to the BMC
bootdev	Device to be used on next boot
	* network
	* floppy
	* hd
	* safe
	* optical
	* setup
	* default
User	Username to connect to the BMC

ipmi_power parameters:

Module name	Description
name	BMC Hostname or IP address

Module name	Description
password	Password to connect to the BMC
user	Username to connect to the BMC
State	Check if the machine is on the desired status
	* on
	* off
	* shutdown
	* reset
	* boot

4.2. USING THE IPMI_BOOT MODULE

The following example shows how to use the **ipmi_boot** module in a playbook to set a boot device for the next boot. For simplicity, the examples use the same host as the Ansible control host and managed host, thus executing the modules on the same host where the playbook is executed.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- The **ansible-collection-redhat-rhel mgmt** package is installed.
- The **python3-pyghmi** package is installed either on the control node or the managed nodes.
- The IPMI BMC that you want to control is accessible over network from the control node or the
 managed host (if not using localhost as the managed host). Note that the host whose BMC is
 being configured by the module is generally different from the managed host, as the module
 contacts the BMC over the network using the IPMI protocol.
- You have credentials to access BMC with an appropriate level of access.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

.-...

 name: Set boot device to be used on next boot hosts: managed-node-01.example.com tasks:

name: Ensure boot device is HD redhat.rhel_mgmt.ipmi_boot:

user: <admin_user>
password: <password>

bootdev: hd

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

• When you run the playbook, Ansible returns **success**.

Additional resources

• /usr/share/ansible/collections/ansible collections/redhat/rhel mgmt/README.md file

4.3. USING THE IPMI_POWER MODULE

This example shows how to use the **ipmi_boot** module in a playbook to check if the system is turned on. For simplicity, the examples use the same host as the Ansible control host and managed host, thus executing the modules on the same host where the playbook is executed.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- The ansible-collection-redhat-rhel_mgmt package is installed.
- The **python3-pyghmi** package is installed either on the control node or the managed nodes.
- The IPMI BMC that you want to control is accessible over network from the control node or the
 managed host (if not using **localhost** as the managed host). Note that the host whose BMC is
 being configured by the module is generally different from the managed host, as the module
 contacts the BMC over the network using the IPMI protocol.
- You have credentials to access BMC with an appropriate level of access.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

- name: Power management

hosts: managed-node-01.example.com tasks:

- name: Ensure machine is powered on redhat.rhel_mgmt.ipmi_power:

user: <admin_user>
password: <password>

state: on

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

• When you run the playbook, Ansible returns **true**.

Additional resources

• /usr/share/ansible/collections/ansible_collections/redhat/rhel_mgmt/README.md file

CHAPTER 5. THE REDFISH MODULES IN RHEL

The Redfish modules for remote management of devices are now part of the **redhat.rhel_mgmt** Ansible collection. With the Redfish modules, you can easily use management automation on baremetal servers and platform hardware by getting information about the servers or control them through an Out-Of-Band (OOB) controller, using the standard HTTPS transport and JSON format.

5.1. THE REDFISH MODULES

The **redhat.rhel_mgmt** Ansible collection provides the Redfish modules to support hardware management in Ansible over Redfish. The **redhat.rhel_mgmt** collection is available in the **ansible-collection-redhat-rhel_mgmt** package. To install it, see Installing the redhat.rhel_mgmt Collection using the CLI.

The following Redfish modules are available in the **redhat.rhel_mgmt** collection:

- 1. **redfish_info**: The **redfish_info** module retrieves information about the remote Out-Of-Band (OOB) controller such as systems inventory.
- redfish_command: The redfish_command module performs Out-Of-Band (OOB) controller operations like log management and user management, and power operations such as system restart, power on and off.
- 3. **redfish_config**: The **redfish_config** module performs OOB controller operations such as changing OOB configuration, or setting the BIOS configuration.

5.2. REDFISH MODULES PARAMETERS

The parameters used for the Redfish modules are:

redfish_info parameters:	Description
baseuri	(Mandatory) - Base URI of OOB controller.
category	(Mandatory) - List of categories to execute on OOB controller. The default value is ["Systems"].
command	(Mandatory) - List of commands to execute on OOB controller.
username	Username for authentication to OOB controller.
password	Password for authentication to OOB controller.

redfish_command parameters:	Description
baseuri	(Mandatory) - Base URI of OOB controller.
category	(Mandatory) - List of categories to execute on OOB controller. The default value is ["Systems"].

redfish_command parameters: Description

command	(Mandatory) - List of commands to execute on OOB controller.
username	Username for authentication to OOB controller.
password	Password for authentication to OOB controller.

redfish_config parameters:	Description
baseuri	(Mandatory) - Base URI of OOB controller.
category	(Mandatory) - List of categories to execute on OOB controller. The default value is ["Systems"].
command	(Mandatory) - List of commands to execute on OOB controller.
username	Username for authentication to OOB controller.
password	Password for authentication to OOB controller.
bios_attributes	BIOS attributes to update.

5.3. USING THE REDFISH_INFO MODULE

The following example shows how to use the **redfish_info** module in a playbook to get information about the CPU inventory. For simplicity, the example uses the same host as the Ansible control host and managed host, thus executing the modules on the same host where the playbook is executed.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- The ansible-collection-redhat-rhel_mgmt package is installed.
- The **python3-pyghmi** package is installed either on the control node or the managed nodes.
- OOB controller access details.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

- name: Manage out-of-band controllers using Redfish APIs

hosts: managed-node-01.example.com

tasks:

name: Get CPU inventory redhat.rhel_mgmt.redfish_info:

baseuri: "<URI>"

username: "<username>" password: "<password>"

category: Systems

command: GetCpuInventory

register: result

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

• When you run the playbook, Ansible returns the CPU inventory details.

Additional resources

• /usr/share/ansible/collections/ansible_collections/redhat/rhel_mgmt/README.md file

5.4. USING THE REDFISH COMMAND MODULE

The following example shows how to use the **redfish_command** module in a playbook to turn on a system. For simplicity, the example uses the same host as the Ansible control host and managed host, thus executing the modules on the same host where the playbook is executed.

Prerequisites

- You have prepared the control node and the managed nodes.
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- The **ansible-collection-redhat-rhel_mgmt** package is installed.
- The python3-pyghmi package is installed either on the control node or the managed nodes.
- OOB controller access details.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

- name: Manage out-of-band controllers using Redfish APIs

hosts: managed-node-01.example.com

tasks:

- name: Power on system

redhat.rhel_mgmt.redfish_command:

baseuri: "<URI>"

username: "<username>" password: "<password>" category: Systems

command: PowerOn

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

• The system powers on.

Additional resources

/usr/share/ansible/collections/ansible collections/redhat/rhel mgmt/README.md file

5.5. USING THE REDFISH_CONFIG MODULE

The following example shows how to use the **redfish_config** module in a playbook to configure a system to boot with UEFI. For simplicity, the example uses the same host as the Ansible control host and managed host, thus executing the modules on the same host where the playbook is executed.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- The ansible-collection-redhat-rhel_mgmt package is installed.
- The **python3-pyghmi** package is installed either on the control node or the managed nodes.
- OOB controller access details.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

• The system boot mode is set to UEFI.

Additional resources

/usr/share/ansible/collections/ansible_collections/redhat/rhel_mgmt/README.md file

CHAPTER 6. REQUESTING CERTIFICATES BY USING RHEL SYSTEM ROLES

You can use the **certificate** system role to issue and manage certificates.

6.1. THE CERTIFICATE RHEL SYSTEM ROLE

Using the **certificate** system role, you can manage issuing and renewing TLS and SSL certificates using Ansible Core.

The role uses **certmonger** as the certificate provider, and currently supports issuing and renewing self-signed certificates and using the IdM integrated certificate authority (CA).

You can use the following variables in your Ansible playbook with the **certificate** system role:

certificate wait

to specify if the task should wait for the certificate to be issued.

certificate requests

to represent each certificate to be issued and its parameters.

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.certificate/README.md file
- /usr/share/doc/rhel-system-roles/certificate/ directory

6.2. REQUESTING A NEW SELF-SIGNED CERTIFICATE BY USING THE CERTIFICATE RHEL SYSTEM ROLE

With the **certificate** system role, you can use Ansible Core to issue self-signed certificates.

This process uses the **certmonger** provider and requests the certificate through the **getcert** command.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

hosts: managed-node-01.example.com roles:
 rhel-system-roles.certificate vars:
 certificate requests:

name: mycert dns: "*.example.com"

ca: self-sign

- Set the **name** parameter to the desired name of the certificate, such as **mycert**.
- Set the **dns** parameter to the domain to be included in the certificate, such as
 *.example.com.
- Set the ca parameter to self-sign.

By default, **certmonger** automatically tries to renew the certificate before it expires. You can disable this by setting the **auto_renew** parameter in the Ansible playbook to **no**.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.certificate/README.md file
- /usr/share/doc/rhel-system-roles/certificate/ directory

6.3. REQUESTING A NEW CERTIFICATE FROM IDM CA BY USING THE CERTIFICATE RHEL SYSTEM ROLE

With the **certificate** system role, you can use **anible-core** to issue certificates while using an IdM server with an integrated certificate authority (CA). Therefore, you can efficiently and consistently manage the certificate trust chain for multiple systems when using IdM as the CA.

This process uses the **certmonger** provider and requests the certificate through the **getcert** command.

Prerequisites

- You have prepared the control node and the managed nodes.
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

- hosts: managed-node-01.example.com

roles:

- rhel-system-roles.certificate

vars

certificate_requests:

- name: mycert

dns: www.example.com

principal: HTTP/www.example.com@EXAMPLE.COM

ca: ipa

- Set the **name** parameter to the desired name of the certificate, such as **mycert**.
- Set the dns parameter to the domain to be included in the certificate, such as www.example.com.
- Set the **principal** parameter to specify the Kerberos principal, such as **HTTP/www.example.com@EXAMPLE.COM**.
- Set the **ca** parameter to **ipa**.

By default, **certmonger** automatically tries to renew the certificate before it expires. You can disable this by setting the **auto_renew** parameter in the Ansible playbook to **no**.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.certificate/README.md file
- /usr/share/doc/rhel-system-roles/certificate/ directory

6.4. SPECIFYING COMMANDS TO RUN BEFORE OR AFTER CERTIFICATE ISSUANCE BY USING THE CERTIFICATE RHEL SYSTEM ROLE

With the **certificate** Role, you can use Ansible Core to execute a command before and after a certificate is issued or renewed.

In the following example, the administrator ensures stopping the **httpd** service before a self-signed certificate for **www.example.com** is issued or renewed, and restarting it afterwards.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.

The account you use to connect to the managed nodes has sudo permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

- hosts: managed-node-01.example.com

- rhel-system-roles.certificate

vars

certificate_requests:

- name: mycert

dns: www.example.com

ca: self-sign

run_before: systemctl stop httpd.service run_after: systemctl start httpd.service

- Set the **name** parameter to the desired name of the certificate, such as **mycert**.
- Set the dns parameter to the domain to be included in the certificate, such as www.example.com.
- Set the **ca** parameter to the CA you want to use to issue the certificate, such as **self-sign**.
- Set the **run_before** parameter to the command you want to execute before this certificate is issued or renewed, such as **systemctl stop httpd.service**.
- Set the **run_after** parameter to the command you want to execute after this certificate is issued or renewed, such as **systemctl start httpd.service**.

By default, **certmonger** automatically tries to renew the certificate before it expires. You can disable this by setting the **auto_renew** parameter in the Ansible playbook to **no**.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.certificate/README.md file
- /usr/share/doc/rhel-system-roles/certificate/ directory

CHAPTER 7. INSTALLING AND CONFIGURING WEB CONSOLE BY USING RHEL SYSTEM ROLES

With the **cockpit** RHEL system role, you can automatically deploy and enable the web console on multiple RHEL systems.

7.1. INSTALLING THE WEB CONSOLE BY USING THECOCKPIT RHEL SYSTEM ROLE

You can use the **cockpit** system role to automate installing and enabling the RHEL web console on multiple systems.

In this example, you use the **cockpit** system role to:

- Install the RHEL web console.
- Configure the web console to use a custom port number (9050/tcp). By default, the web console uses port 9090.
- Allow the **firewalld** and **selinux** system roles to configure the system for opening new ports.
- Set the web console to use a certificate from the **ipa** trusted certificate authority instead of using a self-signed certificate.



NOTE

You do not have to call the **firewall** or **certificate** system roles in the playbook to manage the firewall or create the certificate. The **cockpit** system role calls them automatically as needed.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example, ~/playbook.yml, with the following content:

 name: Manage the RHEL web console hosts: managed-node-01.example.com tasks:

- name: Install RHEL web console ansible.builtin.include_role:

name: rhel-system-roles.cockpit

vars:

cockpit_packages: default

cockpit_port: 9050

cockpit_manage_selinux: true cockpit_manage_firewall: true

cockpit_certificates:

 name: /etc/cockpit/ws-certs.d/01-certificate dns: ['localhost', 'www.example.com'] ca: ipa

The settings specified in the example playbook include the following:

cockpit_manage_selinux: true

Allow using the **selinux** system role to configure SELinux for setting up the correct port permissions on the **websm_port_t** SELinux type.

cockpit manage firewall: true

Allow the **cockpit** system role to use the **firewalld** system role for adding ports.

cockpit_certificates: <YAML_dictionary>

By default, the RHEL web console uses a self-signed certificate. Alternatively, you can add the **cockpit_certificates** variable to the playbook and configure the role to request certificates from an IdM certificate authority (CA) or to use an existing certificate and private key that is available on the managed node.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.cockpit/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.cockpit/README.md file
- /usr/share/doc/rhel-system-roles/cockpit directory
- Requesting certificates using RHEL system roles

CHAPTER 8. SETTING A CUSTOM CRYPTOGRAPHIC POLICY BY USING RHEL SYSTEM ROLES

Custom cryptographic policies are a set of rules and configurations that manage the use of cryptographic algorithms and protocols. These policies help you to maintain a protected, consistent, and manageable security environment across multiple systems and applications.

By using the **crypto_policies** RHEL system role, you can quickly and consistently configure custom cryptographic policies across many operating systems in an automated fashion.

8.1. ENHANCING SECURITY WITH THE FUTURE CRYPTOGRAPHIC POLICY USING THE CRYPTO_POLICIES RHEL SYSTEM ROLE

You can use the **crypto_policies** RHEL system role to configure the **FUTURE** policy on your managed nodes. This policy helps to achieve for example:

- Future-proofing against emerging threats: anticipates advancements in computational power.
- Enhanced security: stronger encryption standards require longer key lengths and more secure algorithms.
- Compliance with high-security standards: for example in healthcare, telco, and finance the data sensitivity is high, and availability of strong cryptography is critical.

Typically, **FUTURE** is suitable for environments handling highly sensitive data, preparing for future regulations, or adopting long-term security strategies.



WARNING

Legacy systems or software does not have to support the more modern and stricter algorithms and protocols enforced by the **FUTURE** policy. For example, older systems might not support TLS 1.3 or larger key sizes. This could lead to compatibility problems.

Also, using strong algorithms usually increases the computational workload, which could negatively affect your system performance.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

 name: Configure cryptographic policies hosts: managed-node-01.example.com

- name: Configure the FUTURE cryptographic security policy on the managed node ansible.builtin.include role:

name: rhel-system-roles.crypto_policies

vars:

- crypto_policies_policy: FUTURE- crypto_policies_reboot_ok: true

The settings specified in the example playbook include the following:

crypto_policies_policy: FUTURE

Configures the required cryptographic policy (**FUTURE**) on the managed node. It can be either the base policy or a base policy with some sub-policies. The specified base policy and sub-policies have to be available on the managed node. The default value is **null**. It means that the configuration is not changed and the **crypto_policies** RHEL system role will only collect the Ansible facts.

crypto_policies_reboot_ok: true

Causes the system to reboot after the cryptographic policy change to make sure all of the services and applications will read the new configuration files. The default value is **false**.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.crypto_policies/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml



WARNING

Because the **FIPS:OSPP** system-wide subpolicy contains further restrictions for cryptographic algorithms required by the Common Criteria (CC) certification, the system is less interoperable after you set it. For example, you cannot use RSA and DH keys shorter than 3072 bits, additional SSH algorithms, and several TLS groups. Setting **FIPS:OSPP** also prevents connecting to Red Hat Content Delivery Network (CDN) structure. Furthermore, you cannot integrate Active Directory (AD) into the IdM deployments that use **FIPS:OSPP**, communication between RHEL hosts using **FIPS:OSPP** and AD domains might not work, or some AD accounts might not be able to authenticate.

Note that your **system is not CC-compliant** after you set the **FIPS:OSPP** cryptographic subpolicy. The only correct way to make your RHEL system compliant with the CC standard is by following the guidance provided in the **cc-config** package. See the Common Criteria section in the Compliance Activities and Government Standards Knowledgebase article for a list of certified RHEL versions, validation reports, and links to CC guides hosted at the National Information Assurance Partnership (NIAP) website.

Verification

1. On the control node, create another playbook named, for example, **verify_playbook.yml**:

- name: Verification

hosts: managed-node-01.example.com

tasks:

- name: Verify active cryptographic policy

ansible.builtin.include_role:

name: rhel-system-roles.crypto_policies

- name: Display the currently active cryptographic policy

ansible.builtin.debug:

var: crypto_policies_active

The settings specified in the example playbook include the following:

crypto_policies_active

An exported Ansible fact that contains the currently active policy name in the format as accepted by the **crypto_policies_policy** variable.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/verify_playbook.yml

3. Run the playbook:

```
$ ansible-playbook ~/verify_playbook.yml
TASK [debug] ********************
ok: [host] => {
```

```
"crypto_policies_active": "FUTURE"
}
```

The **crypto_policies_active** variable shows the active policy on the managed node.

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.crypto_policies/README.md file
- /usr/share/doc/rhel-system-roles/crypto_policies/ directory
- update-crypto-policies(8) and crypto-policies(7) manual pages

CHAPTER 9. CONFIGURING FIREWALLD BY USING RHEL SYSTEM ROLES

RHEL system roles is a set of contents for the Ansible automation utility. This content together with the Ansible automation utility provides a consistent configuration interface to remotely manage multiple systems at once.

The **rhel-system-roles** package contains the **rhel-system-roles.firewall** RHEL system role. This role was introduced for automated configurations of the **firewalld** service.

With the **firewall** RHEL system role you can configure many different **firewalld** parameters, for example:

- Zones
- The services for which packets should be allowed
- Granting, rejection, or dropping of traffic access to ports
- Forwarding of ports or port ranges for a zone

To apply the firewall parameters on one or more systems in an automated fashion, use the **firewall** variable in your Ansible playbook. A playbook is a list of one or more plays that is written in the text-based YAML format and can look as follows:

 name: Enable web services in default zone hosts: managed-node-01.example.com tasks:

name: Enable http and https ansible.builtin.include_role:

name: rhel-system-roles.firewall

vars: firewall:

- service:

- http

- https

state: enabled

After you run the **firewall** RHEL system role on the control node, it applies the **firewalld** parameters to the managed node immediately and makes the parameters persist across reboots.

9.1. RESETTING THE FIREWALLD SETTINGS BY USING THE FIREWALL RHEL SYSTEM ROLE

Over time, updates to your firewall configuration can accumulate to the point, where they could lead to unintended security risks. With the **firewall** RHEL system role, you can reset the **firewalld** settings to their default state in an automated fashion. This way you can efficiently remove any unintentional or insecure firewall rules and simplify their management.

Prerequisites

• You have prepared the control node and the managed nodes .

- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

- name: Reset firewalld example

hosts: managed-node-01.example.com

tasks:

 name: Reset firewalld ansible.builtin.include_role: name: rhel-system-roles.firewall

vars: firewall:

- previous: replaced

The settings specified in the example playbook include the following:

previous: replaced

Removes all existing user-defined settings and resets the **firewalld** settings to defaults. If you combine the **previous:replaced** parameter with other settings, the **firewall** role removes all existing settings before applying new ones.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.firewall/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

 Run this command on the control node to remotely check that all firewall configuration on your managed node was reset to its default values:

ansible managed-node-01.example.com -m ansible.builtin.command -a 'firewall-cmd --list-all-zones'

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.firewall/README.md file
- /usr/share/doc/rhel-system-roles/firewall/ directory

9.2. FORWARDING INCOMING TRAFFIC IN FIREWALLD FROM ONE LOCAL PORT TO A DIFFERENT LOCAL PORT BY USING THE FIREWALL RHEL SYSTEM ROLE

You can use the **firewall** RHEL system role to remotely configure forwarding of incoming traffic from one local port to a different local port.

For example, if you have an environment where multiple services co-exist on the same machine and need the same default port, there are likely to become port conflicts. These conflicts can disrupt services and cause a downtime. With the **firewall** RHEL system role, you can efficiently forward traffic to alternative ports to ensure that your services can run simultaneously without modification to their configuration.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

name: Configure firewalld
hosts: managed-node-01.example.com
tasks:

name: Forward incoming traffic on port 8080 to 443
ansible.builtin.include_role:
name: rhel-system-roles.firewall
vars:
firewall:
- forward port: 8080/tcp;443;

state: enabled runtime: true permanent: true

The settings specified in the example playbook include the following:

forward port: 8080/tcp:443

Traffic coming to the local port 8080 using the TCP protocol is forwarded to the port 443.

runtime: true

Enables changes in the runtime configuration. The default is set to **true**. For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhelsystem-roles.firewall/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

 On the control node, run the following command to remotely check the forwarded-ports on your managed node:

ansible managed-node-01.example.com -m ansible.builtin.command -a 'firewall-cmd --list-forward-ports'

managed-node-01.example.com | CHANGED | rc=0 >> port=8080:proto=tcp:toport=443:toaddr=

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.firewall/README.md file
- /usr/share/doc/rhel-system-roles/firewall/ directory

9.3. CONFIGURING A FIREWALLD DMZ ZONE BY USING THE FIREWALL RHEL SYSTEM ROLE

As a system administrator, you can use the **firewall** RHEL system role to configure a **dmz** zone on the **enp1s0** interface to permit **HTTPS** traffic to the zone. In this way, you enable external users to access your web servers.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

- name: Configure firewalld

hosts: managed-node-01.example.com

tasks:

- name: Creating a DMZ with access to HTTPS port and masquerading for hosts in DMZ ansible.builtin.include_role:

name: rhel-system-roles.firewall

vars: firewall: - zone: dmz

interface: enp1s0

service: https state: enabled runtime: true permanent: true

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.firewall/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

• On the control node, run the following command to remotely check the information about the **dmz** zone on your managed node:

ansible managed-node-01.example.com -m ansible.builtin.command -a 'firewall-cmd --zone=dmz --list-all'

managed-node-01.example.com | CHANGED | rc=0 >>

dmz (active)

target: default

icmp-block-inversion: no interfaces: enp1s0

sources:

services: https ssh

ports: protocols: forward: no masquerade: no forward-ports: source-ports: icmp-blocks:

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.firewall/README.md file
- /usr/share/doc/rhel-system-roles/firewall/ directory

CHAPTER 10. CONFIGURING A HIGH-AVAILABILITY CLUSTER BY USING RHEL SYSTEM ROLES

With the **ha_cluster** system role, you can configure and manage a high-availability cluster that uses the Pacemaker high availability cluster resource manager.

10.1. VARIABLES OF THE HA_CLUSTER RHEL SYSTEM ROLE

In an **ha_cluster** system role playbook, you define the variables for a high availability cluster according to the requirements of your cluster deployment.

The variables you can set for an **ha cluster** system role are as follows:

ha_cluster_enable_repos

A boolean flag that enables the repositories containing the packages that are needed by the **ha_cluster** system role. When this variable is set to **true**, the default value, you must have active subscription coverage for RHEL and the RHEL High Availability Add-On on the systems that you will use as your cluster members or the system role will fail.

ha_cluster_enable_repos_resilient_storage

(RHEL 9.4 and later) A boolean flag that enables the repositories containing resilient storage packages, such as **dlm** or **gfs2**. For this option to take effect, **ha_cluster_enable_repos** must be set to **true**. The default value of this variable is **false**.

ha_cluster_manage_firewall

(RHEL 9.2 and later) A boolean flag that determines whether the **ha_cluster** system role manages the firewall. When **ha_cluster_manage_firewall** is set to **true**, the firewall high availability service and the **fence-virt** port are enabled. When **ha_cluster_manage_firewall** is set to **false**, the **ha_cluster** system role does not manage the firewall. If your system is running the **firewalld** service, you must set the parameter to **true** in your playbook.

You can use the **ha_cluster_manage_firewall** parameter to add ports, but you cannot use the parameter to remove ports. To remove ports, use the **firewall** system role directly.

As of RHEL 9.2, the firewall is no longer configured by default, because it is configured only when **ha_cluster_manage_firewall** is set to **true**.

ha cluster manage selinux

(RHEL 9.2 and later) A boolean flag that determines whether the **ha_cluster** system role manages the ports belonging to the firewall high availability service using the **selinux** system role. When **ha_cluster_manage_selinux** is set to **true**, the ports belonging to the firewall high availability service are associated with the SELinux port type **cluster_port_t**. When

ha_cluster_manage_selinux is set to false, the ha_cluster system role does not manage SELinux. If your system is running the selinux service, you must set this parameter to true in your playbook. Firewall configuration is a prerequisite for managing SELinux. If the firewall is not installed, the managing SELinux policy is skipped.

You can use the **ha_cluster_manage_selinux** parameter to add policy, but you cannot use the parameter to remove policy. To remove policy, use the **selinux** system role directly.

ha_cluster_cluster_present

A boolean flag which, if set to **true**, determines that HA cluster will be configured on the hosts according to the variables passed to the role. Any cluster configuration not specified in the playbook and not supported by the role will be lost.

If **ha_cluster_cluster_present** is set to **false**, all HA cluster configuration will be removed from the target hosts.

The default value of this variable is **true**.

The following example playbook removes all cluster configuration on node1 and node2

- hosts: node1 node2

vars:

ha_cluster_cluster_present: false

roles

- rhel-system-roles.ha cluster

ha cluster start on boot

A boolean flag that determines whether cluster services will be configured to start on boot. The default value of this variable is **true**.

ha_cluster_fence_agent_packages

List of fence agent packages to install. The default value of this variable is **fence-agents-all**, **fence-virt**.

ha_cluster_extra_packages

List of additional packages to be installed. The default value of this variable is no packages. This variable can be used to install additional packages not installed automatically by the role, for example custom resource agents.

It is possible to specify fence agents as members of this list. However,

ha_cluster_fence_agent_packages is the recommended role variable to use for specifying fence agents, so that its default value is overridden.

ha_cluster_hacluster_password

A string value that specifies the password of the **hacluster** user. The **hacluster** user has full access to a cluster. To protect sensitive data, vault encrypt the password, as described in Encrypting content with Ansible Vault. There is no default password value, and this variable must be specified.

ha_cluster_hacluster_qdevice_password

(RHEL 9.3 and later) A string value that specifies the password of the **hacluster** user for a quorum device. This parameter is needed only if the **ha_cluster_quorum** parameter is configured to use a quorum device of type **net** and the password of the **hacluster** user on the quorum device is different from the password of the **hacluster** user specified with the **ha_cluster_hacluster_password** parameter. The **hacluster** user has full access to a cluster. To protect sensitive data, vault encrypt the password, as described in Encrypting content with Ansible Vault. There is no default value for this password.

ha_cluster_corosync_key_src

The path to Corosync **authkey** file, which is the authentication and encryption key for Corosync communication. It is highly recommended that you have a unique **authkey** value for each cluster. The key should be 256 bytes of random data.

If you specify a key for this variable, it is recommended that you vault encrypt the key, as described in Encrypting content with Ansible Vault.

If no key is specified, a key already present on the nodes will be used. If nodes do not have the same key, a key from one node will be distributed to other nodes so that all nodes have the same key. If no node has a key, a new key will be generated and distributed to the nodes.

If this variable is set, **ha_cluster_regenerate_keys** is ignored for this key.

The default value of this variable is null.

ha_cluster_pacemaker_key_src

The path to the Pacemaker **authkey** file, which is the authentication and encryption key for Pacemaker communication. It is highly recommended that you have a unique **authkey** value for each cluster. The key should be 256 bytes of random data.

If you specify a key for this variable, it is recommended that you vault encrypt the key, as described in Encrypting content with Ansible Vault.

If no key is specified, a key already present on the nodes will be used. If nodes do not have the same key, a key from one node will be distributed to other nodes so that all nodes have the same key. If no node has a key, a new key will be generated and distributed to the nodes.

If this variable is set, ha_cluster_regenerate_keys is ignored for this key.

The default value of this variable is null.

ha cluster fence virt key src

The path to the **fence-virt** or **fence-xvm** pre-shared key file, which is the location of the authentication key for the **fence-virt** or **fence-xvm** fence agent.

If you specify a key for this variable, it is recommended that you vault encrypt the key, as described in Encrypting content with Ansible Vault.

If no key is specified, a key already present on the nodes will be used. If nodes do not have the same key, a key from one node will be distributed to other nodes so that all nodes have the same key. If no node has a key, a new key will be generated and distributed to the nodes. If the **ha_cluster** system role generates a new key in this fashion, you should copy the key to your nodes' hypervisor to ensure that fencing works.

If this variable is set, **ha_cluster_regenerate_keys** is ignored for this key.

The default value of this variable is null.

ha cluster pcsd public key srcr, ha cluster pcsd private key src

The path to the **pcsd** TLS certificate and private key. If this is not specified, a certificate-key pair already present on the nodes will be used. If a certificate-key pair is not present, a random new one will be generated.

If you specify a private key value for this variable, it is recommended that you vault encrypt the key, as described in Encrypting content with Ansible Vault.

If these variables are set, **ha_cluster_regenerate_keys** is ignored for this certificate-key pair.

The default value of these variables is null.

ha_cluster_pcsd_certificates

(RHEL 9.2 and later) Creates a **pcsd** private key and certificate using the **certificate** system role. If your system is not configured with a **pcsd** private key and certificate, you can create them in one of two ways:

Set the ha_cluster_pcsd_certificates variable. When you set the
ha_cluster_pcsd_certificates variable, the certificate system role is used internally and it
creates the private key and certificate for pcsd as defined.

 Do not set the ha_cluster_pcsd_public_key_src, ha_cluster_pcsd_private_key_src, or the ha_cluster_pcsd_certificates variables. If you do not set any of these variables, the ha_cluster system role will create pcsd certificates by means of pcsd itself. The value of ha_cluster_pcsd_certificates is set to the value of the variable certificate_requests as specified in the certificate system role. For more information about the certificate system role, see Requesting certificates using RHEL system roles.

The following operational considerations apply to the use of the **ha_cluster_pcsd_certificate** variable:

- Unless you are using IPA and joining the systems to an IPA domain, the certificate system
 role creates self-signed certificates. In this case, you must explicitly configure trust settings
 outside of the context of RHEL system roles. System roles do not support configuring trust
 settings.
- When you set the ha_cluster_pcsd_certificates variable, do not set the
 ha_cluster_pcsd_public_key_src and ha_cluster_pcsd_private_key_src variables.
- When you set the **ha_cluster_pcsd_certificates** variable, **ha_cluster_regenerate_keys** is ignored for this certificate key pair.

The default value of this variable is [].

For an example **ha_cluster** system role playbook that creates TLS certificates and key files in a high availability cluster, see Creating pcsd TLS certificates and key files for a high availability cluster .

ha_cluster_regenerate_keys

A boolean flag which, when set to **true**, determines that pre-shared keys and TLS certificates will be regenerated. For more information about when keys and certificates will be regenerated, see the descriptions of the **ha_cluster_corosync_key_src**, **ha_cluster_pacemaker_key_src**, **ha_cluster_pcsd_public_key_src**, and **ha_cluster_pcsd_private_key_src** variables.

The default value of this variable is false.

ha cluster pcs permission list

Configures permissions to manage a cluster using **pcsd**. The items you configure with this variable are as follows:

- type user or group
- name user or group name
- **allow_list** Allowed actions for the specified user or group:
 - read View cluster status and settings
 - write Modify cluster settings except permissions and ACLs
 - grant Modify cluster permissions and ACLs
 - **full** Unrestricted access to a cluster including adding and removing nodes and access to keys and certificates

The structure of the **ha cluster pcs permission list** variable and its default values are as follows:

ha_cluster_pcs_permission_list:

- type: group name: hacluster allow_list:grant
 - readwrite

ha_cluster_cluster_name

The name of the cluster. This is a string value with a default of **my-cluster**.

ha_cluster_transport

(RHEL 9.1 and later) Sets the cluster transport method. The items you configure with this variable are as follows:

- **type** (optional) Transport type: **knet**, **udp**, or **udpu**. The **udp** and **udpu** transport types support only one link. Encryption is always disabled for **udp** and **udpu**. Defaults to **knet** if not specified.
- **options** (optional) List of name-value dictionaries with transport options.
- **links** (optional) List of list of name-value dictionaries. Each list of name-value dictionaries holds options for one Corosync link. It is recommended that you set the **linknumber** value for each link. Otherwise, the first list of dictionaries is assigned by default to the first link, the second one to the second link, and so on.
- **compression** (optional) List of name-value dictionaries configuring transport compression. Supported only with the **knet** transport type.
- **crypto** (optional) List of name-value dictionaries configuring transport encryption. By default, encryption is enabled. Supported only with the **knet** transport type.

For a list of allowed options, see the **pcs -h cluster setup** help page or the **setup** description in the **cluster** section of the **pcs**(8) man page. For more detailed descriptions, see the **corosync.conf**(5) man page.

The structure of the **ha cluster transport** variable is as follows:

```
ha_cluster_transport:
 type: knet
 options:
  - name: option1 name
   value: option1_value
  - name: option2 name
   value: option2 value
 links:
   - name: option1_name
    value: option1 value
   - name: option2 name
    value: option2_value
   - name: option1 name
    value: option1_value
   - name: option2_name
    value: option2_value
 compression:
```

name: option1_name
value: option1_value
name: option2_name
value: option2_value
crypto:

name: option1_name value: option1_valuename: option2_name value: option2_value

For an example **ha_cluster** system role playbook that configures a transport method, see Configuring Corosync values in a high availability cluster .

ha_cluster_totem

(RHEL 9.1 and later) Configures Corosync totem. For a list of allowed options, see the **pcs -h cluster setup** help page or the **setup** description in the **cluster** section of the **pcs**(8) man page. For a more detailed description, see the **corosync.conf**(5) man page.

The structure of the **ha_cluster_totem** variable is as follows:

ha_cluster_totem:

options:

name: option1_name value: option1_valuename: option2_name value: option2_value

For an example **ha_cluster** system role playbook that configures a Corosync totem, see Configuring Corosync values in a high availability cluster.

ha_cluster_quorum

(RHEL 9.1 and later) Configures cluster quorum. You can configure the following items for cluster quorum:

- options (optional) List of name-value dictionaries configuring quorum. Allowed options are: auto_tie_breaker, last_man_standing, last_man_standing_window, and wait_for_all. For information about quorum options, see the votequorum(5) man page.
- **device** (optional) (RHEL 9.2 and later) Configures the cluster to use a quorum device. By default, no quorum device is used.
 - model (mandatory) Specifies a quorum device model. Only net is supported
 - o model_options (optional) List of name-value dictionaries configuring the specified quorum device model. For model net, you must specify host and algorithm options. Use the pcs-address option to set a custom pcsd address and port to connect to the qnetd host. If you do not specify this option, the role connects to the default pcsd port on the host.
 - **generic_options** (optional) List of name-value dictionaries setting quorum device options that are not model specific.
 - **heuristics_options** (optional) List of name-value dictionaries configuring quorum device heuristics.

For information about quorum device options, see the **corosync-qdevice**(8) man page. The generic options are **sync_timeout** and **timeout**. For model **net** options see the

quorum.device.net section. For heuristics options, see the **quorum.device.heuristics** section.

To regenerate a quorum device TLS certificate, set the **ha_cluster_regenerate_keys** variable to **true**.

The structure of the **ha_cluster_quorum** variable is as follows:

ha_cluster_quorum:
options:
- name: option1_name
value: option1_value
- name: option2_name
value: option2_value

device:

model: string model_options:

 name: option1_name value: option1_value
 name: option2_name value: option2_value
 generic_options:

name: option1_name
 value: option1_value
 name: option2_name
 value: option2_value
 heuristics_options:

name: option1_name value: option1_valuename: option2_name value: option2_value

For an example **ha_cluster** system role playbook that configures cluster quorum, see Configuring Corosync values in a high availability cluster. For an example **ha_cluster** system role playbook that configures a cluster using a quorum device, see Configuring a high availability cluster using a quorum device.

ha cluster sbd enabled

(RHEL 9.1 and later) A boolean flag which determines whether the cluster can use the SBD node fencing mechanism. The default value of this variable is **false**.

For an example **ha_cluster** system role playbook that enables SBD, see Configuring a high availability cluster with SBD node fencing.

ha_cluster_sbd_options

(RHEL 9.1 and later) List of name-value dictionaries specifying SBD options. Supported options are:

- delay-start defaults to no
- startmode defaults to always
- timeout-action defaults to flush,reboot
- watchdog-timeout defaults to 5

For information about these options, see the **Configuration via environment** section of the **sbd**(8) man page.

For an example **ha_cluster** system role playbook that configures SBD options, see Configuring a high availability cluster with SBD node fencing.

When using SBD, you can optionally configure watchdog and SBD devices for each node in an inventory. For information about configuring watchdog and SBD devices in an inventory file, see Specifying an inventory for the ha_cluster system role.

ha_cluster_cluster_properties

List of sets of cluster properties for Pacemaker cluster-wide configuration. Only one set of cluster properties is supported.

The structure of a set of cluster properties is as follows:

ha_cluster_cluster_properties:

- attrs:

name: property1_name value: property1_valuename: property2_name value: property2_value

By default, no properties are set.

The following example playbook configures a cluster consisting of **node1** and **node2** and sets the **stonith-enabled** and **no-quorum-policy** cluster properties.

- hosts: node1 node2

vars:

ha_cluster_cluster_name: my-new-cluster ha_cluster_hacluster_password: password

ha_cluster_cluster_properties:

- attrs:

- name: stonith-enabled

value: 'true'

- name: no-quorum-policy

value: stop

roles:

- rhel-system-roles.ha_cluster

ha_cluster_node_options

(RHEL 9.4 and later) This variable defines various settings which vary from one cluster node to another. It sets the options for the specified nodes, but does not specify which nodes form the cluster. You specify which nodes form the cluster with the **hosts** parameter in an inventory or a playbook.

The items you configure with this variable are as follows:

- **node_name** (mandatory) Name of the node for which to define Pacemaker node attributes.
- **attributes** (optional) List of sets of Pacemaker node attributes for the node. Currently no more than one set for each node is supported.

The structure of the **ha cluster node options** variable is as follows:

ha cluster node options:

- node_name: node1 attributes:
 - attrs:

name: attribute1value: value1_node1name: attribute2value: value2_node1

- node_name: node2

attributes:
- attrs:

name: attribute1value: value1_node2name: attribute2value: value2 node2

By default, no node options are defined.

For an example **ha_cluster** system role playbook that includes node options configuration, see Configuring a high availability cluster with node attributes.

ha_cluster_resource_primitives

This variable defines pacemaker resources configured by the system role, including fencing resources. You can configure the following items for each resource:

- id (mandatory) ID of a resource.
- agent (mandatory) Name of a resource or fencing agent, for example
 ocf:pacemaker:Dummy or stonith:fence_xvm. It is mandatory to specify stonith: for
 STONITH agents. For resource agents, it is possible to use a short name, such as Dummy,
 instead of ocf:pacemaker:Dummy. However, if several agents with the same short name
 are installed, the role will fail as it will be unable to decide which agent should be used.
 Therefore, it is recommended that you use full names when specifying a resource agent.
- **instance_attrs** (optional) List of sets of the resource's instance attributes. Currently, only one set is supported. The exact names and values of attributes, as well as whether they are mandatory or not, depend on the resource or fencing agent.
- **meta_attrs** (optional) List of sets of the resource's meta attributes. Currently, only one set is supported.
- copy_operations_from_agent (optional) (RHEL 9.3 and later) Resource agents usually define default settings for resource operations, such as interval and timeout, optimized for the specific agent. If this variable is set to true, then those settings are copied to the resource configuration. Otherwise, clusterwide defaults apply to the resource. If you also define resource operation defaults for the resource with the ha_cluster_resource_operation_defaults role variable, you can set this to false. The default value of this variable is true.
- operations (optional) List of the resource's operations.
 - **action** (mandatory) Operation action as defined by pacemaker and the resource or fencing agent.
 - o attrs (mandatory) Operation options, at least one option must be specified.

The structure of the resource definition that you configure with the **ha_cluster** system role is as follows:

```
- id: resource-id
 agent: resource-agent
 instance attrs:
  - attrs:
    - name: attribute1_name
      value: attribute1_value
    - name: attribute2 name
      value: attribute2_value
 meta_attrs:
  - attrs:
    - name: meta_attribute1_name
      value: meta attribute1 value
    - name: meta_attribute2_name
      value: meta_attribute2_value
 copy_operations_from_agent: bool
 operations:
  - action: operation1-action
   attrs:
    - name: operation1_attribute1_name
      value: operation1 attribute1 value
    - name: operation1_attribute2_name
      value: operation1_attribute2_value
  - action: operation2-action
   attrs:
     - name: operation2 attribute1 name
      value: operation2 attribute1 value
    - name: operation2_attribute2_name
      value: operation2_attribute2_value
```

By default, no resources are defined.

For an example **ha_cluster** system role playbook that includes resource configuration, see Configuring a high availability cluster with fencing and resources.

ha_cluster_resource_groups

This variable defines pacemaker resource groups configured by the system role. You can configure the following items for each resource group:

- id (mandatory) ID of a group.
- **resources** (mandatory) List of the group's resources. Each resource is referenced by its ID and the resources must be defined in the **ha_cluster_resource_primitives** variable. At least one resource must be listed.
- **meta_attrs** (optional) List of sets of the group's meta attributes. Currently, only one set is supported.

The structure of the resource group definition that you configure with the **ha_cluster** system role is as follows:

```
ha_cluster_resource_groups:
- id: group-id
```

resource_ids:

- resource1-id
- resource2-id

meta_attrs:

- attrs:
 - name: group_meta_attribute1_name value: group_meta_attribute1_value
 name: group_meta_attribute2_name value: group_meta_attribute2_value

By default, no resource groups are defined.

For an example **ha_cluster** system role playbook that includes resource group configuration, see Configuring a high availability cluster with fencing and resources .

ha_cluster_resource_clones

This variable defines pacemaker resource clones configured by the system role. You can configure the following items for a resource clone:

- **resource_id** (mandatory) Resource to be cloned. The resource must be defined in the **ha_cluster_resource_primitives** variable or the **ha_cluster_resource_groups** variable.
- promotable (optional) Indicates whether the resource clone to be created is a promotable clone, indicated as true or false.
- **id** (optional) Custom ID of the clone. If no ID is specified, it will be generated. A warning will be displayed if this option is not supported by the cluster.
- meta_attrs (optional) List of sets of the clone's meta attributes. Currently, only one set is supported.

The structure of the resource clone definition that you configure with the **ha_cluster** system role is as follows:

ha cluster resource clones:

resource_id: resource-to-be-cloned promotable: true
id: custom-clone-id meta_attrs:
- attrs:

name: clone_meta_attribute1_name value: clone_meta_attribute1_valuename: clone_meta_attribute2_name value: clone_meta_attribute2_value

By default, no resource clones are defined.

For an example **ha_cluster** system role playbook that includes resource clone configuration, see Configuring a high availability cluster with fencing and resources .

ha_cluster_resource_defaults

(RHEL 9.3 and later) This variable defines sets of resource defaults. You can define multiple sets of defaults and apply them to resources of specific agents using rules. The defaults you specify with the **ha_cluster_resource_defaults** variable do not apply to resources which override them with their own defined values.

Only meta attributes can be specified as defaults.

You can configure the following items for each defaults set:

- id (optional) ID of the defaults set. If not specified, it is autogenerated.
- **rule** (optional) Rule written using **pcs** syntax defining when and for which resources the set applies. For information on specifying a rule, see the **resource defaults set create** section of the **pcs**(8) man page.
- score (optional) Weight of the defaults set.
- attrs (optional) Meta attributes applied to resources as defaults.

The structure of the **ha_cluster_resource_defaults** variable is as follows:

ha cluster resource defaults:

meta attrs:

 id: defaults-set-1-id rule: rule-string score: score-value

attrs:

 name: meta_attribute1_name value: meta_attribute1_value
 name: meta_attribute2_name value: meta_attribute2_value

 id: defaults-set-2-id rule: rule-string score: score-value

attrs:

name: meta_attribute3_name value: meta_attribute3_value
name: meta_attribute4_name value: meta_attribute4_value

For an example **ha_cluster** system role playbook that configures resource defaults, see Configuring a high availability cluster with resource and resource operation defaults.

ha_cluster_resource_operation_defaults

(RHEL 9.3 and later) This variable defines sets of resource operation defaults. You can define multiple sets of defaults and apply them to resources of specific agents and specific resource operations using rules. The defaults you specify with the **ha_cluster_resource_operation_defaults** variable do not apply to resource operations which override them with their own defined values. By default, the **ha_cluster** system role configures resources to define their own values for resource operations. For information about overriding these defaults with the

ha_cluster_resource_operations_defaults variable, see the description of the copy_operations_from_agent item in ha_cluster_resource_primitives.

Only meta attributes can be specified as defaults.

The structure of the **ha_cluster_resource_operations_defaults** variable is the same as the structure for the **ha_cluster_resource_defaults** variable, with the exception of how you specify a rule. For information about specifying a rule to describe the resource operation to which a set applies, see the **resource op defaults set create** section of the **pcs**(8) man page.

ha_cluster_stonith_levels

(RHEL 9.4 and later) This variable defines STONITH levels, also known as fencing topology. Fencing levels configure a cluster to use multiple devices to fence nodes. You can define alternative devices in case one device fails and you can require multiple devices to all be executed successfully to consider a node successfully fenced. For more information on fencing levels, see Configuring fencing levels in Configuring and managing high availability clusters.

You can configure the following items when defining fencing levels:

- **level** (mandatory) Order in which to attempt the fencing level. Pacemaker attempts levels in ascending order until one succeeds.
- target (optional) Name of a node this level applies to.
- You must specify one of the following three selections:
 - **target_pattern** POSIX extended regular expression matching the names of the nodes this level applies to.
 - target attribute Name of a node attribute that is set for the node this level applies to.
 - **target_attribute** and **target_value** Name and value of a node attribute that is set for the node this level applies to.
- **resouce_ids** (mandatory) List of fencing resources that must all be tried for this level. By default, no fencing levels are defined.

The structure of the fencing levels definition that you configure with the **ha_cluster** system role is as follows:

```
ha cluster stonith levels:
 - level: 1..9
  target: node_name
  target_pattern: node_name_regular_expression
  target attribute: node attribute name
  target value: node attribute value
  resource ids:
   - fence_device_1
   - fence device 2
 - level: 1..9
  target: node name
  target_pattern: node_name_regular_expression
  target_attribute: node_attribute_name
  target value: node attribute value
  resource ids:
   - fence_device_1
   - fence device 2
```

For an example **ha_cluster** system role playbook that configures fencing defaults, see Configuring a high availability cluster with fencing levels.

ha_cluster_constraints_location

This variable defines resource location constraints. Resource location constraints indicate which nodes a resource can run on. You can specify a resources specified by a resource ID or by a pattern, which can match more than one resource. You can specify a node by a node name or by a rule. You can configure the following items for a resource location constraint:

- resource (mandatory) Specification of a resource the constraint applies to.
- **node** (mandatory) Name of a node the resource should prefer or avoid.
- id (optional) ID of the constraint. If not specified, it will be autogenerated.
- options (optional) List of name-value dictionaries.
 - **score** Sets the weight of the constraint.
 - A positive **score** value means the resource prefers running on the node.
 - A negative **score** value means the resource should avoid running on the node.
 - A **score** value of **-INFINITY** means the resource must avoid running on the node.
 - If **score** is not specified, the score value defaults to **INFINITY**.

By default no resource location constraints are defined.

The structure of a resource location constraint specifying a resource ID and node name is as follows:

ha_cluster_constraints_location:

- resource:

id: resource-id node: node-name id: constraint-id

options:

name: score value: score-valuename: option-name value: option-value

The items that you configure for a resource location constraint that specifies a resource pattern are the same items that you configure for a resource location constraint that specifies a resource ID, with the exception of the resource specification itself. The item that you specify for the resource specification is as follows:

• **pattern** (mandatory) - POSIX extended regular expression resource IDs are matched against.

The structure of a resource location constraint specifying a resource pattern and node name is as follows:

ha_cluster_constraints_location:

- resource:

pattern: resource-pattern

node: node-name id: constraint-id

options:

name: score value: score-value

name: resource-discovery value: resource-discovery-value

You can configure the following items for a resource location constraint that specifies a resource ID and a rule:

- resource (mandatory) Specification of a resource the constraint applies to.
 - id (mandatory) Resource ID.
 - role (optional) The resource role to which the constraint is limited: Started,
 Unpromoted, Promoted.
- **rule** (mandatory) Constraint rule written using **pcs** syntax. For further information, see the **constraint location** section of the **pcs**(8) man page.
- Other items to specify have the same meaning as for a resource constraint that does not specify a rule.

The structure of a resource location constraint that specifies a resource ID and a rule is as follows:

ha cluster constraints location:

- resource:

id: resource-id role: resource-role rule: rule-string id: constraint-id options:

name: score value: score-value

 name: resource-discovery value: resource-discovery-value

The items that you configure for a resource location constraint that specifies a resource pattern and a rule are the same items that you configure for a resource location constraint that specifies a resource ID and a rule, with the exception of the resource specification itself. The item that you specify for the resource specification is as follows:

 pattern (mandatory) - POSIX extended regular expression resource IDs are matched against.

The structure of a resource location constraint that specifies a resource pattern and a rule is as follows:

ha_cluster_constraints_location:

- resource:

pattern: resource-pattern role: resource-role rule: rule-string

options:

id: constraint-id

name: score value: score-value

- name: resource-discovery value: resource-discovery-value

For an example **ha_cluster** system role playbook that creates a cluster with resource constraints, see Configuring a high availability cluster with resource constraints.

ha_cluster_constraints_colocation

This variable defines resource colocation constraints. Resource colocation constraints indicate that

the location of one resource depends on the location of another one. There are two types of colocation constraints: a simple colocation constraint for two resources, and a set colocation constraint for multiple resources.

You can configure the following items for a simple resource colocation constraint:

- resource_follower (mandatory) A resource that should be located relative to resource_leader.
 - id (mandatory) Resource ID.
 - role (optional) The resource role to which the constraint is limited: Started,
 Unpromoted, Promoted.
- **resource_leader** (mandatory) The cluster will decide where to put this resource first and then decide where to put **resource_follower**.
 - id (mandatory) Resource ID.
 - role (optional) The resource role to which the constraint is limited: Started,
 Unpromoted, Promoted.
- **id** (optional) ID of the constraint. If not specified, it will be autogenerated.
- **options** (optional) List of name-value dictionaries.
 - **score** Sets the weight of the constraint.
 - Positive **score** values indicate the resources should run on the same node.
 - Negative **score** values indicate the resources should run on different nodes.
 - A **score** value of **+INFINITY** indicates the resources must run on the same node.
 - A **score** value of **-INFINITY** indicates the resources must run on different nodes.
 - If **score** is not specified, the score value defaults to **INFINITY**.

By default no resource colocation constraints are defined.

The structure of a simple resource colocation constraint is as follows:

ha_cluster_constraints_colocation:

- resource_follower:

id: resource-id1

role: resource-role1

resource_leader:

id: resource-id2

role: resource-role2

id: constraint-id

options:

- name: score

value: score-value

- name: option-name

value: option-value

You can configure the following items for a resource set colocation constraint:

• resource_sets (mandatory) - List of resource sets.

- resource_ids (mandatory) List of resources in a set.
- **options** (optional) List of name-value dictionaries fine-tuning how resources in the sets are treated by the constraint.
- id (optional) Same values as for a simple colocation constraint.
- **options** (optional) Same values as for a simple colocation constraint.

The structure of a resource set colocation constraint is as follows:

ha cluster constraints colocation:

- resource_sets:
 - resource ids:
 - resource-id1
 - resource-id2

options:

 name: option-name value: option-value

id: constraint-id

options:

name: score value: score-valuename: option-name value: option-value

For an example **ha_cluster** system role playbook that creates a cluster with resource constraints, see Configuring a high availability cluster with resource constraints.

ha cluster constraints order

This variable defines resource order constraints. Resource order constraints indicate the order in which certain resource actions should occur. There are two types of resource order constraints: a simple order constraint for two resources, and a set order constraint for multiple resources. You can configure the following items for a simple resource order constraint:

- resource first (mandatory) Resource that the resource then resource depends on.
 - id (mandatory) Resource ID.
 - **action** (optional) The action that must complete before an action can be initiated for the **resource_then** resource. Allowed values: **start**, **stop**, **promote**, **demote**.
- resource_then (mandatory) The dependent resource.
 - id (mandatory) Resource ID.
 - **action** (optional) The action that the resource can execute only after the action on the **resource_first** resource has completed. Allowed values: **start**, **stop**, **promote**, **demote**.
- id (optional) ID of the constraint. If not specified, it will be autogenerated.
- **options** (optional) List of name-value dictionaries.

By default no resource order constraints are defined.

The structure of a simple resource order constraint is as follows:

ha cluster constraints order:

- resource first:

id: resource-id1

action: resource-action1

resource_then: id: resource-id2

action: resource-action2

id: constraint-id

options:

name: score value: score-valuename: option-name value: option-value

You can configure the following items for a resource set order constraint:

- resource_sets (mandatory) List of resource sets.
 - resource_ids (mandatory) List of resources in a set.
 - **options** (optional) List of name-value dictionaries fine-tuning how resources in the sets are treated by the constraint.
- id (optional) Same values as for a simple order constraint.
- options (optional) Same values as for a simple order constraint.

The structure of a resource set order constraint is as follows:

ha_cluster_constraints_order:

- resource_sets:
 - resource ids:
 - resource-id1
 - resource-id2

options:

 name: option-name value: option-value

id: constraint-id

options:

- name: score

value: score-value - name: option-name value: option-value

For an example **ha_cluster** system role playbook that creates a cluster with resource constraints, see Configuring a high availability cluster with resource constraints.

ha cluster constraints ticket

This variable defines resource ticket constraints. Resource ticket constraints indicate the resources that depend on a certain ticket. There are two types of resource ticket constraints: a simple ticket constraint for one resource, and a ticket order constraint for multiple resources.

You can configure the following items for a simple resource ticket constraint:

• resource (mandatory) - Specification of a resource the constraint applies to.

- id (mandatory) Resource ID.
- role (optional) The resource role to which the constraint is limited: Started, Unpromoted, Promoted.
- ticket (mandatory) Name of a ticket the resource depends on.
- id (optional) ID of the constraint. If not specified, it will be autogenerated.
- options (optional) List of name-value dictionaries.
 - **loss-policy** (optional) Action to perform on the resource if the ticket is revoked.

By default no resource ticket constraints are defined.

The structure of a simple resource ticket constraint is as follows:

ha_cluster_constraints_ticket:

- resource:

id: resource-id role: resource-role ticket: ticket-name id: constraint-id options:

name: loss-policy value: loss-policy-valuename: option-name value: option-value

You can configure the following items for a resource set ticket constraint:

- resource_sets (mandatory) List of resource sets.
 - resource_ids (mandatory) List of resources in a set.
 - **options** (optional) List of name-value dictionaries fine-tuning how resources in the sets are treated by the constraint.
- **ticket** (mandatory) Same value as for a simple ticket constraint.
- id (optional) Same value as for a simple ticket constraint.
- **options** (optional) Same values as for a simple ticket constraint.

The structure of a resource set ticket constraint is as follows:

ha_cluster_constraints_ticket:

- resource_sets:
 - resource ids:
 - resource-id1
 - resource-id2

options:

 name: option-name value: option-value ticket: ticket-name

ticket: ticket-name id: constraint-id

options:

 name: option-name value: option-value

For an example **ha_cluster** system role playbook that creates a cluster with resource constraints, see Configuring a high availability cluster with resource constraints.

ha_cluster_qnetd

(RHEL 9.2 and later) This variable configures a **qnetd** host which can then serve as an external quorum device for clusters.

You can configure the following items for a **qnetd** host:

- present (optional) If true, configure a qnetd instance on the host. If false, remove qnetd configuration from the host. The default value is false. If you set this true, you must set ha_cluster_cluster_present to false.
- **start_on_boot** (optional) Configures whether the **qnetd** instance should start automatically on boot. The default value is **true**.
- **regenerate_keys** (optional) Set this variable to **true** to regenerate the **qnetd** TLS certificate. If you regenerate the certificate, you must either re-run the role for each cluster to connect it to the **qnetd** host again or run **pcs** manually.

You cannot run **qnetd** on a cluster node because fencing would disrupt **qnetd** operation. For an example **ha_cluster** system role playbook that configures a cluster using a quorum device, see Configuring a cluster using a quorum device.

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.ha_cluster/README.md file
- /usr/share/doc/rhel-system-roles/ha_cluster/ directory

10.2. SPECIFYING AN INVENTORY FOR THEHA_CLUSTER RHEL SYSTEM ROLE

When configuring an HA cluster using the **ha_cluster** system role playbook, you configure the names and addresses of the nodes for the cluster in an inventory.

10.2.1. Configuring node names and addresses in an inventory

For each node in an inventory, you can optionally specify the following items:

- **node_name** the name of a node in a cluster.
- **pcs_address** an address used by **pcs** to communicate with the node. It can be a name, FQDN or an IP address and it can include a port number.
- **corosync_addresses** list of addresses used by Corosync. All nodes which form a particular cluster must have the same number of addresses and the order of the addresses matters.

The following example shows an inventory with targets **node1** and **node2**. **node1** and **node2** must be either fully qualified domain names or must otherwise be able to connect to the nodes as when, for example, the names are resolvable through the /etc/hosts file.

```
all:
 hosts:
  node1:
   ha cluster:
    node_name: node-A
    pcs_address: node1-address
    corosync addresses:
     - 192.168.1.11
     - 192.168.2.11
  node2:
   ha cluster:
    node name: node-B
    pcs address: node2-address:2224
    corosync addresses:
      - 192.168.1.12
      - 192.168.2.12
```

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.ha_cluster/README.md file
- /usr/share/doc/rhel-system-roles/ha_cluster/ directory

10.2.2. Configuring watchdog and SBD devices in an inventory

(RHEL 9.1 and later) When using SBD, you can optionally configure watchdog and SBD devices for each node in an inventory. Even though all SBD devices must be shared to and accessible from all nodes, each node can use different names for the devices. Watchdog devices can be different for each node as well. For information about the SBD variables you can set in a system role playbook, see the entries for **ha_cluster_sbd_enabled** and **ha_cluster_sbd_options** in Variables of the **ha_cluster** system role.

For each node in an inventory, you can optionally specify the following items:

- **sbd_watchdog_modules** (optional) (RHEL 9.3 and later) Watchdog kernel modules to be loaded, which create /dev/watchdog* devices. Defaults to empty list if not set.
- **sbd_watchdog_modules_blocklist** (optional) (RHEL 9.3 and later) Watchdog kernel modules to be unloaded and blocked. Defaults to empty list if not set.
- sbd_watchdog Watchdog device to be used by SBD. Defaults to /dev/watchdog if not set.
- **sbd_devices** Devices to use for exchanging SBD messages and for monitoring. Defaults to empty list if not set.

The following example shows an inventory that configures watchdog and SBD devices for targets **node1** and **node2**.

```
all:
hosts:
node1:
ha_cluster:
```

```
sbd_watchdog_modules:
   - module1
   - module2
  sbd_watchdog: /dev/watchdog2
  sbd devices:
   - /dev/vdx
   - /dev/vdv
node2:
 ha cluster:
  sbd_watchdog_modules:
   - module1
  sbd_watchdog_modules_blocklist:
   - module2
  sbd_watchdog: /dev/watchdog1
  sbd_devices:
   - /dev/vdw
   - /dev/vdz
```

For information about creating a high availability cluster that uses SBD fencing, see Configuring a high availability cluster with SBD node fencing.

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.ha_cluster/README.md file
- /usr/share/doc/rhel-system-roles/ha_cluster/ directory

10.3. CREATING PCSD TLS CERTIFICATES AND KEY FILES FOR A HIGH AVAILABILITY CLUSTER

(RHEL 9.2 and later)

You can use the **ha_cluster** system role to create TLS certificates and key files in a high availability cluster. When you run this playbook, the **ha_cluster** system role uses the **certificate** system role internally to manage TLS certificates.



WARNING

The **ha_cluster** system role replaces any existing cluster configuration on the specified nodes. Any settings not specified in the playbook will be lost.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

- The systems that you will use as your cluster members have active subscription coverage for RHEL and the RHEL High Availability Add-On.
- The inventory file specifies the cluster nodes as described in Specifying an inventory for the ha_cluster system role.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

This playbook configures a cluster running the **firewalld** and **selinux** services and creates a self-signed **pcsd** certificate and private key files in /var/lib/pcsd. The **pcsd** certificate has the file name **FILENAME.crt** and the key file is named **FILENAME.key**.

When creating your playbook file for production, vault encrypt the password, as described in Encrypting content with Ansible Vault.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook \sim /playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.ha_cluster/README.md file
- /usr/share/doc/rhel-system-roles/ha_cluster/ directory Requesting certificates using RHEL system roles

10.4. CONFIGURING A HIGH AVAILABILITY CLUSTER RUNNING NO RESOURCES

The following procedure uses the **ha_cluster** system role, to create a high availability cluster with no fencing configured and which runs no resources.



WARNING

The **ha_cluster** system role replaces any existing cluster configuration on the specified nodes. Any settings not specified in the playbook will be lost.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- The systems that you will use as your cluster members have active subscription coverage for RHEL and the RHEL High Availability Add-On.
- The inventory file specifies the cluster nodes as described in Specifying an inventory for the ha_cluster system role.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

- name: Create a high availability cluster with no fencing and which runs no resources hosts: node1 node2

roles:

- rhel-system-roles.ha_cluster

vars:

ha_cluster_cluster_name: my-new-cluster ha_cluster_hacluster_password: <password>

ha_cluster_manage_firewall: true ha_cluster_manage_selinux: true

This example playbook file configures a cluster running the **firewalld** and **selinux** services with no fencing configured and which runs no resources.

When creating your playbook file for production, vault encrypt the password, as described in Encrypting content with Ansible Vault.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.ha_cluster/README.md file
- /usr/share/doc/rhel-system-roles/ha_cluster/ directory

10.5. CONFIGURING A HIGH AVAILABILITY CLUSTER WITH FENCING AND RESOURCES

The following procedure uses the **ha_cluster** system role to create a high availability cluster that includes a fencing device, cluster resources, resource groups, and a cloned resource.



WARNING

The **ha_cluster** system role replaces any existing cluster configuration on the specified nodes. Any settings not specified in the playbook will be lost.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- The systems that you will use as your cluster members have active subscription coverage for RHEL and the RHEL High Availability Add-On.
- The inventory file specifies the cluster nodes as described in Specifying an inventory for the ha_cluster system role.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

--

- name: Create a high availability cluster that includes a fencing device and resources hosts: node1 node2

roles:

- rhel-system-roles.ha_cluster

vars:

ha_cluster_cluster_name: my-new-cluster ha_cluster_hacluster_password: <password>

ha_cluster_manage_firewall: true ha_cluster_manage_selinux: true ha_cluster_resource_primitives:

- id: xvm-fencing

```
agent: 'stonith:fence_xvm'
  instance_attrs:
   - attrs:
      - name: pcmk_host_list
       value: node1 node2
 - id: simple-resource
  agent: 'ocf:pacemaker:Dummy'
 - id: resource-with-options
  agent: 'ocf:pacemaker:Dummy'
  instance attrs:
   - attrs:
     - name: fake
       value: fake-value
      - name: passwd
       value: passwd-value
  meta attrs:
   - attrs:
      - name: target-role
       value: Started
      - name: is-managed
       value: 'true'
  operations:
   - action: start
    attrs:
      - name: timeout
       value: '30s'
   - action: monitor
    attrs:
      - name: timeout
       value: '5'
      - name: interval
       value: '1min'
 - id: dummy-1
  agent: 'ocf:pacemaker:Dummy'
 - id: dummy-2
  agent: 'ocf:pacemaker:Dummy'
 - id: dummy-3
  agent: 'ocf:pacemaker:Dummy'
 - id: simple-clone
  agent: 'ocf:pacemaker:Dummy'
 - id: clone-with-options
  agent: 'ocf:pacemaker:Dummy'
ha_cluster_resource_groups:
 - id: simple-group
  resource_ids:
   - dummy-1
   - dummy-2
  meta attrs:
   - attrs:
      - name: target-role
       value: Started
      - name: is-managed
       value: 'true'
 - id: cloned-group
  resource_ids:
   - dummy-3
```

ha_cluster_resource_clones:

- resource_id: simple-clone
- resource_id: clone-with-options

promotable: yes id: custom-clone-id

meta_attrs:
- attrs:

- name: clone-max

value: '2'

- name: clone-node-max

value: '1'

- resource_id: cloned-group

promotable: yes

This example playbook file configures a cluster running the **firewalld** and **selinux** services. The cluster includes fencing, several resources, and a resource group. It also includes a resource clone for the resource group.

When creating your playbook file for production, vault encrypt the password, as described in Encrypting content with Ansible Vault.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.ha_cluster/README.md file
- /usr/share/doc/rhel-system-roles/ha_cluster/ directory

10.6. CONFIGURING A HIGH AVAILABILITY CLUSTER WITH RESOURCE AND RESOURCE OPERATION DEFAULTS

(RHEL 9.3 and later) The following procedure uses the **ha_cluster** system role to create a high availability cluster that defines resource and resource operation defaults.



WARNING

The **ha_cluster** system role replaces any existing cluster configuration on the specified nodes. Any settings not specified in the playbook will be lost.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- The systems that you will use as your cluster members have active subscription coverage for RHEL and the RHEL High Availability Add-On.
- The inventory file specifies the cluster nodes as described in Specifying an inventory for the ha_cluster system role.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Create a high availability cluster that defines resource and resource operation
defaults
 hosts: node1 node2
 roles:
  - rhel-system-roles.ha_cluster
  ha cluster cluster name: my-new-cluster
  ha cluster hacluster password: <password>
  ha_cluster_manage_firewall: true
  ha cluster manage selinux: true
  # Set a different resource-stickiness value during
  # and outside work hours. This allows resources to
  # automatically move back to their most
  # preferred hosts, but at a time that
  # does not interfere with business activities.
  ha_cluster_resource_defaults:
   meta_attrs:
    - id: core-hours
      rule: date-spec hours=9-16 weekdays=1-5
      score: 2
      attrs:
       - name: resource-stickiness
        value: INFINITY
     - id: after-hours
      score: 1
      attrs:
       - name: resource-stickiness
        value: 0
  # Default the timeout on all 10-second-interval
  # monitor actions on IPaddr2 resources to 8 seconds.
  ha_cluster_resource_operation_defaults:
   meta attrs:
    - rule: resource ::IPaddr2 and op monitor interval=10s
      score: INFINITY
      attrs:
       - name: timeout
```

value: 8s

This example playbook file configures a cluster running the **firewalld** and **selinux** services. The cluster includes resource and resource operation defaults.

When creating your playbook file for production, vault encrypt the password, as described in Encrypting content with Ansible Vault.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.ha_cluster/README.md file
- /usr/share/doc/rhel-system-roles/ha_cluster/ directory

10.7. CONFIGURING A HIGH AVAILABILITY CLUSTER WITH FENCING LEVELS

(RHEL 9.4 and later) The following procedure uses the **ha_cluster** system role to create a high availability cluster that defines fencing levels.



WARNING

The **ha_cluster** system role replaces any existing cluster configuration on the specified nodes. Any settings not specified in the playbook will be lost.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- The systems that you will use as your cluster members have active subscription coverage for RHEL and the RHEL High Availability Add-On.
- The inventory file specifies the cluster nodes as described in Specifying an inventory for the ha_cluster system role. For general information about creating an inventory file, see Preparing a control node on RHEL 9.

Procedure

- 1. Store your sensitive variables in an encrypted file:
 - a. Create the vault:

\$ ansible-vault create vault.yml
New Vault password:

Confirm New Vault password: <vault_password>

b. After the **ansible-vault create** command opens an editor, enter the sensitive data in the **<key>: <value>** format:

```
cluster_password: <cluster_password>
fence1_password: <fence1_password>
fence2_password: <fence2_password>
```

- c. Save the changes, and close the editor. Ansible encrypts the data in the vault.
- 2. Create a playbook file, for example ~/playbook.yml. This example playbook file configures a cluster running the **firewalld** and **selinux** services.

```
- name: Create a high availability cluster
 hosts: node1 node2
 vars files:
  - vault.yml
 tasks:
  - name: Configure a cluster that defines fencing levels
   ansible.builtin.include_role:
    name: rhel-system-roles.ha_cluster
   vars:
    ha_cluster_cluster_name: my-new-cluster
     ha cluster_hacluster_password: "{{ cluster_password }}"
     ha_cluster_manage_firewall: true
     ha cluster manage selinux: true
    ha_cluster_resource_primitives:
      - id: apc1
       agent: 'stonith:fence apc snmp'
       instance attrs:
        - attrs:
           - name: ip
            value: apc1.example.com
           - name: username
            value: user
           - name: password
            value: "{{ fence1_password }}"
           - name: pcmk_host_map
            value: node1:1;node2:2
       agent: 'stonith:fence_apc_snmp'
       instance attrs:
        - attrs:
           - name: ip
            value: apc2.example.com
           - name: username
```

```
value: user
      - name: password
       value: "{{ fence2_password }}"
      - name: pcmk_host_map
       value: node1:1;node2:2
# Nodes have redundant power supplies, apc1 and apc2. Cluster must
# ensure that when attempting to reboot a node, both power
# supplies # are turned off before either power supply is turned
# back on.
ha cluster stonith levels:
 - level: 1
  target: node1
  resource_ids:
   - apc1
   - apc2
 - level: 1
  target: node2
  resource_ids:
   - apc1
   - apc2
```

3. Validate the playbook syntax:

\$ ansible-playbook --syntax-check --ask-vault-pass ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

\$ ansible-playbook --ask-vault-pass ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.ha_cluster/README.md file
- /usr/share/doc/rhel-system-roles/ha_cluster/ directory
- Ansible vault

10.8. CONFIGURING A HIGH AVAILABILITY CLUSTER WITH RESOURCE CONSTRAINTS

The following procedure uses the **ha_cluster** system role to create a high availability cluster that includes resource location constraints, resource colocation constraints, resource order constraints, and resource ticket constraints.



WARNING

- id: dummy-5

The **ha_cluster** system role replaces any existing cluster configuration on the specified nodes. Any settings not specified in the playbook will be lost.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- The systems that you will use as your cluster members have active subscription coverage for RHEL and the RHEL High Availability Add-On.
- The inventory file specifies the cluster nodes as described in Specifying an inventory for the ha_cluster system role.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Create a high availability cluster with resource constraints
 hosts: node1 node2
 roles:
  - rhel-system-roles.ha_cluster
 vars:
  ha cluster cluster name: my-new-cluster
  ha_cluster_password: <password>
  ha_cluster_manage_firewall: true
  ha_cluster_manage_selinux: true
  # In order to use constraints, we need resources the constraints will apply
  # to.
  ha_cluster_resource_primitives:
   - id: xvm-fencing
    agent: 'stonith:fence xvm'
    instance_attrs:
     - attrs:
        - name: pcmk host list
         value: node1 node2
   - id: dummy-1
    agent: 'ocf:pacemaker:Dummy'
   - id: dummy-2
    agent: 'ocf:pacemaker:Dummy'
   - id: dummy-3
    agent: 'ocf:pacemaker:Dummy'
   - id: dummy-4
    agent: 'ocf:pacemaker:Dummy'
```

```
agent: 'ocf:pacemaker:Dummy'
 - id: dummy-6
  agent: 'ocf:pacemaker:Dummy'
# location constraints
ha cluster constraints location:
 # resource ID and node name
 - resource:
   id: dummy-1
  node: node1
  options:
   - name: score
    value: 20
 # resource pattern and node name
 - resource:
   pattern: dummy-\d+
  node: node1
  options:
   - name: score
    value: 10
 # resource ID and rule
 - resource:
   id: dummy-2
  rule: '#uname eq node2 and date in_range 2022-01-01 to 2022-02-28'
 # resource pattern and rule
 - resource:
   pattern: dummy-\d+
  rule: node-type eq weekend and date-spec weekdays=6-7
# colocation constraints
ha_cluster_constraints_colocation:
 # simple constraint
 - resource_leader:
   id: dummy-3
  resource follower:
   id: dummy-4
  options:
   - name: score
    value: -5
 # set constraint
 - resource_sets:
   - resource_ids:
      - dummy-1
     - dummy-2
   - resource ids:
      - dummy-5
      - dummy-6
    options:
      - name: sequential
       value: "false"
  options:
   - name: score
    value: 20
# order constraints
ha_cluster_constraints_order:
 # simple constraint
 - resource_first:
   id: dummy-1
```

```
resource_then:
   id: dummy-6
  options:
   - name: symmetrical
     value: "false"
 # set constraint
 - resource sets:
   - resource ids:
      - dummy-1
      - dummy-2
     options:
      - name: require-all
       value: "false"
      - name: sequential
       value: "false"
   - resource ids:
      - dummy-3
   - resource ids:
      - dummy-4
      - dummy-5
     options:
      - name: sequential
       value: "false"
# ticket constraints
ha_cluster_constraints_ticket:
 # simple constraint
 - resource:
   id: dummy-1
  ticket: ticket1
  options:
   - name: loss-policy
     value: stop
 # set constraint
 - resource sets:
   - resource ids:
      - dummy-3
      - dummy-4
      - dummy-5
  ticket: ticket2
  options:
   - name: loss-policy
     value: fence
```

This example playbook file configures a cluster running the **firewalld** and **selinux** services. The cluster includes resource location constraints, resource colocation constraints, resource order constraints, and resource ticket constraints.

When creating your playbook file for production, vault encrypt the password, as described in Encrypting content with Ansible Vault.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.ha cluster/README.md file
- /usr/share/doc/rhel-system-roles/ha_cluster/ directory

10.9. CONFIGURING COROSYNC VALUES IN A HIGH AVAILABILITY CLUSTER

(RHEL 9.1 and later) The following procedure uses the **ha_cluster** system role to create a high availability cluster that configures Corosync values.



WARNING

The **ha_cluster** system role replaces any existing cluster configuration on the specified nodes. Any settings not specified in the playbook will be lost.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- The systems that you will use as your cluster members have active subscription coverage for RHEL and the RHEL High Availability Add-On.
- The inventory file specifies the cluster nodes as described in Specifying an inventory for the ha_cluster system role.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

- name: Create a high availability cluster that configures Corosync values

hosts: node1 node2

roles:

- rhel-system-roles.ha_cluster

vars:

ha_cluster_cluster_name: my-new-cluster ha_cluster_hacluster_password: <password>

ha_cluster_manage_firewall: true ha_cluster_manage_selinux: true

```
ha_cluster_transport:
 type: knet
 options:
  - name: ip_version
   value: ipv4-6
  - name: link_mode
   value: active
 links:
   - name: linknumber
    value: 1
   - name: link_priority
    value: 5
   - name: linknumber
    value: 0
   - name: link_priority
    value: 10
 compression:
  - name: level
   value: 5
  - name: model
   value: zlib
 crypto:
  - name: cipher
   value: none
  - name: hash
   value: none
ha_cluster_totem:
 options:
  - name: block_unlisted_ips
   value: 'yes'
  - name: send join
   value: 0
ha_cluster_quorum:
 options:
  - name: auto_tie_breaker
   value: 1
  - name: wait_for_all
   value: 1
```

This example playbook file configures a cluster running the **firewalld** and **selinux** services that configures Corosync properties.

When creating your playbook file for production, Vault encrypt the password, as described in Encrypting content with Ansible Vault.

2. Validate the playbook syntax:

$\$\ ansible-playbook\ --syntax-check\ \sim\!/playbook.yml$

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.ha_cluster/README.md file
- /usr/share/doc/rhel-system-roles/ha_cluster/ directory

10.10. CONFIGURING A HIGH AVAILABILITY CLUSTER WITH SBD NODE FENCING

(RHEL 9.1 and later) The following procedure uses the **ha_cluster** system role to create a high availability cluster that uses SBD node fencing.



WARNING

The **ha_cluster** system role replaces any existing cluster configuration on the specified nodes. Any settings not specified in the playbook will be lost.

This playbook uses an inventory file that loads a watchdog module (supported in RHEL 9.3 and later) as described in Configuring watchdog and SBD devices in an inventory.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- The systems that you will use as your cluster members have active subscription coverage for RHEL and the RHEL High Availability Add-On.
- The inventory file specifies the cluster nodes as described in Specifying an inventory for the ha_cluster system role.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

- name: Create a high availability cluster that uses SBD node fencing

hosts: node1 node2

roles:

rhel-system-roles.ha_cluster

vars:

ha_cluster_manage_firewall: true

```
ha_cluster_manage_selinux: true
ha_cluster_sbd_enabled: yes
ha_cluster_sbd_options:
 - name: delay-start
  value: 'no'
 - name: startmode
  value: always
 - name: timeout-action
  value: 'flush,reboot'
 - name: watchdog-timeout
  value: 30
# Suggested optimal values for SBD timeouts:
# watchdog-timeout * 2 = msgwait-timeout (set automatically)
# msgwait-timeout * 1.2 = stonith-timeout
ha_cluster_cluster_properties:
 - attrs:
   - name: stonith-timeout
    value: 72
ha_cluster_resource_primitives:
 - id: fence sbd
  agent: 'stonith:fence_sbd'
  instance_attrs:
   - attrs:
      # taken from host vars
      - name: devices
       value: "{{ ha_cluster.sbd_devices | join(',') }}"
      - name: pcmk_delay_base
       value: 30
```

This example playbook file configures a cluster running the **firewalld** and **selinux** services that uses SBD fencing and creates the SBD Stonith resource.

When creating your playbook file for production, vault encrypt the password, as described in Encrypting content with Ansible Vault.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.ha_cluster/README.md file
- /usr/share/doc/rhel-system-roles/ha_cluster/ directory

10.11. CONFIGURING A HIGH AVAILABILITY CLUSTER USING A QUORUM DEVICE

(RHEL 9.2 and later) To configure a high availability cluster with a separate quorum device by using the **ha_cluster** system role, first set up the quorum device. After setting up the quorum device, you can use the device in any number of clusters.

10.11.1. Configuring a quorum device

To configure a quorum device using the **ha_cluster** system role, follow these steps. Note that you cannot run a quorum device on a cluster node.



WARNING

The **ha_cluster** system role replaces any existing cluster configuration on the specified nodes. Any settings not specified in the playbook will be lost.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- The system that you will use to run the quorum device has active subscription coverage for RHEL and the RHEL High Availability Add-On.
- The inventory file specifies the quorum devices as described in Specifying an inventory for the ha_cluster system role.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

 name: Configure a quorum device hosts: nodeQ

roles:
- rhel-system-roles.ha_cluster

vars:

ha_cluster_cluster_present: false

ha_cluster_password: <password>

ha_cluster_manage_firewall: true ha_cluster_manage_selinux: true

ha_cluster_qnetd: present: true

This example playbook file configures a quorum device on a system running the **firewalld** and **selinux** services.

When creating your playbook file for production, vault encrypt the password, as described in Encrypting content with Ansible Vault.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.ha_cluster/README.md file
- /usr/share/doc/rhel-system-roles/ha cluster/ directory

10.11.2. Configuring a cluster to use a quorum device

To configure a cluster to use a quorum device, follow these steps.



WARNING

The **ha_cluster** system role replaces any existing cluster configuration on the specified nodes. Any settings not specified in the playbook will be lost.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- The systems that you will use as your cluster members have active subscription coverage for RHEL and the RHEL High Availability Add-On.
- The inventory file specifies the cluster nodes as described in Specifying an inventory for the ha_cluster system role.
- You have configured a quorum device.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

- name: Configure a cluster to use a quorum device

hosts: node1 node2

roles:

```
rhel-system-roles.ha_cluster
vars:
ha_cluster_cluster_name: my-new-cluster
ha_cluster_hacluster_password: <password>
ha_cluster_manage_firewall: true
ha_cluster_manage_selinux: true
ha_cluster_quorum:
device:
model: net
model_options:
name: host
value: nodeQ
name: algorithm
value: lms
```

This example playbook file configures a cluster running the **firewalld** and **selinux** services that uses a quorum device.

When creating your playbook file for production, vault encrypt the password, as described in Encrypting content with Ansible Vault.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.ha_cluster/README.md file
- /usr/share/doc/rhel-system-roles/ha_cluster/ directory

10.12. CONFIGURING A HIGH AVAILABILITY CLUSTER WITH NODE ATTRIBUTES

(RHEL 9.4 and later) The following procedure uses the **ha_cluster** system role to create a high availability cluster that configures node attributes.

Prerequisites

• You have **ansible-core** installed on the node from which you want to run the playbook.



NOTE

You do not need to have **ansible-core** installed on the cluster member nodes.

- You have the **rhel-system-roles** package installed on the system from which you want to run the playbook.
- The systems that you will use as your cluster members have active subscription coverage for RHEL and the RHEL High Availability Add-On.



WARNING

The **ha_cluster** system role replaces any existing cluster configuration on the specified nodes. Any settings not specified in the playbook will be lost.

Procedure

- 1. Create an inventory file specifying the nodes in the cluster, as described in Specifying an inventory for the ha_cluster system role.
- 2. Create a playbook file, for example **new-cluster.yml**.



NOTE

When creating your playbook file for production, vault encrypt the password, as described in Encrypting content with Ansible Vault.

The following example playbook file configures a cluster running the **firewalld** and **selinux** services with node attributes configured for the nodes in the cluster.

- hosts: node1 node2

vars:

ha_cluster_cluster_name: my-new-cluster ha_cluster_hacluster_password: password

ha_cluster_manage_firewall: true ha_cluster_manage_selinux: true

ha_cluster_node_options:

node_name: node1 attributes:

- attrs:

name: attribute1 value: value1Aname: attribute2 value: value2A

- node_name: node2

attributes:

- attrs:

name: attribute1 value: value1Bname: attribute2 value: value2B

roles:

- linux-system-roles.ha_cluster

- 3. Save the file.
- 4. Run the playbook, specifying the path to the inventory file inventory you created in Step 1.

ansible-playbook -i inventory new-cluster.yml

10.13. CONFIGURING AN APACHE HTTP SERVER IN A HIGH AVAILABILITY CLUSTER WITH THE HA_CLUSTER RHEL SYSTEM ROLE

This procedure configures an active/passive Apache HTTP server in a two-node Red Hat Enterprise Linux High Availability Add-On cluster using the **ha_cluster** system role.



WARNING

The **ha_cluster** system role replaces any existing cluster configuration on the specified nodes. Any settings not specified in the playbook will be lost.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- The systems that you will use as your cluster members have active subscription coverage for RHEL and the RHEL High Availability Add-On.
- The inventory file specifies the cluster nodes as described in Specifying an inventory for the ha_cluster system role.
- You have configured an LVM logical volume with an XFS file system, as described in Configuring an LVM volume with an XFS file system in a Pacemaker cluster.
- You have configured an Apache HTTP server, as described in Configuring an Apache HTTP Server.
- Your system includes an APC power switch that will be used to fence the cluster nodes.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

- name: Configure active/passive Apache server in a high availability cluster hosts: z1.example.com z2.example.com roles:
 - rhel-system-roles.ha_cluster

vars

ha_cluster_password: <password>

```
ha_cluster_cluster_name: my_cluster
ha_cluster_manage_firewall: true
ha_cluster_manage_selinux: true
ha_cluster_fence_agent_packages:
- fence-agents-apc-snmp
ha_cluster_resource_primitives:
 - id: myapc
  agent: stonith:fence_apc_snmp
  instance attrs:
   - attrs:
      - name: ipaddr
       value: zapc.example.com
      - name: pcmk_host_map
       value: z1.example.com:1;z2.example.com:2
      - name: login
       value: apc
      - name: passwd
       value: apc
 - id: my lvm
  agent: ocf:heartbeat:LVM-activate
  instance attrs:
   - attrs:
      - name: vgname
       value: my vg
      - name: vg_access_mode
       value: system_id
 - id: my_fs
  agent: Filesystem
  instance attrs:
   - attrs:
      - name: device
       value: /dev/my_vg/my_lv
     - name: directory
       value: /var/www
      - name: fstype
       value: xfs
 - id: VirtualIP
  agent: IPaddr2
  instance_attrs:
   - attrs:
      - name: ip
       value: 198.51.100.3
     - name: cidr_netmask
       value: 24
 - id: Website
  agent: apache
  instance attrs:
   - attrs:
      - name: configfile
       value: /etc/httpd/conf/httpd.conf
      - name: statusurl
       value: http://127.0.0.1/server-status
ha_cluster_resource_groups:
 - id: apachegroup
  resource_ids:
   - my_lvm
```

- my_fs
- VirtualIP
- Website

This example playbook file configures a previously-created Apache HTTP server in an active/passive two-node HA cluster running the **firewalld** and **selinux** services.

This example uses an APC power switch with a host name of **zapc.example.com**. If the cluster does not use any other fence agents, you can optionally list only the fence agents your cluster requires when defining the **ha_cluster_fence_agent_packages** variable, as in this example.

When creating your playbook file for production, vault encrypt the password, as described in Encrypting content with Ansible Vault.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

4. When you use the **apache** resource agent to manage Apache, it does not use **systemd**. Because of this, you must edit the **logrotate** script supplied with Apache so that it does not use **systemctl** to reload Apache.

Remove the following line in the /etc/logrotate.d/httpd file on each node in the cluster.

/bin/systemctl reload httpd.service > /dev/null 2>/dev/null || true

Replace the line you removed with the following three lines, specifying /var/run/httpd-website.pid as the PID file path where website is the name of the Apache resource. In this example, the Apache resource name is **Website**.

/usr/bin/test -f /var/run/httpd-Website.pid >/dev/null 2>/dev/null && /usr/bin/ps -q \$(/usr/bin/cat /var/run/httpd-Website.pid) >/dev/null 2>/dev/null && /usr/sbin/httpd -f /etc/httpd/conf/httpd.conf -c "PidFile /var/run/httpd-Website.pid" -k graceful > /dev/null 2>/dev/null || true

Verification

From one of the nodes in the cluster, check the status of the cluster. Note that all four resources are running on the same node, z1.example.com.
 If you find that the resources you configured are not running, you can run the pcs resource debug-start resource command to test the resource configuration.

[root@z1 ~]# pcs status Cluster name: my_cluster

Last updated: Wed Jul 31 16:38:51 2013

Last change: Wed Jul 31 16:42:14 2013 via crm_attribute on z1.example.com

Stack: corosync

Current DC: z2.example.com (2) - partition with quorum

Version: 1.1.10-5.el7-9abe687

2 Nodes configured6 Resources configured

Online: [z1.example.com z2.example.com]

Full list of resources:

myapc (stonith:fence_apc_snmp): Started z1.example.com

Resource Group: apachegroup

my_lvm (ocf::heartbeat:LVM-activate): Started z1.example.com
my_fs (ocf::heartbeat:Filesystem): Started z1.example.com
VirtualIP (ocf::heartbeat:IPaddr2): Started z1.example.com
Website (ocf::heartbeat:apache): Started z1.example.com

2. Once the cluster is up and running, you can point a browser to the IP address you defined as the **IPaddr2** resource to view the sample display, consisting of the simple word "Hello".

Hello

3. To test whether the resource group running on **z1.example.com** fails over to node **z2.example.com**, put node **z1.example.com** in **standby** mode, after which the node will no longer be able to host resources.

[root@z1 ~]# pcs node standby z1.example.com

4. After putting node **z1** in **standby** mode, check the cluster status from one of the nodes in the cluster. Note that the resources should now all be running on **z2**.

[root@z1 ~]# pcs status

Cluster name: my_cluster

Last updated: Wed Jul 31 17:16:17 2013

Last change: Wed Jul 31 17:18:34 2013 via crm_attribute on z1.example.com

Stack: corosync

Current DC: z2.example.com (2) - partition with quorum

Version: 1.1.10-5.el7-9abe687

2 Nodes configured6 Resources configured

Node z1.example.com (1): standby

Online: [z2.example.com]

Full list of resources:

myapc (stonith:fence apc snmp): Started z1.example.com

Resource Group: apachegroup

my_lvm (ocf::heartbeat:LVM-activate): Started z2.example.com my_fs (ocf::heartbeat:Filesystem): Started z2.example.com VirtualIP (ocf::heartbeat:IPaddr2): Started z2.example.com Website (ocf::heartbeat:apache): Started z2.example.com

The web site at the defined IP address should still display, without interruption.

5. To remove **z1** from **standby** mode, enter the following command.

[root@z1 ~]# pcs node unstandby z1.example.com

NOTE

Removing a node from **standby** mode does not in itself cause the resources to fail back over to that node. This will depend on the **resource-stickiness** value for the resources. For information about the **resource-stickiness** meta attribute, see Configuring a resource to prefer its current node.

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.ha_cluster/README.md file
- /usr/share/doc/rhel-system-roles/ha_cluster/ directory

CHAPTER 11. CONFIGURING THE SYSTEMD JOURNAL BY USING RHEL SYSTEM ROLES

With the **journald** RHEL system role you can automate the **systemd** journal, and configure persistent logging by using the Red Hat Ansible Automation Platform.

11.1. CONFIGURING PERSISTENT LOGGING BY USING THEJOURNALD RHEL SYSTEM ROLE

By default, the **systemd** journal stores logs only in a small ring buffer in /run/log/journal, which is not persistent. Rebooting the system also removes journal database logs. You can configure persistent logging consistently on multiple systems by using the journald RHEL system role.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

- name: Configure journald hosts: managed-node-01.example.com tasks:

 name: Configure persistent logging ansible.builtin.include_role:

name: rhel-system-roles.journald

vars:

journald_persistent: true journald_max_disk_size: <size>

journald_per_user: true

journald_sync_interval: <interval>

The settings specified in the example playbook include the following:

journald_persistent: true

Enables persistent logging.

journald_max_disk_size: <size>

Specifies the maximum size of disk space for journal files in MB, for example, 2048.

journald_per_user: true

Configures **journald** to keep log data separate for each user.

journald_sync_interval: <interval>

Sets the synchronization interval in minutes, for example, 1.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-

system-roles.journald/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.journald/README.md file
- /usr/share/doc/rhel-system-roles/journald/ directory

CHAPTER 12. CONFIGURING AUTOMATIC CRASH DUMPS BY USING RHEL SYSTEM ROLES

To manage kdump using Ansible, you can use the **kdump** role, which is one of the RHEL system roles available in RHEL 9.

Using the **kdump** role enables you to specify where to save the contents of the system's memory for later analysis.

12.1. CONFIGURING THE KERNEL CRASH DUMPING MECHANISM BY USING THE KDUMP RHEL SYSTEM ROLE

You can set basic kernel dump parameters on multiple systems by using the **kdump** system role by running an Ansible playbook.



WARNING

The **kdump** Systeme Role replaces the **kdump** configuration of the managed hosts entirely by replacing the /**etc/kdump.conf** file. Additionally, if the **kdump** role is applied, all previous **kdump** settings are also replaced, even if they are not specified by the role variables, by replacing the /**etc/sysconfig/kdump** file.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

- hosts: managed-node-01.example.com

roles

- rhel-system-roles.kdump

vars:

kdump_path: /var/crash

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.kdump/README.md file
- /usr/share/doc/rhel-system-roles/kdump/ directory

CHAPTER 13. CONFIGURING KERNEL PARAMETERS PERMANENTLY BY USING RHEL SYSTEM ROLES

You can use the **kernel_settings** RHEL system role to configure kernel parameters on multiple clients at once. This solution:

- Provides a friendly interface with efficient input setting.
- Keeps all intended kernel parameters in one place.

After you run the **kernel_settings** role from the control machine, the kernel parameters are applied to the managed systems immediately and persist across reboots.



IMPORTANT

Note that RHEL system role delivered over RHEL channels are available to RHEL customers as an RPM package in the default AppStream repository. RHEL system role are also available as a collection to customers with Ansible subscriptions over Ansible Automation Hub.

13.1. INTRODUCTION TO THE KERNEL_SETTINGS RHEL SYSTEM ROLE

RHEL system roles is a set of roles that provide a consistent configuration interface to remotely manage multiple systems.

RHEL system roles were introduced for automated configurations of the kernel using the **kernel_settings** RHEL system role. The **rhel-system-roles** package contains this system role, and also the reference documentation.

To apply the kernel parameters on one or more systems in an automated fashion, use the **kernel_settings** role with one or more of its role variables of your choice in a playbook. A playbook is a list of one or more plays that are human-readable, and are written in the YAML format.

You can use an inventory file to define a set of systems that you want Ansible to configure according to the playbook.

With the **kernel_settings** role you can configure:

- The kernel parameters using the **kernel_settings_sysctl** role variable
- Various kernel subsystems, hardware devices, and device drivers using the kernel_settings_sysfs role variable
- The CPU affinity for the systemd service manager and processes it forks using the kernel_settings_systemd_cpu_affinity role variable
- The kernel memory subsystem transparent hugepages using the kernel_settings_transparent_hugepages and kernel settings transparent hugepages defrag role variables

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.kernel_settings/README.md file
- /usr/share/doc/rhel-system-roles/kernel_settings/ directory

- Working with playbooks
- How to build your inventory

13.2. APPLYING SELECTED KERNEL PARAMETERS BY USING THE KERNEL_SETTINGS RHEL SYSTEM ROLE

Follow these steps to prepare and apply an Ansible playbook to remotely configure kernel parameters with persisting effect on multiple managed operating systems.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

- name: Configure kernel settings

hosts: managed-node-01.example.com

roles:

- rhel-system-roles.kernel_settings

vars:

kernel_settings_sysctl:

- name: fs.file-max

value: 400000

- name: kernel.threads-max

value: 65536

kernel settings sysfs:

- name: /sys/class/net/lo/mtu

value: 65000

kernel_settings_transparent_hugepages: madvise

- **name**: optional key which associates an arbitrary string with the play as a label and identifies what the play is for.
- hosts: key in the play which specifies the hosts against which the play is run. The value or
 values for this key can be provided as individual names of managed hosts or as groups of
 hosts as defined in the inventory file.
- **vars**: section of the playbook which represents a list of variables containing selected kernel parameter names and values to which they have to be set.
- **role**: key which specifies what RHEL system role is going to configure the parameters and values mentioned in the **vars** section.



NOTE

You can modify the kernel parameters and their values in the playbook to fit your needs.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

4. Restart your managed hosts and check the affected kernel parameters to verify that the changes have been applied and persist across reboots.

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.kernel_settings/README.md file
- /usr/share/doc/rhel-system-roles/kernel_settings/ directory
- Working With Playbooks
- Using Variables
- Roles

CHAPTER 14. CONFIGURING THE GRUB 2 BOOT LOADER BY USING RHEL SYSTEM ROLES

By using the **bootloader** RHEL system role, you can automate the configuration and management tasks related to the GRUB2 boot loader.

This role currently supports configuring the GRUB2 boot loader, which runs on the following CPU architectures:

- AMD and Intel 64-bit architectures (x86-64)
- The 64-bit ARM architecture (ARMv8.0)
- IBM Power Systems, Little Endian (POWER9)

14.1. UPDATING THE EXISTING BOOT LOADER ENTRIES BY USING THE BOOTLOADER RHEL SYSTEM ROLE

You can use the **bootloader** RHEL system role to update the existing entries in the GRUB2 boot menu in an automated fashion. This way you can efficiently pass specific kernel command-line parameters that can optimize the performance or behavior of your systems.

For example, if you leverage systems, where detailed boot messages from the kernel and init system are not necessary, use **bootloader** to apply the **quiet** parameter to your existing boot loader entries on your managed nodes to achieve a cleaner, less cluttered, and more user-friendly booting experience.

Prerequisites

- You have prepared the control node and the managed nodes.
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- You identified the kernel that corresponds to the boot loader entry you want to update.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

 name: Configuration and management of GRUB2 boot loader hosts: managed-node-01.example.com tasks:

- name: Update existing boot loader entries ansible.builtin.include role:

name: rhel-system-roles.bootloader

vars:

bootloader_settings:

kernel: path: /boot/vmlinuz-5.14.0-362.24.1.el9_3.aarch64 options: name: quiet state: present

bootloader_reboot_ok: true

The settings specified in the example playbook include the following:

kernel

Specifies the kernel connected with the boot loader entry that you want to update.

options

Specifies the kernel command-line parameters to update for your chosen boot loader entry (kernel).

bootloader_reboot_ok: true

The role detects that a reboot is needed for the changes to take effect and performs a restart of the managed node.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.bootloader/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

• Check that your specified boot loader entry has updated kernel command-line parameters:

```
# ansible managed-node-01.example.com -m ansible.builtin.command -a 'grubby -- info=ALL'
```

...
index=1
kernel="/boot/vmlinuz-5.14.0-362.24.1.el9_3.aarch64"
args="ro crashkernel=1G-4G:256M,4G-64G:320M,64G-:576M rd.lvm.lv=rhel/root rd.lvm.lv=rhel/swap \$tuned_params quiet"

managed-node-01.example.com | CHANGED | rc=0 >>

root="/dev/mapper/rhel-root"

initrd="/boot/initramfs-5.14.0-362.24.1.el9_3.aarch64.img \$tuned_initrd" title="Red Hat Enterprise Linux (5.14.0-362.24.1.el9_3.aarch64) 9.4 (Plow)" id="2c9ec787230141a9b087f774955795ab-5.14.0-362.24.1.el9_3.aarch64"

...

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.bootloader/README.md file
- /usr/share/doc/rhel-system-roles/bootloader/ directory

- Working With Playbooks
- Using Variables
- Roles
- Configuring kernel command-line parameters

14.2. SECURING THE BOOT MENU WITH PASSWORD BY USING THE BOOTLOADER RHEL SYSTEM ROLE

You can use the **bootloader** RHEL system role to set a password to the GRUB2 boot menu in an automated fashion. This way you can efficiently prevent unauthorized users from modifying boot parameters, and to have better control over the system boot.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

- 1. Store your sensitive variables in an encrypted file:
 - a. Create the vault:

\$ ansible-vault create vault.yml
New Vault password: <vault_password>
Confirm New Vault password: <vault_password>

b. After the **ansible-vault create** command opens an editor, enter the sensitive data in the **<**key>: **<**value> format:

pwd: <password>

- c. Save the changes, and close the editor. Ansible encrypts the data in the vault.
- 2. Create a playbook file, for example ~/playbook.yml, with the following content:

--- name: Configuration and management of GRUB2 boot loader hosts: managed-node-01.example.com vars_files:
- vault.yml tasks:
- name: Set the bootloader password ansible.builtin.include role:

name: rhel-system-roles.bootloader vars:
bootloader_password: "{{ pwd }}"
bootloader reboot ok: true

The settings specified in the example playbook include the following:

bootloader password: "{{ pwd }}"

The variable ensures protection of boot parameters with a password.

bootloader_reboot_ok: true

The role detects that a reboot is needed for the changes to take effect and performs a restart of the managed node.



IMPORTANT

Changing the boot loader password is not an idempotent transaction. This means that if you apply the same Ansible playbook again, the result will not be the same, and the state of the managed node will change.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.bootloader/README.md file on the control node.

3. Validate the playbook syntax:

\$ ansible-playbook --syntax-check --ask-vault-pass ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

\$ ansible-playbook --ask-vault-pass ~/playbook.yml

Verification

1. On your managed node during the GRUB2 boot menu screen, press the **e** key for edit.



2. You will be prompted for a username and a password:

```
Enter username:
root
Enter password:
-
```

Enter username: root

The boot loader username is always **root** and you do not need to specify it in your Ansible playbook.

The boot loader password corresponds to the **pwd** variable that you defined in the **vault.yml** file.

3. You can view or edit configuration of the particular boot loader entry:

```
GRUB version 2.06

load_video
set gfxpayload=keep
insmod gzio
linux ($root)/vmlinuz-5.14.0-362.24.1.e19_3.aarch64 root=/dev/mapper/rhel-r\
oot ro crashkernel=16-46:256M,46-646:320M,646-:576M rd.lum.lu=rhel/root rd.\
lum.lu=rhel/swap quiet
initrd ($root)/initramfs-5.14.0-362.24.1.e19_3.aarch64.img $tuned_initrd

Minimum Emacs-like screen editing is supported. TAB lists
completions. Press Ctrl-x or F10 to boot, Ctrl-c or F2 for a
command-line or ESC to discard edits and return to the GRUB menu.
```

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.bootloader/README.md file
- /usr/share/doc/rhel-system-roles/bootloader/ directory
- Working With Playbooks
- Using Variables
- Roles

14.3. SETTING A TIMEOUT FOR THE BOOT LOADER MENU BY USING THE BOOTLOADER RHEL SYSTEM ROLE

You can use the **bootloader** RHEL system role to configure a timeout for the GRUB2 boot loader menu in an automated fashion. This way you can efficiently update a period of time during which you can intervene and select a non-default boot entry for various purposes.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

 name: Configuration and management of GRUB2 boot loader hosts: managed-node-01.example.com

 name: Update the boot loader timeout ansible.builtin.include role:

name: rhel-system-roles.bootloader

vars:

bootloader_timeout: 10

The settings specified in the example playbook include the following:

bootloader_timeout: 10

Input an integer to control for how long the GRUB2 boot loader menu is displayed before booting the default entry.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.bootloader/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

1. Remotely restart your managed node:

```
# ansible managed-node-01.example.com -m ansible.builtin.reboot
managed-node-01.example.com | CHANGED => {
   "changed": true,
```

```
"elapsed": 21,
"rebooted": true
}
```

2. On the managed node, observe the GRUB2 boot menu screen.

```
Red Hat Enterprise Linux (5.14.0-427.22.1.e19_4.aarch64) 9.4 (Plow)

*Red Hat Enterprise Linux (5.14.0-362.24.1.e19_3.aarch64) 9.4 (Plow)

Red Hat Enterprise Linux (0-rescue-2c9ec787230141a9b087f774955795ab) 9.4 (▶

UEFI Firmware Settings

Use the ▲ and ▼ keys to select which entry is highlighted.

Press enter to boot the selected OS, `e' to edit the commands before booting or `c' for a command-line. ESC to return previous menu.

The highlighted entry will be executed automatically in 10s.
```

The highlighted entry will be executed automatically in 10s

For how long this boot menu is displayed before GRUB2 automatically uses the default entry.

• Alternative: you can remotely query for the "timeout" settings in the /boot/grub2/grub.cfg file of your managed node:

```
# ansible managed-node-01.example.com -m ansible.builtin.command -a "grep
'timeout' /boot/grub2/grub.cfg"
managed-node-01.example.com | CHANGED | rc=0 >>
if [ x$feature_timeout_style = xy ] ; then
 set timeout style=menu
 set timeout=10
# Fallback normal timeout code in case the timeout_style feature is
 set timeout=10
if [ x$feature_timeout_style = xy ] ; then
  set timeout style=menu
  set timeout=10
  set orig timeout style=${timeout style}
  set orig_timeout=${timeout}
   # timeout style=menu + timeout=0 avoids the countdown code keypress check
   set timeout_style=menu
   set timeout=10
   set timeout style=hidden
   set timeout=10
if [x$feature_timeout_style = xy]; then
 if [ "${menu_show_once_timeout}" ]; then
```

set timeout_style=menu
set timeout=10
unset menu_show_once_timeout
save_env menu_show_once_timeout

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.bootloader/README.md file
- /usr/share/doc/rhel-system-roles/bootloader/ directory
- Working With Playbooks
- Using Variables
- Roles

14.4. COLLECTING THE BOOT LOADER CONFIGURATION INFORMATION BY USING THE BOOTLOADER RHEL SYSTEM ROLE

You can use the **bootloader** RHEL system role to gather information about the GRUB2 boot loader entries in an automated fashion. This way you can quickly identify that your systems are set up to boot correctly, all entries point to the right kernels and initial RAM disk images.

As a result, you can for example:

- Prevent boot failures.
- Revert to a known good state when troubleshooting.
- Be sure that security-related kernel command-line parameters are correctly configured.

Prerequisites

- You have prepared the control node and the managed nodes.
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

 name: Configuration and management of GRUB2 boot loader hosts: managed-node-01.example.com

tasks:

- name: Gather information about the boot loader configuration ansible.builtin.include_role:

name: rhel-system-roles.bootloader

vars:

bootloader_gather_facts: true

- name: Display the collected boot loader configuration information debug:

var: bootloader_facts

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.bootloader/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

• After you run the preceding playbook on the control node, you will see a similar command-line output as in the following example:

The command-line output shows the following notable configuration information about the boot entry:

args

Command-line parameters passed to the kernel by the GRUB2 boot loader during the boot process. They configure various settings and behaviors of the kernel, initramfs, and other boot-time components.

id

Unique identifier assigned to each boot entry in a boot loader menu. It consists of machine ID and the kernel version.

root

The root filesystem for the kernel to mount and use as the primary filesystem during the boot.

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.bootloader/README.md file
- /usr/share/doc/rhel-system-roles/bootloader/ directory
- Working With Playbooks
- Using Variables
- Roles
- Understanding boot entries

CHAPTER 15. CONFIGURING LOGGING BY USING RHEL SYSTEM ROLES

As a system administrator, you can use the **logging** RHEL system role to configure a Red Hat Enterprise Linux host as a logging server to collect logs from many client systems.

15.1. THE LOGGING RHEL SYSTEM ROLE

With the **logging** RHEL system role, you can deploy logging configurations on local and remote hosts.

Logging solutions provide multiple ways of reading logs and multiple logging outputs.

For example, a logging system can receive the following inputs:

- Local files
- systemd/journal
- Another logging system over the network

In addition, a logging system can have the following outputs:

- Logs stored in the local files in the /var/log directory
- Logs sent to Elasticsearch
- Logs forwarded to another logging system

With the **logging** RHEL system role, you can combine the inputs and outputs to fit your scenario. For example, you can configure a logging solution that stores inputs from **journal** in a local file, whereas inputs read from files are both forwarded to another logging system and stored in the local log files.

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.logging/README.md file
- /usr/share/doc/rhel-system-roles/logging/ directory
- RHEL system roles

15.2. APPLYING A LOCALLOGGING RHEL SYSTEM ROLE

Prepare and apply an Ansible playbook to configure a logging solution on a set of separate machines. Each machine records logs locally.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.



NOTE

You do not have to have the **rsyslog** package installed, because the RHEL system role installs **rsyslog** when deployed.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

- name: Deploying basics input and implicit files output

hosts: managed-node-01.example.com

roles:

- rhel-system-roles.logging

vars:

logging_inputs:

- name: system_input

type: basics

logging_outputs:

- name: files_output

type: files logging_flows:

- name: flow1

inputs: [system_input]
outputs: [files_output]

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

1. Test the syntax of the /etc/rsyslog.conf file:

rsysload -N 1

rsyslogd: version 8.1911.0-6.el8, config validation run...

rsyslogd: End of config validation run. Bye.

- 2. Verify that the system sends messages to the log:
 - a. Send a test message:

logger test

b. View the /var/log/messages log, for example:

cat /var/log/messages

Aug 5 13:48:31 < hostname > root[6778]: test

Where **<hostname>** is the host name of the client system. Note that the log contains the user name of the user that entered the logger command, in this case **root**.

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.logging/README.md file
- /usr/share/doc/rhel-system-roles/logging/ directory

15.3. FILTERING LOGS IN A LOCAL LOGGING RHEL SYSTEM ROLE

You can deploy a logging solution which filters the logs based on the **rsyslog** property-based filter.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.



NOTE

You do not have to have the **rsyslog** package installed, because the RHEL system role installs **rsyslog** when deployed.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

- name: Deploying files input and configured files output

hosts: managed-node-01.example.com

roles:

- rhel-system-roles.logging

vars:

logging inputs:

- name: files_input

type: basics

logging_outputs:

- name: files_output0

type: files

property: msg

property_op: contains property_value: error path: /var/log/errors.log

- name: files_output1

type: files

property: msg

property_op: "!contains"
property value: error

path: /var/log/others.log

outputs: [files_output0, files_output1]

Using this configuration, all messages that contain the **error** string are logged in /var/log/errors.log, and all other messages are logged in /var/log/others.log.

You can replace the **error** property value with the string by which you want to filter.

You can modify the variables according to your preferences.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

1. Test the syntax of the /etc/rsyslog.conf file:

rsyslogd -N 1

rsyslogd: version 8.1911.0-6.el8, config validation run...

rsyslogd: End of config validation run. Bye.

- 2. Verify that the system sends messages that contain the error string to the log:
 - a. Send a test message:

logger error

b. View the /var/log/errors.log log, for example:

cat /var/log/errors.log

Aug 5 13:48:31 hostname root[6778]: error

Where *hostname* is the host name of the client system. Note that the log contains the user name of the user that entered the logger command, in this case **root**.

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.logging/README.md file
- /usr/share/doc/rhel-system-roles/logging/ directory

15.4. APPLYING A REMOTE LOGGING SOLUTION BY USING THE LOGGING RHEL SYSTEM ROLE

Follow these steps to prepare and apply a Red Hat Ansible Core playbook to configure a remote logging solution. In this playbook, one or more clients take logs from **systemd-journal** and forward them to a remote server. The server receives remote input from **remote_rsyslog** and **remote_files** and outputs the logs to local files in directories named by remote host names.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.



NOTE

You do not have to have the **rsyslog** package installed, because the RHEL system role installs **rsyslog** when deployed.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Deploying remote input and remote files output
hosts: managed-node-01.example.com
  - rhel-system-roles.logging
vars:
  logging_inputs:
   - name: remote_udp_input
    type: remote
    udp_ports: [ 601 ]
   - name: remote tcp input
    type: remote
    tcp_ports: [ 601 ]
  logging_outputs:
   - name: remote_files_output
    type: remote files
  logging_flows:
   - name: flow 0
    inputs: [remote_udp_input, remote_tcp_input]
    outputs: [remote_files_output]
- name: Deploying basics input and forwards output
hosts: managed-node-02.example.com
  - rhel-system-roles.logging
vars:
  logging_inputs:
   - name: basic_input
    type: basics
  logging_outputs:
```

name: forward_output0

type: forwards severity: info

target: <host1.example.com>

udp_port: 601

- name: forward_output1

type: forwards facility: mail

target: <host1.example.com>

tcp_port: 601
logging_flows:
- name: flows0
inputs: [basic_input]

outputs: [forward_output0, forward_output1]

[basic_input]
[forward_output0, forward_output1]

Where **<host1.example.com>** is the logging server.



NOTE

You can modify the parameters in the playbook to fit your needs.



WARNING

The logging solution works only with the ports defined in the SELinux policy of the server or client system and open in the firewall. The default SELinux policy includes ports 601, 514, 6514, 10514, and 20514. To use a different port, modify the SELinux policy on the client and server systems.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

1. On both the client and the server system, test the syntax of the /etc/rsyslog.conf file:

rsyslogd -N 1

rsyslogd: version 8.1911.0-6.el8, config validation run (level 1), master config /etc/rsyslog.conf

rsyslogd: End of config validation run. Bye.

- 2. Verify that the client system sends messages to the server:
 - a. On the client system, send a test message:

logger test

b. On the server system, view the /var/log/<host2.example.com>/messages log, for example:

cat /var/log/<host2.example.com>/messages
Aug 5 13:48:31 <host2.example.com> root[6778]: test

Where **<host2.example.com>** is the host name of the client system. Note that the log contains the user name of the user that entered the logger command, in this case **root**.

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.logging/README.md file
- /usr/share/doc/rhel-system-roles/logging/ directory

15.5. USING THE LOGGING RHEL SYSTEM ROLE WITH TLS

Transport Layer Security (TLS) is a cryptographic protocol designed to allow secure communication over the computer network.

As an administrator, you can use the **logging** RHEL system role to configure a secure transfer of logs using Red Hat Ansible Automation Platform.

15.5.1. Configuring client logging with TLS

You can use an Ansible playbook with the **logging** RHEL system role to configure logging on RHEL clients and transfer logs to a remote logging system using TLS encryption.

This procedure creates a private key and certificate, and configures TLS on all hosts in the clients group in the Ansible inventory. The TLS protocol encrypts the message transmission for secure transfer of logs over the network.



NOTE

You do not have to call the **certificate** RHEL system role in the playbook to create the certificate. The **logging** RHEL system role calls it automatically.

In order for the CA to be able to sign the created certificate, the managed nodes must be enrolled in an IdM domain.

Prerequisites

- You have prepared the control node and the managed nodes.
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has sudo permissions on them.

- The managed nodes are enrolled in an IdM domain.
- If the logging server you want to configure on the manage node runs RHEL 9.2 or later and the FIPS mode is enabled, clients must either support the Extended Master Secret (EMS) extension or use TLS 1.3. TLS 1.2 connections without EMS fail. For more information, see the TLS extension "Extended Master Secret" enforced Knowledgebase article.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Deploying files input and forwards output with certs
hosts: managed-node-01.example.com
roles:
  - rhel-system-roles.logging
  logging certificates:
   - name: logging_cert
    dns: ['localhost', 'www.example.com']
    ca: ipa
  logging_pki_files:
   - ca cert: /local/path/to/ca cert.pem
    cert: /local/path/to/logging cert.pem
    private_key: /local/path/to/logging_cert.pem
  logging_inputs:
   - name: input name
    type: files
    input log path: /var/log/containers/*.log
  logging_outputs:
   - name: output name
    type: forwards
    target: your_target_host
    tcp_port: 514
    tls: true
    pki authmode: x509/name
    permitted server: 'server.example.com'
  logging_flows:
   - name: flow_name
    inputs: [input name]
    outputs: [output name]
```

The playbook uses the following parameters:

logging_certificates

The value of this parameter is passed on to **certificate_requests** in the **certificate** RHEL system role and used to create a private key and certificate.

logging_pki_files

Using this parameter, you can configure the paths and other settings that logging uses to find the CA, certificate, and key files used for TLS, specified with one or more of the following sub-parameters: **ca_cert**, **ca_cert_src**, **cert**, **cert_src**, **private_key**, **private_key_src**, and **tls**.



NOTE

If you are using **logging_certificates** to create the files on the target node, do not use **ca_cert_src**, **cert_src**, and **private_key_src**, which are used to copy files not created by **logging_certificates**.

ca cert

Represents the path to the CA certificate file on the target node. Default path is /etc/pki/tls/certs/ca.pem and the file name is set by the user.

cert

Represents the path to the certificate file on the target node. Default path is /etc/pki/tls/certs/server-cert.pem and the file name is set by the user.

private_key

Represents the path to the private key file on the target node. Default path is /etc/pki/tls/private/server-key.pem and the file name is set by the user.

ca_cert_src

Represents the path to the CA certificate file on the control node which is copied to the target host to the location specified by **ca_cert**. Do not use this if using **logging_certificates**.

cert src

Represents the path to a certificate file on the control node which is copied to the target host to the location specified by **cert**. Do not use this if using **logging_certificates**.

private_key_src

Represents the path to a private key file on the control node which is copied to the target host to the location specified by **private_key**. Do not use this if using **logging_certificates**.

tls

Setting this parameter to **true** ensures secure transfer of logs over the network. If you do not want a secure wrapper, you can set **tls: false**.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.logging/README.md file
- /usr/share/doc/rhel-system-roles/logging/ directory
- Requesting certificates using RHEL system roles.

15.5.2. Configuring server logging with TLS

You can use an Ansible playbook with the **logging** RHEL system role to configure logging on RHEL servers and set them to receive logs from a remote logging system using TLS encryption.

This procedure creates a private key and certificate, and configures TLS on all hosts in the server group in the Ansible inventory.



NOTE

You do not have to call the **certificate** RHEL system role in the playbook to create the certificate. The **logging** RHEL system role calls it automatically.

In order for the CA to be able to sign the created certificate, the managed nodes must be enrolled in an IdM domain.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- The managed nodes are enrolled in an IdM domain.
- If the logging server you want to configure on the manage node runs RHEL 9.2 or later and the FIPS mode is enabled, clients must either support the Extended Master Secret (EMS) extension or use TLS 1.3. TLS 1.2 connections without EMS fail. For more information, see the TLS extension "Extended Master Secret" enforced Knowledgebase article.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Deploying remote input and remote files output with certs
hosts: managed-node-01.example.com
 roles:
  - rhel-system-roles.logging
 vars:
  logging_certificates:
   - name: logging_cert
    dns: ['localhost', 'www.example.com']
    ca: ipa
  logging_pki_files:
   - ca_cert: /local/path/to/ca_cert.pem
    cert: /local/path/to/logging_cert.pem
    private_key: /local/path/to/logging_cert.pem
  logging inputs:
   - name: input_name
    type: remote
    tcp_ports: 514
    tls: true
    permitted_clients: ['clients.example.com']
  logging_outputs:
    name: output_name
    type: remote files
```

remote_log_path: /var/log/remote/%FROMHOST%/%PROGRAMNAME:::secpath-replace%.log

async_writing: true client_count: 20 io_buffer_size: 8192

logging_flows:

name: flow_name inputs: [input_name] outputs: [output_name]

The playbook uses the following parameters:

logging_certificates

The value of this parameter is passed on to **certificate_requests** in the **certificate** RHEL system role and used to create a private key and certificate.

logging_pki_files

Using this parameter, you can configure the paths and other settings that logging uses to find the CA, certificate, and key files used for TLS, specified with one or more of the following sub-parameters: **ca_cert**, **ca_cert_src**, **cert**, **cert_src**, **private_key**, **private_key_src**, and **tls**.



NOTE

If you are using **logging_certificates** to create the files on the target node, do not use **ca_cert_src**, **cert_src**, and **private_key_src**, which are used to copy files not created by **logging_certificates**.

ca cert

Represents the path to the CA certificate file on the target node. Default path is /etc/pki/tls/certs/ca.pem and the file name is set by the user.

cert

Represents the path to the certificate file on the target node. Default path is /etc/pki/tls/certs/server-cert.pem and the file name is set by the user.

private_key

Represents the path to the private key file on the target node. Default path is /etc/pki/tls/private/server-key.pem and the file name is set by the user.

ca_cert_src

Represents the path to the CA certificate file on the control node which is copied to the target host to the location specified by **ca_cert**. Do not use this if using **logging_certificates**.

cert_src

Represents the path to a certificate file on the control node which is copied to the target host to the location specified by **cert**. Do not use this if using **logging certificates**.

private_key_src

Represents the path to a private key file on the control node which is copied to the target host to the location specified by **private_key**. Do not use this if using **logging_certificates**.

tls

Setting this parameter to **true** ensures secure transfer of logs over the network. If you do not want a secure wrapper, you can set **tls: false**.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.logging/README.md file
- /usr/share/doc/rhel-system-roles/logging/ directory
- Requesting certificates using RHEL system roles .

15.6. USING THE LOGGING RHEL SYSTEM ROLES WITH RELP

Reliable Event Logging Protocol (RELP) is a networking protocol for data and message logging over the TCP network. It ensures reliable delivery of event messages and you can use it in environments that do not tolerate any message loss.

The RELP sender transfers log entries in form of commands and the receiver acknowledges them once they are processed. To ensure consistency, RELP stores the transaction number to each transferred command for any kind of message recovery.

You can consider a remote logging system in between the RELP Client and RELP Server. The RELP Client transfers the logs to the remote logging system and the RELP Server receives all the logs sent by the remote logging system.

Administrators can use the **logging** RHEL system role to configure the logging system to reliably send and receive log entries.

15.6.1. Configuring client logging with RELP

You can use the **logging** RHEL system role to configure logging in RHEL systems that are logged on a local machine and can transfer logs to the remote logging system with RELP by running an Ansible playbook.

This procedure configures RELP on all hosts in the **clients** group in the Ansible inventory. The RELP configuration uses Transport Layer Security (TLS) to encrypt the message transmission for secure transfer of logs over the network.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has sudo permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Deploying basic input and relp output
 hosts: managed-node-01.example.com
 roles:
  - rhel-system-roles.logging
  logging_inputs:
   - name: basic_input
    type: basics
  logging_outputs:
   - name: relp_client
    type: relp
     target: logging.server.com
     port: 20514
    tls: true
     ca cert: /etc/pki/tls/certs/ca.pem
     cert: /etc/pki/tls/certs/client-cert.pem
     private_key: /etc/pki/tls/private/client-key.pem
     pki_authmode: name
     permitted servers:
      - '*.server.example.com'
  logging_flows:
   - name: example_flow
     inputs: [basic_input]
     outputs: [relp_client]
```

The playbook uses following settings:

target

This is a required parameter that specifies the host name where the remote logging system is running.

port

Port number the remote logging system is listening.

tls

Ensures secure transfer of logs over the network. If you do not want a secure wrapper you can set the **tls** variable to **false**. By default **tls** parameter is set to true while working with RELP and requires key/certificates and triplets {**ca_cert**, **cert**, **private_key**} and/or {**ca_cert_src**, **cert_src**, **private_key_src**}.

- If the {ca_cert_src, cert_src, private_key_src} triplet is set, the default locations
 /etc/pki/tls/certs and /etc/pki/tls/private are used as the destination on the managed
 node to transfer files from control node. In this case, the file names are identical to the
 original ones in the triplet
- If the {ca_cert, cert, private_key} triplet is set, files are expected to be on the default path before the logging configuration.
- If both triplets are set, files are transferred from local path from control node to specific path of the managed node.

ca_cert

Represents the path to CA certificate. Default path is /etc/pki/tls/certs/ca.pem and the file name is set by the user.

cert

Represents the path to certificate. Default path is /etc/pki/tls/certs/server-cert.pem and the file name is set by the user.

private_key

Represents the path to private key. Default path is /etc/pki/tls/private/server-key.pem and the file name is set by the user.

ca_cert_src

Represents local CA certificate file path which is copied to the target host. If **ca_cert** is specified, it is copied to the location.

cert src

Represents the local certificate file path which is copied to the target host. If **cert** is specified, it is copied to the location.

private_key_src

Represents the local key file path which is copied to the target host. If **private_key** is specified, it is copied to the location.

pki_authmode

Accepts the authentication mode as **name** or **fingerprint**.

permitted servers

List of servers that will be allowed by the logging client to connect and send logs over TLS.

inputs

List of logging input dictionary.

outputs

List of logging output dictionary.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.logging/README.md file
- /usr/share/doc/rhel-system-roles/logging/ directory

15.6.2. Configuring server logging with RELP

You can use the **logging** RHEL system role to configure logging in RHEL systems as a server and can receive logs from the remote logging system with RELP by running an Ansible playbook.

This procedure configures RELP on all hosts in the **server** group in the Ansible inventory. The RELP configuration uses TLS to encrypt the message transmission for secure transfer of logs over the network.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Deploying remote input and remote files output
hosts: managed-node-01.example.com
  - rhel-system-roles.logging
vars:
  logging_inputs:
   name: relp_server
    type: relp
    port: 20514
    tls: true
    ca cert: /etc/pki/tls/certs/ca.pem
    cert: /etc/pki/tls/certs/server-cert.pem
    private_key: /etc/pki/tls/private/server-key.pem
    pki authmode: name
    permitted_clients:
      - '*example.client.com'
  logging_outputs:
   - name: remote_files_output
    type: remote_files
  logging_flows:
   name: example_flow
    inputs: relp_server
    outputs: remote_files_output
```

The playbooks uses the following settings:

port

Port number the remote logging system is listening.

tls

Ensures secure transfer of logs over the network. If you do not want a secure wrapper you can set the **tls** variable to **false**. By default **tls** parameter is set to true while working with RELP and requires key/certificates and triplets {**ca_cert**, **cert**, **private_key**} and/or {**ca_cert_src**, **cert_src**, **private_key_src**}.

If the {ca_cert_src, cert_src, private_key_src} triplet is set, the default locations /etc/pki/tls/certs and /etc/pki/tls/private are used as the destination on the managed node to transfer files from control node. In this case, the file names are identical to the original ones in the triplet

- If the {ca_cert, cert, private_key} triplet is set, files are expected to be on the default path before the logging configuration.
- If both triplets are set, files are transferred from local path from control node to specific path of the managed node.

ca cert

Represents the path to CA certificate. Default path is /etc/pki/tls/certs/ca.pem and the file name is set by the user.

cert

Represents the path to the certificate. Default path is /etc/pki/tls/certs/server-cert.pem and the file name is set by the user.

private_key

Represents the path to private key. Default path is /etc/pki/tls/private/server-key.pem and the file name is set by the user.

ca cert src

Represents local CA certificate file path which is copied to the target host. If **ca_cert** is specified, it is copied to the location.

cert src

Represents the local certificate file path which is copied to the target host. If **cert** is specified, it is copied to the location.

private_key_src

Represents the local key file path which is copied to the target host. If **private_key** is specified, it is copied to the location.

pki_authmode

Accepts the authentication mode as **name** or **fingerprint**.

permitted clients

List of clients that will be allowed by the logging server to connect and send logs over TLS.

inputs

List of logging input dictionary.

outputs

List of logging output dictionary.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

$\$\ ansible-playbook\ {\sim}/playbook.yml$

Additional resources

• /usr/share/ansible/roles/rhel-system-roles.logging/README.md file

• /usr/share/doc/rhel-system-roles/logging/ directory

CHAPTER 16. MONITORING PERFORMANCE BY USING THE RHEL SYSTEM ROLE

As a system administrator, you can use the **metrics** RHEL system role to monitor the performance of a system.

16.1. INTRODUCTION TO THE METRICS RHEL SYSTEM ROLE

RHEL system roles is a collection of Ansible roles and modules that provide a consistent configuration interface to remotely manage multiple RHEL systems. The **metrics** system role configures performance analysis services for the local system and, optionally, includes a list of remote systems to be monitored by the local system. The **metrics** system role enables you to use **pcp** to monitor your systems performance without having to configure **pcp** separately, as the set-up and deployment of **pcp** is handled by the playbook.

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.metrics/README.md file
- /usr/share/doc/rhel-system-roles/metrics/ directory

16.2. USING THE METRICS RHEL SYSTEM ROLE TO MONITOR YOUR LOCAL SYSTEM WITH VISUALIZATION

This procedure describes how to use the **metrics** RHEL system role to monitor your local system while simultaneously provisioning data visualization via **Grafana**.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- **localhost** is configured in the inventory file on the control node:
 - localhost ansible_connection=local

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

--- name: Manage metrics
hosts: localhost
roles:
 - rhel-system-roles.metrics
vars:
 metrics_graph_service: yes
 metrics_manage_firewall: true
 metrics manage selinux: true

Because the metrics_graph_service boolean is set to value="yes", Grafana is automatically installed and provisioned with pcp added as a data source. Because metrics_manage_firewall and metrics_manage_selinux are both set to true, the metrics role uses the firewall and selinux system roles to manage the ports used by the metrics role.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

• To view visualization of the metrics being collected on your machine, access the **grafana** web interface as described in Accessing the Grafana web UI.

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.metrics/README.md file
- /usr/share/doc/rhel-system-roles/metrics/ directory

16.3. USING THE METRICS RHEL SYSTEM ROLE TO SET UP A FLEET OF INDIVIDUAL SYSTEMS TO MONITOR THEMSELVES

This procedure describes how to use the **metrics** system role to set up a fleet of machines to monitor themselves.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
---
- name: Configure a fleet of machines to monitor themselves hosts: managed-node-01.example.com roles:
- rhel-system-roles.metrics
vars:
metrics_retention_days: 0
metrics_manage_firewall: true
metrics_manage_selinux: true
```

Because metrics_manage_firewall and metrics_manage_selinux are both set to true, the metrics role uses the firewall and selinux roles to manage the ports used by the metrics role.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.metrics/README.md file
- /usr/share/doc/rhel-system-roles/metrics/ directory

16.4. USING THE METRICS RHEL SYSTEM ROLE TO MONITOR A FLEET OF MACHINES CENTRALLY USING YOUR LOCAL MACHINE

This procedure describes how to use the **metrics** system role to set up your local machine to centrally monitor a fleet of machines while also provisioning visualization of the data via **grafana** and querying of the data via **redis**.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- **localhost** is configured in the inventory file on the control node:
 - localhost ansible_connection=local

Procedure

- 1. Create a playbook file, for example ~/playbook.yml, with the following content:
 - name: Set up your local machine to centrally monitor a fleet of machines hosts: localhost

- rhel-system-roles.metrics

vars:

roles:

metrics_graph_service: yes metrics_query_service: yes metrics_retention_days: 10 metrics_monitored_hosts: ["database.example.com", "webserver.example.com"]

metrics_manage_firewall: yes metrics_manage_selinux: yes

Because the metrics_graph_service and metrics_query_service booleans are set to value="yes", grafana is automatically installed and provisioned with pcp added as a data source with the pcp data recording indexed into redis, allowing the pcp querying language to be used for complex querying of the data. Because metrics_manage_firewall and metrics_manage_selinux are both set to true, the metrics role uses the firewall and selinux roles to manage the ports used by the metrics role.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

 To view a graphical representation of the metrics being collected centrally by your machine and to query the data, access the **grafana** web interface as described in Accessing the Grafana web UI.

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.metrics/README.md file
- /usr/share/doc/rhel-system-roles/metrics/ directory

16.5. SETTING UP AUTHENTICATION WHILE MONITORING A SYSTEM BY USING THE METRICS RHEL SYSTEM ROLE

PCP supports the **scram-sha-256** authentication mechanism through the Simple Authentication Security Layer (SASL) framework. The **metrics** RHEL system role automates the steps to setup authentication by using the **scram-sha-256** authentication mechanism. This procedure describes how to setup authentication by using the **metrics** RHEL system role.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Edit an existing playbook file, for example ~/playbook.yml, and add the authentication-related variables:

 name: Set up authentication by using the scram-sha-256 authentication mechanism hosts: managed-node-01.example.com roles:

- rhel-system-roles.metrics

vars:

metrics_retention_days: 0
metrics_manage_firewall: true
metrics_manage_selinux: true
metrics_username: <username>
metrics_password: password>

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

• Verify the **sasl** configuration:

pminfo -f -h "pcp://managed-node-01.example.com?username=<username>" disk.dev.read
Password: <password>
disk.dev.read
inst [0 or "sda"] value 19540

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.metrics/README.md file
- /usr/share/doc/rhel-system-roles/metrics/ directory

16.6. USING THE METRICS RHEL SYSTEM ROLE TO CONFIGURE AND ENABLE METRICS COLLECTION FOR SQL SERVER

This procedure describes how to use the **metrics** RHEL system role to automate the configuration and enabling of metrics collection for Microsoft SQL Server via **pcp** on your local system.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

- You have installed Microsoft SQL Server for Red Hat Enterprise Linux and established a trusted connection to an SQL server.
- You have installed the Microsoft ODBC driver for SQL Server for Red Hat Enterprise Linux.
- **localhost** is configured in the inventory file on the control node:

localhost ansible_connection=local

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
---
- name: Configure and enable metrics collection for Microsoft SQL Server hosts: localhost roles:
    - rhel-system-roles.metrics
    vars:
    metrics_from_mssql: true
    metrics_manage_firewall: true
    metrics_manage_selinux: true
```

Because metrics_manage_firewall and metrics_manage_selinux are both set to true, the metrics role uses the firewall and selinux roles to manage the ports used by the metrics role.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

• Use the **pcp** command to verify that SQL Server PMDA agent (mssql) is loaded and running:

```
# pcp
platform: Linux sqlserver.example.com 4.18.0-167.el8.x86_64 #1 SMP Sun Dec 15 01:24:23
UTC 2019 x86_64
hardware: 2 cpus, 1 disk, 1 node, 2770MB RAM
timezone: PDT+7
services: pmcd pmproxy
pmcd: Version 5.0.2-1, 12 agents, 4 clients
pmda: root pmcd proc pmproxy xfs linux nfsclient mmv kvm mssql
jbd2 dm
pmlogger: primary logger: /var/log/pcp/pmlogger/sqlserver.example.com/20200326.16.31
pmie: primary engine: /var/log/pcp/pmie/sglserver.example.com/pmie.log
```

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.metrics/README.md file
- /usr/share/doc/rhel-system-roles/metrics/ directory

16.7. CONFIGURING PMIE WEBHOOKS USING THE METRICS RHEL SYSTEM ROLE

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- In the Ansible inventory, you have defined the servers and metrics_monitor host groups. In this example, the servers group includes server-node-01.example.com and server-node-02.example.com. The metrics_monitor group includes pcp-monitor-node-01.example.com.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Configure PCP webhooks
hosts: servers
tasks:
  - name: Configure PCP metrics recording
   ansible.builtin.include role:
    name: rhel-system-roles.metrics
   vars:
    metrics_retention_days: 7
    metrics manage firewall: true
- name: Configure the PMIE webhooks
hosts: metrics_monitor
tasks:
  - name: Configure the monitoring node
   ansible.builtin.include role:
    name: redhat.rhel_system_roles.metrics
   vars:
    metrics manage firewall: true
    metrics retention days: 7
    metrics_monitored_hosts: "{{ groups['servers'] }}"
    metrics_webhook_endpoint: "http://<webserver>:<port>/<endpoint>"
```

The settings specified in the example playbook include the following:

metrics manage firewall

When **true**, the **firewall** RHEL system role manages the ports used by the **metrics** role.

metrics_retention_days

Number of days to keep the collected metrics.

metrics_monitored_hosts

Hosts that the monitoring system should observe.

metrics webhook endpoint

A webhook endpoint where notifications of any detected performance issues are sent. By default, these detections are logged to the local system only.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.metrics/README.md file on the control node. The playbook configures the pcp-monitor-node-01.example.com host as the central monitoring site for itself and the server-node-01.example.com and server-node-02.example.com systems. The playbook also configures the global webhook_action and global webhook_endpoint PMIE configuration options for all 3 systems and restarts the PMIE service to apply the changes.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

1. Check the configuration summary on **pcp-monitor-node-01.example.com**:

```
[root@pcp-monitor-node-01 ~]# pcp summary
Performance Co-Pilot configuration on pcp-monitor-node-01.example.com:
platform: Linux pcp-monitor-node-01.example.com 5.14.0-427.el9.x86_64 #1 SMP
PREEMPT DYNAMIC Fri Feb 23 01:51:18 EST 2024 x86 64
hardware: 8 cpus, 1 disk, 1 node, 1773MB RAM
timezone: CEST-2
services: pmcd pmproxy
pmcd: Version 6.2.0-1, 12 agents, 6 clients
pmda: root pmcd proc pmproxy xfs linux nfsclient mmv kvm jbd2
    dm openmetrics
pmlogger: primary logger: /var/log/pcp/pmlogger/pcp-monitor-node-
01.example.com/20240510.16.25
      server-node-01.example.com: /var/log/pmlogger/server-node-
01.example.com/20240510.16.25
      server-node-02.example.com: /var/log/pmlogger/server-node-
02.example.com/20240510.16.25
pmie: primary engine: /var/log/pcp/pmie/pcp-monitor-node-01.example.com/pmie.log
    server-node-01.example.com::/var/log/pcp/pmie/server-node-01.example.com/pmie.log
    server-node-02.example.com::/var/log/pcp/pmie/server-node-02.example.com/pmie.log
```

The final three lines of the summary show that PMIE is configured to monitor all three systems.

2. Verify that the **global webhook action** PMIE configuration option is enabled:

[root@pcp-monitor-node-01 \sim]# grep webbook_action /var/lib/pcp/config/pmie/config.default // 0 global webbook_action = yes

CHAPTER 17. CONFIGURING MICROSOFT SQL SERVER BY USING RHEL SYSTEM ROLES

You can use the **microsoft.sql.server** Ansible system role to automate the installation and management of Microsoft SQL Server. This role also optimizes Red Hat Enterprise Linux (RHEL) to improve the performance and throughput of SQL Server by applying the **mssql** TuneD profile.



NOTE

During the installation, the role adds repositories for SQL Server and related packages to the managed hosts. Packages in these repositories are provided, maintained, and hosted by Microsoft.

17.1. INSTALLING AND CONFIGURING SQL SERVER WITH AN EXISTING TLS CERTIFICATE BY USING THE MICROSOFT.SQL.SERVER ANSIBLE SYSTEM ROLE

If your application requires a Microsoft SQL Server database, you can configure SQL Server with TLS encryption to enable secure communication between the application and the database. By using the **microsoft.sql.server** Ansible system role, you can automate this process and remotely install and configure SQL Server with TLS encryption. In the playbook, you can use an existing private key and a TLS certificate that was issued by a certificate authority (CA).

Depending on the RHEL version on the managed host, the version of SQL Server that you can install differs:

- RHEL 7.9: SQL Server 2017 and 2019
- RHEL 8: SQL Server 2017, 2019, and 2022
- RHEL 9.4 and later: SQL Server 2022

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- You installed the **ansible-collection-microsoft-sql** package or the **microsoft.sql** collection on the control node.
- The managed node has 2 GB or more RAM installed.
- The managed node uses one of the following versions: RHEL 7.9, RHEL 8, RHEL 9.4 or later.
- You stored the certificate in the **sql_crt.pem** file in the same directory as the playbook.
- You stored the private key in the **sql_cert.key** file in the same directory as the playbook.
- SQL clients trust the CA that issued the certificate.

Procedure

- 1. Store your sensitive variables in an encrypted file:
 - a. Create the vault:

\$ ansible-vault create vault.yml

New Vault password: <vault_password>

Confirm New Vault password: <vault_password>

b. After the **ansible-vault create** command opens an editor, enter the sensitive data in the **<key>: <value>** format:

```
sa_pwd: <sa_password>
```

- c. Save the changes, and close the editor. Ansible encrypts the data in the vault.
- 2. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Installing and configuring Microsoft SQL Server
hosts: managed-node-01.example.com
 vars files:
  - vault.yml
 tasks:
  - name: SQL Server with an existing private key and certificate
   ansible.builtin.include role:
    name: microsoft.sql.server
   vars:
    mssql_accept_microsoft_odbc_driver_17_for_sql_server_eula: true
    mssql_accept_microsoft_cli_utilities_for_sql_server_eula: true
    mssql_accept_microsoft_sql_server_standard_eula: true
    mssql version: 2022
    mssql password: "{{ sa pwd }}"
    mssql edition: Developer
    mssql_tcp_port: 1433
    mssql_manage_firewall: true
    mssql tls enable: true
    mssql_tls_cert: sql_crt.pem
    mssql_tls_private_key: sql_cert.key
    mssql_tls_version: 1.2
    mssql tls force: true
```

The settings specified in the example playbook include the following:

mssql_tls_enable: true

Enables TLS encryption. If you enable this setting, you must also define **mssql_tls_cert** and **mssql_tls_private_key**.

```
mssql_tls_cert: <path>
```

Sets the path to the TLS certificate stored on the control node. The role copies this file to the /etc/pki/tls/certs/ directory on the managed node.

```
mssql_tls_private_key: <path>
```

Sets the path to the TLS private key on the control node. The role copies this file to the /etc/pki/tls/private/ directory on the managed node.

mssql_tls_force: true

Replaces the TLS certificate and private key in their destination directories if they exist.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/microsoft.sql-server/README.md file on the control node.

3. Validate the playbook syntax:

\$ ansible-playbook --ask-vault-pass --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

\$ ansible-playbook --ask-vault-pass ~/playbook.yml

Verification

• On the SQL Server host, use the **sqlcmd** utility with the **-N** parameter to establish an encrypted connection to SQL server and run a query, for example:

\$ /opt/mssql-tools/bin/sqlcmd -N -S server.example.com -U "sa" -P <sa_password> -Q 'SELECT SYSTEM_USER'

If the command succeeds, the connection to the server was TLS encrypted.

Additional resources

/usr/share/ansible/roles/microsoft.sql-server/README.md file

17.2. INSTALLING AND CONFIGURING SQL SERVER WITH A TLS CERTIFICATE ISSUED FROM IDM BY USING THE MICROSOFT.SQL.SERVER ANSIBLE SYSTEM ROLE

If your application requires a Microsoft SQL Server database, you can configure SQL Server with TLS encryption to enable secure communication between the application and the database. If the SQL Server host is a member in a Red Hat Identity Management (IdM) domain, the **certmonger** service can manage the certificate request and future renewals.

By using the **microsoft.sql.server** Ansible system role, you can automate this process. You can remotely install and configure SQL Server with TLS encryption, and the **microsoft.sql.server** role uses the **certificate** Ansible system role to configure **certmonger** and request a certificate from IdM.

Depending on the RHEL version on the managed host, the version of SQL Server that you can install differs:

- RHEL 7.9: SQL Server 2017 and 2019
- RHEL 8: SQL Server 2017, 2019, and 2022
- RHEL 9.4 and later: SQL Server 2022

Draraquicitas

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- You installed the **ansible-collection-microsoft-sql** package or the **microsoft.sql** collection on the control node.
- The managed node has 2 GB or more RAM installed.
- The managed node uses one of the following versions: RHEL 7.9, RHEL 8, RHEL 9.4 or later.
- You enrolled the managed node in a Red Hat Identity Management (IdM) domain.

Procedure

- 1. Store your sensitive variables in an encrypted file:
 - a. Create the vault:

```
$ ansible-vault create vault.yml
New Vault password: <vault_password>
Confirm New Vault password: <vault_password>
```

b. After the **ansible-vault create** command opens an editor, enter the sensitive data in the **<key>: <value>** format:

```
sa_pwd: <sa_password>
```

- c. Save the changes, and close the editor. Ansible encrypts the data in the vault.
- 2. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Installing and configuring Microsoft SQL Server
 hosts: managed-node-01.example.com
 vars_files:
  - vault.yml
 tasks:
  - name: SQL Server with certificates issued by Red Hat IdM
   ansible.builtin.include_role:
    name: microsoft.sql.server
   vars:
    mssql_accept_microsoft_odbc_driver_17_for_sql_server_eula: true
    mssql accept microsoft cli utilities for sql server eula: true
    mssql_accept_microsoft_sql_server_standard_eula: true
    mssql_version: 2022
    mssql_password: "{{ sa_pwd }}"
    mssql_edition: Developer
    mssql_tcp_port: 1433
     mssql_manage_firewall: true
```

mssql_tls_enable: true mssql_tls_certificates: - name: sql_cert

dns: server.example.com

ca: ipa

The settings specified in the example playbook include the following:

mssql_tls_enable: true

Enables TLS encryption. If you enable this setting, you must also define **mssql_tls_certificates**.

mssql_tls_certificates

A list of YAML dictionaries with settings for the **certificate** role.

name: <file_name>

Defines the base name of the certificate and private key. The **certificate** role stores the certificate in the /etc/pki/tls/certs/<file_name>.crt and the private key in the /etc/pki/tls/private/<file_name>.key file.

dns: <hostname_or_list_of_hostnames>

Sets the hostnames that the Subject Alternative Names (SAN) field in the issued certificate contains. You can use a wildcard (*) or specify multiple names in YAML list format.

ca: <ca_type>

Defines how the **certificate** role requests the certificate. Set the variable to **ipa** if the host is enrolled in an IdM domain or **self-sign** to request a self-signed certificate.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/microsoft.sql-server/README.md file on the control node.

3. Validate the playbook syntax:

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

\$ ansible-playbook --ask-vault-pass ~/playbook.yml

Verification

• On the SQL Server host, use the **sqlcmd** utility with the **-N** parameter to establish an encrypted connection to SQL server and run a query, for example:

\$ /opt/mssql-tools/bin/sqlcmd -N -S server.example.com -U "sa" -P <sa_password> -Q
'SELECT SYSTEM_USER'

If the command succeeds, the connection to the server was TLS encrypted.

Additional resources

/usr/share/ansible/roles/microsoft.sql-server/README.md file

Requesting certificates by using RHEL system roles

17.3. INSTALLING AND CONFIGURING SQL SERVER WITH CUSTOM STORAGE PATHS BY USING THE MICROSOFT.SQL.SERVER ANSIBLE SYSTEM ROLE

When you use the **microsoft.sql.server** Ansible system role to install and configure a new SQL Server, you can customize the paths and modes of the data and log directories. For example, configure custom paths if you want to store databases and log files in a different directory with more storage.



IMPORTANT

If you change the data or log path and re-run the playbook, the previously-used directories and all their content remains at the original path. Only new databases and logs are stored in the new location.

Table 17.1. SQL Server default settings for data and log directories

Туре	Directory	Mode	Owner	Group
Data	/var/opt/mssql/data/	[a]	mssql	mssql
Logs	/var/opt/mssql/los/	[a]	mssql	mssql

[a] If the directory exists, the role preserves the mode. If the directory does not exist, the role applies the default **umask** on the managed node when it creates the directory.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- You installed the **ansible-collection-microsoft-sql** package or the **microsoft.sql** collection on the control node.
- The managed node has 2 GB or more RAM installed.
- The managed node uses one of the following versions: RHEL 7.9, RHEL 8, RHEL 9.4 or later.

Procedure

- 1. Store your sensitive variables in an encrypted file:
 - a. Create the vault:

\$ ansible-vault create vault.yml

New Vault password: <vault_password>

Confirm New Vault password: <vault_password>

b. After the **ansible-vault create** command opens an editor, enter the sensitive data in the **<key>: <value>** format:

```
sa_pwd: <sa_password>
```

- c. Save the changes, and close the editor. Ansible encrypts the data in the vault.
- 2. Edit an existing playbook file, for example ~/playbook.yml, and add the storage and log-related variables:

```
- name: Installing and configuring Microsoft SQL Server
hosts: managed-node-01.example.com
 vars_files:

    vault.yml

 tasks:
  - name: SQL Server with custom storage paths
   ansible.builtin.include role:
    name: microsoft.sql.server
   vars:
    mssql_accept_microsoft_odbc_driver_17_for_sql_server_eula: true
    mssql accept microsoft cli utilities for sql server eula: true
    mssql_accept_microsoft_sql_server_standard_eula: true
    mssql_version: 2022
    mssql_password: "{{ sa_pwd }}"
    mssql_edition: Developer
    mssql_tcp_port: 1433
    mssql_manage_firewall: true
    mssql datadir: /var/lib/mssql/
    mssql_datadir_mode: '0700'
    mssql_logdir: /var/log/mssql/
    mssql_logdir_mode: '0700'
```

The settings specified in the example playbook include the following:

mssql_datadir_mode and mssql_logdir_mode

Set the permission modes. Specify the value in single quotes to ensure that the role parses the value as a string and not as an octal number.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/microsoft.sql-server/README.md file on the control node.

3. Validate the playbook syntax:

$\$\ ansible-playbook\ --ask-vault-pass\ --syntax-check\ \sim /playbook.yml$

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

\$ ansible-playbook --ask-vault-pass ~/playbook.yml

Verification

1. Display the mode of the data directory:

\$ ansible managed-node-01.example.com -m command -a 'ls -ld /var/lib/mssql/' drwx-----. 12 mssql mssql 4096 Jul 3 13:53 /var/lib/mssql/

2. Display the mode of the log directory:

\$ ansible managed-node-01.example.com -m command -a 'ls -ld /var/log/mssql/' drwx-----. 12 mssql mssql 4096 Jul 3 13:53 /var/log/mssql/

Additional resources

• /usr/share/ansible/roles/microsoft.sql-server/README.md file

17.4. INSTALLING AND CONFIGURING SQL SERVER WITH AD INTEGRATION BY USING THE MICROSOFT.SQL.SERVER ANSIBLE SYSTEM ROLE

You can integrate Microsoft SQL Server into an Active Directory (AD) to enable AD users to authenticate to SQL Server. By using the **microsoft.sql.server** Ansible system role, you can automate this process and remotely install and configure SQL Server accordingly. Note that you must still perform manual steps in AD and SQL Server after you run the playbook.

Depending on the RHEL version on the managed host, the version of SQL Server that you can install differs:

- RHEL 7.9: SQL Server 2017 and 2019
- RHEL 8: SQL Server 2017, 2019, and 2022
- RHEL 9.4 and later: SQL Server 2022

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- You installed the ansible-collection-microsoft-sql package or the microsoft.sql collection on the control node.
- The managed node has 2 GB or more RAM installed.
- The managed node uses one of the following versions: RHEL 7.9, RHEL 8, RHEL 9.4 or later.
- An AD domain is available in the network.
- A reverse DNS (RDNS) zone exists in AD, and it contains Pointer (PTR) resource records for each AD domain controller (DC).

- The managed host's network settings use an AD DNS server.
- The managed host can resolve the following DNS entries:
 - Both the hostnames and the fully-qualified domain names (FQDNs) of the AD DCs resolve to their IP addresses.
 - The IP addresses of the AD DCs resolve to their FQDNs.

Procedure

- 1. Store your sensitive variables in an encrypted file:
 - a. Create the vault:

```
$ ansible-vault create vault.yml
New Vault password: <vault_password>
Confirm New Vault password: <vault_password>
```

b. After the **ansible-vault create** command opens an editor, enter the sensitive data in the **<key>: <value>** format:

```
sa_pwd: <sa_password>
sql_pwd: <SQL_AD_password>
ad_admin_pwd: <AD_admin_password>
```

- c. Save the changes, and close the editor. Ansible encrypts the data in the vault.
- 2. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Installing and configuring Microsoft SQL Server
 hosts: managed-node-01.example.com
 vars files:
  - vault.yml
 tasks:
  - name: SQL Server with AD authentication
   ansible.builtin.include role:
    name: microsoft.sql.server
   vars:
    mssql_accept_microsoft_odbc_driver_17_for_sql_server_eula: true
    mssql_accept_microsoft_cli_utilities_for_sql_server_eula: true
    mssql accept microsoft sql server standard eula: true
    mssql_version: 2022
    mssql_password: "{{ sa_pwd }}"
    mssql_edition: Developer
    mssql tcp port: 1433
    mssql_manage_firewall: true
    mssql_ad_configure: true
    mssql ad join: true
    mssql ad sql user: sqluser
    mssql_ad_sql_password: "{{ sql_pwd }}"
```

ad_integration_realm: ad.example.com
ad_integration_user: Administrator
ad_integration_password: "{{ ad_admin_pwd }}"

The settings specified in the example playbook include the following:

mssql_ad_configure: true

Enables authentication against AD.

mssql ad join: true

Uses the **ad_integration** RHEL system role to join the managed node to AD. The role uses the settings from the **ad_integration_realm**, **ad_integration_user**, and **ad_integration_password** variables to join the domain.

mssql_ad_sql_user: <username>

Sets the name of an AD account that the role should create in AD and SQL Server for administration purposes.

ad_integration_user: <AD_user>

Sets the name of an AD user with privileges to join machines to the domain and to create the AD user specified in **mssql_ad_sql_user**.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/microsoft.sql-server/README.md file on the control node.

3. Validate the playbook syntax:

\$ ansible-playbook --ask-vault-pass --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

\$ ansible-playbook --ask-vault-pass ~/playbook.yml

- 5. In your AD domain, enable 128 bit and 256 bit Kerberos authentication for the AD SQL user which you specified in the playbook. Use one of the following options:
 - In the Active Directory Users and Computers application:
 - i. Navigate to ad.example.com > Users > sqluser > Accounts.
 - ii. In the Account options list, select This account supports Kerberos AES 128 bit encryption and This account supports Kerberos AES 256 bit encryption
 - iii. Click Apply.
 - In PowerShell in admin mode, enter:

C:\> Set-ADUser -Identity sqluser -KerberosEncryptionType AES128,AES256

- 6. Authorize AD users that should be able to authenticate to SQL Server. On the SQL Server, perform the following steps:
 - a. Obtain a Kerberos ticket for the **Administrator** user:

\$ kinit Administrator@ad.example.com

b. Authorize an AD user:

 $\protect\$ /opt/mssql-tools/bin/sqlcmd -S. -Q 'CREATE LOGIN [AD\<AD_user>] FROM WINDOWS;'

Repeat this step for every AD user who should be able to access SQL Server.

Verification

- On the managed node that runs SQL Server:
 - a. Obtain a Kerberos ticket for an AD user:
 - \$ kinit <AD_user>@ad.example.com
 - b. Use the **sqlcmd** utility to log in to SQL Server and run a query, for example:
 - \$ /opt/mssql-tools/bin/sqlcmd -S. -Q 'SELECT SYSTEM_USER'

Additional resources

• /usr/share/ansible/roles/microsoft.sql-server/README.md file

CHAPTER 18. CONFIGURING NBDE BY USING RHEL SYSTEM ROLES

You can use the **nbde_client** and **nbde_server** RHEL system roles for automated deployments of Policy-Based Decryption (PBD) solutions using Clevis and Tang. The **rhel-system-roles** package contains these system roles, the related examples, and also the reference documentation.

18.1. USING THE NBDE_SERVER RHEL SYSTEM ROLE FOR SETTING UP MULTIPLE TANG SERVERS

By using the **nbde_server** system role, you can deploy and manage a Tang server as part of an automated disk encryption solution. This role supports the following features:

- Rotating Tang keys
- Deploying and backing up Tang keys

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
name: Deploy a Tang server
hosts: tang.server.example.com
tasks:
name: Install and configure periodic key rotation ansible.builtin.include_role:
name: rhel-system-roles.nbde_server
vars:
nbde_server_rotate_keys: yes
nbde_server_manage_firewall: true
nbde_server_manage_selinux: true
```

This example playbook ensures deploying of your Tang server and a key rotation.

The settings specified in the example playbook include the following:

nbde_server_manage_firewall: true

Use the **firewall** system role to manage ports used by the **nbde_server** role.

nbde_server_manage_selinux: true

Use the **selinux** system role to manage ports used by the **nbde_server** role. For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.nbde_server/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

• On your NBDE client, verify that your Tang server works correctly by using the following command. The command must return the identical message you pass for encryption and decryption:

ansible managed-node-01.example.com -m command -a 'echo test | clevis encrypt tang '{"url":"<tang.server.example.com>"}' -y | clevis decrypt' test

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.nbde server/README.md file
- /usr/share/doc/rhel-system-roles/nbde_server/ directory

18.2. SETTING UP CLEVIS CLIENTS WITH DHCP BY USING THE NBDE CLIENT RHEL SYSTEM ROLE

The **nbde_client** system role enables you to deploy multiple Clevis clients in an automated way.

This role supports binding a LUKS-encrypted volume to one or more Network-Bound (NBDE) servers - Tang servers. You can either preserve the existing volume encryption with a passphrase or remove it. After removing the passphrase, you can unlock the volume only using NBDE. This is useful when a volume is initially encrypted using a temporary key or password that you should remove after you provision the system.

If you provide both a passphrase and a key file, the role uses what you have provided first. If it does not find any of these valid, it attempts to retrieve a passphrase from an existing binding.

Policy-Based Decryption (PBD) defines a binding as a mapping of a device to a slot. This means that you can have multiple bindings for the same device. The default slot is slot 1.



NOTE

The **nbde_client** system role supports only Tang bindings. Therefore, you cannot use it for TPM2 bindings.

Prerequisites

• You have prepared the control node and the managed nodes .

- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- A volume that is already encrypted by using LUKS.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

vars:

- name: Configure clients for unlocking of encrypted volumes by Tang servers hosts: managed-node-01.example.com tasks:
 - name: Create NBDE client bindings ansible.builtin.include_role: name: rhel-system-roles.nbde_client

nbde_client_bindings:

 device: /dev/rhel/root encryption_key_src: /etc/luks/keyfile nbde_client_early_boot: true state: present

servers:

- http://server1.example.comhttp://server2.example.com
- http://server2.example.comdevice: /dev/rhel/swap
- encryption_key_src: /etc/luks/keyfile servers:
 - http://server1.example.com
 - http://server2.example.com

This example playbook configures Clevis clients for automated unlocking of two LUKS-encrypted volumes when at least one of two Tang servers is available.

The settings specified in the example playbook include the following:

state: present

The values of **state** indicate the configuration after you run the playbook. Use the **present** value for either creating a new binding or updating an existing one. Contrary to a **clevis luks bind** command, you can use **state: present** also for overwriting an existing binding in its device slot. The **absent** value removes a specified binding.

nbde_client_early_boot: true

The **nbde_client** role ensures that networking for a Tang pin is available during early boot by default. If you scenario requires to disable this feature, add the **nbde_client_early_boot: false** variable to your playbook.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.nbde_client/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

1. On your NBDE client, check that the encrypted volume that should be automatically unlocked by your Tang servers contain the corresponding information in its LUKS pins:

```
# ansible managed-node-01.example.com -m command -a 'clevis luks list -d /dev/rhel/root' 1: tang '{"url":"<a href="http://server1.example.com/>"}' 2: tang '{"url":"<a href="http://server2.example.com/>"}'
```

2. If you do not use the **nbde_client_early_boot: false** variable, verify that the bindings are available for the early boot, for example:

```
# ansible managed-node-01.example.com -m command -a 'lsinitrd | grep clevis-luks' lrwxrwxrwx 1 root root 48 Jan 4 02:56 etc/systemd/system/cryptsetup.target.wants/clevis-luks-askpass.path -> /usr/lib/systemd/system/clevis-luks-askpass.path ...
```

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.nbde client/README.md file
- /usr/share/doc/rhel-system-roles/nbde client/ directory

18.3. SETTING UP STATIC-IP CLEVIS CLIENTS BY USING THE NBDE_CLIENT RHEL SYSTEM ROLE

The **nbde_client** RHEL system role supports only scenarios with Dynamic Host Configuration Protocol (DHCP). On an NBDE client with static IP configuration, you must pass your network configuration as a kernel boot parameter.

Typically, administrators want to reuse a playbook and not maintain individual playbooks for each host to which Ansible assigns static IP addresses during early boot. In this case, you can use variables in the playbook and provide the settings in an external file. As a result, you need only one playbook and one file with the settings.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- A volume that is already encrypted by using LUKS.

Procedure

1. Create a file with the network settings of your hosts, for example, **static-ip-settings-clients.yml**, and add the values you want to dynamically assign to the hosts:

```
clients:
       managed-node-01.example.com:
        ip v4: 192.0.2.1
        gateway v4: 192.0.2.254
        netmask v4: 255.255.255.0
        interface: enp1s0
       managed-node-02.example.com:
        ip_v4: 192.0.2.2
        gateway_v4: 192.0.2.254
        netmask_v4: 255.255.255.0
        interface: enp1s0
2. Create a playbook file, for example, ~/playbook.yml, with the following content:
      - name: Configure clients for unlocking of encrypted volumes by Tang servers
       hosts: managed-node-01.example.com, managed-node-02.example.com
       vars files:
        - ~/static-ip-settings-clients.yml
        - name: Create NBDE client bindings
          ansible.builtin.include_role:
           name: rhel-system-roles.network
           nbde client bindings:
            - device: /dev/rhel/root
             encryption key src: /etc/luks/keyfile
             servers:
              - http://server1.example.com
              http://server2.example.com
            - device: /dev/rhel/swap
             encryption_key_src: /etc/luks/keyfile
             servers:
              http://server1.example.com
              - http://server2.example.com
        - name: Configure a Clevis client with static IP address during early boot
          ansible.builtin.include role:
           name: rhel-system-roles.bootloader
          vars:
           bootloader settings:
            - kernel: ALL
             options:
              - name: ip
                value: "{{ clients[inventory_hostname]['ip_v4'] }}::{{ clients[inventory_hostname]
      ['gateway_v4'] }}:{{ clients[inventory_hostname]['netmask_v4'] }}::{{
```

This playbook reads certain values dynamically for each host listed in the ~/static-ip-settings-clients.yml file.

clients[inventory_hostname]['interface'] }}:none"

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.network/README.md file on the control node.

3. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.nbde_client/README.md file
- /usr/share/doc/rhel-system-roles/nbde_client/ directory
- Looking forward to Linux network configuration in the initial ramdisk (initrd) (Red Hat Enable Sysadmin)

CHAPTER 19. CONFIGURING NETWORK SETTINGS BY USING RHEL SYSTEM ROLES

By using the **network** RHEL system role, you can automate network-related configuration and management tasks.

19.1. CONFIGURING AN ETHERNET CONNECTION WITH A STATIC IP ADDRESS BY USING THE NETWORK RHEL SYSTEM ROLE WITH AN INTERFACE NAME

To connect a Red Hat Enterprise Linux host to an Ethernet network, create a NetworkManager connection profile for the network device. By using Ansible and the **network** RHEL system role, you can automate this process and remotely configure connection profiles on the hosts defined in a playbook.

You can use the **network** RHEL system role to configure an Ethernet connection with static IP addresses, gateways, and DNS settings, and assign them to a specified interface name.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- A physical or virtual Ethernet device exists in the server's configuration.
- The managed nodes use NetworkManager to configure the network.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Configure the network
 hosts: managed-node-01.example.com
 tasks:
  - name: Ethernet connection profile with static IP address settings
   ansible.builtin.include role:
    name: rhel-system-roles.network
    network connections:
      - name: enp1s0
       interface_name: enp1s0
       type: ethernet
       autoconnect: yes
       ip:
        address:
         - 192.0.2.1/24
         - 2001:db8:1::1/64
        gateway4: 192.0.2.254
        gateway6: 2001:db8:1::fffe
        dns:
         - 192.0.2.200
```

```
- 2001:db8:1::ffbb
dns_search:
- example.com
state: up
```

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.network/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

• Query the Ansible facts of the managed node and verify the active network settings:

```
# ansible managed-node-01.example.com -m ansible.builtin.setup
```

```
"ansible_default_ipv4": {
  "address": "192.0.2.1",
  "alias": "enp1s0",
  "broadcast": "192.0.2.255",
  "gateway": "192.0.2.254",
  "interface": "enp1s0",
  "macaddress": "52:54:00:17:b8:b6",
  "mtu": 1500,
  "netmask": "255.255.255.0",
  "network": "192.0.2.0",
  "prefix": "24",
  "type": "ether"
"ansible_default_ipv6": {
  "address": "2001:db8:1::1",
  "gateway": "2001:db8:1::fffe",
  "interface": "enp1s0",
  "macaddress": "52:54:00:17:b8:b6",
  "mtu": 1500,
  "prefix": "64",
  "scope": "global",
  "type": "ether"
},
"ansible_dns": {
  "nameservers": [
     "192.0.2.1",
     "2001:db8:1::ffbb"
  "search": [
```

```
"example.com"
]
},
...
```

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.network/README.md file
- /usr/share/doc/rhel-system-roles/network/ directory

19.2. CONFIGURING AN ETHERNET CONNECTION WITH A STATIC IP ADDRESS BY USING THE NETWORK RHEL SYSTEM ROLE WITH A DEVICE PATH

To connect a Red Hat Enterprise Linux host to an Ethernet network, create a NetworkManager connection profile for the network device. By using Ansible and the **network** RHEL system role, you can automate this process and remotely configure connection profiles on the hosts defined in a playbook.

You can use the **network** RHEL system role to configure an Ethernet connection with static IP addresses, gateways, and DNS settings, and assign them to a device based on its path instead of its name.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- A physical or virtual Ethernet device exists in the server's configuration.
- The managed nodes use NetworkManager to configure the network.
- You know the path of the device. You can display the device path by using the **udevadm info** /sys/class/net/<device_name> | grep ID_PATH= command.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
---
- name: Configure the network
hosts: managed-node-01.example.com
tasks:
- name: Ethernet connection profile with static IP address settings
ansible.builtin.include_role:
    name: rhel-system-roles.network
vars:
    network_connections:
    - name: example
    match:
    path:
```

```
- pci-0000:00:0[1-3].0
    - &lpci-0000:00:02.0

type: ethernet
autoconnect: yes
ip:
    address:
    - 192.0.2.1/24
    - 2001:db8:1::1/64
gateway4: 192.0.2.254
gateway6: 2001:db8:1::fffe
dns:
    - 192.0.2.200
    - 2001:db8:1::ffbb
dns_search:
    - example.com
state: up
```

The settings specified in the example playbook include the following:

match

Defines that a condition must be met in order to apply the settings. You can only use this variable with the **path** option.

path

Defines the persistent path of a device. You can set it as a fixed path or an expression. Its value can contain modifiers and wildcards. The example applies the settings to devices that match PCI ID **0000:00:0[1-3].0**, but not **0000:00:02.0**.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.network/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

• Query the Ansible facts of the managed node and verify the active network settings:

```
# ansible managed-node-01.example.com -m ansible.builtin.setup
...

"ansible_default_ipv4": {
    "address": "192.0.2.1",
    "alias": "enp1s0",
    "broadcast": "192.0.2.255",
    "gateway": "192.0.2.254",
    "interface": "enp1s0",
    "macaddress": "52:54:00:17:b8:b6",
```

```
"mtu": 1500,
  "netmask": "255.255.255.0",
  "network": "192.0.2.0",
  "prefix": "24",
  "type": "ether"
"ansible default ipv6": {
  "address": "2001:db8:1::1",
  "gateway": "2001:db8:1::fffe",
  "interface": "enp1s0",
  "macaddress": "52:54:00:17:b8:b6",
  "mtu": 1500,
  "prefix": "64",
  "scope": "global",
  "type": "ether"
},
"ansible dns": {
  "nameservers": [
     "192.0.2.1",
     "2001:db8:1::ffbb"
   "search": [
     "example.com"
},
```

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.network/README.md file
- /usr/share/doc/rhel-system-roles/network/ directory

19.3. CONFIGURING AN ETHERNET CONNECTION WITH A DYNAMIC IP ADDRESS BY USING THE NETWORK RHEL SYSTEM ROLE WITH AN INTERFACE NAME

To connect a Red Hat Enterprise Linux host to an Ethernet network, create a NetworkManager connection profile for the network device. By using Ansible and the **network** RHEL system role, you can automate this process and remotely configure connection profiles on the hosts defined in a playbook.

You can use the **network** RHEL system role to configure an Ethernet connection that retrieves its IP addresses, gateways, and DNS settings from a DHCP server and IPv6 stateless address autoconfiguration (SLAAC). With this role you can assign the connection profile to the specified interface name.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

- A physical or virtual Ethernet device exists in the server's configuration.
- A DHCP server and SLAAC are available in the network.
- The managed nodes use the NetworkManager service to configure the network.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Configure the network
 hosts: managed-node-01.example.com
 tasks:
  - name: Ethernet connection profile with dynamic IP address settings
   ansible.builtin.include role:
    name: rhel-system-roles.network
   vars:
    network_connections:
     - name: enp1s0
       interface name: enp1s0
       type: ethernet
       autoconnect: yes
       ip:
        dhcp4: yes
        auto6: yes
       state: up
```

The settings specified in the example playbook include the following:

dhcp4: yes

Enables automatic IPv4 address assignment from DHCP, PPP, or similar services.

auto6: yes

Enables IPv6 auto-configuration. By default, NetworkManager uses Router Advertisements. If the router announces the **managed** flag, NetworkManager requests an IPv6 address and prefix from a DHCPv6 server.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.network/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

• Query the Ansible facts of the managed node and verify that the interface received IP addresses and DNS settings:

```
# ansible managed-node-01.example.com -m ansible.builtin.setup
     "ansible default ipv4": {
       "address": "192.0.2.1",
       "alias": "enp1s0",
       "broadcast": "192.0.2.255",
       "gateway": "192.0.2.254",
       "interface": "enp1s0",
       "macaddress": "52:54:00:17:b8:b6".
       "mtu": 1500.
       "netmask": "255.255.255.0",
       "network": "192.0.2.0",
       "prefix": "24",
       "type": "ether"
     },
     "ansible_default_ipv6": {
       "address": "2001:db8:1::1",
       "gateway": "2001:db8:1::fffe",
       "interface": "enp1s0",
       "macaddress": "52:54:00:17:b8:b6",
       "mtu": 1500,
       "prefix": "64",
       "scope": "global",
       "type": "ether"
    },
     "ansible dns": {
       "nameservers": [
          "192.0.2.1",
          "2001:db8:1::ffbb"
       "search": [
          "example.com"
    },
```

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.network/README.md file
- /usr/share/doc/rhel-system-roles/network/ directory

19.4. CONFIGURING AN ETHERNET CONNECTION WITH A DYNAMIC IP ADDRESS BY USING THE NETWORK RHEL SYSTEM ROLE WITH A DEVICE PATH

To connect a Red Hat Enterprise Linux host to an Ethernet network, create a NetworkManager connection profile for the network device. By using Ansible and the **network** RHEL system role, you can automate this process and remotely configure connection profiles on the hosts defined in a playbook.

You can use the **network** RHEL system role to configure an Ethernet connection that retrieves its IP addresses, gateways, and DNS settings from a DHCP server and IPv6 stateless address autoconfiguration (SLAAC). The role can assign the connection profile to a device based on its path instead of an interface name.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- A physical or virtual Ethernet device exists in the server's configuration.
- A DHCP server and SLAAC are available in the network.
- The managed hosts use NetworkManager to configure the network.
- You know the path of the device. You can display the device path by using the udevadm info /sys/class/net/<device_name> | grep ID_PATH= command.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Configure the network
 hosts: managed-node-01.example.com
  - name: Ethernet connection profile with dynamic IP address settings
   ansible.builtin.include_role:
    name: rhel-system-roles.network
   vars:
    network_connections:
      - name: example
       match:
        path:
         - pci-0000:00:0[1-3].0
         - &!pci-0000:00:02.0
       type: ethernet
       autoconnect: yes
       ip:
        dhcp4: yes
        auto6: yes
       state: up
```

The settings specified in the example playbook include the following:

match: path

Defines that a condition must be met in order to apply the settings. You can only use this variable with the **path** option.

path: <path_and_expressions>

Defines the persistent path of a device. You can set it as a fixed path or an expression. Its value can contain modifiers and wildcards. The example applies the settings to devices that match PCI ID **0000:00:0[1-3].0**, but not **0000:00:02.0**.

dhcp4: yes

Enables automatic IPv4 address assignment from DHCP, PPP, or similar services.

auto6: yes

Enables IPv6 auto-configuration. By default, NetworkManager uses Router Advertisements. If the router announces the **managed** flag, NetworkManager requests an IPv6 address and prefix from a DHCPv6 server.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.network/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

 Query the Ansible facts of the managed node and verify that the interface received IP addresses and DNS settings:

ansible managed-node-01.example.com -m ansible.builtin.setup

```
"ansible_default_ipv4": {
  "address": "192.0.2.1",
  "alias": "enp1s0",
  "broadcast": "192.0.2.255",
  "gateway": "192.0.2.254",
  "interface": "enp1s0",
  "macaddress": "52:54:00:17:b8:b6",
  "mtu": 1500,
  "netmask": "255.255.255.0",
  "network": "192.0.2.0",
  "prefix": "24",
  "type": "ether"
"ansible_default_ipv6": {
  "address": "2001:db8:1::1",
  "gateway": "2001:db8:1::fffe",
  "interface": "enp1s0",
  "macaddress": "52:54:00:17:b8:b6",
   "mtu": 1500,
   "prefix": "64",
  "scope": "global",
  "type": "ether"
},
```

```
"ansible_dns": {
    "nameservers": [
        "192.0.2.1",
        "2001:db8:1::ffbb"
    ],
    "search": [
        "example.com"
    ]
},
...
```

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.network/README.md file
- /usr/share/doc/rhel-system-roles/network/ directory

19.5. CONFIGURING VLAN TAGGING BY USING THE NETWORK RHEL SYSTEM ROLE

If your network uses Virtual Local Area Networks (VLANs) to separate network traffic into logical networks, create a NetworkManager connection profile to configure VLAN tagging. By using Ansible and the **network** RHEL system role, you can automate this process and remotely configure connection profiles on the hosts defined in a playbook.

You can use the **network** RHEL system role to configure VLAN tagging and, if a connection profile for the VLAN's parent device does not exists, the role can create it as well.



NOTE

If the VLAN device requires an IP address, default gateway, and DNS settings, configure them on the VLAN device and not on the parent device.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
---
- name: Configure the network
hosts: managed-node-01.example.com
tasks:
- name: VLAN connection profile with Ethernet port
ansible.builtin.include_role:
    name: rhel-system-roles.network
vars:
```

```
network_connections:
# Ethernet profile
- name: enp1s0
  type: ethernet
  interface_name: enp1s0
  autoconnect: yes
  state: up
  ip:
   dhcp4: no
   auto6: no
# VLAN profile
- name: enp1s0.10
  type: vlan
  vlan:
   id: 10
  ip:
   dhcp4: yes
   auto6: yes
  parent: enp1s0
  state: up
```

e settings specified in the example playbook include the following:

type: type>

Sets the type of the profile to create. The example playbook creates two connection profiles: One for the parent Ethernet device and one for the VLAN device.

dhcp4: <value>

If set to **yes**, automatic IPv4 address assignment from DHCP, PPP, or similar services is enabled. Disable the IP address configuration on the parent device.

auto6: <value>

If set to **yes**, IPv6 auto-configuration is enabled. In this case, by default, NetworkManager uses Router Advertisements and, if the router announces the **managed** flag, NetworkManager requests an IPv6 address and prefix from a DHCPv6 server. Disable the IP address configuration on the parent device.

parent: parent_device>

Sets the parent device of the VLAN connection profile. In the example, the parent is the Ethernet interface.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.network/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

Verify the VLAN settings:

ansible managed-node-01.example.com -m command -a 'ip -d addr show enp1s0.10' managed-node-01.example.com | CHANGED | rc=0 >> 4: vlan10@enp1s0: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc noqueue state UP group default qlen 1000 link/ether 52:54:00:72:2f:6e brd ff:ff:ff:ff:ff promiscuity 0 vlan protocol 802.1Q id 10 <REORDER_HDR> numtxqueues 1 numrxqueues 1 gso_max_size 65536 gso_max_segs 65535 ...

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.network/README.md file
- /usr/share/doc/rhel-system-roles/network/ directory

19.6. CONFIGURING A NETWORK BRIDGE BY USING THENETWORK RHEL SYSTEM ROLE

You can connect multiple networks on layer 2 of the Open Systems Interconnection (OSI) model by creating a network bridge. To configure a bridge, create a connection profile in NetworkManager. By using Ansible and the **network** RHEL system role, you can automate this process and remotely configure connection profiles on the hosts defined in a playbook.

You can use the **network** RHEL system role to configure a bridge and, if a connection profile for the bridge's parent device does not exists, the role can create it as well.



NOTE

If you want to assign IP addresses, gateways, and DNS settings to a bridge, configure them on the bridge and not on its ports.

Prerequisites

- You have prepared the control node and the managed nodes.
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- Two or more physical or virtual network devices are installed on the server.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

- name: Configure the network

hosts: managed-node-01.example.com

tasks:

- name: Bridge connection profile with two Ethernet ports

```
ansible.builtin.include_role:
 name: rhel-system-roles.network
vars:
 network_connections:
  # Bridge profile
  - name: bridge0
   type: bridge
   interface_name: bridge0
     dhcp4: yes
     auto6: yes
   state: up
  # Port profile for the 1st Ethernet device
  - name: bridge0-port1
   interface_name: enp7s0
   type: ethernet
   controller: bridge0
   port_type: bridge
   state: up
  # Port profile for the 2nd Ethernet device
  - name: bridge0-port2
   interface name: enp8s0
   type: ethernet
   controller: bridge0
   port_type: bridge
   state: up
```

The settings specified in the example playbook include the following:

type: type>

Sets the type of the profile to create. The example playbook creates three connection profiles: One for the bridge and two for the Ethernet devices.

dhcp4: yes

Enables automatic IPv4 address assignment from DHCP, PPP, or similar services.

auto6: yes

Enables IPv6 auto-configuration. By default, NetworkManager uses Router Advertisements. If the router announces the **managed** flag, NetworkManager requests an IPv6 address and prefix from a DHCPv6 server.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.network/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

1. Display the link status of Ethernet devices that are ports of a specific bridge:

ansible managed-node-01.example.com -m command -a 'ip link show master bridge0'

managed-node-01.example.com | CHANGED | rc=0 >>

3: enp7s0: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc fq_codel master bridge0 state UP mode DEFAULT group default qlen 1000

link/ether 52:54:00:62:61:0e brd ff:ff:ff:ff:ff

4: enp8s0: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc fq_codel master bridge0 state UP mode DEFAULT group default qlen 1000

link/ether 52:54:00:9e:f1:ce brd ff:ff:ff:ff:ff

2. Display the status of Ethernet devices that are ports of any bridge device:

ansible managed-node-01.example.com -m command -a 'bridge link show'

managed-node-01.example.com | CHANGED | rc=0 >>

3: enp7s0: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 master bridge0 state forwarding priority 32 cost 100

4: enp8s0: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 master bridge0 state listening priority 32 cost 100

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.network/README.md file
- /usr/share/doc/rhel-system-roles/network/ directory

19.7. CONFIGURING A NETWORK BOND BY USING THENETWORK RHEL SYSTEM ROLE

You can combine network interfaces in a bond to provide a logical interface with higher throughput or redundancy. To configure a bond, create a NetworkManager connection profile. By using Ansible and the **network** RHEL system role, you can automate this process and remotely configure connection profiles on the hosts defined in a playbook.

You can use the **network** RHEL system role to configure a network bond and, if a connection profile for the bond's parent device does not exist, the role can create it as well.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- Two or more physical or virtual network devices are installed on the server.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

- name: Configure the network

hosts: managed-node-01.example.com

tasks:

- name: Bond connection profile with two Ethernet ports

ansible.builtin.include_role:

name: rhel-system-roles.network

vars:

network connections:

Bond profile
- name: bond0
type: bond

interface_name: bond0

ip:

dhcp4: yes auto6: yes

bond:

mode: active-backup

state: up

Port profile for the 1st Ethernet device

name: bond0-port1 interface_name: enp7s0

type: ethernet controller: bond0

state: up

Port profile for the 2nd Ethernet device

name: bond0-port2 interface_name: enp8s0

type: ethernet controller: bond0

state: up

The settings specified in the example playbook include the following:

type:

Sets the type of the profile to create. The example playbook creates three connection profiles: One for the bond and two for the Ethernet devices.

dhcp4: yes

Enables automatic IPv4 address assignment from DHCP, PPP, or similar services.

auto6: yes

Enables IPv6 auto-configuration. By default, NetworkManager uses Router Advertisements. If the router announces the **managed** flag, NetworkManager requests an IPv6 address and prefix from a DHCPv6 server.

mode: <bond_mode>

Sets the bonding mode. Possible values are:

- balance-rr (default)
- active-backup
- balance-xor

- broadcast
- 802.3ad
- balance-tlb
- balance-alb.

Depending on the mode you set, you need to set additional variables in the playbook.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.network/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

• Temporarily remove the network cable from one of the network devices and check if the other device in the bond handling the traffic.

Note that there is no method to properly test link failure events using software utilities. Tools that deactivate connections, such as **nmcli**, show only the bonding driver's ability to handle port configuration changes and not actual link failure events.

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.network/README.md file
- /usr/share/doc/rhel-system-roles/network/ directory

19.8. CONFIGURING AN IPOIB CONNECTION BY USING THENETWORK RHEL SYSTEM ROLE

You can use IP over InfiniBand (IPoIB) to send IP packets over an InfiniBand interface. To configure IPoIB, create a NetworkManager connection profile. By using Ansible and the **network** system role, you can automate this process and remotely configure connection profiles on the hosts defined in a playbook.

You can use the **network** RHEL system role to configure IPoIB and, if a connection profile for the InfiniBand's parent device does not exists, the role can create it as well.

Prerequisites

• You have prepared the control node and the managed nodes .

- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- An InfiniBand device named **mlx4_ib0** is installed in the managed nodes.
- The managed nodes use NetworkManager to configure the network.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Configure the network
hosts: managed-node-01.example.com
tasks:
  - name: IPoIB connection profile with static IP address settings
   ansible.builtin.include_role:
    name: rhel-system-roles.network
   vars:
    network connections:
     # InfiniBand connection mlx4_ib0
     - name: mlx4 ib0
       interface name: mlx4 ib0
       type: infiniband
     # IPoIB device mlx4_ib0.8002 on top of mlx4_ib0
     - name: mlx4 ib0.8002
       type: infiniband
       autoconnect: yes
       infiniband:
        p key: 0x8002
        transport_mode: datagram
       parent: mlx4 ib0
       ip:
        address:
         - 192.0.2.1/24
         - 2001:db8:1::1/64
       state: up
```

The settings specified in the example playbook include the following:

type:

Sets the type of the profile to create. The example playbook creates two connection profiles: One for the InfiniBand connection and one for the IPoIB device.

parent: parent_device>

Sets the parent device of the IPoIB connection profile.

p_key: <value>

Sets the InfiniBand partition key. If you set this variable, do not set **interface_name** on the IPoIB device.

transport_mode: <mode>

Sets the IPoIB connection operation mode. You can set this variable to **datagram** (default) or **connected**.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.network/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

1. Display the IP settings of the mlx4_ib0.8002 device:

```
# ansible managed-node-01.example.com -m command -a 'ip address show mlx4_ib0.8002'
managed-node-01.example.com | CHANGED | rc=0 >>
...
inet 192.0.2.1/24 brd 192.0.2.255 scope global noprefixroute ib0.8002
valid_lft forever preferred_lft forever
inet6 2001:db8:1::1/64 scope link tentative noprefixroute
valid_lft forever preferred_lft forever
```

2. Display the partition key (P_Key) of the **mlx4_ib0.8002** device:

```
# ansible managed-node-01.example.com -m command -a 'cat /sys/class/net/mlx4_ib0.8002/pkey' managed-node-01.example.com | CHANGED | rc=0 >> 0x8002
```

3. Display the mode of the **mlx4_ib0.8002** device:

```
\# ansible managed-node-01.example.com -m command -a 'cat /sys/class/net/mlx4_ib0.8002/mode' managed-node-01.example.com | CHANGED | rc=0 >> datagram
```

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.network/README.md file
- /usr/share/doc/rhel-system-roles/network/ directory


19.9. ROUTING TRAFFIC FROM A SPECIFIC SUBNET TO A DIFFERENT DEFAULT GATEWAY BY USING THE NETWORK RHEL SYSTEM ROLE

You can use policy-based routing to configure a different default gateway for traffic from certain subnets. For example, you can configure RHEL as a router that, by default, routes all traffic to internet provider A using the default route. However, traffic received from the internal workstations subnet is

routed to provider B. By using Ansible and the **network** RHEL system role, you can automate this process and remotely configure connection profiles on the hosts defined in a playbook.

You can use the **network** RHEL system role to configure the connection profiles, including routing tables and rules.

This procedure assumes the following network topology:



60_RHEL_0120

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- The managed nodes uses the NetworkManager and firewalld services.
- The managed nodes you want to configure has four network interfaces:
 - The **enp7s0** interface is connected to the network of provider A. The gateway IP in the provider's network is **198.51.100.2**, and the network uses a /**30** network mask.
 - The **enp1s0** interface is connected to the network of provider B. The gateway IP in the provider's network is **192.0.2.2**, and the network uses a /30 network mask.
 - The **enp8s0** interface is connected to the **10.0.0.0/24** subnet with internal workstations.
 - The **enp9s0** interface is connected to the **203.0.113.0/24** subnet with the company's servers.
- Hosts in the internal workstations subnet use **10.0.0.1** as the default gateway. In the procedure, you assign this IP address to the **enp8s0** network interface of the router.
- Hosts in the server subnet use 203.0.113.1 as the default gateway. In the procedure, you assign
 this IP address to the enp9s0 network interface of the router.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Configuring policy-based routing
hosts: managed-node-01.example.com
tasks:
  - name: Routing traffic from a specific subnet to a different default gateway
   ansible.builtin.include_role:
    name: rhel-system-roles.network
   vars:
    network_connections:
      - name: Provider-A
       interface_name: enp7s0
       type: ethernet
       autoconnect: True
       ip:
        address:
         - 198.51.100.1/30
        gateway4: 198.51.100.2
        dns:
         - 198.51.100.200
       state: up
       zone: external
      - name: Provider-B
       interface_name: enp1s0
       type: ethernet
       autoconnect: True
       ip:
        address:
         - 192.0.2.1/30
        route:
         - network: 0.0.0.0
           prefix: 0
           gateway: 192.0.2.2
           table: 5000
       state: up
       zone: external
      - name: Internal-Workstations
       interface_name: enp8s0
       type: ethernet
       autoconnect: True
       ip:
        address:
         - 10.0.0.1/24
        route:
         - network: 10.0.0.0
           prefix: 24
           table: 5000
        routing_rule:
         - priority: 5
           from: 10.0.0.0/24
           table: 5000
       state: up
       zone: trusted
```

- name: Servers
interface_name: enp9s0
type: ethernet
autoconnect: True
ip:
address:
- 203.0.113.1/24
state: up
zone: trusted

The settings specified in the example playbook include the following:

table: <value>

Assigns the route from the same list entry as the **table** variable to the specified routing table.

routing rule: < list>

Defines the priority of the specified routing rule and from a connection profile to which routing table the rule is assigned.

zone: <zone_name>

Assigns the network interface from a connection profile to the specified **firewalld** zone.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.network/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

- 1. On a RHEL host in the internal workstation subnet:
 - a. Install the **traceroute** package:

dnf install traceroute

b. Use the **traceroute** utility to display the route to a host on the internet:

The output of the command displays that the router sends packets over **192.0.2.1**, which is the network of provider B.

- 2. On a RHEL host in the server subnet:
 - a. Install the traceroute package:

dnf install traceroute

b. Use the **traceroute** utility to display the route to a host on the internet:

traceroute redhat.com

traceroute to redhat.com (209.132.183.105), 30 hops max, 60 byte packets 1 203.0.113.1 (203.0.113.1) 2.179 ms 2.073 ms 1.944 ms 2 198.51.100.2 (198.51.100.2) 1.868 ms 1.798 ms 1.549 ms ...

The output of the command displays that the router sends packets over **198.51.100.2**, which is the network of provider A.

- 3. On the RHEL router that you configured using the RHEL system role:
 - a. Display the rule list:

ip rule list

0: from all lookup local

5: from 10.0.0.0/24 lookup 5000

32766: from all lookup main 32767: from all lookup default

By default, RHEL contains rules for the tables local, main, and default.

b. Display the routes in table 5000:

ip route list table 5000

0.0.0.0/0 via 192.0.2.2 dev enp1s0 proto static metric 100 10.0.0.0/24 dev enp8s0 proto static scope link src 192.0.2.1 metric 102

c. Display the interfaces and firewall zones:

firewall-cmd --get-active-zones

external

interfaces: enp1s0 enp7s0

trusted

interfaces: enp8s0 enp9s0

d. Verify that the **external** zone has masquerading enabled:

firewall-cmd --info-zone=external

external (active) target: default

icmp-block-inversion: no interfaces: enp1s0 enp7s0

sources: services: ssh ports: protocols: masquerade: yes ...

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.network/README.md file
- /usr/share/doc/rhel-system-roles/network/ directory

19.10. CONFIGURING A STATIC ETHERNET CONNECTION WITH 802.1X NETWORK AUTHENTICATION BY USING THE NETWORK RHEL SYSTEM ROLE

Network Access Control (NAC) protects a network from unauthorized clients. You can specify the details that are required for the authentication in NetworkManager connection profiles to enable clients to access the network. By using Ansible and the **network** RHEL system role, you can automate this process and remotely configure connection profiles on the hosts defined in a playbook.

You can use an Ansible playbook to copy a private key, a certificate, and the CA certificate to the client, and then use the **network** RHEL system role to configure a connection profile with 802.1X network authentication.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- The network supports 802.1X network authentication.
- The managed nodes use NetworkManager.
- The following files required for the TLS authentication exist on the control node:
 - The client key is stored in the /srv/data/client.key file.
 - The client certificate is stored in the /srv/data/client.crt file.
 - The Certificate Authority (CA) certificate is stored in the /srv/data/ca.crt file.

Procedure

- 1. Store your sensitive variables in an encrypted file:
 - a. Create the vault:

\$ ansible-vault create vault.yml

New Vault password: <vault_password>

Confirm New Vault password: <vault_password>

b. After the **ansible-vault create** command opens an editor, enter the sensitive data in the **<**key>: **<**value> format:

pwd: <password>

- c. Save the changes, and close the editor. Ansible encrypts the data in the vault.
- 2. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Configure an Ethernet connection with 802.1X authentication
hosts: managed-node-01.example.com
 vars files:
  - vault.yml
 tasks:
  - name: Copy client key for 802.1X authentication
   ansible.builtin.copy:
    src: "/srv/data/client.key"
     dest: "/etc/pki/tls/private/client.key"
     mode: 0600
  - name: Copy client certificate for 802.1X authentication
   ansible.builtin.copy:
     src: "/srv/data/client.crt"
     dest: "/etc/pki/tls/certs/client.crt"
  - name: Copy CA certificate for 802.1X authentication
   ansible.builtin.copy:
    src: "/srv/data/ca.crt"
    dest: "/etc/pki/ca-trust/source/anchors/ca.crt"
  - name: Ethernet connection profile with static IP address settings and 802.1X
   ansible.builtin.include role:
    name: rhel-system-roles.network
   vars:
     network_connections:
      - name: enp1s0
       type: ethernet
       autoconnect: yes
       ip:
        address:
          - 192.0.2.1/24
          - 2001:db8:1::1/64
        gateway4: 192.0.2.254
        gateway6: 2001:db8:1::fffe
        dns:
          - 192.0.2.200
          - 2001:db8:1::ffbb
        dns_search:
          - example.com
       ieee802_1x:
        identity: <user_name>
        eap: tls
        private_key: "/etc/pki/tls/private/client.key"
        private_key_password: "{{ pwd }}"
```

client_cert: "/etc/pki/tls/certs/client.crt"

ca_cert: "/etc/pki/ca-trust/source/anchors/ca.crt"

domain_suffix_match: example.com

state: up

The settings specified in the example playbook include the following:

ieee802 1x

This variable contains the 802.1X-related settings.

eap: tls

Configures the profile to use the certificate-based **TLS** authentication method for the Extensible Authentication Protocol (EAP).

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.network/README.md file on the control node.

3. Validate the playbook syntax:

\$ ansible-playbook --ask-vault-pass --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

 $\$\ ansible-playbook\ \hbox{--ask-vault-pass}\ \hbox{\sim/playbook.yml}$

Verification

• Access resources on the network that require network authentication.

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.network/README.md file
- /usr/share/doc/rhel-system-roles/network/ directory
- Ansible vault

19.11. CONFIGURING A WIFI CONNECTION WITH 802.1X NETWORK AUTHENTICATION BY USING THE NETWORK RHEL SYSTEM ROLE

Network Access Control (NAC) protects a network from unauthorized clients. You can specify the details that are required for the authentication in NetworkManager connection profiles to enable clients to access the network. By using Ansible and the **network** RHEL system role, you can automate this process and remotely configure connection profiles on the hosts defined in a playbook.

You can use an Ansible playbook to copy a private key, a certificate, and the CA certificate to the client, and then use the **network** RHEL system role to configure a connection profile with 802.1X network authentication.

Prerequisites

You have prepared the control node and the managed nodes.

- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- The network supports 802.1X network authentication.
- You installed the **wpa_supplicant** package on the managed node.
- DHCP is available in the network of the managed node.
- The following files required for TLS authentication exist on the control node:
 - The client key is stored in the /srv/data/client.key file.
 - The client certificate is stored in the /srv/data/client.crt file.
 - The CA certificate is stored in the /srv/data/ca.crt file.

Procedure

- 1. Store your sensitive variables in an encrypted file:
 - a. Create the vault:

\$ ansible-vault create vault.yml

New Vault password: <vault_password>

Confirm New Vault password: <vault_password>

b. After the **ansible-vault create** command opens an editor, enter the sensitive data in the **<key>: <value>** format:

pwd: <password>

- c. Save the changes, and close the editor. Ansible encrypts the data in the vault.
- 2. Create a playbook file, for example ~/playbook.yml, with the following content:

- name: Configure a wifi connection with 802.1X authentication hosts: managed-node-01.example.com tasks:
 - name: Copy client key for 802.1X authentication ansible.builtin.copy:

src: "/srv/data/client.key"

dest: "/etc/pki/tls/private/client.key"

mode: 0400

- name: Copy client certificate for 802.1X authentication ansible.builtin.copy:

src: "/srv/data/client.crt"

dest: "/etc/pki/tls/certs/client.crt"

 name: Copy CA certificate for 802.1X authentication ansible.builtin.copy:

src: "/srv/data/ca.crt"

dest: "/etc/pki/ca-trust/source/anchors/ca.crt"

```
- name: Wifi connection profile with dynamic IP address settings and 802.1X
 ansible.builtin.import role:
  name: rhel-system-roles.network
 vars:
  network connections:
   - name: Wifi connection profile with dynamic IP address settings and 802.1X
    interface name: wlp1s0
    state: up
    type: wireless
    autoconnect: yes
      dhcp4: true
      auto6: true
    wireless:
      ssid: "Example-wifi"
      key_mgmt: "wpa-eap"
     ieee802_1x:
      identity: <user_name>
      eap: tls
      private key: "/etc/pki/tls/client.key"
      private_key_password: "{{ pwd }}"
      private_key_password_flags: none
      client cert: "/etc/pki/tls/client.pem"
      ca_cert: "/etc/pki/tls/cacert.pem"
      domain_suffix_match: "example.com"
```

The settings specified in the example playbook include the following:

ieee802_1x

This variable contains the 802.1X-related settings.

eap: tls

Configures the profile to use the certificate-based **TLS** authentication method for the Extensible Authentication Protocol (EAP).

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.network/README.md file on the control node.

3. Validate the playbook syntax:

\$ ansible-playbook --ask-vault-pass --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.network/README.md file
- /usr/share/doc/rhel-system-roles/network/ directory

- Ansible vault
- Ansible vault

19.12. SETTING THE DEFAULT GATEWAY ON AN EXISTING CONNECTION BY USING THE NETWORK RHEL SYSTEM ROLE

A host forwards a network packet to its default gateway if the packet's destination can neither be reached through the directly-connected networks nor through any of the routes configured on the host. To configure the default gateway of a host, set it in the NetworkManager connection profile of the interface that is connected to the same network as the default gateway. By using Ansible and the **network** RHEL system role, you can automate this process and remotely configure connection profiles on the hosts defined in a playbook.

In most situations, administrators set the default gateway when they create a connection. However, you can also set or update the default gateway setting on a previously-created connection.



WARNING

You cannot use the **network** RHEL system role to update only specific values in an existing connection profile. The role ensures that a connection profile exactly matches the settings in a playbook. If a connection profile with the same name already exists, the role applies the settings from the playbook and resets all other settings in the profile to their defaults. To prevent resetting values, always specify the whole configuration of the network connection profile in the playbook, including the settings that you do not want to change.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

--

- name: Configure the network

hosts: managed-node-01.example.com

tasks:

- name: Ethernet connection profile with static IP address settings

ansible.builtin.include_role:

name: rhel-system-roles.network

vars:

network_connections:name: enp1s0

type: ethernet

```
autoconnect: yes
ip:
    address:
    - 198.51.100.20/24
    - 2001:db8:1::1/64
    gateway4: 198.51.100.254
    gateway6: 2001:db8:1::fffe
    dns:
    - 198.51.100.200
    - 2001:db8:1::ffbb
    dns_search:
    - example.com
    state: up
```

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.network/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

• Query the Ansible facts of the managed node and verify the active network settings:

```
# ansible managed-node-01.example.com -m ansible.builtin.setup
...
    "ansible_default_ipv4": {
    ...
        "gateway": "198.51.100.254",
        "interface": "enp1s0",
    ...
     },
     "ansible_default_ipv6": {
    ...
        "gateway": "2001:db8:1::fffe",
        "interface": "enp1s0",
    ...
}
...
```

- /usr/share/ansible/roles/rhel-system-roles.network/README.md file
- /usr/share/doc/rhel-system-roles/network/ directory

19.13. CONFIGURING A STATIC ROUTE BY USING THENETWORK RHEL SYSTEM ROLE

A static route ensures that you can send traffic to a destination that cannot be reached through the default gateway. You configure static routes in the NetworkManager connection profile of the interface that is connected to the same network as the next hop. By using Ansible and the **network** RHEL system role, you can automate this process and remotely configure connection profiles on the hosts defined in a playbook.



WARNING

You cannot use the **network** RHEL system role to update only specific values in an existing connection profile. The role ensures that a connection profile exactly matches the settings in a playbook. If a connection profile with the same name already exists, the role applies the settings from the playbook and resets all other settings in the profile to their defaults. To prevent resetting values, always specify the whole configuration of the network connection profile in the playbook, including the settings that you do not want to change.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Configure the network
 hosts: managed-node-01.example.com
 tasks:
  - name: Ethernet connection profile with static IP address settings
   ansible.builtin.include role:
    name: rhel-system-roles.network
   vars:
    network connections:
      - name: enp7s0
       type: ethernet
       autoconnect: yes
        address:
         - 192.0.2.1/24
         - 2001:db8:1::1/64
        gateway4: 192.0.2.254
        gateway6: 2001:db8:1::fffe
```

dns:

```
- 192.0.2.200
- 2001:db8:1::ffbb
dns_search:
- example.com
route:
- network: 198.51.100.0
prefix: 24
gateway: 192.0.2.10
- network: 2001:db8:2::
prefix: 64
gateway: 2001:db8:1::10
state: up
```

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.network/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

1. Display the IPv4 routes:

```
# ansible managed-node-01.example.com -m command -a 'ip -4 route' managed-node-01.example.com | CHANGED | rc=0 >> \dots 198.51.100.0/24 via 192.0.2.10 dev enp7s0
```

2. Display the IPv6 routes:

```
# ansible managed-node-01.example.com -m command -a 'ip -6 route' managed-node-01.example.com | CHANGED | rc=0 >> ...
2001:db8:2::/64 via 2001:db8:1::10 dev enp7s0 metric 1024 pref medium
```

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.network/README.md file
- /usr/share/doc/rhel-system-roles/network/ directory

19.14. CONFIGURING AN ETHTOOL OFFLOAD FEATURE BY USING THE NETWORK RHEL SYSTEM ROLE

Network interface controllers can use the TCP offload engine (TOE) to offload processing certain

operations to the network controller. This improves the network throughput. You configure offload features in the connection profile of the network interface. By using Ansible and the **network** RHEL system role, you can automate this process and remotely configure connection profiles on the hosts defined in a playbook.



WARNING

You cannot use the **network** RHEL system role to update only specific values in an existing connection profile. The role ensures that a connection profile exactly matches the settings in a playbook. If a connection profile with the same name already exists, the role applies the settings from the playbook and resets all other settings in the profile to their defaults. To prevent resetting values, always specify the whole configuration of the network connection profile in the playbook, including the settings that you do not want to change.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Configure the network
 hosts: managed-node-01.example.com
 tasks:
  - name: Ethernet connection profile with dynamic IP address settings and offload features
   ansible.builtin.include role:
    name: rhel-system-roles.network
   vars:
    network_connections:
     - name: enp1s0
       type: ethernet
       autoconnect: yes
        dhcp4: yes
        auto6: yes
       ethtool:
        features:
         gro: no
         gso: yes
         tx_sctp_segmentation: no
       state: up
```

The settings specified in the example playbook include the following:

gro: no

Disables Generic receive offload (GRO).

aso: ves

Enables Generic segmentation offload (GSO).

tx_sctp_segmentation: no

Disables TX stream control transmission protocol (SCTP) segmentation.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.network/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

• Query the Ansible facts of the managed node and verify the offload settings:

```
# ansible managed-node-01.example.com -m ansible.builtin.setup
...
    "ansible_enp1s0": {
        "active": true,
        "device": "enp1s0",
        "features": {
            ...
        "rx_gro_hw": "off,
            ...
        "tx_gso_list": "on,
            ...
        "tx_sctp_segmentation": "off",
            ...
        }
        ...
}
```

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.network/README.md file
- /usr/share/doc/rhel-system-roles/network/ directory

19.15. CONFIGURING AN ETHTOOL COALESCE SETTINGS BY USING THE NETWORK RHEL SYSTEM ROLE

By using interrupt coalescing, the system collects network packets and generates a single interrupt for multiple packets. This increases the amount of data sent to the kernel with one hardware interrupt, which

reduces the interrupt load, and maximizes the throughput. You configure coalesce settings in the connection profile of the network interface. By using Ansible and the **network** RHEL role, you can automate this process and remotely configure connection profiles on the hosts defined in a playbook.



WARNING

You cannot use the **network** RHEL system role to update only specific values in an existing connection profile. The role ensures that a connection profile exactly matches the settings in a playbook. If a connection profile with the same name already exists, the role applies the settings from the playbook and resets all other settings in the profile to their defaults. To prevent resetting values, always specify the whole configuration of the network connection profile in the playbook, including the settings that you do not want to change.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Configure the network
hosts: managed-node-01.example.com
  - name: Ethernet connection profile with dynamic IP address settings and coalesce
settings
   ansible.builtin.include role:
    name: rhel-system-roles.network
    network_connections:
     - name: enp1s0
       type: ethernet
       autoconnect: yes
        dhcp4: yes
        auto6: yes
       ethtool:
        coalesce:
         rx frames: 128
         tx frames: 128
       state: up
```

The settings specified in the example playbook include the following:

rx_frames: <value>

Sets the number of RX frames.

gso: <value>

Sets the number of TX frames.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel**system-roles.network/README.md** file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

• Display the current offload features of the network device:

ansible managed-node-01.example.com -m command -a 'ethtool -c enp1s0' managed-node-01.example.com | CHANGED | rc=0 >> rx-frames: 128

tx-frames: 128

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.network/README.md file
- /usr/share/doc/rhel-system-roles/network/ directory

19.16. INCREASING THE RING BUFFER SIZE TO REDUCE A HIGH PACKET DROP RATE BY USING THE NETWORK RHEL SYSTEM ROLE

Increase the size of an Ethernet device's ring buffers if the packet drop rate causes applications to report a loss of data, timeouts, or other issues.

Ring buffers are circular buffers where an overflow overwrites existing data. The network card assigns a transmit (TX) and receive (RX) ring buffer. Receive ring buffers are shared between the device driver and the network interface controller (NIC). Data can move from NIC to the kernel through either hardware interrupts or software interrupts, also called SoftIRQs.

The kernel uses the RX ring buffer to store incoming packets until the device driver can process them. The device driver drains the RX ring, typically by using SoftlRQs, which puts the incoming packets into a kernel data structure called an **sk_buff** or **skb** to begin its journey through the kernel and up to the application that owns the relevant socket.

The kernel uses the TX ring buffer to hold outgoing packets which should be sent to the network. These ring buffers reside at the bottom of the stack and are a crucial point at which packet drop can occur, which in turn will adversely affect network performance.

You configure ring buffer settings in the NetworkManager connection profiles. By using Ansible and the **network** RHEL system role, you can automate this process and remotely configure connection profiles on the hosts defined in a playbook.



WARNING

You cannot use the **network** RHEL system role to update only specific values in an existing connection profile. The role ensures that a connection profile exactly matches the settings in a playbook. If a connection profile with the same name already exists, the role applies the settings from the playbook and resets all other settings in the profile to their defaults. To prevent resetting values, always specify the whole configuration of the network connection profile in the playbook, including the settings that you do not want to change.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- You know the maximum ring buffer sizes that the device supports.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Configure the network
hosts: managed-node-01.example.com
 tasks:
  - name: Ethernet connection profile with dynamic IP address setting and increased ring
buffer sizes
   ansible.builtin.include_role:
    name: rhel-system-roles.network
   vars:
    network connections:
      - name: enp1s0
       type: ethernet
       autoconnect: yes
       ip:
        dhcp4: yes
        auto6: yes
       ethtool:
        ring:
```

rx: 4096 tx: 4096 state: up

The settings specified in the example playbook include the following:

rx: <value>

Sets the maximum number of received ring buffer entries.

tx: <value>

Sets the maximum number of transmitted ring buffer entries.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.network/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

Display the maximum ring buffer sizes:

ansible managed-node-01.example.com -m command -a 'ethtool -g enp1s0' managed-node-01.example.com | CHANGED | rc=0 >>

Current hardware settings:

RX: 4096 RX Mini: 0 RX Jumbo: 0 TX: 4096

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.network/README.md file
- /usr/share/doc/rhel-system-roles/network/ directory

19.17. NETWORK STATES FOR THE NETWORK RHEL SYSTEM ROLE

The **network** RHEL system role supports state configurations in playbooks to configure the devices. For this, use the **network_state** variable followed by the state configurations.

Benefits of using the **network_state** variable in a playbook:

• Using the declarative method with the state configurations, you can configure interfaces, and the NetworkManager creates a profile for these interfaces in the background.

• With the **network_state** variable, you can specify the options that you require to change, and all the other options will remain the same as they are. However, with the **network_connections** variable, you must specify all settings to change the network connection profile.

For example, to create an Ethernet connection with dynamic IP address settings, use the following **vars** block in your playbook:

Playbook with state configurations	Regular playbook
vars: network_state: interfaces: - name: enp7s0 type: ethernet state: up ipv4: enabled: true auto-dns: true auto-gateway: true dhcp: true ipv6: enabled: true auto-dns: true auto-dns: true dhcp: true ipv6: enabled: true auto-dns: true auto-dns: true auto-fateway: true auto-gateway: true auto-routes: true auto-routes: true auto-routes: true	vars: network_connections: - name: enp7s0 interface_name: enp7s0 type: ethernet autoconnect: yes ip: dhcp4: yes auto6: yes state: up

For example, to only change the connection status of dynamic IP address settings that you created as above, use the following **vars** block in your playbook:

Playbook with state configurations	Regular playbook
vars: network_state: interfaces: - name: enp7s0 type: ethernet state: down	vars: network_connections: - name: enp7s0 interface_name: enp7s0 type: ethernet autoconnect: yes ip: dhcp4: yes auto6: yes state: down

Additional resources

• /usr/share/ansible/roles/rhel-system-roles.network/README.md file

• /usr/share/doc/rhel-system-roles/network/ directory

CHAPTER 20. MANAGING CONTAINERS BY USING RHEL SYSTEM ROLES

With the **podman** RHEL system role, you can manage Podman configuration, containers, and **systemd** services that run Podman containers.

20.1. CREATING A ROOTLESS CONTAINER WITH BIND MOUNT USING THE PODMAN RHEL SYSTEM ROLE

You can use the **podman** RHEL system role to create rootless containers with bind mount by running an Ansible playbook and with that, manage your application configuration.

The example Ansible playbook starts two Kubernetes pods: one for a database and another for a web application. The database pod configuration is specified in the playbook, while the web application pod is defined in an external YAML file.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- The user and group **webapp** exist, and must be listed in the /etc/subuid and /etc/subgid files on the host.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Configure Podman
hosts: managed-node-01.example.com
tasks:
  - name: Create a web application and a database
   ansible.builtin.include role:
    name: rhel-system-roles.podman
    podman_create_host_directories: true
    podman firewall:
     - port: 8080-8081/tcp
      state: enabled
     - port: 12340/tcp
      state: enabled
    podman selinux ports:
     - ports: 8080-8081
      setype: http_port_t
    podman_kube_specs:
     - state: started
      run_as_user: dbuser
      run_as_group: dbgroup
      kube_file_content:
        apiVersion: v1
        kind: Pod
```

```
metadata:
   name: db
  spec:
   containers:
    - name: db
      image: quay.io/linux-system-roles/mysql:5.6
      ports:
       - containerPort: 1234
        hostPort: 12340
      volumeMounts:
       - mountPath: /var/lib/db:Z
        name: db
   volumes:
    - name: db
      hostPath:
       path: /var/lib/db
- state: started
 run_as_user: webapp
 run_as_group: webapp
 kube file src:/path/to/webapp.yml
```

The settings specified in the example playbook include the following:

run_as_user and run_as_group

Specify that containers are rootless.

kube_file_content

Contains a Kubernetes YAML file defining the first container named **db**. You can generate the Kubernetes YAML file using the **podman kube generate** command.

- The **db** container is based on the **quay.io/db/db:stable** container image.
- The **db** bind mount maps the /**var/lib/db** directory on the host to the /**var/lib/db** directory in the container. The **Z** flag labels the content with a private unshared label, therefore, only the **db** container can access the content.

kube file src: <path>

Defines the second container. The content of the /path/to/webapp.yml file on the controller node will be copied to the **kube** file field on the managed node.

volumes: < list>

A YAML list to define the source of the data to provide in one or more containers. For example, a local disk on the host (**hostPath**) or other disk device.

volumeMounts: < list>

A YAML list to define the destination where the individual container will mount a given volume.

podman_create_host_directories: true

Creates the directory on the host. This instructs the role to check the kube specification for **hostPath** volumes and create those directories on the host. If you need more control over the ownership and permissions, use **podman_host_directories**.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.podman/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check --ask-vault-pass ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook --ask-vault-pass ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.podman/README.md file
- /usr/share/doc/rhel-system-roles/podman/ directory

20.2. CREATING A ROOTFUL CONTAINER WITH PODMAN VOLUME USING THE PODMAN RHEL SYSTEM ROLE

You can use the **podman** RHEL system role to create a rootful container with a Podman volume by running an Ansible playbook and with that, manage your application configuration.

The example Ansible playbook deploys a Kubernetes pod named **ubi8-httpd** running an HTTP server container from the **registry.access.redhat.com/ubi8/httpd-24** image. The container's web content is mounted from a persistent volume named **ubi8-html-volume**. By default, the **podman** role creates rootful containers.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
name: Configure Podman
hosts: managed-node-01.example.com
tasks:

name: Start Apache server on port 8080
ansible.builtin.include_role:
name: rhel-system-roles.podman
vars:
podman_firewall:

port: 8080/tcp
state: enabled
podman_kube_specs:

state: started
kube_file_content:
apiVersion: v1
kind: Pod
```

metadata:

name: ubi8-httpd

spec:

containers:

name: ubi8-httpd

image: registry.access.redhat.com/ubi8/httpd-24

ports:

- containerPort: 8080 hostPort: 8080 volumeMounts:

- mountPath: /var/www/html:Z

name: ubi8-html

volumes:

- name: ubi8-html

persistentVolumeClaim:

claimName: ubi8-html-volume

The settings specified in the example playbook include the following:

kube_file_content

Contains a Kubernetes YAML file defining the first container named **db**. You can generate the Kubernetes YAML file using the **podman kube generate** command.

- The ubi8-httpd container is based on the registry.access.redhat.com/ubi8/httpd-24 container image.
- The **ubi8-html-volume** maps the /**var/www/html** directory on the host to the container. The **Z** flag labels the content with a private unshared label, therefore, only the **ubi8-httpd** container can access the content.
- The pod mounts the existing persistent volume named **ubi8-html-volume** with the mount path /var/www/html.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.podman/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

 $\$\ ansible-playbook\ {\sim}/playbook.yml$

- /usr/share/ansible/roles/rhel-system-roles.podman/README.md file
- /usr/share/doc/rhel-system-roles/podman/ directory

20.3. CREATING A QUADLET APPLICATION WITH SECRETS USING THE PODMAN RHEL SYSTEM ROLE

You can use the **podman** RHEL system role to create a Quadlet application with secrets by running an Ansible playbook.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- The certificate and the corresponding private key that the web server in the container should use are stored in the **~/certificate.pem** and **~/key.pem** files.

Procedure

1. Display the contents of the certificate and private key files:

```
$ cat ~/certificate.pem
----BEGIN CERTIFICATE----
...
----END CERTIFICATE----
$ cat ~/key.pem
----BEGIN PRIVATE KEY----
...
----END PRIVATE KEY----
```

You require this information in a later step.

- 2. Store your sensitive variables in an encrypted file:
 - a. Create the vault:

```
$ ansible-vault create vault.yml
New Vault password: <vault_password>
Confirm New Vault password: <vault_password>
```

b. After the **ansible-vault create** command opens an editor, enter the sensitive data in the **<key>: <value>** format:

```
root_password: <root_password>
certificate: |-
-----BEGIN CERTIFICATE-----
...
-----END CERTIFICATE-----
key: |-
-----BEGIN PRIVATE KEY-----
...
-----END PRIVATE KEY-----
```

Ensure that all lines in the **certificate** and **key** variables start with two spaces.

- c. Save the changes, and close the editor. Ansible encrypts the data in the vault.
- 3. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Deploy a wordpress CMS with MySQL database
hosts: managed-node-01.example.com
vars_files:
  - vault.yml
tasks:
- name: Create and run the container
  ansible.builtin.include_role:
   name: rhel-system-roles.podman
  vars:
   podman_create_host_directories: true
   podman activate systemd unit: false
   podman_quadlet_specs:
    - name: quadlet-demo
     type: network
     file_content: |
       [Network]
       Subnet=192.168.30.0/24
       Gateway=192.168.30.1
       Label=app=wordpress
    - file_src: quadlet-demo-mysql.volume
    - template_src: quadlet-demo-mysql.container.j2
    - file_src: envoy-proxy-configmap.yml
    file_src: quadlet-demo.yml
    - file src: quadlet-demo.kube
     activate_systemd_unit: true
   podman_firewall:
    - port: 8000/tcp
     state: enabled
    - port: 9000/tcp
     state: enabled
   podman_secrets:
    - name: mysql-root-password-container
     state: present
     skip_existing: true
     data: "{{ root_password }}"
    - name: mysql-root-password-kube
     state: present
     skip existing: true
     data: |
       apiVersion: v1
        password: "{{ root_password | b64encode }}"
       kind: Secret
       metadata:
        name: mysql-root-password-kube
    - name: envoy-certificates
     state: present
     skip_existing: true
     data: |
       apiVersion: v1
       data:
        certificate.key: {{ key | b64encode }}
```

certificate.pem: {{ certificate | b64encode }}

kind: Secret metadata:

name: envoy-certificates

The procedure creates a WordPress content management system paired with a MySQL database. The **podman_quadlet_specs role** variable defines a set of configurations for the Quadlet, which refers to a group of containers or services that work together in a certain way. It includes the following specifications:

- The Wordpress network is defined by the **quadlet-demo** network unit.
- The volume configuration for MySQL container is defined by the file_src: quadlet-demo-mysql.volume field.
- The **template_src: quadlet-demo-mysql.container.j2** field is used to generate a configuration for the MySQL container.
- Two YAML files follow: **file_src: envoy-proxy-configmap.yml** and **file_src: quadlet-demo.yml**. Note that .yml is not a valid Quadlet unit type, therefore these files will just be copied and not processed as a Quadlet specification.
- The Wordpress and envoy proxy containers and configuration are defined by the file_src: quadlet-demo.kube field. The kube unit refers to the previous YAML files in the [Kube] section as Yaml=quadlet-demo.yml and ConfigMap=envoy-proxy-configmap.yml.
- 4. Validate the playbook syntax:

\$ ansible-playbook --syntax-check --ask-vault-pass ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

5. Run the playbook:

\$ ansible-playbook --ask-vault-pass ~/playbook.yml

- /usr/share/ansible/roles/rhel-system-roles.podman/README.md file
- /usr/share/doc/rhel-system-roles/podman/ directory

CHAPTER 21. CONFIGURING POSTFIX MTA BY USING RHEL SYSTEM ROLES

With the **postfix** RHEL system role, you can consistently streamline automated configurations of the Postfix service, a Sendmail-compatible mail transfer agent (MTA) with modular design and a variety of configuration options. The **rhel-system-roles** package contains this RHEL system role, and also the reference documentation.

21.1. USING THE POSTFIX RHEL SYSTEM ROLE TO AUTOMATE BASIC POSTFIX MTA ADMINISTRATION

You can install, configure and start the Postfix Mail Transfer Agent on the managed nodes by using the **postfix** RHEL system role.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

--- name: Manage postfix
hosts: managed-node-01.example.com
roles:
- rhel-system-roles.postfix
vars:
 postfix_conf:
 relay_domains: \$mydestination
 relayhost: example.com

• If you want Postfix to use a different hostname than the fully-qualified domain name (FQDN) that is returned by the **gethostname()** function, add the **myhostname** parameter under the **postfix conf:** line in the file:

myhostname = smtp.example.com

• If the domain name differs from the domain name in the **myhostname** parameter, add the **mydomain** parameter. Otherwise, the **\$myhostname** minus the first component is used.

mydomain = <example.com>

• Use **postfix_manage_firewall: true** variable to ensure that the SMTP port is open in the firewall on the servers.

Manage the SMTP related ports, **25/tcp**, **465/tcp**, and **587/tcp**. If the variable is set to **false**, the **postfix** role does not manage the firewall. The default is **false**.



NOTE

The **postfix_manage_firewall** variable is limited to adding ports. It cannot be used for removing ports. If you want to remove ports, use the **firewall** RHEL system role directly.

If your scenario involves using non-standard ports, set the postfix_manage_selinux: true
variable to ensure that the port is properly labeled for SELinux on the servers.



NOTE

The **postfix_manage_selinux** variable is limited to adding rules to the SELinux policy. It cannot remove rules from the policy. If you want to remove rules, use the **selinux** RHEL system role directly.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

- /usr/share/ansible/roles/rhel-system-roles.postfix/README.md file
- /usr/share/doc/rhel-system-roles/postfix/ directory

CHAPTER 22. INSTALLING AND CONFIGURING POSTGRESQL BY USING RHEL SYSTEM ROLES

As a system administrator, you can use the **postgresql** RHEL system role to install, configure, manage, start, and improve performance of the PostgreSQL server.

22.1. INTRODUCTION TO THE POSTGRESQL RHEL SYSTEM ROLE

To install, configure, manage, and start the PostgreSQL server using Ansible, you can use the **postgresql** RHEL system role.

You can also use the **postgresql** role to optimize the database server settings and improve performance.

The role supports the currently released and supported versions of PostgreSQL on RHEL 8 and RHEL 9 managed nodes.

22.2. CONFIGURING THE POSTGRESQL SERVER BY USING THE POSTGRESQL RHEL SYSTEM ROLE

You can use the **postgresql** RHEL system role to install, configure, manage, and start the PostgreSQL server.



WARNING

The **postgresql** role replaces PostgreSQL configuration files in the /**var/lib/pgsql/data**/ directory on the managed hosts. Previous settings are changed to those specified in the role variables, and lost if they are not specified in the role variables.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

- name: Manage PostgreSQL

hosts: managed-node-01.example.com

roles:

rhel-system-roles.postgresql vars: postgresql_version: "13"

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

- /usr/share/ansible/roles/rhel-system-roles.postgresql/README.md file
- /usr/share/doc/rhel-system-roles/postgresql/ directory
- Using PostgreSQL

CHAPTER 23. REGISTERING THE SYSTEM BY USING RHEL SYSTEM ROLES

The **rhc** RHEL system role enables administrators to automate the registration of multiple systems with Red Hat Subscription Management (RHSM) and Satellite servers. The role also supports Insights-related configuration and management tasks by using Ansible.

23.1. INTRODUCTION TO THE RHC RHEL SYSTEM ROLE

RHEL system role is a set of roles that provides a consistent configuration interface to remotely manage multiple systems. The remote host configuration (**rhc**) RHEL system role enables administrators to easily register RHEL systems to Red Hat Subscription Management (RHSM) and Satellite servers. By default, when you register a system by using the **rhc** RHEL system role, the system is connected to Insights. Additionally, with the **rhc** RHEL system role, you can:

- Configure connections to Red Hat Insights
- Enable and disable repositories
- Configure the proxy to use for the connection
- Configure insights remediations and, auto updates
- Set the release of the system
- Configure insights tags

23.2. REGISTERING A SYSTEM BY USING THERHC RHEL SYSTEM ROLE

You can register your system to Red Hat by using the **rhc** RHEL system role. By default, the **rhc** RHEL system role connects the system to Red Hat Insights when you register it.

Prerequisites

- You have prepared the control node and the managed nodes.
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

- 1. Store your sensitive variables in an encrypted file:
 - a. Create the vault:

\$ ansible-vault create vault.yml

New Vault password: <password>

Confirm New Vault password: <vault_password>

b. After the **ansible-vault create** command opens an editor, enter the sensitive data in the **<**key>: **<**value> format:

```
activationKey: <activation_key> username: <username> password: <password>
```

- c. Save the changes, and close the editor. Ansible encrypts the data in the vault.
- 2. Create a playbook file, for example ~/playbook.yml, with the following content:
 - To register by using an activation key and organization ID (recommended), use the following playbook:

```
---
- name: Registering system using activation key and organization ID hosts: managed-node-01.example.com
vars_files:
- vault.yml
roles:
- role: rhel-system-roles.rhc
vars:
rhc_auth:
activation_keys:
    keys:
- "{{ activationKey }}"
rhc_organization: organizationID
```

• To register by using a username and password, use the following playbook:

```
---
- name: Registering system with username and password hosts: managed-node-01.example.com vars_files:
- vault.yml
vars:
- rhc_auth:
- login:
- username: "{{ username }}"
- password: "{{ password }}"
roles:
- role: rhel-system-roles.rhc
```

3. Validate the playbook syntax:

\$ ansible-playbook --syntax-check --ask-vault-pass ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

\$ ansible-playbook --ask-vault-pass ~/playbook.yml

Additional resources

/usr/share/ansible/roles/rhel-system-roles.rhc/README.md file

- /usr/share/doc/rhel-system-roles/rhc/ directory
- Ansible Vault

23.3. REGISTERING A SYSTEM WITH SATELLITE BY USING THERHOR RHEL SYSTEM ROLE

When organizations use Satellite to manage systems, it is necessary to register the system through Satellite. You can remotely register your system with Satellite by using the **rhc** RHEL system role.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

- 1. Store your sensitive variables in an encrypted file:
 - a. Create the vault:

```
$ ansible-vault create vault.yml
New Vault password: confirm New Vault password: <vault_password>
```

b. After the **ansible-vault create** command opens an editor, enter the sensitive data in the **<**key>: **<**value> format:

```
activationKey: <activation_key>
```

- c. Save the changes, and close the editor. Ansible encrypts the data in the vault.
- 2. Create a playbook file, for example ~/playbook.yml, with the following content:

```
---
- name: Register to the custom registration server and CDN hosts: managed-node-01.example.com vars_files:
    - vault.yml roles:
    - role: rhel-system-roles.rhc vars:
    rhc_auth:
    login:
        activation_keys:
        keys:
        - "{{ activationKey }}"
        rhc_organization: organizationID
    rhc_server:
        hostname: example.com
```

port: 443 prefix: /rhsm

rhc baseurl: http://example.com/pulp/content

3. Validate the playbook syntax:

\$ ansible-playbook --syntax-check --ask-vault-pass ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

\$ ansible-playbook --ask-vault-pass ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.rhc/README.md file
- /usr/share/doc/rhel-system-roles/rhc/ directory
- Ansible Vault

23.4. DISABLING THE CONNECTION TO INSIGHTS AFTER THE REGISTRATION BY USING THE RHC RHEL SYSTEM ROLE

When you register a system by using the rhc RHEL system role, the role by default, enables the connection to Red Hat Insights. You can disable it by using the **rhc** RHEL system role, if not required.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- You have registered the system.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

- name: Disable Insights connection hosts: managed-node-01.example.com

- role: rhel-system-roles.rhc

vars:

rhc_insights: state: absent

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.rhc/README.md file
- /usr/share/doc/rhel-system-roles/rhc/ directory

23.5. ENABLING REPOSITORIES BY USING THERRIC RHEL SYSTEM ROLE

You can remotely enable or disable repositories on managed nodes by using the **rhc** RHEL system role.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- You have details of the repositories which you want to enable or disable on the managed nodes.
- You have registered the system.

Procedure

- 1. Create a playbook file, for example ~/playbook.yml, with the following content:
 - To enable a repository:

--- name: Enable repository
hosts: managed-node-01.example.com
roles:
- role: rhel-system-roles.rhc
vars:

vars: rhc repositories:

- {name: "RepositoryName", state: enabled}
- To disable a repository:

--- name: Disable repository
hosts: managed-node-01.example.com
vars:
 rhc_repositories:

- {name: "RepositoryName", state: disabled} roles:- role: rhel-system-roles.rhc

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

 $\$\ ansible\text{-playbook}\ \text{\sim/playbook.yml}$

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.rhc/README.md file
- /usr/share/doc/rhel-system-roles/rhc/ directory

23.6. SETTING RELEASE VERSIONS BY USING THERRIC RHEL SYSTEM ROLE

You can limit the system to use only repositories for a particular minor RHEL version instead of the latest one. This way, you can lock your system to a specific minor RHEL version.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- You know the minor RHEL version to which you want to lock the system. Note that you can only lock the system to the RHEL minor version that the host currently runs or a later minor version.
- You have registered the system.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

- name: Set Release

hosts: managed-node-01.example.com

roles:

- role: rhel-system-roles.rhc

vars:

rhc_release: "8.6"

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.rhc/README.md file
- /usr/share/doc/rhel-system-roles/rhc/ directory

23.7. USING A PROXY SERVER WHEN REGISTERING THE HOST BY USING THE RHC RHEL SYSTEM ROLE

If your security restrictions allow access to the Internet only through a proxy server, you can specify the proxy's settings in the playbook when you register the system using the **rhc** RHEL system role.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

- 1. Store your sensitive variables in an encrypted file:
 - a. Create the vault:

\$ ansible-vault create vault.yml New Vault password: <password>

Confirm New Vault password: <vault_password>

b. After the **ansible-vault create** command opens an editor, enter the sensitive data in the **<**key>: **<**value> format:

username: <username> password: <password>

- c. Save the changes, and close the editor. Ansible encrypts the data in the vault.
- 2. Create a playbook file, for example ~/playbook.yml, with the following content:
 - To register to the Red Hat Customer Portal by using a proxy:

```
- name: Register using proxy
hosts: managed-node-01.example.com
vars_files:
  - vault.yml
roles:
  - role: rhel-system-roles.rhc
vars:
  rhc auth:
   login:
    username: "{{ username }}"
    password: "{{ password }}"
  rhc_proxy:
   hostname: proxy.example.com
   port: 3128
   username: "{{ proxy_username }}"
   password: "{{ proxy_password }}"
```

 To remove the proxy server from the configuration of the Red Hat Subscription Manager service:

```
---
- name: To stop using proxy server for registration hosts: managed-node-01.example.com vars_files:
- vault.yml
vars:
rhc_auth:
login:
username: "{{ username }}"
password: "{{ password }}"
rhc_proxy: {"state":"absent"}
roles:
- role: rhel-system-roles.rhc
```

3. Validate the playbook syntax:

\$ ansible-playbook --syntax-check --ask-vault-pass ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

- /usr/share/ansible/roles/rhel-system-roles.rhc/README.md file
- /usr/share/doc/rhel-system-roles/rhc/ directory
- Ansible Vault

23.8. DISABLING AUTO UPDATES OF INSIGHTS RULES BY USING THE RHC RHEL SYSTEM ROLE

You can disable the automatic collection rule updates for Red Hat Insights by using the **rhc** RHEL system role. By default, when you connect your system to Red Hat Insights, this option is enabled. You can disable it by using the **rhc** RHEL system role.



NOTE

If you disable this feature, you risk using outdated rule definition files and not getting the most recent validation updates.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- You have registered the system.

Procedure

- 1. Store your sensitive variables in an encrypted file:
 - a. Create the vault:

\$ ansible-vault create vault.yml
New Vault password: confirm New Vault password: <vault_password>

b. After the **ansible-vault create** command opens an editor, enter the sensitive data in the **<**key>: **<**value> format:

```
username: <username>
password: <password>
```

- c. Save the changes, and close the editor. Ansible encrypts the data in the vault.
- 2. Create a playbook file, for example ~/playbook.yml, with the following content:

```
---
- name: Disable Red Hat Insights autoupdates hosts: managed-node-01.example.com vars_files:
- vault.yml roles:
- role: rhel-system-roles.rhc vars:
    rhc_auth:
    login:
        username: "{{ username }}"
        password: "{{ password }}"
```

rhc_insights: autoupdate: false state: present

3. Validate the playbook syntax:

\$ ansible-playbook --syntax-check --ask-vault-pass ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.rhc/README.md file
- /usr/share/doc/rhel-system-roles/rhc/ directory
- Ansible Vault

23.9. DISABLING INSIGHTS REMEDIATIONS BY USING THERHC RHEL SYSTEM ROLE

You can configure systems to automatically update the dynamic configuration by using the **rhc** RHEL system role. When you connect your system to Red hat Insights, it is enabled by default. You can disable it, if not required.



NOTE

Enabling remediation with the **rhc** RHEL system role ensures your system is ready to be remediated when connected directly to Red Hat. For systems connected to a Satellite, or Capsule, enabling remediation must be achieved differently. For more information about Red Hat Insights remediations, see Red Hat Insights Remediations Guide.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- You have Insights remediations enabled.
- You have registered the system.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

- name: Disable remediation

hosts: managed-node-01.example.com

roles:

- role: rhel-system-roles.rhc

vars:

rhc_insights:

remediation: absent state: present

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.rhc/README.md file
- /usr/share/doc/rhel-system-roles/rhc/ directory

23.10. CONFIGURING INSIGHTS TAGS BY USING THE RHC RHEL SYSTEM ROLE

You can use tags for system filtering and grouping. You can also customize tags based on the requirements.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

- 1. Store your sensitive variables in an encrypted file:
 - a. Create the vault:

\$ ansible-vault create vault.yml

New Vault password: <password>

Confirm New Vault password: <vault password>

b. After the **ansible-vault create** command opens an editor, enter the sensitive data in the **<key>: <value>** format:

username: <username>
password: <password>

- c. Save the changes, and close the editor. Ansible encrypts the data in the vault.
- 2. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Creating tags
 hosts: managed-node-01.example.com
 vars files:
  - vault.yml
 roles:
  - role: rhel-system-roles.rhc
 vars:
  rhc auth:
   login:
    username: "{{ username }}"
    password: "{{ password }}"
  rhc insights:
   tags:
     group: group-name-value
    location: location-name-value
    description:
      - RHEL8
      - SAP
     sample_key:value
   state: present
```

3. Validate the playbook syntax:

\$ ansible-playbook --syntax-check --ask-vault-pass ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.rhc/README.md file
- /usr/share/doc/rhel-system-roles/rhc/ directory
- Ansible Vault

23.11. UNREGISTERING A SYSTEM BY USING THERHC RHEL SYSTEM ROLE

You can unregister the system from Red Hat if you no longer need the subscription service.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- The system is already registered.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

- name: Unregister the system

hosts: managed-node-01.example.com

roles:

- role: rhel-system-roles.rhc

vars:

rhc_state: absent

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

- /usr/share/ansible/roles/rhel-system-roles.rhc/README.md file
- /usr/share/doc/rhel-system-roles/rhc/ directory

CHAPTER 24. CONFIGURING SELINUX BY USING RHEL SYSTEM ROLES

You can configure and manage SELinux permissions on other systems by using the **selinux** RHEL system role.

24.1. INTRODUCTION TO THE SELINUX RHEL SYSTEM ROLE

RHEL system roles is a collection of Ansible roles and modules that provide a consistent configuration interface to remotely manage multiple RHEL systems. You can perform the following actions by using the **selinux** RHEL system role:

- Cleaning local policy modifications related to SELinux booleans, file contexts, ports, and logins.
- Setting SELinux policy booleans, file contexts, ports, and logins.
- Restoring file contexts on specified files or directories.
- Managing SELinux modules.

The /usr/share/doc/rhel-system-roles/selinux/example-selinux-playbook.yml example playbook installed by the rhel-system-roles package demonstrates how to set the targeted policy in enforcing mode. The playbook also applies several local policy modifications and restores file contexts in the /tmp/test_dir/ directory.

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.selinux/README.md file
- /usr/share/doc/rhel-system-roles/selinux/ directory

24.2. USING THE SELINUX RHEL SYSTEM ROLE TO APPLY SELINUX SETTINGS ON MULTIPLE SYSTEMS

With the **selinux** RHEL system role, you can prepare and apply an Ansible playbook with your verified SELinux settings.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Prepare your playbook. You can either start from scratch or modify the example playbook installed as a part of the **rhel-system-roles** package:

cp /usr/share/doc/rhel-system-roles/selinux/example-selinux-playbook.yml <my-selinux-playbook.yml>

vi <my-selinux-playbook.yml>

2. Change the content of the playbook to fit your scenario. For example, the following part ensures that the system installs and enables the **selinux-local-1.pp** SELinux module:

```
selinux_modules:
- { path: "selinux-local-1.pp", priority: "400" }
```

- 3. Save the changes, and exit the text editor.
- 4. Validate the playbook syntax:

\$ ansible-playbook < my-selinux-playbook.yml > --syntax-check

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

5. Run your playbook:

\$ ansible-playbook <my-selinux-playbook.yml>

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.selinux/README.md file
- /usr/share/doc/rhel-system-roles/selinux/ directory
- SELinux hardening with Ansible Knowledgebase article

24.3. MANAGING PORTS BY USING THE SELINUX RHEL SYSTEM ROLE

You can automate managing port access in SELinux consistently across multiple systems by using the **selinux** RHEL system role. This might be useful, for example, when configuring an Apache HTTP server to listen on a different port. You can do this by creating a playbook with the **selinux** RHEL system role that assigns the **http_port_t** SELinux type to a specific port number. After you run the playbook on the managed nodes, specific services defined in the SELinux policy can access this port.

You can automate managing port access in SELinux either by using the **seport** module, which is quicker than using the entire role, or by using the **selinux** RHEL system role, which is more useful when you also make other changes in SELinux configuration. The methods are equivalent, in fact the **selinux** RHEL system role uses the **seport** module when configuring ports. Each of the methods has the same effect as entering the command **semanage port -a -t http_port_t -p tcp <***port_number>* on the managed node.

Prerequisites

- You have prepared the control node and the managed nodes.
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- Optional: To verify port status by using the semanage command, the policycoreutils-pythonutils package must be installed.

Procedure

• To configure just the port number without making other changes, use the **seport** module:

```
- name: Allow Apache to listen on tcp port <port_number>
community.general.seport:
  ports: <port_number>
  proto: tcp
  setype: http_port_t
  state: present
```

Replace **<port_number>** with the port number to which you want to assign the http_port_t
type.

 For more complex configuration of the managed nodes that involves other customizations of SELinux, use the **selinux** RHEL system role. Create a playbook file, for example, ~/playbook.yml, and add the following content:

```
---
- name: Modify SELinux port mapping example
hosts: all
vars:

# Map tcp port <port_number> to the 'http_port_t' SELinux port type
selinux_ports:
- ports: <port_number>
    proto: tcp
    setype: http_port_t
    state: present

tasks:
- name: Include selinux role
    ansible.builtin.include_role:
    name: rhel-system-roles.selinux
```

Replace **<port_number>** with the port number to which you want to assign the **http_port_t** type.

Verification

• Verify that the port is assigned to the **http_port_t** type:

```
# semanage port --list | grep http_port_t
http_port_t tcp cport_number>, 80, 81, 443, 488, 8008, 8009, 8443, 9000
```

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.selinux/README.md file
- /usr/share/doc/rhel-system-roles/selinux/ directory

CHAPTER 25. RESTRICTING THE EXECUTION OF APPLICATIONS BY USING THE FAPOLICYD RHEL SYSTEM ROLE

By using the **fapolicyd** software framework, you can restrict the execution of applications based on a user-defined policy and the framework verifies the integrity of applications before execution. This an efficient method to prevent running untrustworthy and possibly malicious applications. You can automate the installation and configuration of **fapolicyd** by using the **fapolicyd** RHEL system role.



IMPORTANT

The **fapolicyd** service prevents only the execution of unauthorized applications that run as regular users, and not as **root**.

25.1. PREVENTING USERS FROM EXECUTING UNTRUSTWORTHY CODE BY USING THE FAPOLICYD RHEL SYSTEM ROLE

You can automate the installation and configuration of the **fapolicyd** service by using the **fapolicyd** RHEL system role. With this role, you can remotely configure the service to allow users to execute only trusted applications, for example, the ones which are listed in the RPM database and in an allow list. Additionally, the service can perform integrity checks before it executes an allowed application.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

--

- name: Configuring fapolicyd

hosts: managed-node-01.example.com

tasks:

 name: Allow only executables installed from RPM database and specific files ansible.builtin.include_role:

name: rhel-system-roles.fapolicyd

vars:

fapolicyd_setup_permissive: false fapolicyd_setup_integrity: sha256 fapolicyd_setup_trust: rpmdb,file fapolicyd_add_trusted_file:

- <path_to_allowed_command>

- <path_to_allowed_service>

The settings specified in the example playbook include the following:

fapolicyd setup permissive: <true/false>

Enables or disables sending policy decisions to the kernel for enforcement. Set this variable for debugging and testing purposes to **false**.

fapolicyd_setup_integrity: <type_type>

Defines the integrity checking method. You can set one of the following values:

- **none** (default): Disables integrity checking.
- **size**: The service compares only the file sizes of allowed applications.
- **ima**: The service checks the SHA-256 hash that the kernel's Integrity Measurement Architecture (IMA) stored in a file's extended attribute. Additionally, the service performs a size check. Note that the role does not configure the IMA kernel subsystem. To use this option, you must manually configure the IMA subsystem.
- **sha256**: The service compares the SHA-256 hash of allowed applications.

fapolicyd_setup_trust: <trust_backends>

Defines the list of trust backends. If you include the **file** backend, specify the allowed executable files in the **fapolicyd add trusted file** list.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.fapolicyd.README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook ~/playbook.yml --syntax-check

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

• Execute a binary application that is not on the allow list as a user:

\$ ansible managed-node-01.example.com -m command -a 'su -c "/bin/not_authorized_application " <user_name>' bash: line 1: /bin/not_authorized_application: Operation not permitted non-zero return code

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.fapolicyd/README.md file
- /usr/share/doc/rhel-system-roles/fapolicyd/ directory

CHAPTER 26. CONFIGURING SECURE COMMUNICATION BY USING RHEL SYSTEM ROLES

As an administrator, you can use the **sshd** system role to configure SSH servers and the **ssh** system role to configure SSH clients consistently on any number of RHEL systems at the same time using the Ansible Core package.

26.1. VARIABLES OF THE SSHD RHEL SYSTEM ROLE

In an **sshd** system role playbook, you can define the parameters for the SSH configuration file according to your preferences and limitations.

If you do not configure these variables, the system role produces an **sshd_config** file that matches the RHEL defaults.

In all cases, Booleans correctly render as **yes** and **no** in **sshd** configuration. You can define multi-line configuration items using lists. For example:

sshd ListenAddress:

- 0.0.0.0
- _ '--'

renders as:

ListenAddress 0.0.0.0 ListenAddress ::

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.sshd/README.md file
- /usr/share/doc/rhel-system-roles/sshd/ directory

26.2. CONFIGURING OPENSSH SERVERS BY USING THE SSHD RHEL SYSTEM ROLF

You can use the **sshd** RHEL system role to configure multiple SSH servers by running an Ansible playbook.



NOTE

You can use the **sshd** RHEL system role with other RHEL system roles that change SSH and SSHD configuration, for example the Identity Management RHEL system roles. To prevent the configuration from being overwritten, make sure that the **sshd** role uses namespaces (RHEL 8 and earlier versions) or a drop-in directory (RHEL 9).

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.

The account you use to connect to the managed nodes has sudo permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

--- name: SSH server configuration
hosts: managed-node-01.example.com
tasks:

- name: Configure sshd to prevent root and password login except from particular subnet ansible.builtin.include_role:

name: rhel-system-roles.sshd

vars: sshd:

PermitRootLogin: no

PasswordAuthentication: no

Match:

- Condition: "Address 192.0.2.0/24"

PermitRootLogin: yes

PasswordAuthentication: yes

The playbook configures the managed node as an SSH server configured so that:

- password and root user login is disabled
- password and root user login is enabled only from the subnet 192.0.2.0/24
- 2. Validate the playbook syntax:

 $\$\ ansible-playbook\ --syntax-check\ \sim\!/playbook.yml$

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

1. Log in to the SSH server:

\$ ssh <username>@<ssh_server>

2. Verify the contents of the **sshd** config file on the SSH server:

\$ cat /etc/ssh/sshd_config.d/00-ansible_system_role.conf #
Ansible managed
PasswordAuthentication no
PermitRootLogin no

Match Address 192.0.2.0/24 PasswordAuthentication yes PermitRootLogin yes

- 3. Check that you can connect to the server as root from the 192.0.2.0/24 subnet:
 - a. Determine your IP address:

\$ hostname -I 192.0.2.1

If the IP address is within the **192.0.2.1** - **192.0.2.254** range, you can connect to the server.

b. Connect to the server as root:

\$ ssh root@<ssh_server>

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.sshd/README.md file
- /usr/share/doc/rhel-system-roles/sshd/ directory

26.3. USING THE SSHD RHEL SYSTEM ROLE FOR NON-EXCLUSIVE CONFIGURATION

Normally, applying the **sshd** system role overwrites the entire configuration. This may be problematic if you have previously adjusted the configuration, for example, with a different system role or playbook. To apply the **sshd** system role for only selected configuration options while keeping other options in place, you can use the non-exclusive configuration.

You can apply a non-exclusive configuration:

- In RHEL 8 and earlier by using a configuration snippet.
- In RHEL 9 and later by using files in a drop-in directory. The default configuration file is already placed in the drop-in directory as /etc/ssh/sshd_config.d/00-ansible_system_role.conf.

Prerequisites

- You have prepared the control node and the managed nodes.
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

- 1. Create a playbook file, for example ~/playbook.yml, with the following content:
 - For managed nodes that run RHEL 8 or earlier:

- name: Non-exclusive sshd configuration

```
hosts: managed-node-01.example.com
tasks:
- name: <Configure SSHD to accept some useful environment variables>
ansible.builtin.include_role:
    name: rhel-system-roles.sshd
    vars:
    sshd_config_namespace: <my-application>
    sshd:
    # Environment variables to accept
    AcceptEnv:
    LANG
    LS_COLORS
    EDITOR
```

For managed nodes that run RHEL 9 or later:

```
name: Non-exclusive sshd configuration
hosts: managed-node-01.example.com
tasks:

name: <Configure sshd to accept some useful environment variables>
ansible.builtin.include_role:
name: rhel-system-roles.sshd
vars:
sshd_config_file: /etc/ssh/sshd_config.d/<42-my-application>.conf
sshd:
# Environment variables to accept
AcceptEnv:
LANG
LS_COLORS
EDITOR
```

In the **sshd_config_file** variable, define the **.conf** file into which the **sshd** system role writes the configuration options. Use a two-digit prefix, for example **42-** to specify the order in which the configuration files will be applied.

2. Validate the playbook syntax:

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

- Verify the configuration on the SSH server:
 - For managed nodes that run RHEL 8 or earlier:

```
# cat /etc/ssh/sshd_config.d/42-my-application.conf
# Ansible managed
#
```

AcceptEnv LANG LS_COLORS EDITOR

• For managed nodes that run RHEL 9 or later:

```
# cat /etc/ssh/sshd_config
```

• • • •

BEGIN sshd system role managed block: namespace <my-application> Match all

AcceptEnv LANG LS COLORS EDITOR

END sshd system role managed block: namespace <my-application>

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.sshd/README.md file
- /usr/share/doc/rhel-system-roles/sshd/ directory

26.4. OVERRIDING THE SYSTEM-WIDE CRYPTOGRAPHIC POLICY ON AN SSH SERVER BY USING THE SSHD RHEL SYSTEM ROLE

You can override the system-wide cryptographic policy on an SSH server by using the **sshd** RHEL system role.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
name: Overriding the system-wide cryptographic policy hosts: managed-node-01.example.com roles:

rhel_system_roles.sshd

vars:

sshd_sysconfig: true
sshd_sysconfig_override_crypto_policy: true
sshd_KexAlgorithms: ecdh-sha2-nistp521
sshd_Ciphers: aes256-ctr
sshd_MACs: hmac-sha2-512-etm@openssh.com
sshd_HostKeyAlgorithms: rsa-sha2-512,rsa-sha2-256
```

- sshd_KexAlgorithms:: You can choose key exchange algorithms, for example, ecdh-sha2-nistp256, ecdh-sha2-nistp384, ecdh-sha2-nistp521,diffie-hellman-group14-sha1, or diffie-hellman-group-exchange-sha256.
- sshd_Ciphers:: You can choose ciphers, for example, aes128-ctr, aes192-ctr, or aes256-ctr.

- sshd_MACs:: You can choose MACs, for example, hmac-sha2-256, hmac-sha2-512, or hmac-sha1.
- sshd_HostKeyAlgorithms:: You can choose a public key algorithm, for example, ecdsa-sha2-nistp256, ecdsa-sha2-nistp384, ecdsa-sha2-nistp521, ssh-rsa, or ssh-dss.

On RHEL 9 managed nodes, the system role writes the configuration into the /etc/ssh/sshd_config.d/00-ansible_system_role.conf file, where cryptographic options are applied automatically. You can change the file by using the sshd_config_file variable. However, to ensure the configuration is effective, use a file name that lexicographically preceds the /etc/ssh/sshd_config.d/50-redhat.conf file, which includes the configured crypto policies.

On RHEL 8 managed nodes, you must enable override by setting the **sshd_sysconfig_override_crypto_policy** and **sshd_sysconfig** variables to **true**.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

• You can verify the success of the procedure by using the verbose SSH connection and check the defined variables in the following output:

\$ ssh -vvv <ssh_server>

...

debug2: peer server KEXINIT proposal

debug2: KEX algorithms: ecdh-sha2-nistp521

debug2: host key algorithms: rsa-sha2-512,rsa-sha2-256

debug2: ciphers ctos: aes256-ctr debug2: ciphers stoc: aes256-ctr

debug2: MACs ctos: hmac-sha2-512-etm@openssh.com debug2: MACs stoc: hmac-sha2-512-etm@openssh.com

• • •

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.sshd/README.md file
- /usr/share/doc/rhel-system-roles/sshd/ directory

26.5. VARIABLES OF THE SSH RHEL SYSTEM ROLE

In an **ssh** system role playbook, you can define the parameters for the client SSH configuration file according to your preferences and limitations.

If you do not configure these variables, the system role produces a global **ssh_config** file that matches the RHEL defaults.

In all cases, booleans correctly render as **yes** or **no** in **ssh** configuration. You can define multi-line configuration items using lists. For example:

LocalForward:

- 22 localhost:2222
- 403 localhost:4003

renders as:

LocalForward 22 localhost:2222 LocalForward 403 localhost:4003



NOTE

The configuration options are case sensitive.

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.ssh/README.md file
- /usr/share/doc/rhel-system-roles/ssh/ directory

26.6. CONFIGURING OPENSSH CLIENTS BY USING THE SSH RHEL SYSTEM ROLE

You can use the **ssh** RHEL system role to configure multiple SSH clients by running an Ansible playbook.



NOTE

You can use the **ssh** RHEL system role with other system roles that change SSH and SSHD configuration, for example the Identity Management RHEL system roles. To prevent the configuration from being overwritten, make sure that the **ssh** role uses a drop-in directory (default in RHEL 8 and later).

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

- name: SSH client configuration

hosts: managed-node-01.example.com

tasks:

 name: "Configure ssh clients" ansible.builtin.include_role: name: rhel-system-roles.ssh

vars:

ssh_user: root

ssh:

Compression: true

GSSAPIAuthentication: no

ControlMaster: auto

ControlPath: ~/.ssh/.cm%C

Host:

- Condition: example

Hostname: server.example.com

User: user1 ssh_ForwardX11: no

This playbook configures the **root** user's SSH client preferences on the managed nodes with the following configurations:

- Compression is enabled.
- ControlMaster multiplexing is set to auto.
- The **example** alias for connecting to the **server.example.com** host is **user1**.
- The **example** host alias is created, which represents a connection to the **server.example.com** host the with the **user1** user name.
- X11 forwarding is disabled.
- 2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

 Verify that the managed node has the correct configuration by displaying the SSH configuration file:

cat ~/root/.ssh/config

Ansible managed

Compression yes

ControlMaster auto

ControlPath ~/.ssh/.cm%C

ForwardX11 no

GSSAPIAuthentication no

Host example Hostname example.com User user1

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.ssh/README.md file
- /usr/share/doc/rhel-system-roles/ssh/ directory

CHAPTER 27. MANAGING LOCAL STORAGE BY USING RHEL SYSTEM ROLES

To manage LVM and local file systems (FS) by using Ansible, you can use the **storage** role, which is one of the RHEL system roles available in RHEL 9.

Using the **storage** role enables you to automate administration of file systems on disks and logical volumes on multiple machines and across all versions of RHEL starting with RHEL 7.7.

27.1. INTRODUCTION TO THE STORAGE RHEL SYSTEM ROLE

The **storage** role can manage:

- File systems on disks which have not been partitioned
- Complete LVM volume groups including their logical volumes and file systems
- MD RAID volumes and their file systems

With the **storage** role, you can perform the following tasks:

- Create a file system
- Remove a file system
- Mount a file system
- Unmount a file system
- Create LVM volume groups
- Remove LVM volume groups
- Create logical volumes
- Remove logical volumes
- Create RAID volumes
- Remove RAID volumes
- Create LVM volume groups with RAID
- Remove LVM volume groups with RAID
- Create encrypted LVM volume groups
- Create LVM logical volumes with RAID

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.storage/README.md file
- /usr/share/doc/rhel-system-roles/storage/ directory

27.2. CREATING AN XFS FILE SYSTEM ON A BLOCK DEVICE BY USING THE STORAGE RHEL SYSTEM ROLE

The example Ansible playbook applies the **storage** role to create an XFS file system on a block device using the default parameters.



NOTE

The **storage** role can create a file system only on an unpartitioned, whole disk or a logical volume (LV). It cannot create the file system on a partition.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
---
- hosts: managed-node-01.example.com roles:
- rhel-system-roles.storage vars:
storage_volumes:
- name: barefs
type: disk
disks:
- sdb
fs type: xfs
```

- The volume name (*barefs* in the example) is currently arbitrary. The **storage** role identifies the volume by the disk device listed under the **disks:** attribute.
- You can omit the **fs_type: xfs** line because XFS is the default file system in RHEL 9.
- To create the file system on an LV, provide the LVM setup under the disks: attribute, including the enclosing volume group. For details, see Managing logical volumes by using the storage RHEL system role.

Do not provide the path to the LV device.

2. Validate the playbook syntax:

$\$\ ansible-playbook\ --syntax-check\ \sim\!/playbook.yml$

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.storage/README.md file
- /usr/share/doc/rhel-system-roles/storage/ directory

27.3. PERSISTENTLY MOUNTING A FILE SYSTEM BY USING THE STORAGE RHEL SYSTEM ROLE

The example Ansible applies the **storage** role to immediately and persistently mount an XFS file system.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
---
- hosts: managed-node-01.example.com roles:
- rhel-system-roles.storage vars:
storage_volumes:
- name: barefs
type: disk
disks:
- sdb
fs_type: xfs
mount_point: /mnt/data
mount_user: somebody
mount_group: somegroup
mount_mode: 0755
```

- This playbook adds the file system to the /etc/fstab file, and mounts the file system immediately.
- If the file system on the /dev/sdb device or the mount point directory do not exist, the playbook creates them.
- 2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.storage/README.md file
- /usr/share/doc/rhel-system-roles/storage/ directory

27.4. MANAGING LOGICAL VOLUMES BY USING THESTORAGE RHEL SYSTEM ROLE

The example Ansible playbook applies the **storage** role to create an LVM logical volume in a volume group.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
hosts: managed-node-01.example.com roles:

rhel-system-roles.storage

vars:

storage_pools:
name: myvg
disks:

sda
sdb
sdc

volumes:

name: mylv
size: 2G
fs_type: ext4
mount_point: /mnt/dat
```

- The **myvg** volume group consists of the following disks: /dev/sda, /dev/sdb, and /dev/sdc.
- If the **myvg** volume group already exists, the playbook adds the logical volume to the volume group.
- If the **myvg** volume group does not exist, the playbook creates it.
- The playbook creates an Ext4 file system on the **mylv** logical volume, and persistently mounts the file system at /**mnt**.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.storage/README.md file
- /usr/share/doc/rhel-system-roles/storage/ directory

27.5. ENABLING ONLINE BLOCK DISCARD BY USING THESTORAGE RHEL SYSTEM ROLE

The example Ansible playbook applies the **storage** role to mount an XFS file system with online block discard enabled.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
---
- hosts: managed-node-01.example.com roles:
- rhel-system-roles.storage vars:
storage_volumes:
- name: barefs
type: disk
disks:
- sdb
fs_type: xfs
mount_point: /mnt/data
mount_options: discard
```

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.storage/README.md file
- /usr/share/doc/rhel-system-roles/storage/ directory

27.6. CREATING AND MOUNTING AN EXT4 FILE SYSTEM BY USING THE STORAGE RHEL SYSTEM ROLE

The example Ansible playbook applies the **storage** role to create and mount an Ext4 file system.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
---
- hosts: managed-node-01.example.com roles:
- rhel-system-roles.storage vars:
storage_volumes:
- name: barefs
type: disk
disks:
- sdb
fs_type: ext4
fs_label: label-name
mount_point: /mnt/data
```

- The playbook creates the file system on the /dev/sdb disk.
- The playbook persistently mounts the file system at the /mnt/data directory.
- The label of the file system is **label-name**.
- 2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.storage/README.md file
- /usr/share/doc/rhel-system-roles/storage/ directory

27.7. CREATING AND MOUNTING AN EXT3 FILE SYSTEM BY USING THE STORAGE RHEL SYSTEM ROLE

The example Ansible playbook applies the **storage** role to create and mount an Ext3 file system.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
---
- hosts: all
roles:
    - rhel-system-roles.storage
vars:
    storage_volumes:
    - name: barefs
    type: disk
    disks:
    - sdb
    fs_type: ext3
    fs_label: label-name
    mount_point: /mnt/data
    mount_user: somebody
    mount_group: somegroup
    mount_mode: 0755
```

- The playbook creates the file system on the /dev/sdb disk.
- The playbook persistently mounts the file system at the /mnt/data directory.
- The label of the file system is **label-name**.
- 2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.storage/README.md file
- /usr/share/doc/rhel-system-roles/storage/ directory

27.8. RESIZING AN EXISTING FILE SYSTEM ON LVM BY USING THE STORAGE RHEL SYSTEM ROLE

The example Ansible playbook applies the **storage** RHEL system role to resize an LVM logical volume with a file system.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

 name: Create LVM pool over three disks hosts: managed-node-01.example.com

tasks:

- name: Resize LVM logical volume with file system

ansible.builtin.include role:

name: rhel-system-roles.storage

vars:

storage_pools:

- name: myvg

disks:

- /dev/sda

- /dev/sdb

- /dev/sdc

volumes:

name: mylv1 size: 10 GiB fs type: ext4

mount_point: /opt/mount1

- name: mylv2

size: 50 GiB fs_type: ext4

mount_point: /opt/mount2

This playbook resizes the following existing file systems:

- The Ext4 file system on the mylv1 volume, which is mounted at /opt/mount1, resizes to 10 GiB.
- The Ext4 file system on the mylv2 volume, which is mounted at /opt/mount2, resizes to 50 GiB.
- 2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.storage/README.md file
- /usr/share/doc/rhel-system-roles/storage/ directory

27.9. CREATING A SWAP VOLUME BY USING THESTORAGE RHEL SYSTEM ROLE

This section provides an example Ansible playbook. This playbook applies the **storage** role to create a swap volume, if it does not exist, or to modify the swap volume, if it already exist, on a block device by using the default parameters.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has sudo permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

- name: Create a disk device with swap hosts: managed-node-01.example.com

roles:

- rhel-system-roles.storage

vars:

storage_volumes:
- name: swap_fs
type: disk
disks:
- /dev/sdb
size: 15 GiB
fs type: swap

The volume name (**swap_fs** in the example) is currently arbitrary. The **storage** role identifies the volume by the disk device listed under the **disks**: attribute.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.storage/README.md file
- /usr/share/doc/rhel-system-roles/storage/ directory

27.10. CONFIGURING A RAID VOLUME BY USING THESTORAGE RHEL SYSTEM ROLE

With the **storage** system role, you can configure a RAID volume on RHEL by using Red Hat Ansible Automation Platform and Ansible-Core. Create an Ansible playbook with the parameters to configure a RAID volume to suit your requirements.



WARNING

Device names might change in certain circumstances, for example, when you add a new disk to a system. Therefore, to prevent data loss, do not use specific disk names in the playbook.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

 name: Configure the storage hosts: managed-node-01.example.com tasks:

 name: Create a RAID on sdd, sde, sdf, and sdg ansible.builtin.include role:

name: rhel-system-roles.storage

vars:

storage_safe_mode: false storage_volumes:

- name: data type: raid

disks: [sdd, sde, sdf, sdg]

raid_level: raid0

raid_chunk_size: 32 KiB mount_point: /mnt/data

state: present

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.storage/README.md file
- /usr/share/doc/rhel-system-roles/storage/ directory

27.11. CONFIGURING AN LVM POOL WITH RAID BY USING THESTORAGE RHEL SYSTEM ROLE

With the **storage** system role, you can configure an LVM pool with RAID on RHEL by using Red Hat Ansible Automation Platform. You can set up an Ansible playbook with the available parameters to configure an LVM pool with RAID.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

D.....

Proceaure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

- name: Configure LVM pool with RAID hosts: managed-node-01.example.com - rhel-system-roles.storage vars: storage_safe_mode: false storage_pools: - name: my_pool type: lvm disks: [sdh, sdi] raid level: raid1 volumes: - name: my volume size: "1 GiB" mount_point: "/mnt/app/shared" fs_type: xfs state: present

To create an LVM pool with RAID, you must specify the RAID type by using the **raid_level** parameter.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

 $\$\ ansible-playbook\ {\sim}/playbook.yml$

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.storage/README.md file
- /usr/share/doc/rhel-system-roles/storage/ directory
- Managing RAID

27.12. CONFIGURING A STRIPE SIZE FOR RAID LVM VOLUMES BY USING THE STORAGE RHEL SYSTEM ROLE

With the **storage** system role, you can configure a stripe size for RAID LVM volumes on RHEL by using Red Hat Ansible Automation Platform. You can set up an Ansible playbook with the available parameters to configure an LVM pool with RAID.

Prerequisites

• You have prepared the control node and the managed nodes .

- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Configure stripe size for RAID LVM volumes
 hosts: managed-node-01.example.com
  - rhel-system-roles.storage
 vars:
  storage_safe_mode: false
  storage_pools:
   name: my_pool
    type: lvm
    disks: [sdh, sdi]
    volumes:
     - name: my_volume
       size: "1 GiB"
       mount point: "/mnt/app/shared"
       fs type: xfs
       raid_level: raid1
       raid_stripe_size: "256 KiB"
       state: present
```

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.storage/README.md file
- /usr/share/doc/rhel-system-roles/storage/ directory
- Managing RAID

27.13. COMPRESSING AND DEDUPLICATING A VDO VOLUME ON LVM BY USING THE STORAGE RHEL SYSTEM ROLE

The example Ansible playbook applies the **storage** RHEL system role to enable compression and deduplication of Logical Volumes (LVM) by using Virtual Data Optimizer (VDO).



NOTE

Because of the **storage** system role use of LVM VDO, only one volume per pool can use the compression and deduplication.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Create LVM VDO volume under volume group 'myvg'
hosts: managed-node-01.example.com
roles:
  - rhel-system-roles.storage
 vars:
  storage pools:
   - name: myvg
    disks:
     - /dev/sdb
    volumes:
     - name: mylv1
      compression: true
      deduplication: true
      vdo pool size: 10 GiB
      size: 30 GiB
      mount_point: /mnt/app/shared
```

In this example, the **compression** and **deduplication** pools are set to true, which specifies that the VDO is used. The following describes the usage of these parameters:

- The deduplication is used to deduplicate the duplicated data stored on the storage volume.
- The compression is used to compress the data stored on the storage volume, which results in more storage capacity.
- The vdo_pool_size specifies the actual size the volume takes on the device. The virtual size of VDO volume is set by the **size** parameter.
- 2. Validate the playbook syntax:
 - $\$ \ ansible-playbook \ \hbox{--syntax-check} \ \hbox{\sim/playbook.yml}$

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.storage/README.md file
- /usr/share/doc/rhel-system-roles/storage/ directory

27.14. CREATING A LUKS2 ENCRYPTED VOLUME BY USING THE STORAGE RHEL SYSTEM ROLE

You can use the **storage** role to create and configure a volume encrypted with LUKS by running an Ansible playbook.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
---
- name: Create and configure a volume encrypted with LUKS hosts: managed-node-01.example.com roles:
    - rhel-system-roles.storage vars:
    storage_volumes:
    - name: barefs
    type: disk
    disks:
    - sdb
    fs_type: xfs
    fs_label: label-name
    mount_point: /mnt/data
    encryption: true
    encryption_password>
```

You can also add other encryption parameters, such as **encryption_key**, **encryption_cipher**, **encryption key size**, and **encryption luks**, to the playbook file.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

1. View the encryption status:

cryptsetup status sdb

/dev/mapper/sdb is active and is in use.

type: LUKS2

cipher: aes-xts-plain64 keysize: 512 bits key location: keyring device: /dev/sdb

...

2. Verify the created LUKS encrypted volume:

cryptsetup luksDump /dev/sdb

Version: 2 Epoch: 6

Metadata area: 16384 [bytes] Keyslots area: 33521664 [bytes]

UUID: a4c6be82-7347-4a91-a8ad-9479b72c9426

Label: (no label)

Subsystem: (no subsystem) Flags: allow-discards

Data segments:

0: crypt

offset: 33554432 [bytes] length: (whole device) cipher: aes-xts-plain64 sector: 4096 [bytes]

...

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.storage/README.md file
- /usr/share/doc/rhel-system-roles/storage/ directory
- Encrypting block devices by using LUKS

27.15. EXPRESSING POOL VOLUME SIZES AS PERCENTAGE BY USING THE STORAGE RHEL SYSTEM ROLE

The example Ansible playbook applies the **storage** system role to enable you to express Logical Manager Volumes (LVM) volume sizes as a percentage of the pool's total size.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.

• The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

- name: Express volume sizes as a percentage of the pool's total size hosts: managed-node-01.example.com - rhel-system-roles.storage vars: storage_pools: - name: myvg disks: - /dev/sdb volumes: - name: data size: 60% mount_point: /opt/mount/data - name: web size: 30% mount_point: /opt/mount/web - name: cache size: 10%

This example specifies the size of LVM volumes as a percentage of the pool size, for example: **60%**. Alternatively, you can also specify the size of LVM volumes as a percentage of the pool size in a human-readable size of the file system, for example, **10g** or **50 GiB**.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

mount_point: /opt/cache/mount

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.storage/README.md file
- /usr/share/doc/rhel-system-roles/storage/ directory

CHAPTER 28. MANAGING SYSTEMD UNITS BY USING RHEL SYSTEM ROLES

By using the **systemd** RHEL system role, you can automate certain systemd-related tasks and perform them remotely. You can use the role for the following actions:

- Manage services
- Deploy units
- Deploy drop-in files

28.1. MANAGING SERVICES BY USING THE SYSTEMD RHEL SYSTEM ROLE

You can automate and remotely manage systemd units, such as starting or enabling services, by using the **systemd** RHEL system role.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content. Use only the variables depending on what actions you want to perform.

- name: Managing systemd services hosts: managed-node-01.example.com tasks:
 - name: Perform action on systemd units ansible.builtin.include_role: name: rhel-system-roles.systemd vars:

systemd started units:

- <systemd_unit_1>.service
 systemd stopped units:
- <systemd_unit_2>.service
 systemd_restarted_units:
- <systemd_unit_3>.service
 systemd_reloaded_units:
- <systemd_unit_4>.service
 systemd enabled units:
- <systemd_unit_5>.service
 systemd_disabled_units:
- <systemd_unit_6>.service
 systemd_masked_units:

- <systemd_unit_7>.service
systemd_unmasked_units:
- <systemd_unit_8>.service

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.systemd/README.md file on the control node.

2. Validate the playbook syntax:

 $\$ \ ansible-playbook \ --syntax-check \ \sim\!/playbook.yml$

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.systemd/README.md file
- /usr/share/doc/rhel-system-roles/systemd/ directory

28.2. DEPLOYING SYSTEMD DROP-IN FILES BY USING THE SYSTEMD RHEL SYSTEM ROLE

Systemd applies drop-in files on top of setting it reads for a unit from other locations. Therefore, you can modify unit settings with drop-in files without changing the original unit file. By using the **systemd** RHEL system role, you can automate the process of deploying drop-in files.



IMPORTANT

The role uses the hard-coded file name **99-override.conf** to store drop-in files in /etc/systemd/system/<name>._<unit_type>/. Note that it overrides existing files with this name in the destination directory.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a Jinja2 template with the systemd drop-in file contents. For example, create the ~/sshd.service.conf.j2 file with the following content:

```
{{ ansible_managed | comment }}
[Unit]
After=
After=network.target sshd-keygen.target network-online.target
```

This drop-in file specifies the same units in the **After** setting as the original /usr/lib/systemd/system/sshd.service file and, additionally, network-online.target. With this extra target, **sshd** starts after the network interfaces are actived and have IP addresses assigned. This ensures that **sshd** can bind to all IP addresses.

Use the **<name>.<unit_type>.conf.j2** convention for the file name. For example, to add a drop-in for the **sshd.service** unit, you must name the file **sshd.service.conf.j2**. Place the file in the same directory as the playbook.

2. Create a playbook file, for example ~/playbook.yml, with the following content:

- name: Managing systemd services hosts: managed-node-01.example.com

- name: Deploy an sshd.service systemd drop-in file

ansible.builtin.include_role:

name: rhel-system-roles.systemd

vars

systemd dropins:

- sshd.service.conf.j2

The settings specified in the example playbook include the following:

systemd_dropins: < list_of_files>

Specifies the names of the drop-in files to deploy in YAML list format.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.systemd/README.md file on the control node.

3. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

• Verify that the role placed the drop-in file in the correct location:

ansible managed-node-01.example.com -m command -a 'ls /etc/systemd/system/sshd.service.d/'
99-override.conf

Additional resources

• /usr/share/ansible/roles/rhel-system-roles.systemd/README.md file

/usr/share/doc/rhel-system-roles/systemd/ directory

28.3. DEPLOYING SYSTEMD UNITS BY USING THE SYSTEMD RHEL SYSTEM ROLE

You can create unit files for custom applications, and systemd reads them from the /etc/systemd/system/ directory. By using the systemd RHEL system role, you can automate the deployment of custom unit files.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a Jinja2 template with the custom systemd unit file contents. For example, create the ~/example.service.j2 file with the contents for your service:

```
{{ ansible_managed | comment }}
[Unit]
Description=Example systemd service unit file
[Service]
ExecStart=/bin/true
```

Use the **<name>.<unit_type>.j2** convention for the file name. For example, to create the **example.service** unit, you must name the file **example.service.j2**. Place the file in the same directory as the playbook.

2. Create a playbook file, for example ~/playbook.yml, with the following content:

```
---
- name: Managing systemd services
hosts: managed-node-01.example.com
tasks:
- name: Deploy, enable, and start a custom systemd service
ansible.builtin.include_role:
    name: rhel-system-roles.systemd
vars:
    systemd_unit_file_templates:
    - example.service.j2
systemd_enabled_units:
    - example.service
systemd_started_units:
    - example.service
```

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.systemd/README.md file on the control node.

3. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

• Verify that the service is enabled and started:

ansible managed-node-01.example.com -m command -a 'systemctl status example.service'

. . .

example.service - A service for demonstrating purposes
 Loaded: loaded (/etc/systemd/system/example.service; enabled; vendor preset: disabled)
 Active: active (running) since Thu 2024-07-04 15:59:18 CEST; 10min ago

• • •

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.systemd/README.md file
- /usr/share/doc/rhel-system-roles/systemd/ directory

CHAPTER 29. CONFIGURING TIME SYNCHRONIZATION BY USING RHEL SYSTEM ROLES

The Network Time Protocol (NTP) and Precision Time Protocol (PTP) are standards to synchronize the clock of computers over a network. An accurate time synchronization in networks is important because certain services rely on it. For example, Kerberos tolerates only a small time difference between the server and client to prevent replay attacks.

You can set the time service to configure in the **timesync_ntp_provider** variable of a playbook. If you do not set this variable, the role determines the time service based on the following factors:

- On RHEL 8 and later: chronyd
- On RHEL 6 and 7: **chronyd** (default) or, if already installed **ntpd**.

29.1. CONFIGURING TIME SYNCHRONIZATION OVER NTP BY USING THE TIMESYNC RHEL SYSTEM ROLE

The Network Time Protocol (NTP) synchronizes the time of a host with an NTP server over a network. In IT networks, services rely on a correct system time, for example, for security and logging purposes. By using the **timesync** RHEL system role, you can automate the configuration of Red Hat Enterprise Linux NTP clients in your network and keep the time synchronized.



WARNING

The **timesync** RHEL system role replaces the configuration of the specified given or detected provider service on the managed host. Consequently, all settings are lost if they are not specified in the playbook.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

--

 name: Managing time synchronization hosts: managed-node-01.example.com

- name: Configuring NTP with an internal server (preferred) and a public server pool as fallback

ansible.builtin.include_role:

name: rhel-system-roles.timesync

vars:

timesync_ntp_servers:

- hostname: time.example.com

trusted: yes prefer: yes iburst: yes

- hostname: 0.rhel.pool.ntp.org

pool: yes iburst: yes

The settings specified in the example playbook include the following:

pool: <yes/no>

Flags a source as an NTP pool rather than an individual host. In this case, the service expects that the name resolves to multiple IP addresses which can change over time.

iburst: yes

Enables fast initial synchronization.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.timesync/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

- Display the details about the time sources:
 - If the managed node runs the **chronyd** service, enter:

• If the managed node runs the **ntpd** service, enter:

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.time_sync/README.md file
- /usr/share/doc/rhel-system-roles/time_sync/ directory
- Are the rhel.pool.ntp.org NTP servers supported by Red Hat? (Red Hat Knowledgebase)

29.2. CONFIGURING TIME SYNCHRONIZATION OVER NTP WITH NTS BY USING THE TIMESYNC RHEL SYSTEM ROLE

The Network Time Protocol (NTP) synchronizes the time of a host with an NTP server over a network. By using the Network Time Security (NTS) mechanism, clients establish a TLS-encrypted connection to the server and authenticate NTP packets. In IT networks, services rely on a correct system time, for example, for security and logging purposes. By using the **timesync** RHEL system role, you can automate the configuration of Red Hat Enterprise Linux NTP clients in your network and keep the time synchronized over NTS.

Note that you cannot mix NTS servers with non-NTS servers. In mixed configurations, NTS servers are trusted and clients do not fall back to unauthenticated NTP sources because they can be exploited in man-in-the-middle (MITM) attacks. For further details, see the **authselectmode** parameter description in the **chrony.conf(5)** man page on your system.



WARNING

The **timesync** RHEL system role replaces the configuration of the specified given or detected provider service on the managed host. Consequently, all settings are lost if they are not specified in the playbook.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

 name: Managing time synchronization hosts: managed-node-01.example.com

- name: Configuring NTP with NTS-enabled servers

ansible.builtin.include_role:

name: rhel-system-roles.timesync

vars:

timesync_ntp_servers:

- hostname: ptbtime1.ptb.de

trusted: yes nts: yes prefer: yes iburst: yes

- hostname: ptbtime2.ptb.de

trusted: yes nts: yes iburst: yes

The settings specified in the example playbook include the following:

iburst: yes

Enables fast initial synchronization.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.timesync/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

- If the managed node runs the **chronyd** service:
 - 1. Display the details about the time sources:

2. For sources with NTS enabled, display information that is specific to authentication of NTP sources:

Verify that the reported cookies in the **Cook** column is larger than 0.

• If the managed node runs the **ntpd** service, enter:

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.time_sync/README.md file
- /usr/share/doc/rhel-system-roles/time_sync/ directory
- Are the rhel.pool.ntp.org NTP servers supported by Red Hat? (Red Hat Knowledgebase)

CHAPTER 30. CONFIGURING A SYSTEM FOR SESSION RECORDING BY USING RHEL SYSTEM ROLES

Use the **tlog** RHEL system role to record and monitor terminal session activities on your managed nodes in an automatic fashion. You can configure the recording to take place per user or user group by means of the **SSSD** service.

The session recording solution in the tlog RHEL system role consists of the following components:

- The tlog utility
- System Security Services Daemon (SSSD)
- Optional: The web console interface

30.1. CONFIGURING SESSION RECORDING FOR INDIVIDUAL USERS BY USING THE TLOG RHEL SYSTEM ROLE

Prepare and apply an Ansible playbook to configure a RHEL system to log session recording data to the **systemd** journal.

With that, you can enable recording the terminal output and input of a specific user during their sessions, when the user logs in on the console, or by SSH.

The playbook installs **tlog-rec-session**, a terminal session I/O logging program, that acts as the login shell for a user. The role creates an SSSD configuration drop file, and this file defines for which users and groups the login shell should be used. Additionally, if the **cockpit** package is installed on the system, the playbook also installs the **cockpit-session-recording** package, which is a **Cockpit** module that allows you to view and play recordings in the web console interface.

Prerequisites

- You have prepared the control node and the managed nodes.
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

- name: Deploy session recording

hosts: managed-node-01.example.com

tasks:

 name: Enable session recording for specific users ansible.builtin.include_role:

name: rhel-system-roles.tlog

vars:

tlog_scope_sssd: some

tlog users sssd:

- <recorded_user>

tlog_scope_sssd: <value>

The **some** value specifies you want to record only certain users and groups, not **all** or **none**.

tlog users sssd:: < list of users>

A YAML list of users you want to record a session from. Note that the role does not add users if they do not exist.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

1. Check the SSSD drop-in file's content:

cat cd /etc/sssd/conf.d/sssd-session-recording.conf

You can see that the file contains the parameters you set in the playbook.

- 2. Log in as a user whose session will be recorded.
- 3. Play back a recorded session.

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.tlog/README.md file
- /usr/share/doc/rhel-system-roles/tlog/ directory

30.2. EXCLUDING CERTAIN USERS AND GROUPS FROM SESSION RECORDING BY USING THE THE TLOG RHEL SYSTEM ROLE

You can use the **tlog_exclude_users_sssd** and **tlog_exclude_groups_sssd** role variables from the **tlog** RHEL system role to exclude users or groups from having their sessions recorded and logged in the **systemd** journal.

The playbook installs **tlog-rec-session**, a terminal session I/O logging program, that acts as the login shell for a user. The role creates an SSSD configuration drop file, and this file defines for which users and groups the login shell should be used. Additionally, if the **cockpit** package is installed on the system, the playbook also installs the **cockpit-session-recording** package, which is a **Cockpit** module that allows you to view and play recordings in the web console interface.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.

• The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
---
- name: Deploy session recording excluding users and groups hosts: managed-node-01.example.com tasks:
- name: Exclude users and groups ansible.builtin.include_role:
    name: rhel-system-roles.tlog
    vars:
    tlog_scope_sssd: all
    tlog_exclude_users_sssd:
    - jeff
    - james
    tlog_exclude_groups_sssd:
    - admins
```

tlog_scope_sssd: <value>

The value **all** specifies that you want to record all users and groups.

```
tlog_exclude_users_sssd: <user_list>
```

A YAML list of users user names you want to exclude from the session recording.

tlog_exclude_groups_sssd: <group_list>

A YAML list of groups you want to exclude from the session recording.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

1. Check the SSSD drop-in file's content:

cat cd /etc/sssd/conf.d/sssd-session-recording.conf

You can see that the file contains the parameters you set in the playbook.

- 2. Log in as a user whose session will be recorded.
- 3. Play back a recorded session.

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.tlog/README.md file
- /usr/share/doc/rhel-system-roles/tlog/ directory

CHAPTER 31. CONFIGURING VPN CONNECTIONS WITH IPSEC BY USING RHEL SYSTEM ROLES

With the **vpn** system role, you can configure VPN connections on RHEL systems by using Red Hat Ansible Automation Platform. You can use it to set up host-to-host, network-to-network, VPN Remote Access Server, and mesh configurations.

For host-to-host connections, the role sets up a VPN tunnel between each pair of hosts in the list of **vpn_connections** using the default parameters, including generating keys as needed. Alternatively, you can configure it to create an opportunistic mesh configuration between all hosts listed. The role assumes that the names of the hosts under **hosts** are the same as the names of the hosts used in the Ansible inventory, and that you can use those names to configure the tunnels.



NOTE

The **vpn** RHEL system role currently supports only Libreswan, which is an IPsec implementation, as the VPN provider.

31.1. CREATING A HOST-TO-HOST VPN WITH IPSEC BY USING THEVPN RHEL SYSTEM ROLE

You can use the **vpn** system role to configure host-to-host connections by running an Ansible playbook on the control node, which configures all managed nodes listed in an inventory file.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
name: Host to host VPN
hosts: managed-node-01.example.com, managed-node-02.example.com roles:
rhel-system-roles.vpn
vars:
vpn_connections:
hosts:
managed-node-01.example.com:
```

vpn_manage_firewall: true vpn_manage_selinux: true

managed-node-02.example.com:

This playbook configures the connection **managed-node-01.example.com-to-managed-node-02.example.com** by using pre-shared key authentication with keys auto-generated by the system role. Because **vpn_manage_firewall** and **vpn_manage_selinux** are both set to **true**, the **vpn** role uses the **firewall** and **selinux** roles to manage the ports used by the **vpn** role.

To configure connections from managed hosts to external hosts that are not listed in the inventory file, add the following section to the **vpn_connections** list of hosts:

vpn_connections:
 hosts:
 managed-node-01.example.com:
 <external_node>:
 hostname: <IP_address_or_hostname>

This configures one additional connection: managed-node-01.example.com-to-<external node>



NOTE

The connections are configured only on the managed nodes and not on the external node.

2. Optional: You can specify multiple VPN connections for the managed nodes by using additional sections within **vpn connections**, for example, a control plane and a data plane:

name: Multiple VPN
 hosts: managed-node-01.example.com, managed-node-02.example.com
 roles:
 rhel-system-roles.vpn
 vars:

vpn_connections:

name: control_plane_vpn

hosts:

managed-node-01.example.com:

hostname: 192.0.2.0 # IP for the control plane

managed-node-02.example.com:

hostname: 192.0.2.1
- name: data_plane_vpn

hosts:

managed-node-01.example.com:

hostname: 10.0.0.1 # IP for the data plane

managed-node-02.example.com:

hostname: 10.0.0.2

3. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

1. On the managed nodes, confirm that the connection is successfully loaded:

ipsec status | grep <connection_name>

Replace **<connection_name>** with the name of the connection from this node, for example **managed_node1-to-managed_node2**.



NOTE

By default, the role generates a descriptive name for each connection it creates from the perspective of each system. For example, when creating a connection between **managed_node1** and **managed_node2**, the descriptive name of this connection on **managed_node1** is **managed_node1-to-managed_node2** but on **managed_node2** the connection is named **managed_node2-to-managed_node1**.

- 2. On the managed nodes, confirm that the connection is successfully started:
 - # ipsec trafficstatus | grep <connection_name>
- 3. Optional: If a connection does not successfully load, manually add the connection by entering the following command. This provides more specific information indicating why the connection failed to establish:
 - # ipsec auto --add <connection_name>



NOTE

Any errors that may occur during the process of loading and starting the connection are reported in the /var/log/pluto.log file. Because these logs are hard to parse, manually add the connection to obtain log messages from the standard output instead.

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.vpn/README.md file
- /usr/share/doc/rhel-system-roles/vpn/ directory

31.2. CREATING AN OPPORTUNISTIC MESH VPN CONNECTION WITH IPSEC BY USING THE VPN RHEL SYSTEM ROLE

You can use the **vpn** system role to configure an opportunistic mesh VPN connection that uses certificates for authentication by running an Ansible playbook on the control node, which will configure all the managed nodes listed in an inventory file.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has sudo permissions on them.

• The IPsec Network Security Services (NSS) crypto library in the /etc/ipsec.d/ directory contains the necessary certificates.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

- name: Mesh VPN hosts: managed-node-01.example.com, managed-node-02.example.com, managed-node-03.example.com roles: - rhel-system-roles.vpn vpn_connections: - opportunistic: true auth method: cert policies: - policy: private cidr: default - policy: private-or-clear cidr: 198.51.100.0/24 - policy: private cidr: 192.0.2.0/24 - policy: clear

cidr: 192.0.2.7/32 vpn_manage_firewall: true vpn_manage_selinux: true

Authentication with certificates is configured by defining the **auth_method: cert** parameter in the playbook. By default, the node name is used as the certificate nickname. In this example, this is **managed-node-01.example.com**. You can define different certificate names by using the **cert_name** attribute in your inventory.

In this example procedure, the control node, which is the system from which you will run the Ansible playbook, shares the same classless inter-domain routing (CIDR) number as both of the managed nodes (192.0.2.0/24) and has the IP address 192.0.2.7. Therefore, the control node falls under the private policy which is automatically created for CIDR 192.0.2.0/24.

To prevent SSH connection loss during the play, a clear policy for the control node is included in the list of policies. Note that there is also an item in the policies list where the CIDR is equal to default. This is because this playbook overrides the rule from the default policy to make it private instead of private-or-clear.

Because **vpn_manage_firewall** and **vpn_manage_selinux** are both set to **true**, the **vpn** role uses the **firewall** and **selinux** roles to manage the ports used by the **vpn** role.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.vpn/README.md file
- /usr/share/doc/rhel-system-roles/vpn/ directory