Catch & Release

version 1.1

March 2021 update August 2021

Introduction

Catch & Release (C&R) is a collection of procedures that allow one to apply machine learning classification onto field videos. C&R's goal is to facilitate the creation of under-represented knowledge in machine learning in general, and experimental datasets for neural network image classification in particular. C&R allows anyone with a mobile phone and a laptop to create viable datasets for image classification (and to train state of the art convolutional neural networks with these datasets).

Furthermore, C&R can extract text from video. It can extract labels from video and use them as labels to generate image categories associated with the utterance. This is super useful to facilitate image labeling.

This software and the bali-26 dataset are the basis for the 'Return to Bali' project that explores machine learning to support the representation of ethnobotanical knowledge and practices in Central Bali.

Project website: https://realtechsupport.org/projects/return2bali.html Github repository: https://github.com/realtechsupport/return-to-bali

License

Attribution-NonCommercial-ShareAlike 4.0 International (CC BY-NC-SA 4.0). Cite this software project as follows: 'Catch&Release version1.1'

Platform Information

C&R runs on Linux and macOS under Python3 and Flask with Chromium / Chrome or Firefox.

C&R uses the PyTorch framework to train and test image classifiers and connects to the Google Speech API (free) for speech processing. Library versions and dependencies are given in the requirements file. C&R has been tested on a desktop (i7-4770 CPU with 16GB of memory) and a laptop (i7-3667 CPU with 8GB of memory) under Ubuntu (18.04 TLS under kernels 5.2.8 and 5.3.0) and under macOS (Catalina) with images sourced from .mp4 and .webm video (HD [1920 x 1080] at 30f/s; .mp4 H.264 encoded) from multiple (android OS) mobile phones and GoPro Hero 6 action cameras.

Recommended browser: Chromium on Ubuntu, Chrome on Mac.

Install Chromium on Ubuntu:

sudo apt install -y chromium-browser

Install the free Classic Cache Killer:

https://chrome.google.com/webstore/detail/classic-cache-killer/kkmknnnjliniefekpicbaaobdnjjikfp?hl=enSoftware Installation

Software installation

Clone the C&R repository on GitHub Open a terminal window and type:

git clone https://github.com/realtechsupport/c-plus-r.git

Cd to the c-plus-r directory and run the following commands to update your basic python environment:

chmod +x basics.sh sudo sh basics.sh

(This script just updates your Ubuntu installation and requires sudo to do so.)

Create a virtual environment:

python3 -m venv env

Activate the environment:

source ./env/bin/activate

Cd to the c-plus-r directory again. Install Requirements and Dependencies. (This may take about 30 minutes.)

pip3 install -r requirements.txt

Generate an STT key (optional)

While there are multiple providers of Speech to Text services, the most effective offering with the widest range of languages is at this moment provided by Google. If you want to make use of the text from video extraction you should obtain an access key to the Google Speech API. Creation of this key is free of charge and you can use it in this software at no cost as C&R operates within free limits of the API. However, you do require a google account in order to create the key. If that is not palatable, skip the sections that make use of the Speech API.

Instructions to generate a key (https://cloud.google.com/text-to-speech/docs/quickstart-protocol):

- 1. In the Cloud Console, go to the Create service account key page.
- 2. From the Service account list, select New service account.
- 3. In the Service account name field, enter a name.
- 4. Don't select a value from the Role list. No role is required to access this service.
- 5. Click Create.
- 6. Click Create without role. A JSON file that contains your key downloads to your computer.
- 7. Save the JSON file to the C&R project.

Other Speech to Text engines are available, but are not yet integrated into C&R. The key barrier at this point is limited availability of high quality language corpora in less popular languages. This is a major concern beyond C&R.

Launch C&R

Activate the virtual environment:

source ./env/bin/activate

Start C&R (in the c-plus-r directory):

on ubuntu: python3 main.py ubuntu chromium no-debug on mac: python3 main.py mac chrome no-debug

Specify all three items: OS, browser and debug mode. Supported OS: Ubuntu and Mac OS. Supported browsers: Chromium and Firefox (less stable). To run in debug mode replace 'no-debug' with 'debug'.

crtl + / ctrl – increase / decrease zoom factor.

Stop C&R

Stop the app from the terminal: ctrl-c Exit environment at the terminal: ctrl-d If you see browser errors ... clear the browsing history: ctrl-H

clear browsing data

clear data

Description of modules in C&R

Overview

The modules in C&R - with the exception of the last test case – are applicable to all field videos (.mp4 H264 as mentioned above).

When you run C&R for the first time, video samples, image samples and the trained models will be downloaded from pCloud automatically. You need these data files to run the examples.

Here is an overview of the flow of operations

```
> prepare videos

> capture text
> video annotation

> label images from video > check results

> bulk > remove outliers

> by audio label > add labeled images to collection
```

The 'Context' button gives you pertinent information on what the individual functions perform.

The next sections describe the individual modules on C&R.

Prepare field videos

This module allows one to chunk a long field video into smaller parts for processing. Supported formats are .mp4 and .webm. Select the video and choose the chunk size. It is suggested that segments do not exceed 3 minutes.

Chunked segments are saved to the C+R /tmp directory, and are deleted if you go back to start or exit the program. You can also download some sample videos to process and experiment with.

When you have some data ready, continue either onto the text extraction or the video voice-over modules.

Capture text from field video

Use this module to extract text from a field video.

First load a field video to locate a section you want to extract text from, then reload to capture the text. This module requires an access code for the Google Speech API (key for capture text).

If you add a search term, text from video sections that contain that term will be listed separately. If the video is shorter than 1 minute, reduce chunk length.

Reducing the confidence level to below 0.9 increases detection chances and false positives.

This module may take several minutes to complete. It is best to limit the difference between start and end times to a few minutes.

Add voice-over to field video

Caveat – Audio recording can be tricky.

Use this module to replace the field audio with a new audio file. This can be helpful in the event an expert wishes to annotate a field video.

1) Select a video for voiceover (choose file)

Once the file is loaded you will see the file name when the mouse hovers over the 'choose file' button. You will re-select the video file (or change to a different one) before after the audio tests below.

2) Select and set an audio input

Plug in a microphone if you have one. Click 'get-mic-info'. This function will show in the terminal window all the available recording devices on your computer. You will see something like this:

```
* index: 2 alsa.device = "0"
alsa.card = "2"
device.product.name = "Webcam C600"
index: 6 alsa.device = "0"
alsa.card = "3"
device.product.name = "AT2020 USB "
```

The asterisk denotes the current active microphone index (a webcam C600 device). Take note of the alsa card and device numbers of the microphone you want to use. For example, the AT2020 usb microphone is on card number 3 with device number 0.

3) Test the audio setup

Enter the card and device number of the microphone you want to use. Then click 'check-audio' and record a sample (speech). The program will record three seconds of audio from the microphone you selected and play it back after the three second recording event. If you do not hear your recording, something is amiss with either the microphone input, your microphone choice or the speakers. Background noise can negatively impact speech detection. Do not continue until you hear a good test recording of your voice with your selected input device.

Aside - 'Remove-old-audio' will delete old recording assets from previous recording sessions.

4) Load, segment and voice-over

Once the microphone is setup and tested, you can proceed to load, segment and voice-over the video. Set the microphone card and device again and load the target video (from samples, tmp or annotate folder) to identify the spot on which you want to add voice-over. Use the in video controls to move around the video, if necessary. Set start and end times to define the interval in which you will add a voice-over. Make sure the end time is greater than the start time and less than the length of the video.

Then segment the video. This can take a few minutes as the .mp4 file will be re-encoded. The terminal window shows the progress. When the segmentation is complete, the silent segmented video will autoplay. Use the video controls to stop the video and rewind to the start (move the dot in the display timeline to the left).

Turn off your speakers.

Then click voice-over and comment on the video with appropriate key terms – these are the terms that the subsequent module will search for in order to associate text with image.

You can process the newly created voice-over video (stored in the annotate folder) to labeled images with the next module.

Here is a link to a video that demonstrates the annotation procedure: https://filedn.com/lqzjnYhpY3yQ7BdfTulG1yY/c%2Br tutorials/howto-annotate.mp4 (If you cannot hear the audio track online, download the video to your computer.)

Troubleshooting video voice-over

Speech to text

Make sure your voiced-over video has a good audio track. Load the video to check. If you cannot clearly hear the audio or voice over, the speech to text system will not be effective.

The current speech to text system has substantial limitations. Some words will not be detected. (Results are printed to the terminal window, and if you see 'wordcollection: []', then the key term was not detected (and the subsequent quality control page will show no images). Moreover, the system can be fooled if you use compound words (such as 'banana tree') into creating two categories instead of one, for example.

Use simple terms. If you want to detect more than one category via this module, run it multiple times, each time with a different key term.

You can rename incorrectly or inadequately labeled categories/folders manually in the images folder after the labeling, if required. If the speech system does not pick up the voice in the field video, you can go to the 'add voice-over' module and post-annotate the video. Alternatively, you can set the category manually with any ASCII name, select 'bulk label' a selected video file and then manually remove inappropriate images from the resultant folder.

USB microphones

Most any microphone will work, but a good microphone will produce superior results. Recommended: AT2020 (Audio-Technica AT2020 Cardioid Condenser).

General audio troubleshooting

Exit C&R and check audio settings. You can type 'alsamixer' at a terminal prompt to check if your microphone inputs are muted.

Label images from field video

Use this module to create labels from field videos or from your voice-over additions. Creating labels directly from voice input is based on an invention (030-7278 Expertise collection with action cameras) by the author. It makes use of the synchronicity between image and audio streams in video formats and uses the synchronicity to associate an image with a label.

Load the video to check, just in case. There are two options:

A - Label images with key terms from audio track (label by audio)

In this case you will select a single key term and the number of images per utterance. Then set a confidence level for the speech to text API and the language spoken in the video. Select your key file to access the Speech API. If you want to search for multiple key terms, repeat the process above with a new term.

B - *Label all images in the video with a given term (bulk label)*

This option is the easiest to use and does not require speech recognition. In this case, all images generated from a chosen video will be bulk labeled with a given category / folder name. Set the frame rate (number of images to be extracted per second).

When the process has completed, click 'check the results' to open the subsequent module for quality control and collection creation.

Here is a link to a video that demonstrates the image labeling. procedure: https://filedn.com/lqzjnYhpY3yQ7BdfTulG1yY/c%2Br tutorials/howto-labelbyvoice.mp4 (If you cannot hear the audio track online, download the video to your computer.)

Quality control, archiving, sharing

This module allows you to control the quality of the images created from the field videos (both images created by bulk labeling and by audio label). The purpose of this module is to combine automated and human quality control, to remove out of context and low quality images and retain only high quality images for subsequent classification. High quality images will enable better classifier training and performance. The degree to which aesthetics matter for the classifier is not entirely clear. Sharpness is important, but poorly chosen backgrounds and offensive content might not matter for the classifier. The human image organizer plays a significant role in the compilation of these image sets. This is a new field of design.

The following options are available in this module:

Remove-selected

Manually select images for removal. Select (multiple) images with a left click, confirm and then click 'remove- selected'

Remove-divergent

Select a single image as reference with left click, confirm, and then click 'remove-selected'. Hit <enter> to update the page after the removal process has completed.

Images that deviate from this selected reference in luminosity beyond the set min /max levels (under and overexposure) will be deleted. Other images that deviate structurally (different visual contexts or blurry images) beyond the set similarity measure will be deleted.

Once the image set has been reviewed you can add the resultant set to the collection. Once you have several collections / categories, you can archive the collection (compress the data sets) or, if something is amiss, delete everything and start again.

The final archived (compressed) collection will be the input to the classification procedures as described in the next module.

Aside

Each image category should have at least 1500 viable images in order to offer enough information to neural net classifiers. Visually complex categories require substantially more than that. Collections with very many categories have higher collection size requirements. More information on these dependencies forthcoming.