


Kernel Module

Krerk Piromsopa, Ph. D.

What is Kernel Module?


- Pieces of code that can be loaded and unloaded into the kernel upon demand.
- Extend the functionality of the kernel without rebooting the system.
 - o Hardware Drivers
 - o Special API
 - o etc.

Linux kernel diagram



© 2007-2009 Constantine Shulyupin http://www.MakeLinux.net/kernel/diagram

insmod



Caulion.

- o No standard C Lib
 - o no printf, scanf, gets, etc..
 - e no gdb (or any debugging tool)
- o Use kernel functions only
 - o printk

Print

- o Usage
 printk([LEVEL] const char *format_string, ...);
- Example printk(KERN_ERR "something went wrong, return code: %d\n",ret);

Level:

KERN_EMERG

KERN_ALERT

KERN_CRIT

KERN_ERR

KERN_ERR

KERN_NOTICE
KERN_INFO
KERN_DEBUG
KERN_DEFAULT
KERN_CONT

Let's build our first Kernel Module

Dummy Kernel Module

```
#include <linux/module.h>
#include <linux/kernel.h>
MODULE_LICENSE("GPL");
MODULE_AUTHOR("KRERK PIROMSOPA, PH.D. <Krerk.P@chula.ac.th>");
MODULE_DESCRIPTION("CP OS API");
int init_module(void)
        printk(KERN_INFO "CUCPMOD: init\n");
         * non 0 - means init_module failed
        return 0;
void cleanup_module(void)
        printk(KERN_INFO "CUCPMOD: cleanup\n");
                              CPMOD.C
```

Makefile

About Debian

Don't forget to install linux-kernel-headers (linux-libe-dev)

Common Commands

- Ismod Show the status of modules in the Linux Kernel
- insmod Simple program to insert a module into the Linux Kernel insmod [filename] [module options...]
- rmmod Simple program to remove a module from the Linux Kernel rmmod [-f] [-s] [-v] [modulename]
- modprobe Add and remove modules from the Linux Kernel modprobe [-v] [-V] [-C config-file] [-n] [-i] [-q] [-b] [modulename] [module parameters...]
- modinfo Show information about a Linux Kernel module modinfo [-0] [-F field] [-k kernel] [modulename|filename...]
- o dmesg print or control the kernel ring buffer







Device Drivers








LIMUX DEVICES

- a Device File
 - an interface for a device driver in a file system (like an ordinary file)
 - O Use file permissions for device permissions
 - o Use file operations for accessing device

EXOMMELE

A write to /dev/lpo will print to an associated printer



Just for fun.

- o Open a terminal.
- O Use "who" command to figure out the pseudo terminal device file.
- o Try "echo data > /dev/pts/0"

Character Devices

- o sending and receiving single characters
- o Cannot seek
- o eg. Serial/Parallel Port

Block Devices

- o sending entire blocks of data
- o Can seek
- ø eg. Disk, USB Camera

Major and Minor Device No.

- Devices are divided into sets called major device numbers.
- same major number means same driver

```
brw-rw---- 1 root disk 8, 0 Nov 12 14:18 /dev/sda

brw-rw---- 1 root disk 8, 1 Nov 12 14:18 /dev/sda1

brw-rw---- 1 root disk 8, 2 Nov 12 14:18 /dev/sda2

brw-rw---- 1 root disk 8, 5 Nov 12 14:18 /dev/sda5

crw----- 1 krerk tty 136, 0 Nov 23 22:32 /dev/pts/0
```

To create a device

- o Try mknod /dev/osinfo c 250 o
- o This will create

crw-r--r-- 1 root root 250, 0 Nov 23 06:51 /dev/osinfo

File Operations

```
struct file_operations {
  struct module *owner;
  loff_t(*llseek) (struct file *, loff_t, int);
  ssize_t(*read) (struct file *, char __user *, size_t, loff_t *);
  ssize_t(*aio_read) (struct kiocb *, char __user *, size_t, loff_t);
  ssize_t(*write) (struct file *, const char __user *, size_t, loff_t *);
  ssize_t(*aio_write) (struct kiocb *, const char __user *, size_t, loff_t);
  int (*readdir) (struct file *, void *, filldir_t);
  unsigned int (*poll) (struct file *, struct poll_table_struct *);
  int (*ioctl) (struct inode *, struct file *, unsigned int, unsigned long);
  int (*mmap) (struct file *, struct vm_area_struct *);
  int (*open) (struct inode *, struct file *);
 int (*flush) (struct file *);
  int (*release) (struct inode *, struct file *);
  int (*fsync) (struct file *, struct dentry *, int datasync);
  int (*aio_fsync) (struct kiocb *, int datasync);
  int (*fasync) (int, struct file *, int);
  int (*lock) (struct file *, int, struct file_lock *);
  ssize_t(*readv) (struct file *, const struct iovec *, unsigned long, loff_t *);
  ssize_t(*writev) (struct file *, const struct iovec *, unsigned long, loff_t *);
  ssize_t(*sendfile) (struct file *, loff_t *, size_t, read_actor_t, void __user *);
  ssize_t(*sendpage) (struct file *, struct page *, int, size_t, loff_t *, int);
  unsigned long (*get_unmapped_area) (struct file *, unsigned long, unsigned long, unsigned long,
unsigned long);
```

};

see Linux/fs.h for more details

7000

- o Implement only related operations
- a Leave others to NULL


A Deller way

o Use C99 syntax for convenient

```
struct file_operations fops = {
    .read = device_read,
    .write = device_write,
    .open = device_open,
    .release = device_release
};
```

TO register device

- o int
 register_chrdev(unsig
 ned int major, const
 char *name, struct
 file_operations
 *fops);
- o unregister_chrdev(un signed int major, const char *name);



see Linux/fs.h for more details

Example: Read-only char device

More about c

For security, try to use static modifiers for functions, variables in C to make it local to your kernel module.

More about driver

- To avoid module from being unloaded (rmmod) while using,
 - On every access to module (e.g. device_open), please lock the module with try_module_get(THIS_MODULE);
 - On release, release the module with module_put(THIS_MODULE);

Lees have fun

G1 Dunning Mod

- Make a dummy driver that will do the following:
 - o On initial, display

 KERN_INFO "CPMOD: init"
 - o On cleanup, display

 KERN_INFO "CPMOD: cleanup\n"

G2. Char Driver

- © Create osinfo driver (minor no. 0) (at /dev/osinfoa).
- Reading from this device file will display:

```
0:CP ENG CU OS 2018S1 - Instructors
1:          Krerk Piromsopa, Ph. D.
2:          Kunwadee Sripanidkulchai, Ph. D.
3:          Thongchai Rojkangsadan
4:          Veera Muangsin, Ph.D.
```

O3. Adv. Char Driver

- Modify driver in Q2 to display to detect minor no.
- If minor no. == 1, reading from the device will display names of your team members.

0:CP ENG CU OS 2018S1 - Students 1: Krerk Piromsopa, Ph. D.

Hint: To detect minor number, use static inline unsigned iminor(const struct inode *inode)

04. CPU model driver

O Use the following function (taken from arch/x86/include/asm/processor.h) to create a device driver for extracting cpuid (vendor ID, features, serial no.).

For more details, see https://en.wikipedia.org/wiki/CPUID

More Hint.

- a Kernel supports limited string function.
- e For Q4, try
 - o suprintf, strucat.
- See Kernel API (https://www.kernel.org/doc/htmldocs/kernel-api/) for more details.

demonstration

Cerences

- a https://www.kernel.org/
 - * Kernel API https://www.kernel.org/doc/htmldocs/kernel-api/
- http://elixir.free-electrons.com/ linux/latest/source