

Program Directory for IBM Enterprise COBOL for z/OS

V06.05.00

Program Number 5655-EC6

FMIDs HADB650, JADB651, JADB652, JADB65H

for Use with z/OS

Document Date: June 2025

Before using this information and the product it supports, be sure to read the general information under 7.0, "Notices" on page 27.

Contents

	Introduction					
1.1	Enterprise COBOL Description	 	 			. 1
1.2	Enterprise COBOL FMIDs	 	 			. 2
	Program Materials					
2.1						
	Optional Machine-Readable Material					
	Program Publications					
	3.1 Online documentation					
	.3.2 PDF documentation					
	.3.3 Optional Program Publications					
	Program Source Materials					
2.5	Publications Useful During Installation	 	 			. 5
	Program Support					
	Program Services					
	Preventive Service Planning					
3.3	Statement of Support Procedures	 	 			. 6
	Program and Service Level Information					
	Program Level Information					
4.2	Service Level Information	 	 			. 8
- 0	Installation Benedictored Operations					4.
	Installation Requirements and Considerations					
	Driving System Requirements					
	1.1.1 Machine Requirements					
	Target System Requirements					
	2.1 Machine Requirements					
	.2.2 Programming Requirements					
3	5.2.2.1 Installation Requisites					
	5.2.2.2 Operational Requisites					
	5.2.2.3 Toleration/Coexistence Requisites					
	5.2.2.4 Incompatibility (Negative) Requisites					
5	2.2.3 DASD Storage Requirements					
	FMIDs Deleted					
	Special Considerations					
J. 4	opediai Odiisideralidiis	 	 		•	1 /
6 N	Installation Instructions					1.9
	Installing Enterprise COBOL					
	5.1.1 SMP/E Considerations for Installing Enterprise COBOL					
	5.1.2 SMP/E Options Subentry Values					
J	The Chin / E Options Supplied Values	 • •	 	٠.	•	

6	6.1.3 Sample Jobs	10
U	6.1.4 Run REPORT MISSINGFIX	20
6	6.1.5 Set up ISPF Editor Macro (Optional)	21
6	6.1.6 Allocate and Initialize the SMP/E CSI (Optional)	21
	6.1.7 Perform SMP/E RECEIVE	
6	6.1.8 Allocate SMP/E Target and Distribution Libraries	22
6	6.1.9 Allocate, create and mount ZFS Files (Optional)	22
6	6.1.10 Allocate File System Paths	23
6	6.1.11 Create DDDEF Entries	23
6	6.1.12 Perform SMP/E APPLY	23
6	6.1.13 Run the Installation Verification Programs	25
6	6.1.14 Perform SMP/E ACCEPT	25
6.2	Activating Enterprise COBOL	26
6	6.2.1 Running Enterprise COBOL from Unix System Services	26
	6.2.2 Product Customization	
7.0	Notices	27
7.1	Trademarks	27
nea	ader's Comments	20
Fi	gures	
;	guios	
	Program File Content	2
1.	9	
1. 2.	Basic Material	4
1. 2. 3.	Basic Material Publications Useful During Installation	4 5
1. 2. 3. 4.	Basic Material Publications Useful During Installation Component IDs	4 5 6
1. 2. 3. 4. 5.	Basic Material Publications Useful During Installation Component IDs Driving System Software Requirements	4 5 6 11
1. 2. 3. 4. 5. 6.	Basic Material Publications Useful During Installation Component IDs Driving System Software Requirements Target System Mandatory Installation Requisites	4 5 6 11 12
1. 2. 3. 4. 5. 6. 7.	Basic Material Publications Useful During Installation Component IDs Driving System Software Requirements Target System Mandatory Installation Requisites Target System Mandatory Operational Requisites	4 5 6 11 12 12
1. 2. 3. 4. 5. 6. 7.	Basic Material Publications Useful During Installation Component IDs Driving System Software Requirements Target System Mandatory Installation Requisites Target System Mandatory Operational Requisites Total DASD Space Required by Enterprise COBOL	4 5 6 11 12 12 14
1. 2. 3. 4. 5. 6. 7. 8. 9.	Basic Material Publications Useful During Installation Component IDs Driving System Software Requirements Target System Mandatory Installation Requisites Target System Mandatory Operational Requisites Total DASD Space Required by Enterprise COBOL Storage Requirements for Enterprise COBOL Target Libraries	4 5 6 11 12 12 14 16
1. 2. 3. 4. 5. 6. 7. 8. 9.	Basic Material Publications Useful During Installation Component IDs Driving System Software Requirements Target System Mandatory Installation Requisites Target System Mandatory Operational Requisites Total DASD Space Required by Enterprise COBOL Storage Requirements for Enterprise COBOL Target Libraries Enterprise COBOL File System Paths	4 5 6 11 12 12 14 16 16
1. 2. 3. 4. 5. 6. 7. 8. 9. 10.	Basic Material Publications Useful During Installation Component IDs Driving System Software Requirements Target System Mandatory Installation Requisites Target System Mandatory Operational Requisites Total DASD Space Required by Enterprise COBOL Storage Requirements for Enterprise COBOL Target Libraries Enterprise COBOL File System Paths Storage Requirements for Enterprise COBOL Distribution Libraries	4 5 6 11 12 12 14 16 16
1. 2. 3. 4. 5. 6. 7. 8. 9.	Basic Material Publications Useful During Installation Component IDs Driving System Software Requirements Target System Mandatory Installation Requisites Target System Mandatory Operational Requisites Total DASD Space Required by Enterprise COBOL Storage Requirements for Enterprise COBOL Target Libraries Enterprise COBOL File System Paths Storage Requirements for Enterprise COBOL Distribution Libraries SMP/E Options Subentry Values	4 5 6 11 12 14 16 16 16

1.0 Introduction

This program directory is intended for system programmers who are responsible for program installation and maintenance. It contains information about the material and procedures associated with the installation of IBM Enterprise COBOL for z/OS. This publication refers to IBM Enterprise COBOL for z/OS as Enterprise COBOL.

The Program Directory contains the following sections:

- 2.0, "Program Materials" on page 3 identifies the basic program materials and documentation for Enterprise COBOL.
- 3.0, "Program Support" on page 6 describes the IBM support available for Enterprise COBOL.
- 4.0, "Program and Service Level Information" on page 8 lists the APARs (program level) and PTFs (service level) that have been incorporated into Enterprise COBOL.
- 5.0, "Installation Requirements and Considerations" on page 10 identifies the resources and considerations that are required for installing and using Enterprise COBOL.
- 6.0, "Installation Instructions" on page 18 provides detailed installation instructions for Enterprise COBOL. It also describes the procedures for activating the functions of Enterprise COBOL, or refers to appropriate publications.

Before installing Enterprise COBOL, read the *CBPDO Memo To Users* and the *CBPDO Memo To Users Extension* that are supplied with this program in softcopy format and this program directory; then keep them for future reference. Section 3.2, "Preventive Service Planning" on page 6 tells you how to find any updates to the information and procedures in this program directory.

Enterprise COBOL is supplied in a Custom-Built Product Delivery Offering (CBPDO, 5751-CS3). The program directory that is provided in softcopy format on the CBPDO tape is identical to the one included with your order. All service and HOLDDATA for Enterprise COBOL are included on the CBPDO tape.

Do not use this program directory if you install Enterprise COBOL with a SystemPac or ServerPac. When you use one of those offerings, use the jobs and documentation supplied with the offering. The offering will point you to specific sections of this program directory as needed.

1.1 Enterprise COBOL Description

IBM Enterprise COBOL for z/OS is an advanced optimizing compiler that helps clients create and maintain COBOL applications that execute on IBM z/OS and take full advantage of the latest IBM Z hardware features.

New capabilities in Enterprise COBOL for z/OS 6.5 include:

• Support for the latest IBM z17 architecture. Enterprise COBOL 6.5 introduces the ARCH(15) option allowing you to generate application code that leverages the latest IBM z17 hardware without the need

© Copyright IBM Corp. 2025

for any source code changes. Enterprise COBOL for z/OS 6.5 is designed to use the IBM z17 vector packed-decimal enhancement facility 3 to help reduce CPU resources for applications that use the NUMCHECK compiler option, and the IBM z17 vector enhancement facility 3 to help reduce CPU and speed up binary computations.

- · Support for a modern, unstructured NoSQL database (VSAMDB). NoSQL databases enable the storage and querying of data outside the traditional structures found in relational databases. Enterprise COBOL 6.5 supports reading, writing, updating, and deleting of JSON documents in a VSAMDB file using COBOL file processing statements. This function is compatible with IBM EzNoSQL for z/OS.
- Support for creating User-defined type definitions that act like templates that can be reused, using the TYPE clause, to define new data items that acquire all the characteristics of the user-defined type. User-defined types are elementary or group items defined in the WORKING-STORAGE, LOCAL-STORAGE, LINKAGE, or FILE section of a program, using the TYPEDEF clause.

1.2 Enterprise COBOL FMIDs

Enterprise COBOL consists of the following FMIDs:

HADB650 JADB651 JADB652 JADB65H

2.0 Program Materials

An IBM program is identified by a program number. The program number for Enterprise COBOL is 5655-EC6.

Basic Machine-Readable Materials are materials that are supplied under the base license and are required for the use of the product.

The program announcement material describes the features supported by Enterprise COBOL. Ask your IBM representative for this information if you have not already received a copy.

2.1 Basic Machine-Readable Material

The distribution medium for this program is physical media or downloadable files. This program is in SMP/E RELFILE format and is installed by using SMP/E. See 6.0, "Installation Instructions" on page 18 for more information about how to install the program.

You can find information about the physical media for the basic machine-readable materials for Enterprise COBOL in the *CBPDO Memo To Users Extension*.

Figure 1 describes the program file content for Enterprise COBOL. You can refer to the *CBPDO Memo To Users Extension* to see where the files reside on the tape.

Notes:

- 1. The data set attributes in this table must be used in the JCL of jobs that read the data sets. However, because the data sets are in IEBCOPY unloaded format, their actual attributes might be different.
- 2. If any RELFILEs are identified as PDSEs, ensure that SMPTLIB data sets are allocated as PDSEs.

Figure 1 (Page 1 of 2). Program File Content				
Name	O R G	R E C F	L R E C L	BLK SIZE
SMPMCS	SEQ	FB	80	6400
IBM.HADB650.F1	PDS	FB	80	8800
IBM.HADB650.F2	PDSE	U	0	6144
IBM.HADB650.F3	PDS	FB	80	8800
IBM.JADB651.F1	PDSE	U	0	6144
IBM.JADB651.F2	PDS	FB	80	8800

© Copyright IBM Corp. 2025

Figure 1 (Page 2 of 2). Program File Content				
		R	L	
		Ε	R	
	0	С	E	
	R	F	С	BLK
Name	G	M	L	SIZE
IBM.JADB652.F1	PDSE	U	0	6144
IBM.JADB65H.F1	PDS	VB	255	27998

2.2 Optional Machine-Readable Material

No optional machine-readable materials are provided for Enterprise COBOL.

2.3 Program Publications

The following sections identify the basic publications for Enterprise COBOL.

2.3.1 Online documentation

Online documentation is available in IBM Documentation (https://www.ibm.com/docs/cobol-zos/6.5).

2.3.2 PDF documentation

Documentation is provided for download in PDF from IBM Documentation. See PDF version documentation (https://www.ibm.com/docs/cobol-zos/6.5?topic=pdf-version-documentation) for details or you can contact your IBM representative or IBM Business Partner.

Figure 2 (Page 1 of 2). Basic Material					
Publication Title	Form Number	Media Format			
Licensed Program Specifications	GI13-4532-04	https://www.ibm.com/docs/cobol-zos/6.5			
Language Reference	SC27-8713-04	https://www.ibm.com/docs/cobol-zos/6.5			
IBM Enterprise COBOL for z/OS Customization Guide	SC27-8712-04	https://www.ibm.com/docs/cobol-zos/6.5			
Messages and Codes	SC27-4648-03	https://www.ibm.com/docs/cobol-zos/6.5			
Migration Guide	GC27-8715-04	https://www.ibm.com/docs/cobol-zos/6.5			
Performance Tuning Guide	SC27-9202-03	https://www.ibm.com/docs/cobol-zos/6.5			
Programming Guide	SC27-8714-04	https://www.ibm.com/docs/cobol-zos/6.5			

Figure 2 (Page 2 of 2). Basic Material					
Publication Title	Form Number	Media Format			
What's New	SC31-5708-01	https://www.ibm.com/docs/cobol-zos/6.5			

2.3.3 Optional Program Publications

No optional publications are provided for Enterprise COBOL.

2.4 Program Source Materials

No program source materials or viewable program listings are provided for Enterprise COBOL.

2.5 Publications Useful During Installation

You might want to use the publications listed in Figure 3 during the installation of Enterprise COBOL.

Figure 3. Publications Useful During In	Figure 3. Publications Useful During Installation					
Publication Title	Form Number	Media Format				
IBM SMP/E for z/OS User's Guide	SA23-2277-02	https://www.ibm.com/docs/en/zos/3.1.0?topic=zos-sm pe				
IBM SMP/E for z/OS Commands	SA23-2275-05	https://www.ibm.com/docs/en/zos/3.1.0?topic=zos-sm pe				
IBM SMP/E for z/OS Reference	SA23-2276-02	https://www.ibm.com/docs/en/zos/3.1.0?topic=zos-sm pe				
IBM SMP/E for z/OS Messages, Codes, and Diagnosis	GA32-0883-04	https://www.ibm.com/docs/en/zos/3.1.0?topic=zos-sm pe				

3.0 Program Support

This section describes the IBM support available for Enterprise COBOL.

3.1 Program Services

Contact your IBM representative for specific information about available program services.

3.2 Preventive Service Planning

Before you install Enterprise COBOL, make sure that you review the PSP bucket information for IBM Z products document https://www.ibm.com/support/pages/node/7127792. It contains the latest information concerning the installation of IBM products, including the latest service recommendations and cross-product dependencies. This information was previously available in traditional PSP buckets, which are no longer published for IBM Z products.

For support, access the Software Support Website at https://www.ibm.com/mysupport/

3.3 Statement of Support Procedures

For installation and technical support, open a new case or review already-opened cases at the IBM Support (http://www.ibm.com/support) website.

Conduct a search for known problems (https://www.ibm.com/support/pages/mustgather-read-first-problems-encountered-enterprise-cobol-zos#searchforknownproblemshint) before engaging support.

- IBM Business Partners should contact their local IBM office and field technical support specialist for technical marketing assistance.
- Business Partners can find installation and technical support from the IBM Support website.
 Installation and technical support is also available from PartnerWorld Contact Services.
 Support Line is also available for technical support.

Figure 4 identifies the component IDs (COMPID) for Enterprise COBOL.

Figure 4 (Pag	Figure 4 (Page 1 of 2). Component IDs					
FMID	COMPID	Component Name	RETAIN Release			
HADB650	5655EC600	Enterprise COBOL Base	650			
JADB651	5655EC600	Enterprise COBOL US English	651			

Figure 4 (Pag	Figure 4 (Page 2 of 2). Component IDs					
FMID	COMPID	Component Name	RETAIN Release			
JADB652	5655EC600	Enterprise COBOL Japanese	652			
JADB65H	5655EC600	Enterprise COBOL HFS	65H			

4.0 Program and Service Level Information

This section identifies the program and relevant service levels of Enterprise COBOL. The program level refers to the APAR fixes that have been incorporated into the program. The service level refers to the PTFs that have been incorporated into the program.

4.1 Program Level Information

The following APAR fixes against Enterprise COBOLV06.04.00 have been incorporated into this release. They are listed by FMID.

• FMID HADB640

PH48251	PH51749	PH55932	PH59211	PH63227
PH48252	PH51752	PH56112	PH59549	PH63277
PH48254	PH51837	PH56142	PH59594	PH63384
PH48255	PH51942	PH56146	PH59733	PH63477
PH48453	PH51962	PH56204	PH59980	PH63507
PH48662	PH51963	PH56502	PH60077	PH63552
PH48663	PH51964	PH56560	PH60651	PH63727
PH48664	PH51965	PH56724	PH60763	PH63799
PH48665	PH51966	PH56946	PH60896	PH63954
PH48666	PH51967	PH57297	PH60940	PH63992
PH48667	PH51968	PH57321	PH60941	PH64118
PH48668	PH51969	PH57328	PH61202	PH64348
PH48669	PH52463	PH57329	PH61439	PH64349
PH48670	PH52706	PH57397	Ph61502	PH64490
PH48671	PH52707	PH57398	PH61671	PH64491
PH48672	PH52708	PH57400	PH61700	PH64736
PH48673	PH53458	PH57688	PH61979	PH64890
PH48674	PH53631	PH57690	PH61980	PH64892
PH48688	PH53969	PH58188	PH61981	PH65076
PH49122	PH53970	PH58237	PH62042	PH65097
PH49330	PH53971	PH58372	PH62425	PH65391
PH49967	PH54210	PH58384	PH62478	PH65392
PH50294	PH54547	PH58596	PH62526	PH65716
PH50295	PH55203	PH58660	PH62865	PH66014
PH50296	PH55251	PH58661	PH62890	PH66054
PH50297	PH55397	PH58662	PH63024	PH66063
PH50298	PH55843	PH58988	PH63139	PH66209
PH50299	PH55881	PH58933	PH63224	PH66210
PH50300	PH55895			

4.2 Service Level Information

No PTFs against this release of Enterprise COBOL have been incorporated into the product package.

You can also receive the latest HOLDDATA, then add the

FIXCAT(IBM.TargetSystem-RequiredService.Enterprise-COBOL.*).

operand on your APPLY CHECK command. This will allow you to review the recommended and critical service that should be installed with your FMIDs.

5.0 Installation Requirements and Considerations

The following sections identify the system requirements for installing and activating Enterprise COBOL. The following terminology is used:

- Driving system: the system on which SMP/E is executed to install the program.
 - The program might have specific operating system or product level requirements for using processes, such as binder or assembly utilities during the installation.
- Target system: the system on which the program is configured and run.
 - The program might have specific product level requirements, such as needing access to the library of another product for link-edits. These requirements, either mandatory or optional, might directly affect the element during the installation or in its basic or enhanced operation.

In many cases, you can use a system as both a driving system and a target system. However, you can make a separate IPL-able clone of the running system to use as a target system. The clone must include copies of all system libraries that SMP/E updates, copies of the SMP/E CSI data sets that describe the system libraries, and your PARMLIB and PROCLIB.

Use separate driving and target systems in the following situations:

- When you install a new level of a product that is already installed, the new level of the product will
 replace the old one. By installing the new level onto a separate target system, you can test the new
 level and keep the old one in production at the same time.
- When you install a product that shares libraries or load modules with other products, the installation
 can disrupt the other products. By installing the product onto a separate target system, you can
 assess these impacts without disrupting your production system.

5.1 Driving System Requirements

This section describes the environment of the driving system required to install Enterprise COBOL.

5.1.1 Machine Requirements

The driving system can run in any hardware environment that supports the required software.

5.1.2 Programming Requirements

10

Figure 5. Driving System Software Requirements						
Program Number	Product Name	Minimum VRM	Minimum Service Level will satisfy these APARs	Included in the shipped product?		
5650-ZOS	z/OS	V02.05.00 or higher	N/A	No		

Note: SMP/E is a requirement for Installation and is an element of z/OS but can also be ordered as a separate product, 5655-G44, minimally V03.06.00.

Note: Installation might require migration to new z/OS releases to be service supported. See https://www.ibm.com/support/pages/lifecycle/details/?q45=S928720R89459D48.

If you plan on installing the Japanese FMID JADB652 then ensure you have codepage 939 which is the Latin-based Japanese codepage that displays both upper and lower case characters correctly. Mixed case character usage is required for the sample IGYWDDEF, IGYWZFS, and IGYISMKD jobs; therefore, codepage 939 is required to run these jobs from the driving system.

Enterprise COBOL is installed into a file system, either HFS or zFS. Before installing Enterprise COBOL, you must ensure that the target system file system data sets are available for processing on the driving system. OMVS must be active on the driving system and the target system file data sets must be mounted on the driving system.

If you plan to install Enterprise COBOL in a zFS file system, this requires that zFS be active on the driving system. Information on activating and using zFS can be found in z/OS Distributed File Service zSeries File System Administration, SC24-5989.

5.2 Target System Requirements

This section describes the environment of the target system required to install and use Enterprise COBOL.

Enterprise COBOL installs in the z/OS (Z038) SREL.

5.2.1 Machine Requirements

Enterprise COBOL V06.05.00 will run on and generates code that runs on the following IBM Z servers:

- IBM z17
- IBM z16 Models A01 and A02
- IBM z15 Models T01 and T02
- IBM z14 Models M01-M05
- IBM z14 Model ZR1
- IBM z13

IBM z13s

5.2.2 Programming Requirements

5.2.2.1 Installation Requisites: Installation requisites identify products that are required and must be present on the system or products that are not required but should be present on the system for the successful installation of this product.

Mandatory installation requisites identify products that are required on the system for the successful installation of this product.

Figure 6. Targe	Figure 6. Target System Mandatory Installation Requisites							
Program Number	Product Name	Minimum VRM	Minimum Service Level will satisfy these APARs	Included in the shipped product?				
5650-ZOS	z/OS	V02.05.00 or higher	N/A	No				

Note: Installation might require migration to new z/OS releases to be service supported. See https://www.ibm.com/support/pages/lifecycle/details/?q45=S928720R89459D48.

Conditional installation requisites identify products that are not required for successful installation of this product but can resolve such things as certain warning messages at installation time.

Enterprise COBOL has no conditional installation requisites.

5.2.2.2 Operational Requisites: Operational requisites are products that are required and *must* be present on the system or products that are not required but should be present on the system for this product to operate all or part of its functions.

Mandatory operational requisites identify products that are required for this product to operate its basic functions.

Figure 7 (Page 1 of 2). Target System Mandatory Operational Requisites				
Program Product Name and Number Minimum VRM/Service Level Function				
5650-ZOS	z/OS V02.05.00 or higher	z/OS Language Environment and Program Management, required to compile and run COBOL applications		

Figure 7 (Page	Figure 7 (Page 2 of 2). Target System Mandatory Operational Requisites					
Program Number	Product Name and Minimum VRM/Service Level	Function				
5650-ZOS	Language Environment for z/OS V2R5 with the PTFs for APARs PH66224 and PH66225 applied	PH66224 COBOL run-time (AMODE31) PH66225 COBOL run-time (AMODE64)				
	Language Environment for z/OS V3R1 with the PTFs for APARs PH66224 and PH66225 applied	PH66224 COBOL run-time (AMODE31) PH66225 COBOL run-time (AMODE64)				
5655-DGH, 5655-DGG, 5655-DGJ 5655-UA1 5655-JB1	IBM SDK for z/OS, Java Technology Edition 8.0.6.36 (JVM), IBM Seremu Runtime Certified Edition for z/OS, V11.0.14.1, or later, Java 17, Java 21	Required for COBOL/Java interoperability feature.				
5650-ZOS	z/OS XML System Services 2.5, or later.	Required for Enterprise COBOL XML PARSE statements in programs, which are compiled with the XMLPARSE(XMLSS) compiler option.				
5650-ZOS	PTFs for APARs OA65272 and OA66674 (VSAM EzNOSQL)	Required for VSAMDB feature				
5650-ZOS	z/OS High Level Assembler	Required for customization during or after installation.				

Note:

Depending on the target system that you are running, ensure that the appropriate level of LE PTF(s) for the following APAR has been installed on your system.

- PH66224 and PH66225 (z/OS V2R5 Language Environment)
- PH66224 and PH66225 (z/OS V3R1 Language Environment)

Conditional operational requisites identify products that are not required for this product to operate its basic functions but are required at run time for this product to operate specific functions.

You may need various other products (eg. Db2, CICS or IMS) depending on the Enterprise COBOL function you are using. Please check the Software Product Compatibilty Reports (SPCR) at https://www.ibm.com/software/reports/compatibility/clarity/index.html for a list of compatible software. From the SPCR home page, click Create a report under In-depth reports, search for Enterprise COBOL for z/OS and choose Version 6.5, and then click Submit.

5.2.2.3 Toleration/Coexistence Requisites: Toleration/coexistence requisites identify products that must be present on sharing systems. These systems can be other systems in a multisystem environment (not necessarily sysplex), a shared DASD environment (such as test and production), or systems that reuse the same DASD environment at different time intervals.

Enterprise COBOL has no toleration/coexistence requisites.

5.2.2.4 Incompatibility (Negative) Requisites: Negative requisites identify products that must not be installed on the same system as this product.

Enterprise COBOL has no incompatibility requisites.

5.2.3 DASD Storage Requirements

Enterprise COBOL libraries can reside on all supported DASD types.

Figure 8 lists the total space that is required for each type of library.

Figure 8. Total DASD Space Required by Enterprise COBOL				
Library Type	Total Space Required in 3390 Trks			
Target	3082			
Distribution	3050			
File System	56			

Notes:

- 1. For non-RECFM U data sets, IBM recommends using system-determined block sizes for efficient DASD utilization. For RECFM U data sets, IBM recommends using a block size of 32760, which is most efficient from the performance and DASD utilization perspective.
- 2. Abbreviations used for data set types are shown as follows.
 - U Unique data set, allocated by this product and used by only this product. This table provides all the required information to determine the correct storage for this data set. You do not need to refer to other tables or program directories for the data set size.
 - S Shared data set, allocated by this product and used by this product and other products. To determine the correct storage needed for this data set, add the storage size given in this table to those given in other tables (perhaps in other program directories). If the data set already exists, it must have enough free space to accommodate the storage size given in this table.
 - Ε Existing shared data set, used by this product and other products. This data set is not allocated by this product. To determine the correct storage for this data set, add the storage size given in this table to those given in other tables (perhaps in other program directories). If

the data set already exists, it must have enough free space to accommodate the storage size given in this table.

If you currently have a previous release of this product installed in these libraries, the installation of this release will delete the old release and reclaim the space that was used by the old release and any service that had been installed. You can determine whether these libraries have enough space by deleting the old release with a dummy function, compressing the libraries, and comparing the space requirements with the free space in the libraries.

For more information about the names and sizes of the required data sets, see 6.1.8, "Allocate SMP/E Target and Distribution Libraries" on page 22.

- 3. Abbreviations used for the file system path type are as follows.
 - New path, created by this product.
 - X Path created by this product, but might already exist from a previous release.
 - Ρ Previously existing path, created by another product.
- 4. All target and distribution libraries listed have the following attributes:
 - The default name of the data set can be changed.
 - The default block size of the data set can be changed.
 - The data set can be merged with another data set that has equivalent characteristics.
 - The data set can be either a PDS or a PDSE, except for SIGYCOMP and AIGYMOD1, which must be PDSEs.
- 5. All target libraries listed have the following attributes:
 - These data sets can be SMS-managed, but they are not required to be SMS-managed.
 - These data sets are not required to reside on the IPL volume.
 - The values in the "Member Type" column are not necessarily the actual SMP/E element types that are identified in the SMPMCS.
- 6. All target libraries that are listed and contain load modules have the following attributes:
 - These data sets can be in the LPA, but they are not required to be in the LPA.
 - These data sets can be in the LNKLST.
 - These data sets are not required to be APF-authorized.
 - Enterprise COBOL requires that the SMPLTS data set must be a PDSE. If your existing SMPLTS is a PDS, you will need to allocate a new PDSE and copy your existing SMPLTS into it and then change the SMPLTS DDDEF entry to indicate the new PDSE data set.

The following figures describe the target and distribution libraries and file system paths required to install Enterprise COBOL. The storage requirements of Enterprise COBOL must be added to the storage required by other programs that have data in the same library or path.

Note: Use the data in these tables to determine which libraries can be merged into common data sets. In addition, since some ALIAS names may not be unique, ensure that no naming conflicts will be introduced before merging libraries.

Figure 9. Storage Requirements for Enterprise COBOL Target Libraries								
Library DDNAME	Member Type	Target Volume	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR BIks
SIGYCOMP	LMOD	ANY	U	PDSE	U	0	3000	n/a
SIGYMAC	MACRO	ANY	U	PDS	FB	80	10	5
SIGYPROC	PROC	ANY	U	PDS	FB	80	2	5
SIGYSAMP	SAMP	ANY	U	PDS	FB	80	35	10
SIGYLIB	SAMP	ANY	U	PDS	FB	80	35	10

Figure 10. Ente	Figure 10. Enterprise COBOL File System Paths				
	Т				
	Υ				
	Р				
DDNAME	E	Path Name			
SIGYHFS	N	/usr/lpp/IBM/cobol/igyv6r5/bin/IBM			

Figure 11. Storage Requirements for Enterprise COBOL Distribution Libraries						
	т		R E	L R	No.	No.
	Y	0	C	E	of	of
Library	P	R	F	C	3390	DIR
DDNAME	E	G	М	L	Trks	Blks
AIGYHFS	U	PDS	VB	255	15	5
AIGYMOD1	U	PDSE	U	0	3000	n/a
AIGYSRC1	U	PDS	FB	80	45	12

5.3 FMIDs Deleted

Installing Enterprise COBOL might result in the deletion of other FMIDs. To see which FMIDs will be deleted, examine the ++VER statement in the SMPMCS of the product.

If you do not want to delete these FMIDs at this time, install Enterprise COBOL into separate SMP/E target and distribution zones.

Note: These FMIDs are not automatically deleted from the Global Zone. If you want to delete these FMIDs from the Global Zone, use the SMP/E REJECT NOFMID DELETEFMID command. See the SMP/E Commands book for details.

5.4 Special Considerations

PDSE Considerations:

Enterprise COBOL uses the "partitioned data set extended" or PDSE format for the SIGYCOMP target library. There are some operational differences between PDS and PDSE data sets. The PDS format may be shared by more than one z/OS system and no special precautions are necessary. However, the PDSE format may only be shared by z/OS systems which are part of a sysplex or which are connected using Global Resource Serialization (are in a GRS complex). If z/OS systems share use of a PDSE data set outside of a sysplex or GRS environment, you may experience severe problems when the data set is updated. This is due to the fact that PDSE directory information is cached in storage, and when the data set is updated from one system, but the other system(s) have no knowledge of the update, and their cached directory information will be incorrect.

You must take care not to share the SIGYCOMP data set between z/OS systems unless they are in a sysplex or are connected in a GRS complex. If you need to share the content of the SIGYCOMP data set, a separate copy must be created for each z/OS system.

6.0 Installation Instructions

This chapter describes the installation method and the step-by-step procedures to install and to activate the functions of Enterprise COBOL.

Please note the following points:

- You can use the sample jobs that are provided to perform part or all of the installation tasks. The SMP/E jobs assume that all DDDEF entries that are required for SMP/E execution have been defined in appropriate zones.
- You can use the SMP/E dialogs instead of the sample jobs to accomplish the SMP/E installation steps.

6.1 Installing Enterprise COBOL

6.1.1 SMP/E Considerations for Installing Enterprise COBOL

Use the SMP/E RECEIVE, APPLY, and ACCEPT commands to install this release of Enterprise COBOL.

6.1.2 SMP/E Options Subentry Values

The recommended values for certain SMP/E CSI subentries are shown in Figure 12. Using values lower than the recommended values can result in failures in the installation. DSSPACE is a subentry in the GLOBAL options entry. PEMAX is a subentry of the GENERAL entry in the GLOBAL options entry. See the SMP/E manuals for instructions on updating the global zone.

Figure 12. SN	Figure 12. SMP/E Options Subentry Values				
Subentry Value Comment					
DSSPACE	(500,500,500)	3390 DASD tracks			
PEMAX SMP/E Default IBM recommends using the SMP/E default for PEMAX.					

6.1.3 Sample Jobs

The following sample installation jobs are provided as part of the product to help you install Enterprise COBOL:

Figure 13 (Page 1 of 2). Sample Installation Jobs						
Job Name Job Type Description RELFILE						
IGYWEDIT	MACRO	ISPF editor macro to aid users in making changes to the sample jobs (Optional)	IBM.HADB650.F3			

Figure 13 (Page 2 of 2). Sample Installation Jobs					
Job Name	Job Type	Description	RELFILE		
IGYWSMPE	SMP/E	Sample job to define and prime a new SMP/E CSI (Optional)	IBM.HADB650.F3		
IGYWRECV	RECEIVE	Sample RECEIVE job	IBM.HADB650.F3		
IGYWALOC	ALLOCATE	Sample job to allocate target and distribution libraries	IBM.HADB650.F3		
IGYWZFS	ALLOMZFS	Sample job to allocate, create mountpoint, & mount zFS data sets (Optional)	IBM.HADB650.F3		
IGYISMKD	MKDIR	Sample job to invoke the supplied IGYMKDIR EXEC to allocate file system paths	IBM.HADB650.F3		
IGYWDDEF	DDDEF	Sample job to define SMP/E DDDEFs	IBM.HADB650.F3		
IGYWAPLY	APPLY	Sample APPLY job	IBM.HADB650.F3		
IGYWIVP1	IVP	Sample job to verify installation has been successful	IBM.HADB650.F3		
IGYWIVP2	IVP	Sample job to verify installation has been successful	IBM.HADB650.F3		
IGYWACPT	ACCEPT	Sample ACCEPT job	IBM.HADB650.F3		

You can access the sample installation jobs by performing an SMP/E RECEIVE (refer to 6.1.7, "Perform SMP/E RECEIVE" on page 21), and then copy the jobs from the RELFILES to a work data set for editing and submission. See Figure 13 on page 18 to find the appropriate relfile data set.

You can also copy the sample installation jobs from the tape or product files by submitting the following job. Depending on your distribution medium, use either the //TAPEIN or the //FILEIN DD statement and comment out or delete the other statement. Before you submit the job, add a job card and change the lowercase parameters to uppercase values to meet the requirements of your site.

```
//STEP1
        EXEC PGM=IEBCOPY
//SYSPRINT DD SYSOUT=*
//********************
//* Make the //TAPEIN DD statement below active if you install*
//* from a CBPDO tape by uncommenting the DD statement below. *
//********************************
//*TAPEIN
         DD DSN=IBM.HADB650.F3,UNIT=tunit,
//*
         VOL=SER=volser, LABEL=(x,SL),
         DISP=(OLD, KEEP)
//*****************
//* Make the //TAPEIN DD statement below active if you install*
//* from a product tape received outside the CBPDO process
//* (using the optional SMP/E RECEIVE job) by uncommenting
//* the DD statement below.
//********************
//*TAPEIN DD DSN=IBM.HADB650.F3,UNIT=tunit,
```

```
//*
           VOL=SER=ADB650, LABEL=(4,SL),
//*
          DISP=(OLD, KEEP)
//*********************************
//* Make the //FILEIN DD statement below active for
//* downloaded DASD files.
//********************
//*FILEIN DD DSN=IBM.HADB650.F3,UNIT=SYSALLDA,DISP=SHR,
//*
          VOL=SER=filevol
//OUT
          DD DSNAME=jcl-library-name,
          DISP=(NEW, CATLG, DELETE),
//
//
          VOL=SER=dasdvol, UNIT=SYSALLDA,
//
          SPACE=(TRK, (20, 10, 5))
//SYSUT3
          DD UNIT=SYSALLDA, SPACE=(CYL, (1,1))
//SYSIN
          DD *
   COPY INDD=xxxxIN,OUTDD=OUT
 SELECT MEMBER=(IGYISMKD,IGYWACPT,IGYWALOC,IGYWAPLY)
 SELECT MEMBER=(IGYWDDEF,IGYWEDIT,IGYWIVP1,IGYWIVP2)
 SELECT MEMBER=(IGYWRECV,IGYWSMPE,IGYWZFS)
/*
```

See the following information to update the statements in the previous sample:

TAPEIN:

tunit is the unit value that matches the product package.

volser is the volume serial that matches the product package.

x is the tape file number that indicates the location of the data set name on the tape.

See the documentation that is provided by CBPDO for the location of IBM.HADB650.F3 on the tape.

FILEIN:

filevol is the volume serial of the DASD device where the downloaded files reside.

OUT:

icl-library-name is the name of the output data set where the sample jobs are stored.

dasdvol is the volume serial of the DASD device where the output data set resides.

SYSIN:

XXXXIN is either TAPEIN or FILEIN depending on your input DD statement.

6.1.4 Run REPORT MISSINGFIX

The SMP/E REPORT MISSINGFIX command helps you determine whether any FIXCAT PTFs exist that are applicable and have not yet been installed. If you find that there are PTFs that need to be installed, we recommend that you install them, before installing COBOL Version 6.5.

Before you install Enterprise COBOL, it is recommended that you run REPORT MISSINGFIX. This requires a global zone with ZONEINDEX entries that describe all the target and distribution libraries to be reported on, the SET BOUNDARY command must specify the global zone.

Here is a sample REPORT MISSINGFIX command to run against your z/OS CSI, (include previous versions):

```
SET BDY(globalzone).
REPORT MISSINGFIX ZONES(targetzone)
FIXCAT(IBM.TargetSystem-RequiredService.Enterprise-COBOL.*).
```

For more information about REPORT MISSINGFIX, see the SMP/E manuals.

6.1.5 Set up ISPF Editor Macro (Optional)

To aid you in making changes to the SMP/E installation jobs (IGYISMKD, IGYWACPT, IGYWALOC, IGYWAPLY, IGYWDDEF, IGYWIVP1, IGYWIVP2, IGYWRECV, IGYWSMPE, and IGYWZFS), an ISPF editor macro, called IGYWEDIT, is supplied and is copied to your output data set jcl-library-name above. (See Figure 13 on page 18).

This macro lets you substitute proper values for all of the required variables in those jobs instead of making the changes repeatedly by hand.

Edit macro IGYWEDIT and provide the proper values, then copy it to any data set in your TSO logon procedure SYSEXEC concatenation. Consult the instructions in the macro for more information.

6.1.6 Allocate and Initialize the SMP/E CSI (Optional)

If you are using an existing CSI do not execute this job.

If you install into existing SMP/E data sets, make sure that you have enough space.

If you plan to install into an existing zone, the cluster should already have been allocated and primed. You can go on to the next step to perform a SMP/E RECEIVE.

To install into a new zone, use the IGYWSMPE sample job to allocate and prime the SMPCSI cluster. Consult the instructions in the sample job for more information.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

6.1.7 Perform SMP/E RECEIVE

If you have obtained Enterprise COBOL as part of a CBPDO, use the RCVPDO job in the CBPDO RIMLIB data set to receive the Enterprise COBOL FMIDs, service, and HOLDDATA that are included on the CBPDO package. For more information, see the documentation that is included in the CBPDO.

You can also choose to edit and submit sample job IGYWRECV to perform the SMP/E RECEIVE for Enterprise COBOL. Consult the instructions in the sample job for more information.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

6.1.8 Allocate SMP/E Target and Distribution Libraries

Edit and submit sample job IGYWALOC to allocate the SMP/E target and distribution libraries for Enterprise COBOL. Consult the instructions in the sample job for more information.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

6.1.9 Allocate, create and mount ZFS Files (Optional)

This job allocates, creates a mountpoint, and mounts zFS data sets.

If you plan to install Enterprise COBOL into a new z/OS UNIX file system, you can edit and submit the optional IGYWZFS job to perform the following tasks:

- Create the z/OS UNIX file system
- Create a mount point
- Mount the z/OS UNIX file system on the mountpoint

Consult the instructions in the sample job for more information.

The recommended z/OS UNIX file system type is zFS. The recommended mount point is /usr/lpp/IBM/cobol/igyv6r5.

Before running the sample job to create the z/OS UNIX file system, you must ensure that OMVS is active on the driving system. zFS must be active on the driving system if you are installing Enterprise COBOL into a file system that is zFS.

If you create a new file system for this product, consider updating the BPXPRMxx PARMLIB member to mount the new file system at IPL time. This action can be helpful if an IPL occurs before the installation is completed.

```
MOUNT FILESYSTEM('#dsn')
 MOUNTPOINT('/usr/lpp/IBM/cobol/igyv6r5')
 MODE (RDWR)
                  /* can be MODE(READ) */
 TYPE(ZFS) PARM('AGGRGROW') /* zFS, with extents */
```

See the following information to update the statements in the previous sample:

- #dsn is the name of the data set holding the z/OS UNIX file system.
- /usr/lpp/IBM/cobol/igyv6r5 is the name of the mount point where the z/OS UNIX file system will be mounted.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

6.1.10 Allocate File System Paths

The target system HFS or zFS data set must be mounted on the driving system when running the sample IGYISMKD job since the job will create paths in the HFS or zFS.

Before running the sample job to create the paths in the file system, you must ensure that OMVS is active on the driving system and that the target system's HFS or zFS file system is mounted to the driving system. zFS must be active on the driving system if you are installing Enterprise COBOL into a file system that is zFS.

If you plan to install Enterprise COBOL into a new HFS or zFS file system, you must create the mountpoint and mount the new file system to the driving system for Enterprise COBOL.

The recommended mountpoint is /usr/lpp/IBM/cobol/igyv6r5.

Edit and submit sample job IGYISMKD to allocate the HFS or zFS paths for Enterprise COBOL. Consult the instructions in the sample job for more information.

If you create a new file system for this product, consider updating the BPXPRMxx PARMLIB member to mount the new file system at IPL time. This action can be helpful if an IPL occurs before the installation is completed.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

6.1.11 Create DDDEF Entries

Edit and submit sample job IGYWDDEF to create DDDEF entries for the SMP/E target and distribution libraries for Enterprise COBOL. Consult the instructions in the sample job for more information.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

6.1.12 Perform SMP/E APPLY

1. Ensure that you have the latest HOLDDATA; then edit and submit sample job IGYWAPLY to perform an SMP/E APPLY CHECK for Enterprise COBOL. Consult the instructions in the sample job for more information.

The latest HOLDDATA is available through several different portals, including http://service.software.ibm.com/holdata/390holddata.html. The latest HOLDDATA may identify HIPER and FIXCAT APARs for the FMIDs you will be installing. An APPLY CHECK will help you determine if any HIPER or FIXCAT APARs are applicable to the FMIDs you are installing. If there are any applicable HIPER or FIXCAT APARs, the APPLY CHECK will also identify fixing PTFs that will resolve the APARs, if a fixing PTF is available.

You should install the FMIDs regardless of the status of unresolved HIPER or FIXCAT APARs. However, do not deploy the software until the unresolved HIPER and FIXCAT APARs have been analyzed to determine their applicability. That is, before deploying the software either ensure fixing PTFs are applied to resolve all HIPER or FIXCAT APARs, or ensure the problems reported by all HIPER or FIXCAT APARs are not applicable to your environment.

To receive the full benefit of the SMP/E Causer SYSMOD Summary Report, do not bypass the PRE, ID, REQ, and IFREQ on the APPLY CHECK. The SMP/E root cause analysis identifies the cause only of errors and not of warnings (SMP/E treats bypassed PRE, ID, REQ, and IFREQ conditions as warnings, instead of errors).

Here are sample APPLY commands:

a. To ensure that all recommended and critical service is installed with the FMIDs, receive the latest HOLDDATA and use the APPLY CHECK command as follows

```
APPLY S(fmid,fmid,...) CHECK
FORFMID (fmid, fmid,...)
SOURCEID(RSU*)
FIXCAT(IBM.ProductInstall-RequiredService)
FIXCAT(IBM.TargetSystem-RequiredService.Enterprise-COBOL.V6R5)
GROUPEXTEND .
```

Some HIPER APARs might not have fixing PTFs available yet. You should analyze the symptom flags for the unresolved HIPER APARs to determine if the reported problem is applicable to your environment and if you should bypass the specific ERROR HOLDs in order to continue the installation of the FMIDs.

This method requires more initial research, but can provide resolution for all HIPERs that have fixing PTFs available and are not in a PE chain. Unresolved PEs or HIPERs might still exist and require the use of BYPASS.

b. To install the FMIDs without regard for unresolved HIPER APARs, you can add the BYPASS(HOLDCLASS(HIPER)) operand to the APPLY CHECK command. This will allow you to install FMIDs even though one or more unresolved HIPER APARs exist. After the FMIDs are installed, use the SMP/E REPORT ERRSYSMODS command to identify unresolved HIPER APARs and any fixing PTFs.

```
APPLY S(fmid,fmid,...) CHECK
FORFMID(fmid, fmid,...)
SOURCEID(RSU*)
FIXCAT(IBM.ProductInstall-RequiredService)
FIXCAT (IBM. TargetSystem-RequiredService. Enterprise-COBOL. V6R5)
GROUPEXTEND
BYPASS(HOLDCLASS(HIPER), HOLDFIXCAT) .
 ..any other parameters documented in the program directory
```

This method is quicker, but requires subsequent review of the Exception SYSMOD report produced by the REPORT ERRSYSMODS command to investigate any unresolved HIPERs. If you have received the latest HOLDDATA, you can also choose to use the REPORT MISSINGFIX command and specify Fix Category IBM.ProductInstall-RequiredService to investigate missing recommended service.

It is recommended that you run REPORT MISSINGFIX specifying your COBOL category against OTHER target zones, to identify required PTFs that are missing from those other target zones.

This is particularly important if COBOL is installed in a target zone different to LE (refer to 6.1.4, "Run REPORT MISSINGFIX" on page 20).

If you bypass HOLDs during the installation of the FMIDs because fixing PTFs are not yet available, you can be notified when the fixing PTFs are available by using the APAR Status Tracking (AST) function of ServiceLink or the APAR Tracking function of ResourceLink.

2. After you take actions that are indicated by the APPLY CHECK, remove the CHECK operand and run the job again to perform the APPLY.

Note: The GROUPEXTEND operand indicates that SMP/E applies all requisite SYSMODs. The requisite SYSMODS might be applicable to other functions.

Expected Return Codes and Messages from APPLY CHECK: You will receive a return code of 0 if this job runs correctly.

Expected Return Codes and Messages from APPLY: You will receive a return code of 0 if this job runs correctly.

6.1.13 Run the Installation Verification Programs

Make sure you have applied the PTFs for the Language Environment and Program Management APARs listed in Figure 7 on page 12, then edit and submit sample jobs IGYWIVP1 and IGYWIVP2 to verify that you have installed Enterprise COBOL correctly. Refer to the instructions in the sample jobs for more information and expected output.

Expected Return Codes and Messages: You will receive return codes of 0 if these jobs run correctly.

Note: If operational requisite PTFs for the Language Environment have not already been applied, the IGYWIVP1 sample job will fail at LINK step. You will receive abend code of RC=0008 and message:

IEW2456E 9207 SYMBOL IGZXLERR UNRESOLVED. MEMBER COULD NOT BE INCLUDED FROM THE DESIGNATED CALL LIBRARY.

6.1.14 Perform SMP/E ACCEPT

Edit and submit sample job IGYWACPT to perform an SMP/E ACCEPT CHECK for Enterprise COBOL. Consult the instructions in the sample job for more information.

To receive the full benefit of the SMP/E Causer SYSMOD Summary Report, do not bypass the PRE, ID, REQ, and IFREQ on the ACCEPT CHECK. The SMP/E root cause analysis identifies the cause of errors but not warnings (SMP/E treats bypassed PRE, ID, REQ, and IFREQ conditions as warnings rather than errors).

Before you use SMP/E to load new distribution libraries, it is recommended that you set the ACCJCLIN indicator in the distribution zone. In this way, you can save the entries that are produced from JCLIN in the distribution zone whenever a SYSMOD that contains inline JCLIN is accepted. For more information about the ACCJCLIN indicator, see the description of inline JCLIN in the SMP/E Commands book for details.

After you take actions that are indicated by the ACCEPT CHECK, remove the CHECK operand and run the job again to perform the ACCEPT.

Note: The GROUPEXTEND operand indicates that SMP/E accepts all requisite SYSMODs. The requisite SYSMODS might be applicable to other functions.

Expected Return Codes and Messages from ACCEPT CHECK: You will receive a return code of 0 if this job runs correctly.

If PTFs that contain replacement modules are accepted, SMP/E ACCEPT processing will link-edit or bind the modules into the distribution libraries. During this processing, the Linkage Editor or Binder might issue messages that indicate unresolved external references, which will result in a return code of 4 during the ACCEPT phase. You can ignore these messages, because the distribution libraries are not executable and the unresolved external references do not affect the executable system libraries.

Expected Return Codes and Messages from ACCEPT: You will receive a return code of 0 if this job runs correctly.

6.2 Activating Enterprise COBOL

6.2.1 Running Enterprise COBOL from Unix System Services

If you mount the file system in which you have installed Enterprise COBOL in read-only mode during execution, then you do not have to take further actions to activate Enterprise COBOL. Refer to 6.1.9, "Allocate, create and mount ZFS Files (Optional)" on page 22 for more information on the file system for Enterprise COBOL.

6.2.2 Product Customization

The publication IBM Enterprise COBOL for z/OS Customization Guide (SC27-8712-04) contains the necessary information to customize and use Enterprise COBOL.

The /usr/lpp/IBM/cobol/igyv6r5/bin/cob2 is a shell script. If you put it in a location other than the default Enterprise COBOL File System Path /usr/lpp/IBM/cobol/igyv6r5, then change the environment variable COBOL_INSTALL_DIR as needed.

7.0 Notices

This information was developed for products and services offered in the U.S.A. IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

APAR numbers are provided in this document to assist in locating PTFs that may be required. Ongoing problem reporting may result in additional APARs being created. Therefore, the APAR lists in this document may not be complete. To obtain current service recommendations and to identify current product service requirements, always contact the IBM Customer Support Center or use S/390 SoftwareXcel to obtain the current "PSP Bucket".

IBM may have patents or pending patent applications covering subject matter in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to the

IBM Director of Licensing IBM Corporation North Castle Drive Armonk, New York 10504-1785 USA

For license inquiries regarding double-byte (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

Intellectual Property Licensing Legal and Intellectual Property Law IBM Japan, Ltd. 19-21, Nihonbashi-Hakozakicho, Chuo-ku Tokyo 103-8510, Japan

7.1 Trademarks

IBM, the IBM logo, and ibm.com are trademarks or registered trademarks of International Business Machines Corp., registered in many jurisdictions worldwide. Other product and service names might be trademarks of IBM or other companies. A current list of IBM trademarks is available on the Web at "Copyright and trademark information" at www.ibm.com/legal/copytrade.shtml.

© Copyright IBM Corp. 2025

Reader's Comments

Program Directory for IBM Enterprise COBOL for z/OS, June 2025

We appreciate your input on this publication. Feel free to comment on the clarity, accuracy, and completeness of the information or give us any other feedback that you might have.

Use one of the following methods to send us your comments:

1. Send an email to comments@us.ibm.com

When you send information to IBM, you grant IBM a nonexclusive right to use or distribute the information in any way it believes appropriate without incurring any obligation to you.

IBM or any other organizations will only use the personal information that you supply to contact you about the issues that you submit.

Thank you for your participation.

IBM

Printed in USA

GI13-4526-04