CorrectCoxVpulse— a python function to correct for spaceclamp errors in voltage-clamp test-pulse experiments

Ricardo Murphy (ricardo_murphy@fastmail.fm)
University of Oslo, Domus Medica, Division of Physiology,
Pb. 1103, Blindern, 0317 Oslo, Norway

Introduction

Whole-cell voltage-clamp is a widely used method for estimating the voltage (V) and time (t) dependence of membrane currents (Sakmann and Neher 1995). This allows the construction of Hodgkin-Huxley type models of V-dependent membrane conductances, which may then be implemented in compartmental models of cells. Typically rectangular test pulses are applied to various V from some holding potential, and the time course of the injected current, I(t), is recorded. Other protocols are also used such as the V-ramp (e.g. Murphy et al., 2023a), but here we will focus on the V-clamp test-pulse protocol. A serious problem when applying the V-clamp technique to neurons is that V is clamped only at the recording site. This will often be the soma, or perhaps an axonal bleb or varicosity, although proximal dendrites can also be patched. Away from the recording site V will not be clamped at the desired values ("space-clamp error"), but the membrane current at those points will contribute to the current measured at the recording site. Hence the interpretation of the recorded values of I and V is not straightforward; rather one must in some way correct for this space-clamp error. Various approaches have been tried (reviewed briefly by Murphy et al., 2023a). Here we take as our starting point the method described by Cox (2008), which provides an initial estimate of the membrane current density, i(t, V). This is then improved upon iteratively. Full details of the method are given in Murphy et al. (2023a,b). Here I describe the use of a Python function CorrectCoxVpulse, which operates in conjunction with the simulator NEURON (Carnevale and Hines, 2009) to correct for space-clamp errors in Vclamp test-pulse data and so return an estimate of i(t,V). Suitable functions are fitted to these data to obtain estimates of the V-dependence of kinetic parameters in a Hodgkin-Huxley style model. To use CorrectCoxVpulse you need to install the statistical software R and the Python module rpy2 (see Technical Notes).

Using the function CorrectCoxVpulse

The folder CorrectCoxVpulseExample contains example data files, parameter files, function files and output, as well as a NEURON model (the .hoc and .mod files; remember to compile the latter). You will need two text files containing leak-subtracted currents: (1) control; (2) with the conductance of interest blocked. The example data files are I_control.txt and I_blocked.txt. Your data must conform to this format, specifically a column of sampling times followed by columns of injected current recorded at increasing test-pulse voltages. You will also need two corresponding parameter files (control_parameters.txt and blocked parameters.txt are provided as examples). You can use any parameter file

names you like, but parameter names and the colons in the parameter files must not be changed. Also each parameter must be assigned a value. As some parameters are needed by the NEURON model, these can be loaded from the parameter file by your hoc script (see <code>mossy_fiber_run.hoc</code>). It can also load the name of the parameter file from the file <code>parameter_file.txt</code> (first line). The meaning of the parameters is given in the Table 1. Note that if filenames include a path, it must be specified using "/", not "\". You will also need two function files, specifying the functions that are to be fitted to the estimated i(t) data at each V (described in detail below); blocked_functions.txt and control_functions.txt are provided as examples. Extra flexibility is provided by files user_parameters.txt and user_functions.py (also described in detail below). These two files must be present in the current folder, even if you don't have any use for them.

Put CorrectCoxVpulse.py and your own Python script(s) into the same (current) folder as the NEURON model, data, function and parameter files, and import CorrectCoxVpulse by putting a line like the following near the start of your script:

```
import CorrectCoxVpulse as cox
```

Calling the function from your script is simple; result is a dictionary (see Table 2):

```
result = cox.CorrectCoxVpulse('blocked parameters.txt')
```

An example script is provided (CorrectCoxVpulseExample.py). The analysis is done in two sweeps: (1) blocked; (2) control. i(t,V) in the blocked condition is then subtracted from that in control to get the current density of interest. So, in the case of the example data, you would first execute the above line. Final results are copied to the output folder (outputdir = blocked in the present case) specified in the parameter file; output file names are given in Table 3. If you wish the temporary folder coxdir to be copied to the output folder, add an argument saveCox = 'yes' when calling CorrectCoxVpulse. The estimated parameters of i(t,V) in the blocked condition are saved by CorrectCoxVpulse to file blocked/cdn_#_paras.txt (where #is the best iteration; of course you may use a different output folder name). Enter that name (here blocked/cdn_4_paras.txt) into the control parameter file (control_parameters.txt in this case; see Table 1) and rerun CorrectCoxVpulse:

```
result = cox.CorrectCoxVpulse('control parameters.txt').
```

Again output, including the parameters for the conductance of interest (here in cdn 5 paras.txt), is sent to the output folder (control in this case).

During the optimisation process, a number of temporary files are created in the current folder. These files, which are described in Table 4, allow your NEURON program to interact with CorrectCoxVpulse. During each iteration, once it has estimated the i(t,V) model parameters, CorrectCoxVpulse will run your NEURON model. The first thing this model should do is load the file parameter_file.txt to find out what the parameter fine name is (first line). The second line in parameter_file.txt will be one of the following:

- Blocked: 0. This is the first iteration under control conditions, and you need to generate a file (cdn_blocked.txt) containing i(t,V) data in the blocked state (and with $R_{\rm access}=0$) so that it can be subtracted by CorrectCoxVpulse from its estimate of i(t,V) in control. [CorrectCoxVpulse always estimates i(t,V) assuming $R_{\rm access}=0$, even if you have $R_{\rm access}>0$ in your model.]
- (2) Iteration: #. The iteration number (#). Load the HH model kinetic parameters from cdn_paras.txt and the leak parameters from cdL_paras.txt (Table 4b). Then run a regular simulation of a *V*-clamp test-pulse experiment, i.e. with *R*_{access} as set in the parameter file. If this is control then the conductance of interest should not be blocked.
- (3) Best_iteration: #. This is the best fit (iteration #). Load model parameters for this iteration and any other relevant data (e.g. for plotting) from the output folder (see mossy_fiber_run.hoc). Do a simulation with $R_{access}=0$ and save the resulting i(t,V) data to outputdir/cdn_#_Raccess=0.txt (replace outputdir with the folder name and # with the iteration number). This is to allow comparison of i(t,V) recorded in the NEURON model with the final estimates generated by CorrectCoxVpulse (see below).

When the current simulation is finished, create a file flag.txt with the following hoc code (or similar) and then quit:

```
objref file
//Notify CorrectCoxVpulse.py that NEURON is done.
proc finish() {
   file = new File()
   file.wopen("flag.txt")
   file.printf("%d\r",$1)
   file.close()
   quit()
}
```

The behaviour of CorrectCoxVpulse depends on the value of the argument \$1: -1, terminate; 0, redo the last iteration, having made some adjustments (e.g. to the fit functions, although this is not recommended); 1, proceed to the next iteration.

CorrectCoxVpulse produces various plots at the start and end of the optimisation. Hopefully they are self-explanatory. Of note is the plot "Leak-subtracted current densities predicted by the model", which compares the NEURON model predictions for i(t,V) with the best estimates obtained by CorrectCoxVpulse (i.e. those minimising the I RMS error). The NEURON predictions are loaded from your file outputdir/cdn_#_Raccess=0.txt (see above) to ensure a valid comparison (since CorrectCoxVpulse estimates i(t,V) assuming $R_{access} = 0$). If you wish to see plots for intermediate iterations (e.g. for troubleshooting) add an argument do plots = 'yes' when calling CorrectCoxVpulse.

Function files

For each iteration, CorrectCoxVpulse estimates i(t,V) as described by Murphy et. al (2023a,b) and then fits a function to the i(t) at each V using the SciPy function optimize.least_squares.. These functions are selected in function files; examples are blocked_functions.txt and control_functions.txt. The first few lines list the available functions. Each line consists of a function name, a colon, and the function expression (which, however, is not evaluated; it's just for information). A number of predefined functions are supplied: A^k ... (A^k) IIf, where A and A indicate activation and inactivation, respectively, while II implies both fast and slow inactivation. Functions A^k+A , A^k+A and A^k+A have a slowly activating component which is absent in A^k . On the other hand, the fast activating component is absent in A^k . On the other hand, the fast activating component is an adjustable parameter that will be estimated by least-squares fitting. Be aware that all these functions assume that the conductance of interest is initially completely deactivated, and that any inactivation has been completely removed. You can also specify your own functions, which are defined in user_functions.py (see below). myfunc in CorrectCoxVpulseExample/control functions.txt is an example.

Next come the values of k and the model reversal potential (Erev (mV)). And after that come a series of lines determining how to extrapolate time constants at low and high V when a component of i is not present. [Components are numbered 1 and 2; if you want more you'll have to supply them yourself.] These lines come in pairs:

```
tau..._extrapolation_(..._V): string
tau... (ms): value
```

string and value control the method of extrapolation in the following way (V_0 is the lowest or highest command V and τ is the nearest available estimated value):

string	Method of extrapolation
constant	tau = value.
last	tau = τ (value is ignored).
linear	tau is linearly interpolated between value at V_0 and τ .
ΔV (number)	tau is assumed to decay exponentially from a value of τ to a plateau value of <i>value</i> with a half V of ΔV .

In general one would expect such extrapolation to be needed only at low V, but an option for high-V extrapolation is provided incase it should ever be needed.

Finally there is a table of voltages and functions to be fitted to i(t) at those V. CorrectCoxVpulse will do its best to choose reasonable starting values for the parameters prior to fitting. But its best may not be good enough, resulting in crazy fits or program termination. In that case you can supply your own starting values by placing parameter-name, value pairs after the function name, e.g.

```
-42 (A^k) Ic tauh1 10
-32 (A^k) IIc tauh1 10 tauh2 100
```

The taum... and tauh... are activation and inactivation time constants, respectively. Note that all time constants are in ms (like t). hlinf and hlinf are stationary inactivation variables as $t \to \infty$, and so ideally should end up in the range (0,1). ilinf and ilinf are stationary current densities (mA cm⁻²) as $t \to \infty$. For inactivating i, ilinf is the value in the absence of inactivation. The remaining adjustable parameter is b, which occurs in functions which approach a straight line for large t, presumably because the relevant time constant is so large. For inactivation (functions (A^k) Ib, (A^k) IIb and (A^k) IIe) b is the negative slope, and inactivation is assumed to be complete (i.e. h#inf = 0). For activation (function A^k+L) b is the slope of the line. Either way b is inversely related to a time constant, and it is the estimate of this time constant that is reported in file cdn_paras.txt, together with the other parameter estimates. For inactivation, tauh# = -1/b. For A^k+L, b = ilinf/taum2, and so to disentangle these two parameters, taum2 is set to a multiple (taum_mult) of the trace length. The default value of taum_mult is 5. You can set your own value by adding an argument "taum mult = #" when calling CorrectCoxVpulse.

The number of parameters reported in cdn_paras.txt is determined by the function in the function table with the largest number of parameters (the full model). Any other models fitted are reduced forms of the full model. Extrapolation (as described above) or, if necessary, linear interpolation is used to fill in any missing values, i.e. when fitting a model that is reduced relative to the full model. For example, in the provided file blocked_functions.txt, (A^k) IIb is the full model, but for $V \le -32$ mV the reduced models A^k and A^k are fitted. If the full model includes an inactivating component #, but it is absent at some V (i.e. you fit a reduced model lacking component # at that V), A^k inf is set to unity. If a function contains an inactivating component # but there is no corresponding A^k inf, inactivation of that component is assumed to be complete (i.e. A^k inf = 0).

Load the parameters in cdn_paras.txt to set up Hodgkin-Huxley type channel mechanisms (.mod) files. Example .mod files are provided. Use of the time constants (tau...) and stationary inactivation variables (h#inf) should be straightforward. Setting up the stationary activation variables (mlinf and, where appropriate, m2inf) is a little more tricky. Perhaps there is more than one way to do this, but the provided .mod files employ the method described by Murphy *et al.* (2023b):

$$m1\inf(V) = \left(\frac{\left(V_{\text{max}} - E_{\text{rev}}\right) \times i1\inf(V)}{\left(V - E_{\text{rev}}\right) \times i1\inf(V_{\text{max}})}\right)^{1/k}, \quad m2\inf(V) = \frac{\left(V_{\text{max}} - E_{\text{rev}}\right) \times i2\inf(V)}{\left(V - E_{\text{rev}}\right) \times i2\inf(V_{\text{max}})}$$

where V_{max} is the maximum command V. The full models associated with the provided .mod files are as follows:

MFB_KA.mod	A^k
MFB_KAA.mod	A^k+A
MFB_KAAadhoc.mod	$A^k+A + ad\ hoc$ function (see below).
MFB_KAI.mod	(A^k)Ic
MFB_KAII.mod	(A^k)IIc
MFB_KAIIadhoc.mod	(A^k)IIc + ad hoc function (see below).

user_parameters.txt and user_functions.py

These files must be present in the current directory even if you don't use them. As the name suggests, you can place your own parameters in user parameters.txt; see CorrectCoxVpulseExample/user parameters.txt for an example. In fact you can place any text lines you like; they will not be altered but just passed as a list (user paras) to the user-defined functions in user functions.py. Another parameter passed to these function is blockedfile, which is the name of the model parameter file in the blocked $condition \ (e.g. \ \verb|blocked/cdn_4| \ paras.txt|). \ Of \ course \ if \ you're \ currently \ analysing \ the$ blocked condition then blockedfile = none. Or in other words if blockedfile ≠ none, you must be analysing data from the control condition. In user functions.py you can define your own functions to fit to i(t), and adjust the parameter table (paratable) saved to cdn paras.txt. It is important to ensure that a parameter estimates ends up in the correct place in the table. For example, in the supplied function 0+A, component 1 is absent but, after fitting, paratable [i, 0] and paratable [i, 1] contain the estimates of i2inf and taum2 (here i indicates the command voltage). But from the structure of the table (see the column names) these should be in paratable [i, 2] and paratable [i, 3], paratable[i, 0] should be zero, and paratable[i, 1] should have an extrapolated value. CorrectCoxVpulse.makes the necessary adjustments, but you will need to take care of paratable for your own functions. Note also that if you want one of your functions to be the full model, you should include # in the function name. You can also define an ad hoc function with fixed parameters that will be added to the fit functions in order to fine tune the fit. (Murphy et al., 2023b). See CorrectCoxVpulseExample/user functions.py for further information on defining your own functions and adjusting paratable.

Table 1. Definition of parameters in the parameters file

Parameter	Example	Description
neuron_path	C:/nrn/bin	Omit this line if you want your system to find neuron.exe.
neuron_file	model.hoc	NEURON model file.
maxit	9	Maximum number of iterations.
DV (mV)	0.1	See Eq. (2) in Murphy et al. (2023b).
Iunit	nA	Unit of current in the data file (pA or nA; the latter will be converted to the former).
tunit	ms	Unit of time in the data file (ms or s; the latter will be converted to the former).
Data_delimeter	tab	In the data file (space or tab).
Number_of_headerlines_to_skip	10	In the data file (excluding column names).
I*(V)_interpolation	modified	Type of interpolation (see Technical Notes).
Stop_on_minimum_RMS_ error	no	If yes, iterations will stop at the first minimum RMS error encountered.
Decimate_data_by _a_factor_of	10	Decimate the data in the data file by this factor.
Moving_average_ window_(ms)	1	The data will be smoothed with this moving average (or not if 0).
Spline_smoothing_of_ I(t)	no	Additional spline smoothing (not recommended).
Fraction_of_trace_ for_estimating_SD	0.25	This terminal fraction of the $I(t)$ trace will be used to estimate $SD(I)^1$.
V_LJP_corrected	yes	If no, a correction will be applied (see LJP).
Leak-subtracted _currents_in_file	I_control.	The input data file (columns: $t I(V_1) I(V_2)$ $I(V_3)$, where V_i increase monotonically).

Model_parameter_fileblocked_condition	none	Or give a file name such as blocked/cdn_4_paras.txt.
Method_forthe_leak _currentiL_(0-3)	1	Method used to estimate the leak current density i_L^2 .
<pre>Fit_functions_for_i(t,V)_in_file</pre>	control_ funcs.txt	These will be fitted to the estimated current density $i(t)$ at each V .
Print_parameter_ estimates_(yes/no)	no	If yes, print the initial and final parameter estimates for the fitted functions.
Print_warnings	no	Do (yes) or don't (no).
Add_this_ad_hoc_ function_to_i(t,V)	none	See CorrectCoxVpulseExample/user_functions.py.
Exclude_this_initial _interval_(ms)	5	If you want to avoid an initial artifact in $i(t)$.
Constrain_i(t,V)_to_ be_positive	no	Do (yes) or don't (no).
coxdir	tempCox	Temporary folder for intermediate data.
outputdir	output	Output folder (absolute or relative); will be deleted if it already exists.
Area(um^2)	100	Membrane area of isopotential compartment (e.g. soma, bleb, dendritic section); nseg = 1.
diam(um)	0.4 0.4	List of neurite diameters (minimum 2).
Ra(Ohm.cm)	100	Axial resistivity.
Raccess (MOhm)	10	Patch access resistance.
Rseal (GOhm)	Inf	Patch seal resistance.
Cm(uF/cm^2)	1.0	Membrane specific capacitance.
LJP(mV)	2.0	Liquid junction potential ³ .
tstart(ms)	100	Pulse on time.

tstop(ms)	400	Pulse off time (includes tstart).
Ihold(pA)	-30	Holding current.
Vhold(mV)	-90	Holding voltage.
Number_of_test_ pulses	10	What it says.
Vcmnd (mV)	-80 -70	Test-pulse voltages.
Leak- subtraction_DV(mV)	-5	V pulse used for leak subtraction.
Leak-subtraction_DI(pA)	-3	Stationary change in current observed on applying the leak-subtraction pulse.
poly	gcv	Method for smoothing $I(V)$ and $I^*(V)^4$.
Plot_I(V)at_these _times_(ms;_max=12)	0 2 4 10	To see how the estimates of $I(V)$ ($k = 0$) and $I^*(V)$ ($k > 0$) look for each iteration.

 1 The minimum RMS error will inevitably be larger than SD(I) because of lack of fit. You can see just how much larger by inspecting IholdVholdVcrctVrestSDI.txt.

²Methods for estimating $i_L = g_L(V - E_L)$ ($g_L = leak$ conductance, $E_L = reversal$ potential). For methods 1 and 2, g_L and E_L are saved to cdL_paras.txt; for method 0, the user must supply this file. For methods 0-2, $i_L(V)$ is saved to cdL.txt. For method 3, the user must supply cdL.txt [two columns: V (mV) and i_L (mA cm⁻²), with names]; E_L and g_L are not defined.

0	Load user-specified values of $g_{\rm L}$ and $E_{\rm L}$ from cdL_paras.txt. Calculate $i_{\rm L}(V)$.
1	Set $i_L = i(V,0)$, i.e. the current density immediately following the <i>V</i> -pulse onset. Also estimate g_L and E_L from a regression line fitted to $i(V,0)$.
2	Estimate g_L and E_L from a regression line fitted to $i(V,0)$. Calculate $i_L(V)$.
3	Load a user-specified $i_{\mathbb{L}}(V)$ from cdL.txt.

 $^{^3}$ Used to calculate the leak current through the seal resistance, $(V + \text{LJP})/R_{\text{seal}}$. Also to correct V values if they aren't already corrected.

⁴Smoothing polynomial(s) for to I(V) and $I^*(V)$ (see also Technical Notes):

3	Fit a cubic polynomial. Fitted with NUMPY function polyfit.
4 4.0	Find the 'best-fit' polynomial of degree ≤ 4 using forward selection with an F -to-enter value (float) of 4.0 (Kutner $et~al.$, 2004).
2 3 -80	Splice together polynomials of degrees 2 and 3 at $V \approx -80$ mV (initial guess). Fitted with SciPy function optimize.least_squares.
CV	Use cross validation (requires <i>R</i> and Python module rpy2).
gcv	Use generalised cross validation (requires R and Python module rpy2).

Table 2. Definition of entries in the result dictionary.

Key	Description
Residuals(pA)	An $n \times n_V$ Numpy array of residual errors (observed I – NEURON-model-predicted I), where n is the number of samples and n_V the number of V pulses.
output_folder	As specified in the parameter file (outputdir).
Best iteration	Iteration (<i>k</i>) with the smallest RMS error.

Table 3. Output file names. # is the best iteration number.

Files saved by CorrectCoxVpulse to the output folder (as specified by outputdir):

File name	Description
cd_#.txt	i(t,V) estimated by CorrectCoxVpulse.
cd_fit_#.txt	Fitted $i(t, V)$ function values.
cdL_#.txt	Estimated $i_L(V)$.
cdL_#_paras.txt	Estimated g_L and E_L .
cdn_#_paras.txt	Current density, $i(t,V)$, parameters.
<pre>lerror_#.txt</pre>	ε = observed I - model-predicted I (total I , including I_{hold} , but corrected for R_{seal}). Used by CorrectCoxVpulse to estimate $i(t,V)$.
Iresids_#.txt	Observed I – model-predicted I (leak-subtracted; used to estimate the RMS error).
Raw_tDI.txt	Raw observed leak-subtracted currents.
Crct_tDI.txt	Leak-subtracted currents corrected for R_{seal} .
Crct_tV.txt	$V(t)$ corrected for $R_{\rm access}$.
IholdVholdVcrctVrestSDI.txt	I_{hold} corrected for R_{seal} ; V_{hold} , V_{rest} and mean-pulse V corrected for R_{acces} ; estimated SD(I).
printout.txt	The run time and RMS error for each iteration.
cdn_#.txt(optional)	i(t,V) predicted by the NEURON-model.
cdn_#_Raccess=0.txt	Predicted $i(t, V)$ when $R_{\text{access}} = 0$.
tDIpred_#.txt	Predicted leak-subtracted currents.
Ihold_DI_#.txt	Predicted values of I_{hold} and the stationary change in I during the leak-subtraction pulse.
cdn_blocked.txt	Predicted $i(t,V)$ in the blocked condition when $R_{\text{access}} = 0$ (subtracted from $i(t,V)$ in control).

Table 4. Temporary files in the current folder.

 Table 4a. NEURON-model output (input for CorrectCoxVpulse).

File name	Description
tDIpred.txt	Save your NEURON-model predictions for the leak-subtracted currents to this file. The format must conform to that of supplied file tDIpred.txt in folder CorrectCoxVpulseExample.
cdn.txt (optional)	Save your NEURON-model predictions for the current density of interest to this file. The format must conform to that of supplied file cdn.txt in folder CorrectCoxVpulseExample.
Ihold_DI.txt	Estimates of the holding current (Ihold(pA)) and the stationary change in current observed on applying the leak-subtraction pulse (DI(pA); see Ihold_DI.txt in folder CorrectCoxVpulseExample
flag.txt	See main text.

 Table 4b.
 CorrectCoxVpulse output (input for your NEURON model).

parameter_file.txt	See main text.
cdn_paras.txt	The current best estimate of the current-density parameters. Pass these data as a FUNCTION_TABLE to your .mod file (see the .hoc and .mod files in folder CorrectCoxVpulseExample).
cdL_paras.txt	$E_{\rm L}$ and $g_{\rm L}$ (passive leak: $i_{\rm L} = g_{\rm L}(V - E_{\rm L})$. For $i_{\rm L}$ methods 1 and 2 (see Table 1, footnote 2); otherwise $i_{\rm L}$ is user-specified (methods 0 and 3 in Table 1, footnote 2). Or load $i_{\rm L}(V)$ from cdL.txt.
cd.txt	i(t,V) estimated by CorrectCoxVpulse (for plotting) ¹ .
cd_fit.txt	Fitted $i(t,V)$ function values vs t at different V (for plotting) ¹ .

¹For evaluating the fits of the functions specified in the function file to the estimates of i(t,V). This seems difficult to achieve with CorrectCoxVpulse while the optimisation is in progress, so I leave it to the user to do the plotting if they wish in their own scripts.

Technical notes

As discussed in Murphy et al. (2023a,b), the Cox method with correction for correcting space-clamp errors involves the solution of a nonlinear ODE in the current density, i [Eq. (1) in Murphy et al. (2023b)]. Specification of the ODE requires estimation of a fictitious current (I^*) , which is determined by linear interpolation (or extrapolation if this s not possible). The interpolation method is set by the parameter I* (V) interpolation in the parameter file. The available choices are simple (as used by Murphy et al. (2023a), standard and modified. The last two are taken from Gerald and Wheatly (1984). In principle they should be more robust than simple, modified is faster than standard and so is the recommended method (and the one used by Murphy et al., 2023b). The initial value i = 0 is taken at $V = V_{\text{rest}}$. Eq. (1) is solved for i(V) using function scipy.integrate.solve ivp from the SciPyPython package. To facilitate the numerical solution, the I(V) and $I^*(V)$ data are smoothed according to the setting of the parameter poly in the parameter file (Table 1, footnote 4). Polynomial smoothing worked well for V ramps (Murphy et al., 2023a) but seems less suited to the analysis of V test-pulse data (Murphy et al., 2023b). So either cross validation (cv) or generalised cross validation (qcv) are the recommended methods, although splicing together two polynomials might be useful in difficult cases. Values of V_{rest} are estimated as the roots of the fitted smoothing functions, obtained with the function numpy.roots for the polynomials or method root for cv and gcv. To use cv or gcv you must install the statistical software R and the Python module rpy2, since smoothing is effected with the R function smooth.spline. I have used rpy2 successfully with Python 3.7.6. For Linux: https://rpy2.github.io/doc/latest/html/index.html. For Windows: https://anaconda.org/r/rpy2. *Anaconda* offers the following advice in the latter case:

Setting up rpy2 on Windows

Problem

If you install rpy2 on Windows and try to use R objects or R magic commands you may see this error message:

The program can't start because libbz2-1.dll is missing from your computer. Try reinstalling the program to fix this problem.

Solution

To resolve this issue, follow these steps:

- 1. If you have not installed rpy2, install from the R channel on <u>Anaconda.org</u>: conda install -c r rpy2
- 2. After the installation is complete, add the following directory paths to your PATH environment variable. This section can be found here:

 Computer -> Properties -> Advanced System Settings -> Environment Variables

If Anaconda was installed for just you, edit the PATH variable for your user. If you have installed for all users, edit the system PATH which may require admin privileges.

Add the two following lines to the end of what is already there. Be sure the full path should matches your installation path and Anaconda directory name:

C:\Users\username\Anaconda2\Library\mingw-w64\lib;

C:\Users\username\Anaconda2\Library\mingw-w64\bin

Your PATH should now have the following line for Anaconda and rpy2:

C:\Users\username\Anaconda2;C:\Users\username\Anaconda2\Scripts;C:\Users\username\Anaconda2\Library\bin;C:\Users\username\Anaconda2\Library\mingw-w64\bin

Close any open command prompts or python consoles, and relaunch them for the PATH to take effect.

For alternative Windows installations check out https://jianghaochu.github.io/how-to-install-rpy2-in-windows-10.html and https://joonro.github.io/blog/posts/install-rpy2-windows-10/.

Acknowledgement

Funding.

References

Carnevale, N. T. and Hines M. L. (2009). *The NEURON Book*, Cambridge University Press.

Cox S. J. (2008). Direct correction of non-space-clamped currents via Cole's theorem. *Journal of Neuroscience Methods* **169**(2): 366-373.

Gerald C.F. and Wheatly P.O. (1984). *Applied Numerical Analysis*. Addison-Wesley.

Kutner M.H., Nachtsheim C.J., Newman E.L. and Li W. (2004). *Applied Linear Statistical Models*. McGraw-Hill/Irwin

Murphy, R., H. Alle, J. R. P. Geiger and J. F. Storm (2023a). "Estimation of persistent sodium-current density in hippocampal mossy fiber axons: correction of space-clamp errors." *In prep.* **0**: 0-0.

Murphy, R., H. Alle, P. Mateos-Aparicio, J. R. P. Geiger and J. F. Storm (2023b). "Estimation of Kv7/KCNQ/M kinetics in hippocampal mossy fiber axons: correction of space-clamp errors." *In prep.* **0**: 0-0.

Sakmann, B. and E. Neher, Eds. (1995). Single-Channel Recording. New York, NY, Springer.