### RICHARD ROBINSON

# ELECTROMAGNETISM

# Contents

Electrostatics 5

Electrodynamics 7

### **Electrostatics**

#### Electric Forces

In Electrodynamics, there is typically a **source point**  $\mathbf{r}'$  where a charge is located and a **field point**  $\mathbf{r}$  where a field is calculated at. The **seperation vector** is defined as

$$\mathbf{\lambda} \equiv \mathbf{r} - \mathbf{r}' \qquad \hat{\mathbf{\lambda}} = \mathbf{\lambda}/\imath$$
 (1)

The force acting on a charge is given by Coulomb's Law,

$$\mathbf{F} = k \sum \frac{q_1 q_2}{v^2} \hat{\mathbf{z}} = \iiint d\mathbf{F}$$
 (2)

The **electric field** exerted on a positive test charge  $+q_0$  at a point is defined as

$$\mathbf{E} = \frac{\mathbf{F}}{q_0} = k \sum \frac{q}{n^2} \hat{\mathbf{\lambda}} \tag{3}$$

**Field lines** point outwards from +q and towards -q, and are parallel or tangential of an electric field. For a continuous charge distribution,

$$\mathbf{E} = k \iiint \frac{dq}{2^2} \hat{\mathbf{z}} = -\nabla V \tag{4}$$

where

$$dq \sim \lambda \, d\ell \sim \sigma \, dA \sim \rho \, dV \sim \lambda R \, d\phi \sim \sigma 2\pi w \, dw$$
 (5)

The **electric dipole** is a configuration of two equal and opposite charges q separated by a distance d, in which the electric dipole moment p = qd in the direction towards +q. If a dipole is in an external field, the torque is

$$\mathbf{o} = \mathbf{p} \times \mathbf{E} \tag{6}$$

such that the work done by the field is

$$W = -\int_{\theta_0}^{\theta} \tau \, d\theta = pE(\Delta \cos \theta) \tag{7}$$

Consequently, the potential energy is defined as

$$U = -pE\cos\theta = -\mathbf{p}\cdot\mathbf{E} \tag{8}$$




Figure 1: A Gaussian surface as a cylinder.




Figure 2: The field at any is the vector sum of the charges.

#### Potentials

Gauss' Law states the electric flux through a field is

$$\Phi_E = \oiint \mathbf{E} \cdot d\mathbf{A} = \frac{q}{\varepsilon_0} \tag{9}$$

such that  $\|\Phi\| = EA\cos\theta$  where  $\theta$  is the angle between the field and field lines. The electric field outside a conductor is given by

$$E = \frac{\sigma}{\varepsilon_0} \iff q = \iint \sigma \, dA \tag{10}$$

The change in electric potential is defined as

$$\Delta U = kq_1 q_2 (\Delta r^{-1}) \tag{11}$$

For a system of charge, the potential energy is

$$U = k \sum_{i} \sum_{j \neq i} \frac{q_i q_j}{r} \tag{12}$$

Consequently, the change in electric potential is

$$\Delta V = \frac{\Delta U}{q_0} = -\frac{W}{q_0} = -\int \mathbf{E} \cdot d\mathbf{s}$$
 (13)

The electric potential at a point is thus defined as

$$V = k \iiint_{a}^{b} \frac{dq}{r} = k \sum_{i} \frac{q_{i}}{r} \sim k \frac{p \cos \theta}{r^{2}}$$
 (14)

where the latter equivalence holds for dipoles. A surface on which the potential has the same value everywhere is **equipotential** such that  $\Delta V = W = 0$ . The field lines must everywhere be perpendicular to the equipotential surfaces, which implies all conductors are equipotential.




Figure 3: A uniformly charged ring with a potential *P* and charge element *da*.




Figure 4: The geometry for calculating V at P for a dipole.

## Electrodynamics

#### Current

THE ELECTRIC current is defined as

$$i = \frac{dq}{dt} = \int \mathbf{j} \cdot d\mathbf{A} \tag{15}$$

where j is the current density and is opposite the motion of electrons. The net charge passing through is therefore

$$q = \int i \, dt \tag{16}$$

The current density is defined as

$$\mathbf{j} = q/At = -en\mathbf{v} = \sigma\mathbf{E} \tag{17}$$

where n is the electron density and  $\sigma = q/A$  is the conductivity. Furthermore, the net charge passing through the surface q = enAL. The resistance of the material is thus  $R = L/\sigma A = \Delta V/i$ .




Figure 5: A parallel-plate capacitor.

#### Capacitance

#### Capacitance is defined as

$$C = \frac{q}{\Delta V} = \frac{\varepsilon_0 A}{d} \tag{18}$$

In a PPC, SC, and CC, the potential is derived via

$$\Delta V_{ppc} = \frac{qd}{\epsilon A} \qquad \Delta V_{sc} = kq \left( \frac{1}{a} - \frac{1}{b} \right) \qquad \Delta V_{ss} = \frac{q \ln(b-a)}{2\pi \epsilon L} \quad (19)$$

In a parallel combination of capacitors,

$$q = \sum q = C_{eq} \Delta V \iff C_{eq} = \sum C \tag{20}$$

and in a series combination,

$$\Delta V = \sum \Delta V = q/C_{eq} \iff C_{eq}^{-1} = \sum C^{-1}$$
 (21)

As well, the potential energy in a capacitor is

$$dU = \Delta V \, dq \iff U = \int_0^q dU = \frac{q^2}{2C} \tag{22}$$

with  $q = C\Delta V$ . Specifically, the energy U is stored in E in the region. Furthermore, the **energy density** u is defined as

$$u = \frac{U}{Ad} = \frac{1}{2}\varepsilon_0 E^2 \tag{23}$$

by Eqns 18 & 22. Using **voltage division**, the voltage of any impedance Z including capacitance may be found via  $q_0 = \sum q$  by

$$V = \frac{Z_1}{Z_{eq}} V_0 \tag{24}$$

For a dielectric capacitor, the charge is defined as

$$q' = q(1 - 1/\kappa) \iff E = E_0/\kappa \tag{25}$$

DC Circuits