Evaluation Metrics for Regression

Dr. JASMEET SINGH ASSISTANT PROFESSOR, CSED TIET, PATIALA

Regression Evaluation Metrics

- The performance of the regression model is generally measured in terms of error in prediction i.e., the difference between the actual values and the predicted values for all the instances in the test set.
- The various error metrics used in regression analysis are:
- 1. Mean Absolute Error
- 2. Mean Squared Error
- 3. Root Mean Squared Error
- 4. R² Score (Coefficient of Determination)
- 5. Adjusted R² Score

Mean Absolute Error

• The Mean Absolute Error(MAE) is the average of all absolute errors where absolute error is the absolute value of the difference between the measured value (predicted) and "true" value (actual).

Mean Absolute Error (MAE) =
$$\frac{1}{n} \sum_{i=1}^{n} |y_i - y_i^{\wedge}|$$

• where y_i is the actual value, y_i^{\wedge} is the predicted value of i^{th} input of test set and n are the total number of test samples.

Mean Squared Error

The mean squared error (MSE) or mean squared deviation (MSD) of an estimator (of a procedure for estimating an unobserved quantity) measures the average of the squares of the errors—that is, the average squared difference between the estimated values and the actual value

Mean Squared Error (MSE) =
$$\frac{1}{n} \sum_{i=1}^{n} (y_i - y_i^{\wedge})^2$$

• where y_i is the actual value, y_i^{\wedge} is the predicted value of ith input of test set and n are the total number of test samples.

Root Mean Squared Error

- The root-mean-square deviation (RMSD) or root-mean-square error (RMSE) is a frequently used measure of the differences between values (sample or population values) predicted by a model.
- It is the square root of the mean squared error.

Root Mean Squared Error (RMSE) =
$$\sqrt{\frac{1}{n} \sum_{i=1}^{n} (y_i - y_i^{\wedge})^2}$$

where y_i is the actual value, y_i^{\wedge} is the predicted value of i^{th} input of test set and n are the total number of test samples.

R² Score/ Coefficient of Determination

- •It measures the proportion of the variation independent variable explained by all the independent variables in the model.
- It assumes that every independent variable in the model helps to explain variation in the dependent variable.
- It is measured as the ratio of the explained variance of the model is to the total variance of the data.

$$R^{2} = \frac{Explained\ Variance\ of\ the\ model}{Total\ Variance\ of\ the\ data} = \frac{\sum_{i=1}^{n}(y_{i}^{\wedge} - \bar{y})^{2}}{\sum_{i=1}^{n}(y_{i} - \bar{y})^{2}}$$

• where y_i is the actual value, y_i^{\wedge} is the predicted value of i^{th} input of test set, \bar{y} is the mean of actual values of y and n are the total number of test samples.

R² Score

•Alternately, R² Score is measured from the unexplained variance as follows:

$$R^{2} = 1 - \frac{Unexplained\ Variance\ of\ the\ model}{Total\ Variance\ of\ the\ data} 1 - \frac{SSE}{SST} = 1 - \frac{\sum_{i=1}^{n} (y_{i} - y_{i}^{\wedge})^{2}}{\sum_{i=1}^{n} (y_{i} - \bar{y})^{2}}$$

- where SSE denote sum square error and SST denote sum square total.
- The value of R2 lies in between -1 and 1. R² is **negative** only when the chosen model does not follow the trend of the data, so fits worse than the regression line.
- Mathematically, it is possible when error sum-of-squares from the model is larger than the total sum-of-squares from the horizontal line.

Significance of R² Score

- R-squared is a statistical measure of how close the data are to the fitted regression line.
- 0% indicates that the model explains none of the variability of the response data around its mean.
- •100% indicates that the model explains all the variability of the response data around its mean.
- *Higher the R-squared, the better the model fits your data.*

Evaluation Metrics- Numerical Example

Consider that the number lectures per day (x) affects the number of hours spent at university per day (y).

The equation of the regression line is

$$y^{\wedge} = 0.143 + 1.229x$$

Find

- (i) MAE
- (ii) MSE
- (iii) RMSE
- (iv) R² Score

For the test set shown in Table

S.No	X	у		
1	2	2		
2	3	4		
3	4	6		
4	6	7		

Evaluation Metrics- Numerical Example

S.No	Х	У	y ^ = 0.143+1.229 x	Error=y-y ^	Ab. Error= y-y ^	Sq. Error	y-mean(y)	SST
1	2	2	2.601	-0.601	0.601	0.361201	-2.75	7.562 5
2	3	4	3.83	0.17	0.17	0.0289	-0.75	0.562 5
3	4	6	5.059	0.941	0.941	0.885481	1.25	1.562 5
4	6	7	7.517	-0.517	0.517	0.267289	2.25	5.062 5
Total		19			2.229	1.542871	0	14.75

Evaluation Metrics- Numerical Example

Mean Absolute Error =
$$\frac{1}{n}\sum_{i=1}^{n}|y_i - y_i^{\wedge}| = \frac{2.29}{4} = 0.5725$$

Mean Square Error = $\frac{1}{n}\sum_{i=1}^{n}(y_i - y_i^{\wedge})^2 = \frac{1.542871}{4} = 0.3857$
Root Mean Square Error = $\sqrt{\frac{1}{n}\sum_{i=1}^{n}(y_i - y_i^{\wedge})^2} = 0.6210$
 R^2 score = $1 - \frac{SSE}{SST} = 1 - \frac{1.542871}{14.75} = 0.895$

Adjusted R² Score

- It measures the proportion of variation explained by only those independent variables that really affect the dependent variable.
- •It penalizes you for adding independent variable that do not affect the dependent variable.
- Every time you add a independent variable to a model, the R-squared increases, even if the independent variable is insignificant. It never declines.
- •Adjusted R-squared increases only when independent variable is significant and affects dependent variable.

Adjusted R² Score

• Adjusted R² is computed as follows:

Adjusted
$$R^2 = 1 - \frac{(1 - R2)(N - 1)}{(N - k - 1)}$$

- where R² is the sample R-square; k is the number of predictors (independent variables) and N is the total sample size.
- Adjusted R² score must be used to compare different regression models with different number of predictors and in case we want to decide the important predictors in our training set.