#### Caches Part II

#### Review

- We would like to have the capacity of disk at the speed of the processor: unfortunately this is not feasible
- So we create a memory hierarchy:
  - each successively higher level contains "most used" data from next lower level
  - exploits <u>temporal locality</u>
- Locality of reference is a Big Idea

Sill COMP 273

#### Big Idea Review

- Mechanism for transparent movement of data among levels of a storage hierarchy
  - set of address/value bindings
  - address provides index to set of candidates
  - compare desired address with tag
  - service hit or miss
    - load new block and binding on miss

Index	Valid	Tag	0x0 - 0x3	0x4 - 0x7	0x8 - 0xb	0xc - 0xf
0						
<b>→</b> 1	1	0	а	b	С	d
2						
3						

#### Outline

- Block Size Tradeoff
- Types of Cache Misses
- Fully Associative Cache
- N-Way Associative Cache
- Block Replacement Policy
- Multilevel Caches (if time)
- Cache write policy (if time)

## Block Size Tradeoff (1/3)

- Benefits of Larger Block Size
  - Spatial Locality: if we access a given word, we're likely to access other nearby words soon (Another Big Idea)
  - Very applicable with Stored-Program Concept: if we execute a given instruction, it's likely that we'll execute the next few as well
  - Works nicely in sequential array accesses too

## Block Size Tradeoff (2/3)


- Drawbacks of Larger Block Size
  - Larger block size means larger miss penalty
    - on a miss, takes longer time to load a new block from next level
  - If block size is too big relative to cache size, then there are too few blocks
    - Result: miss rate goes up
- In general, minimize
  - Average Access Time
    - = Hit Time + Miss Penalty x Miss Rate

## Block Size Tradeoff (3/3)

- <u>Hit Time</u> = time to find and retrieve data from current level cache
- Miss Penalty = average time to retrieve data on a current level miss (includes the possibility of misses on successive levels of memory hierarchy)
- Hit Rate = % of requests that are found in current level cache
- Miss Rate = 1 Hit Rate

Sill COMP 273

#### **Block Size Tradeoff Conclusions**



## Types of Cache Misses (1/2)

#### Compulsory Misses

- occur when a program is first started
- cache does not contain any of that program's data yet, so misses are bound to occur
- can't be avoided easily, so won't focus on these in this course

## Types of Cache Misses (2/2)

#### Conflict Misses

- miss that occurs because two distinct memory addresses map to the same cache location
- two blocks (which happen to map to the same location) can keep overwriting each other
- big problem in direct-mapped caches
- how do we lessen the effect of these?

### Dealing with Conflict Misses


- Solution 1: Make the cache size bigger
  - relatively expensive
- Solution 2: Multiple distinct blocks can fit in the same Cache Index?

# Fully Associative Cache (1/3)

- Memory address fields:
  - Tag: same as before
  - Offset: same as before
  - Index: non-existent
- What does this mean?
  - any block can go anywhere in the cache
  - must compare with all tags in entire cache to see if data is there

# Fully Associative Cache (2/3)

- Fully Associative Cache (e.g., 32 Byte block)
  - compare tags in parallel



McGill COMP 273

15

# Fully Associative Cache (3/3)

- Benefit of Fully Assoc Cache
  - No Conflict Misses (since data can go anywhere)
- Drawbacks of Fully Assoc Cache
  - Need hardware comparator for every single entry:
    - If we have a 64KB of data in cache with 4B entries, we need 16K comparators:
       very expensive
- Small fully associative cache may be feasible

### Third Type of Cache Miss

- Capacity Misses
  - miss that occurs because the cache has a limited size
  - miss that would not occur if we increase the size of the cache
     (or... miss that would not occur if you made the cache FA with LRU policy)
  - sketchy definition, so just get the general idea
- This is the primary type of miss for Fully Associate caches.

## N-Way Set Associative Cache (1/4)

- Memory address fields:
  - Tag: same as before
  - Offset: same as before
  - Index: points us to the correct "row" (called a <u>set</u> in this case)
- So what's the difference?
  - each set contains multiple blocks
  - once we've found correct set, must compare with all tags in that set to find our data

## N-Way Set Associative Cache (2/4)

#### • Summary:

- cache is direct-mapped with respect to sets (where the index is applied)
- each set is fully associative
- If we have T blocks total, then we basically have an T/N directmapped cache (number of sets), where at each index we find a fully associative N block cache. Each has its own valid bit and data.

## N-Way Set Associative Cache (3/4)

- Given memory address:
  - Find correct set using Index value.
  - Compare Tag with all Tag values in the determined set.
  - If a match occurs, it's a hit, otherwise a miss.
  - Finally, use the offset field as usual to find the desired data within the desired block.

# N-Way Set Associative Cache (4/4)

- What's so great about this?
  - even a 2-way set associative cache avoids a lot of conflict misses
  - hardware cost isn't that bad: only need N comparators
- In fact, for a cache with M blocks,
  - it's Direct-Mapped if it's 1-way set associative (1 block per set)
  - it's Fully Associative if it's M-way set associative (M blocks per set)
  - so these two are just special cases of the more general set associative design

# Block Replacement Policy (1/2)

- Direct-Mapped Cache: index completely specifies which position a block can go in on a miss
- N-Way Set Assoc (N > 1): index specifies a set, but block can occupy any position within the set on a miss
- Fully Associative: block can be written into any position (there is no index)
- Question: if we have the choice, where should we write an incoming block?

# Block Replacement Policy (2/2)

- Solution!
- If there are any locations with valid bit off (empty), then usually write the new block into the first one.
- If all possible locations already have a valid block, we must use a <u>replacement policy</u> by which we determine which block gets "cached out" on a miss.

## Block Replacement Policy: LRU

- LRU (Least Recently Used)
  - Idea: cache out block which has been accessed (read or write) least recently
  - Pro: <u>temporal locality</u> => recent past use implies likely future use: in fact, this is a very effective policy
  - Con: with 2-way set assoc, easy to keep track (one LRU bit); with 4-way or greater, requires complicated hardware and much time to keep track of this

### Block Replacement Example

 We have a 2-way set associative cache with a four word total capacity and one word blocks. We perform the following word accesses (ignore bytes for this problem):

0, 8, 0, 4, 16, 0, 9, 12, 20, 16

How many hits and how many misses will there for the LRU block replacement policy?

#### Block Replacement Example: LRU

• Addresses 0, 8, 0, 4, 16, 0, ...

Offset: 2 bits (the

first two low `

significant bits in

the address)

Index: 1 bit (third

low significant bit)

Tag: the rest.

0: miss, bring into set 0 (loc 0)


8: miss, bring into set 0 (loc 1)

0: <u>hit</u>

4: miss, bring into set 1 (loc 0)

16: miss, bring into set 0 (loc 1, replace 8)

0: <u>hit</u>



Block 0 Bloc 1

#### Ways to reduce miss rate

- Larger cache
  - limited by cost and technology
  - hit time of first level cache < cycle time</p>
- More places in the cache to put each block of memory associativity
  - fully-associative
    - any block any line
  - k-way set associated
    - k places for each block
    - direct map: k=1

#### Big Idea


- How do we chose between options of associativity, block size, replacement policy?
- Design against a performance model
  - Minimize: Average Access Time
    - = Hit Time + Miss Penalty x Miss Rate
  - influenced by technology and program behavior

### Example

- Assume
  - Hit Time = 1 cycle
  - Miss rate = 5%
  - Miss penalty = 20 cycles
- Average memory access time = 1 + 0.05 x 20
   = 2 cycle

### Improving Miss Penalty


- When caches first became popular,
   Miss Penalty ~ 10 processor clock cycles
- Today: 1 GHz Processor (1 ns per clock cycle) and 100 ns to go to DRAM
   ⇒ 100 processor clock cycles!



Solution: another cache between memory and the

processor cache: Second Level (L2) Cache

#### Analyzing Multi-level cache hierarchy



Avg Mem Access Time = L1 Hit Time + L1 Miss Rate \* L1 Miss Penalty

L1 Miss Penalty = L2 Hit Time + L2 Miss Rate \* L2 Miss Penalty

Avg Mem Access Time = L1 Hit Time +
L1 Miss Rate \* (L2 Hit Time + L2 Miss Rate \* L2 Miss Penalty)

### **Typical Scale**

- L1
  - size: tens of KB
  - hit time: complete in one clock cycle
- L2
  - size: hundreds of KB
  - hit time: few clock cycles
- L2 miss rate includes L1 misses that also miss in L2

### Example: without L2 cache

- Assume
  - L1 Hit Time = 1 cycle
  - L1 Miss rate = 5%
  - L1 Miss Penalty = 100 cycles
- Average memory access time =  $1 + 0.05 \times 100$ =  $\frac{6}{2} \times 100 \times 100$

#### Example with L2 cache

- Assume
  - L1 Hit Time = 1 cycle
  - L1 Miss rate = 5%
  - L2 Hit Time = 5 cycles
  - L2 Miss rate = 15%
  - L2 Miss Penalty = 100 cycles
- L1 miss penalty = 5 + 0.15 \* 100 = 20
- Average memory access time = 1 + 0.05 x 20= 2 cycle

3x faster with L2 cache

#### What to do on a write hit?

- Write-through
  - update the word in cache block and corresponding word in memory
- Write-back
  - update word in cache block
  - allow memory word to be "stale"
  - add 'dirty' bit to each line indicating that memory needs to be updated when block is replaced
  - OS flushes cache before I/O !!!
- Performance trade-offs?

## "And in conclusion..." (1/2)

- Caches are NOT mandatory:
  - Processor performs arithmetic
  - Memory stores data
  - Caches simply make data transfers go <u>faster</u>
- Each level of memory hierarchy is just a subset of next lower level
- Caches speed up due to temporal locality: store data used recently
- Block size > 1 word speeds up due to spatial locality: store words adjacent to the ones used recently

## "And in conclusion..." (2/2)

- Cache design choices:
  - size of cache: speed v. capacity
  - direct-mapped v. associative
  - for N-way set assoc: choice of N
  - block replacement policy
  - 2nd level cache?
  - Write through v. write back?
- Use <u>performance model</u> to pick between choices, depending on programs, technology, budget, ...

#### Review and More Information

• Sections 5.3 - 5.4 of textbook