# MSc Course - High Performance Computing

# Single Processor Machines: Memory Hierarchies, Memory Bandwidth, Processor Features and Locality

Olaf Schenk
ICS - Institute of Computational Science
USI Lugano, Switzerland
October 01, 2019

## Outline



Introduction memory hierarchy

- Cache mappings
- Memory access
- Case study: Matrix-matrix multiplication

## Motivation

- Most applications run at < 5% of the "peak" performance of a system
  - Peak is the maximum the hardware can physically execute
- Much of this performance is lost on a single processor, i.e., the code running on one processor often runs at only 5% of the processor peak
- Most of the single processor performance loss is in the memory system
  - Moving data takes much longer than arithmetic and logic
- To understand this, we need to look under the hood of modern processors
  - For today, we will look at only a single "core" processor
  - These issues will exist on processors within any parallel computer

## Uniprocessors in the Real World

- Real single-core processors have
  - registers and caches
    - small amounts of fast memory, store values of recently used or nearby data, different memory ops can have very different costs
  - parallelism
    - multiple "functional units" that can run in parallel
    - different orders, instruction mixes have different costs

## pipelining

- a form of parallelism, like an assembly line in a factory
- Why is this your problem?
  - In theory, compilers and hardware "understand" all this and can optimize your program; in practice they don't.
  - They won't know about a different algorithm that might be a much better "match" to the problem

In theory there is no difference between theory and practice.

But in practice there is.


-J. van de Snepscheut




## **About Memory**

- Memory plays a crucial role in performance
- Not accessing memory in the right way will degrade performance on all computer systems
- The extent of the degradation depends on the system
- Knowing more about some of the relevant memory characteristics will help you to write codes such that the problem will be non-existent, or at least minimal

# Typical Cache Based System






Typical size (e.g. Intel Xeon):

- L2 cache 2 MB (=1024 cache lines)
- Cache line 32\*64 Bytes = 2 K

Memory Optimization:
Keep frequently used data close to
the processor

## The Memory Hierarchy


- Most programs have a high degree of locality
  - spatial locality: accessing things nearby previous accesses
  - temporal locality: reusing an item that was previously accessed
- Memory hierarchy use this to improve average case



Speed	1ns	10ns	100ns	10ms	10sec
Size	KB	MB	GB	ТВ	РВ

# Memory Bandwidth Gap

## Memory Bandwidth is Falling Behind: (GFLOP/s) / (GWord/s)






THE UNIVERSITY OF TEXAS AT AUSTIN

#### TEXAS ADVANCED COMPUTING CENTER

# Memory Latency Gap is Worse


## Memory Latency is much worse: (GFLOP/s) / (Memory Latency)






THE UNIVERSITY OF TEXAS AT AUSTIN

#### TEXAS ADVANCED COMPUTING CENTER



# Example – 13<sup>th</sup> degree polynomial

```
for ( i=0 ; i<vlen; i ++)
p[i]=c[0]+q[i]*(c[1]+q[i]*(c[2]+q[i]*(c[3]+ q[i] ...
```




This operation is **CPU bound** i.e. there are much more floating point operations than memory references

- The system realizes over 98% of the absolute peak performance
- Note that's startup effect and the performance drop for larger problems

## Example – Vector Addition

```
for ( i=0 ; i<vlen; i ++)
p[i]= q[i] + r[i];
```




## This operation is <u>memory bound</u>

i.e. there are much more memory references than floating point operations

 Note the start-up effect and the performance drop for larger problems

## Outline

• Intro memory hierarchy



- Memory access
- Case study: Matrix-matrix multiplication

## Cache Choices

- Modern systems use a wide variety of caches
- Typically there are at least 3 types of caches
  - Instruction cache
  - Data cache(s)
  - Page Address Cache (TLB)
- Some key design criteria
  - Size
  - Architecture/Mapping
  - Usage and cost are amongst the key decision factors

## Cache Line Replacement

- Caches have a finite size
- A natural problem is how to replace data
- Three typical methods of doing this:
  - Direct Mapped

Location: Memory location modulo cache size

- Fully Associative


Location: Least Recently Used (LRU, oldest cache line)

– X-way-Set Associative\*

Location: Choose a set first; direct mapped in set

\*Note: X is typically 2, 4 or 8

# A Direct Mapped Cache



## Example Direct Cache Mapping

```
float a[4096], b[4096];
for (i=0; i< 4096; i ++)
sum += a[i]*b[i];
```

#### Assumption:

• A cache line 8\*4 Byte = 32 Byte

```
miss: brings a[0] ... a[7] into cache
load a[0] into a req.
load b[0] into a reg.
                         miss: brings b[0] ... b[7] into cache
sum +=a[0]*b[0]
load a[1] into a reg. hit: brings a[1] still in cache
                         hit: brings b[1] still in cache
load b[1] into a req.
sum +=a[1]*b[1]
                   . . . etc . . .
load a[7] into a reg. hit: brings a[7] still in cache
load b[7] into a reg. hit: brings b[7] still in cache
sum +=a[7]*b[7]
load a[8] into a reg. miss: brings a[8] ... a[15] into cache
                         miss: brings b[8] ... b[15] into cache
load b[8] into a reg.
sum +=a[8]*b[8]
load a[9] into a reg. hit: brings a[9] still in cache
load b[9] into a req.
                         hit: brings b[9] still in cache
sum +=a[9]*b[9]
```


## Assume Different Memory Lay-out

```
float a[4096], b[4096];
for (i=0; i< 4096; i ++)
sum += a[i]*b[i];
```

#### Assumption:

- A cache line 8\*4 Byte = 32 Byte
- The cache size is 16 Kbyte

#### **Main memory**



#### Cache

a[0]	a[7]	
a[8]	a[15]	)    - 
a[16]		b
		)Te
	a[4096]	Š

The cache is completely filled in a[4096]

## Every Reference is a Cache Miss!

```
float a[4096], b[4096];
for (i=0 ; i< 4096; i ++)
sum += a[i]*b[i];
```

#### Assumption:


- A cache line 8\*4 Byte = 32 Byte
- The cache size is 16 Kbyte

```
load a[0] into a req.
                           miss: brings a[0] ... a[7] into cache
load b[0] into a req.
                           miss: brings b[0] ... b[7] into cache
                           load of b[0] removes a[0]..a[7]
sum +=a[0]*b[0]
load a[1] into a req.
                           miss: a[1] has just been removed
                           load of a[1] removes b[0]..b[7]
load b[1] into a req.
                           miss: b[1] has just been removed
                           load of b[1] removes a[0]..a[7]
sum +=a[1]*b[1]
load a[2] into a req.
                           miss: a[2] has just been removed
                           load of a[2] removes b[0]..b[7]
load b[2] into a reg.
                           miss: b[2] has just been removed
                           load of b[2] removes a[0]..a[7]
sum +=a[2]*b[2]
```

## Padding – Change Address


```
float a[4096], padd, b[4096];
for (i=0 ; i< 4096; i ++)
  sum += a[i]*b[i];</pre>
```

## **Main memory**



## X-way Set Associative

- Alternative to the direct mapped cache  $\rightarrow$  have a bunch of them
- Example: 4-way set associative



## Comments


- Choice of a set can be random or last recently used.
- The more sets, the better
- Issues
  - Size per set is 1/x of total
  - Higher chance of thrashing on one set
  - More loads/stores than sets → behavior similar to direct mapped, but set size is smaller

```
Choose a set and within that set:

Cache Location = Memory Adress % Cache Size
```

## Outline


- Intro memory hierarchy
- Cache mappings



• Case study: Matrix-matrix multiplication

## Cache lines

- For **good performance**, it is crucial to use the cache(s) in the intended (=optimal) way
- Recall that the unit of transfer is a cache line
- A cache line is a linear structure i.e. it has a fixed length (in bytes) and a starting address in memory




## Cache Line Utilization

- Two Key <u>Rules for Performance</u> <u>Maximize</u>
- Spatial Locality Use all data in one cache line

This strongly depends on the storage of your data and the access patterns

• **Temporal Locality** – Re-use data in a cache line

This mainly depends on the algorithm used



- On the left we show a typical vector style of coding
- It is not a good approach for cache based systems: all grid elements have to be reloaded for each loop


 It is more beneficial to pre-calculate expression on the already loaded grid points

## Cache Types

- Generally, one can distinguish 3 different caches:
  - Data cache
     Most important in scientific applications
  - Instruction Cache
     More important in business applications
  - TLB Cache (to cache address translation)
     Important for every application
- If these caches are not used in the **expected way**, bad things can happen
- So what is the expected way?

## Memory Access


- Memory has always a 1D linear structure
- Access to multi-dimensional arrays depends on the way data is stored
- This is language dependent:



Bad Memory Access has a Huge Impact on Performance


# Non-unit Stride is always Bad

- If one follows the storage order in memory, all is well; This is called unit stride or (stride=1)
- If data is accessed with **non-unit stride**:




## Experimental Study of Memory

Micro benchmark for memory system performance




# Experimental Study of Memory: What to expect




- Consider the average cost per load
  - Plot one line for each array length, time vs. stride
  - Small stride is best: if cache line holds 4 words, at most ¼ miss
  - If array is smaller than a given cache, all those accesses will hit (after the first run, which is negligible for large enough runs)
  - Picture assumes only one level of cache
  - Values have gotten more difficult to measure on modern procs

## Experimental Study of Memory: AMD Opteron Processor



# SIMD: Single Instruction, Multiple Data


- Scalar processing
  - traditional mode
  - one operation produces one result
- SIMD processing
  - with SSE / SSE2
  - SSE = streaming SIMD extensions
  - one operation **produces** multiple results



Slide Source: Alex Klimovitski & Dean Macri, Intel Corporation

## SSE / SSE2 SIMD on Intel

• SSE2 data types: anything that fits into 16 bytes, e.g.,



- Instructions perform add, multiply etc. on all the data in this 16byte register in parallel
- Challenges: Need to be contiguous in memory and aligned
- Similar on GPUs, vector processors (but many more simultaneous operations)
- Oct 2012: **Intel Xeon Phi** with single-instruction-multiple-data (**SIMD**) instructions using **64 bytes** (512-bits) = 8 doubles

# What does this mean to you?

- In addition to SIMD extensions, the processor may have other special instructions
  - Fused Multiply-Add (FMA) instructions:

$$x = y + c * z$$

is so common some processor execute the multiply/add as a single instruction, at the same rate (bandwidth) as + or \* alone

- In theory, the compiler understands all of this
  - When compiling, it will rearrange instructions to get a good "schedule" that maximizes pipelining, uses FMAs and SIMD
- But in practice the compiler may need your help
  - Choose a different compiler, optimization flags, etc.
  - Rearrange your code to make things more obvious
  - Using special functions ("intrinsics") or write in assembly ☺

## Outline

- Intro memory hierarchy
- Cache mappings
- Memory access



Case study: Matrix-matrix multiplication

### Lessons

- Actual performance of a simple program can be a complicated function of the architecture
  - Slight changes in the architecture or program change the performance significantly
  - To write **fast programs**, need to consider architecture
    - True on sequential or parallel processor
  - We would like simple models to help us design efficient algorithms
- We will illustrate with a common technique for improving cache performance, called **blocking** 
  - Idea: used divide-and-conquer to define a problem that fits in register/L1-cache/L2-cache

## Case study: Matrix-Matrix Multiplication

- Case study: Matrix-Matrix Multiplication
  - Use of performance models to understand performance
  - Simple cache model
- Why Matrix Multiplication?
  - Appears in many linear algebra algorithms
- Optimization ideas can be used in other problems
- The best case for optimization payoffs
- The most-studied algorithm in high performance computing

# Case study: Matrix Multiplication

- Assume just 2 levels in the memory hierarchy, fast and slow
- CPU with Slow Memory

- All data initially in slow memory
  - m = number of memory elements (words) moved between fast and slow memory

    Computational
  - $t_m = time per slow memory operation$
  - f = number of arithmetic operations
  - $t_f$  = time per arithmetic operation in fast memory <<  $t_m$
  - q = f/m average number of flops per slow memory access
- Minimum possible time =  $f^* t_f$  when all data in <u>fast memory</u>
- Actual time

$$- f * t_f + m * t_m = f * t_f * (1 + t_m/t_f * m/f) = f * t_f * (1 + t_m/t_f) * 1/q)$$

- Larger q means time closer to minimum f \* t<sub>f</sub>
  - $-\mathbf{q} \ge \mathbf{t_m}/\mathbf{t_f}$  needed to get at least half of peak speed

Machine Balance: Key to machine efficiency

**Intensity: Key to** 

algorithm efficiency


## Warm up: Vector-vector operation

• **Assumption:** Fast memory large enough to store 2 vectors, "a" is a scalar, x, y are vectors

- $m = number of slow memory accesses \rightarrow m = 3n$
- f = number of floating point operations  $\rightarrow 2n$
- q = average number of flops per slow memory access = f / m = 2/3
- Vector-vector addition is dominated by slow memory access

# Warm up: Matrix-vector multiplication

```
// implements y = y + A*x
for i = 1:n
    for j = 1:n
        y(i) = y(i) + A(i,j)*x(j)
```



# Warm up: Matrix-vector multiplication

**Assumption:** Fast memory large enough to store 2 vectors y and x and one row of matrix A


```
read x(1:n) into fast memory
read y(1:n) into fast memory
for i = 1:n
        read row i of A into fast memory
        for j = 1:n
            y(i) = y(i) + A(i,j)*x(j)
write y(1:n) back to slow memory
```

- $m = number of slow memory refs \rightarrow m = 3n + n^2$
- $f = number of arithmetic operations \rightarrow f = 2n^2$
- $q = f / m \sim = 2$
- Matrix-vector multiplication is limited by slow memory speed

## Naive Matrix-Matrix Multiplication

```
// computes C = C + A*B
for i = 1 to n
   for j = 1 to n
   for k = 1 to n
        c(i,j) = c(i,j) + a(i,k) * b(k,j)
```

• Algorithm has  $2*n^3 = O(n^3)$  Flops and operates on  $4*n^2$  words of memory  $\rightarrow$  q potentially as large as  $2*n^3 / 4*n^2 = O(n)$ 



## Naive Matrix-Matrix Multiplication

**Assumption:** Fast memory large enough to store one row of the matrices A, B and C.

• Number of **slow memory** references on unblocked matrix multiply


```
\mathbf{m} = \mathbf{n}^3 to read each column of B \mathbf{n}^2 times 
 + \mathbf{n}^2 to read each row of A once 
 + 2\mathbf{n}^2 to read and write each element of C once 
 = \mathbf{n}^3 + 3\mathbf{n}^2
```

So  $q = f / m = 2n^3 / (n^3 + 3n^2) \sim 2$  for large n, **no improvement** over matrix-vector multiply, but on previous slide it was O(n)!

### **Blocked Matrix Multiply**

• **Assumption:** Fast memory large enough to store small subblocks row of the matrices A, B and C.

```
Consider A,B,C to be n-by-n matrix viewed as
  N-by-N matrices of b-by-b subblocks where
 / b=n/N is called the block size
for I = 1 to N
   for J = 1 to N
       read block C(I,J) into fast memory
       for K = 1 to N
       read block A(I,K) into fast memory
       read block B(K,J) into fast memory
       // do a matrix multiply on blocks
       C(I,J) = C(I,J) + A(I,K) * B(K,J)
       write block C(I,J) back to slow memory
```



## **Blocked Matrix Multiply**

#### • Recall:

- m is amount memory traffic between slow and fast memory
- matrix has nxn elements, and NxN blocks each of size bxb
- f is number of floating point operations, 2n<sup>3</sup> for this problem
- -q = f / m is the measure of algorithm efficiency in the memory model

#### • So:

```
\mathbf{m} = \mathbf{N}^* \mathbf{n}^2 read each block of B N³ times (\mathbf{N}^3 * \mathbf{b}^2 = \mathbf{N}^3 * (\mathbf{n}/\mathbf{N})^2 = \mathbf{N}^* \mathbf{n}^2)
+ \mathbf{N}^* \mathbf{n}^2 read each block of A N³ times
+ \mathbf{2n}^2 read and write each block of C once
= (\mathbf{2N} + \mathbf{2}) * \mathbf{n}^2
```

### • The computational intensity is

$$q = f / m = 2n^3 / ((2N + 2) * n^2) \sim = n / N = b$$
 for large n

So we can improve performance by **increasing** the blocksize (**cachesize**) b and can be much faster than matrix-vector multiply (q=2)

## Using Analysis to Understand Machines

### The blocked algorithm has <u>computational intensity $q \sim = b$ </u>

- The larger the block size, the more efficient our algorithm will be
- Limit: All three blocks from A,B,C must fit in fast memory (cache), so we cannot make these blocks arbitrarily large
- Assume your fast memory has size M<sub>fast</sub>

$$3b^2 \le M_{fast}$$
, so  $q = b \le sqrt(M_{fast}/3)$ 

• To build a machine to run matrix multiply at 1/2 peak arithmetic speed of the machine, we need a fast memory of size

$$M_{fast} >= 3b^2 \sim = 3q^2 = 3(t_m/t_f)^2$$

- What if more levels of memory hierarchy?
  - Apply blocking recursively, once per level


## Use optimized libraries for matrix-/vector operations


- Industry library standard interface: www.netlib.org/blas
- Vendors, others supply highly optimized implementations

### BLAS – Basic Linear Algebra Subroutines

- BLAS1 (1970s):
  - vector operations: dot product, saxpy (y=a\*x+y), etc
  - $m=2*n, f=2*n, q \sim 1 \text{ or less}$
- BLAS2 (mid 1980s)
  - matrix-vector operations: matrix vector multiply, etc
  - m=n<sup>2</sup>, f=2\*n<sup>2</sup>, q~2, less overhead
  - somewhat faster than BLAS1
- BLAS3 (late 1980s/earlier 90)
  - matrix-matrix operations: matrix-matrix multiply, etc
  - $-m \le 3n^2$ , f=O(n<sup>3</sup>), so q=f/m can possibly be as large as n, so BLAS3 is potentially much faster than BLAS2
- Good algorithms used BLAS3 when possible (LAPACK & ScaLAPACK)
- LAPACK: Linear Algebra Package
  ScaLAPACK: Scalable Linear Algebra Packages (parallel)

### Real Matrix-Matrix Performance on CUB Cluster





### A last note on the complexity of matrix multiply

- The traditional algorithm (with or without blocking) has  $O(n^3)$  flops
- $n \times n \text{ Matrix} = 2 \times 2 \text{ Matrix with } n/2 \times n/2 \text{ block matrices}$

```
Let M = | m11 m12 | = | a11 a12 | * | b11 b12 |

| m21 m22 | = | a21 a22 | | b21 b22 |

m11 = a11*b11 + a12*b21, m12 = a11*b12 + a12*b22

m21 = a21*b11 + a22*b21, m22 = a21*b12 + a22*b22
```

- Reduction to four sub problems with
  - 2 multiplications von n/2 x n/2 matrices
  - 1 addition von n/2 x n/2 matrices
  - Total: 8 Mult, 4 Adds

• Complexity: 
$$T(n) = 8 * T(n/2) + \theta (n^2)$$

#subproblems / size of subproblems / complexity for addition  $= 8 (n/2)^3 = n^{\log_2 8} = n^3$ 
 $= \theta (n^3)$  No reduction!

# A last note on the complexity of matrix multiply

- Upper complexity bound for matrix-matrix multiply?
- Lower complexity bound for matrix-matrix multiply?

## Complexity of Strassen's Matrix Multiply

m22 = p2 - p3 + p5 - p7

- Strassen discovered an algorithm with asymptotically lower flops
   O(n<sup>2.81</sup>)
- Consider a 2x2 matrix multiply, normally takes 8 multiplies, 4 adds
  - Strassen does it with 7 multiplies and 18 adds

```
Let M = | m11 m12 | = | a11 a12 | * | b11 b12 |
| m21 m22 | = | a21 a22 | | b21 b22 |
Let p1 = (a12 - a22) * (b21 + b22)
p2 = (a11 + a22) * (b11 + b22)
p3 = (a11 - a21) * (b11 + b12)
p4 = (a11 + a12) * b22
Then m11 = p1 + p2 - p4 + p6
m12 = p4 + p5
m21 = p6 + p7
Complexity:
T(n) = 7 * T(n/2) + \theta (n^2)
```

$$T(n) = 7 * T(n/2) + \theta (n^2)$$
#subproblems / size of subproblems / complexity for addition
$$= 7 (n/2)^3 = n^{\log_2 7} + \theta (n^2)$$

$$= \theta (n^{2.81})$$

### Summary

- Today's memory hierarchy is very complex
- Performance often depends on the problem size
- Caches play a crucial role in performance
- Key to using memory in the right way:
  - Access your data in storage order
  - Re-use data where possible
- Spatial and temporal locality
- Use optimized libraries as often as possible in your code.