1.1 Electromagnetic Fields

Rkka

August 2024

1 Energy law

The electric and magnetic energy in a given volume V are respectively :

$$W_e = \int_V d\tau (\frac{1}{2}\vec{E} \cdot \vec{D}) \tag{1}$$

$$W_m = \int_V d\tau (\frac{1}{2} \vec{H} \cdot \vec{B}) \tag{2}$$

The electromagnetic energy law is

$$\frac{dW}{dt} + \int_{V} d\tau (\vec{j} \cdot \vec{E}) + \int_{\partial V} \vec{S} \cdot \vec{n} da$$

where $W = W_e + W_m$ and $\vec{S} = \vec{E} \times \vec{H}$.

(Proof)

Start from : $\nabla \times \vec{H} - \frac{\partial}{\partial t}D = \vec{j}$. Applying $\vec{E} \cdot$ on both side,

$$\vec{E} \cdot (\nabla \times \vec{H}) - \vec{E} \cdot \frac{\partial}{\partial t} \vec{D} = \vec{E} \cdot \vec{j}$$
 (3)

Similarily, for $\nabla \times E + \frac{\partial}{\partial t} B = 0$, applying $\vec{H} \cdot$ on both side :

$$\vec{H} \cdot (\nabla \times \vec{E}) + \vec{H} \cdot \frac{\partial}{\partial t} \vec{B} = 0 \tag{4}$$

(Note) $\nabla \cdot (\vec{A} \times \vec{B}) = \vec{B} \cdot (\nabla \times \vec{A}) - \vec{A} \cdot (\nabla \times \vec{B})$. Then,

$$\vec{H}\cdot(\nabla\times\vec{E})-\vec{E}\cdot(\nabla\times\vec{H})=-\vec{H}\cdot\tfrac{\partial}{\partial t}\vec{B}-\vec{E}\cdot\tfrac{\partial}{\partial t}\vec{D}-\vec{E}\cdot\vec{j}$$

$$\rightarrow \nabla \cdot (\vec{E} \times \vec{H}) + [\vec{E} \cdot \tfrac{\partial}{\partial t} \vec{D} + \vec{H} \cdot \tfrac{\partial}{\partial t} \vec{B}] + \vec{j} \cdot \vec{E} = 0$$

In integral form,

$$\int_{\partial V} (\vec{E} \times \vec{H}) \cdot \vec{n} da + \int_{V} d\tau [\vec{E} \cdot \frac{\partial}{\partial t} D + \vec{H} \cdot \frac{\partial}{\partial t} \vec{B}] + \int_{V} d\tau (\vec{j} \cdot \vec{E}) = 0$$
 (5)

This is the energy law of Electromagnetism. We can simplify when we assume the simple material equations : $\vec{j} = \sigma \vec{E}$, $\vec{D} = \epsilon \vec{E}$, $\vec{B} = \mu \vec{H}$. Then,

$$\vec{E} \cdot \frac{\partial}{\partial t} \vec{D} = \vec{E} \cdot \frac{\partial}{\partial t} \epsilon \vec{E} = \frac{1}{2} \frac{\partial}{\partial t} (\epsilon \vec{E}^2) = \frac{1}{2} \frac{\partial}{\partial t} (\vec{E} \cdot \vec{D})$$

Similarily,

$$\vec{H} \cdot \tfrac{\partial}{\partial t} \vec{B} = \vec{H} \cdot \tfrac{\partial}{\partial t} \mu \vec{H} = \tfrac{1}{2} \tfrac{\partial}{\partial t} (\mu \vec{H}^2) = \tfrac{1}{2} \tfrac{\partial}{\partial t} (\vec{H} \cdot \vec{B})$$

Then

$$\int_{V} d\tau \left[\frac{1}{2} \frac{\partial}{\partial t} (\vec{E} \cdot \vec{D}) + \frac{1}{2} \frac{\partial}{\partial t} (\vec{H} \cdot \vec{B}) \right] + \int_{V} d\tau (\vec{j} \cdot \vec{E}) + \int_{\partial V} (\vec{E} \times \vec{H}) \cdot \vec{n} da = 0$$

$$\rightarrow \frac{d}{dt} \int_{V} d\tau \left[\frac{1}{2} (\vec{E} \cdot \vec{D}) + \frac{1}{2} (\vec{H} \cdot \vec{D}) \right] + \int_{V} d\tau (\vec{j} \cdot \vec{E}) + \int_{\partial V} (\vec{E} \times \vec{H}) \cdot \vec{n} da = 0$$

$$\Rightarrow \boxed{\frac{dW}{dt} + \int_{V} d\tau (\vec{j} \cdot \vec{E}) + \int_{\partial V} \vec{S} \cdot \vec{n} da = 0}$$
with $\vec{S} = \vec{E} \times \vec{H}$
(QED)

1.1 More physical representation

When A: total work done to charges,

$$\begin{split} \delta A &= \sum_k \vec{F}_k \cdot \delta \vec{x}_k = \sum_k q_k (\vec{E}_k + \vec{v}_k \times \vec{B}_k) \cdot \delta \vec{x}_k \\ &= \sum_k q_k \vec{E}_k \cdot \delta \vec{x}_k = \sum_k q_k \vec{E}_k \cdot \vec{v}_k \delta t \\ &\to \delta A = \delta t \int_V d\tau (\rho \vec{E} \cdot \vec{v}) \end{split}$$

But, since Maxwell's equations do not contain a velocity \vec{v} , we should remove it to restate the energy law.

Roentgen's experimental discovery: (1) Convection current(moving charges) $\vec{j}_v = \rho \vec{v}$ and (2) Conduction current(electric fields) $\vec{j}_c = \sigma \vec{E}$ give same physical(electromagnetic) effects. $\rightarrow \vec{j} = \vec{j}_c + \vec{j}_v$

So, $\delta A = \delta t \int_V d\tau \vec{j}_v \cdot \vec{E}$. Now, define a scalar $Q \equiv Joule's \ heat$ as:

$$Q \equiv \int_V d\tau \vec{j}_c \cdot \vec{E} = \int_V d\tau \sigma \vec{E}^2$$

Then,

$$\int_V d\tau (\vec{j} \cdot \vec{E}) = \int_V d\tau (\vec{j_c} + \vec{j_v}) \cdot \vec{E} = Q + \int_V d\tau (\vec{j_v} \cdot \vec{E}) = Q + \frac{\delta A}{\delta t}$$

Hence, the energy law :

$$\frac{dW}{dt} = -\frac{\delta A}{\delta t} - Q - \int_{\partial V} \vec{S} \cdot \vec{n} da$$

When $\sigma=0$ (nonconducting) and A=0 (no mechanical work) $\Rightarrow \frac{dw}{dt} + \nabla \cdot \vec{S} = 0$: note that this is a differential form.