

# **CXBanking OptiVault 10.1**Installation Guide

Version 10.1.0 Build 3132 April 2023

# **Copyright and Trademark Information**

The products described in this document are copyrighted works of NCR Corporation.

NCR and APTRA are trademarks of NCR Corporation.

Microsoft and Windows are registered trademarks or trademarks of Microsoft Corporation in the United States and/or other countries.

All other trademarks are the property of their respective owners.

It is the policy of NCR Corporation (NCR) to improve products as new technology, components, software, and firmware become available. NCR, therefore, reserves the right to change specifications without prior notice.

All features, functions, and operations described herein may not be marketed by NCR in all parts of the world. In some instances, photographs are of equipment prototypes. Therefore, before using this document, consult with your NCR representative or NCR office for information that is applicable and current.

© 2020 NCR Corporation Atlanta Georgia USA www.ncr.com

All Rights Reserved

# **Revision Record**

Date	Page No.	Description of Change
January 2023	ALL	Formatting Changes
April 2023	58	Added Note under EPSS Integration for 10.1 Installation

# **Contents**

Co	pyrig	ght and Trademark Information	2
Re	visio	n Record	3
Co	nten	ts	4
Pr	eface	2	8
	Docu	ument conventions	8
	7	Typographical conventions	8
	A	Admonition conventions	8
1	In	troduction	9
2	Αp	pplication Distribution	10
	2.1	Application Component Checklist	10
3	Or	acle Setup	11
	3.1	Configuration	11
	3.2	Tablespaces	11
	3.3	Schema User	12
	3.4	Schema Definition	12
4	SQ	የL Server Setup	14
	4.1	Configuration	
	4.2	Schema User	
	4.3	Schema Definition	
5	JD	Κ	
	5.1	Single Application / Database Server Scenario	
	5.2	Split Application / Batch Server Scenario	
	5.3	All Scenarios - Setting the JAVA_HOME Environment Variable	
6	Ap	pplication Server	17
7	Op	otiVault Deployment (Application Server)	
	7.1	WAR File Deployment	18
8	Op	otiVault Deployment (Using WebLogic Server)	20
	8.1	WAR File Deployment	20
9	Op	otiVault System Configuration	21
10	Op	otiVault Licensing	29
11	Op	otiVault Customization	30
	11.1	Making Changes to the Language File	30
	11.2	Making Changes to the Styles and Logos	30

	11.3	Ma	king Changes to the Report Styles and Text	31
	11.4	Set	ting Custom Order Fields	31
	11.5	Auc	lit Settings	32
12	Bat	ch P	rocesses	39
	12.1	Ant	Based Execution of Batch	39
	12	.1.1	General Parameters	40
	12.2	Loa	d Balance	40
	12	2.2.1	Properties	41
	12	.2.2	Syntax	41
	12.3	Firs	t Level Aggregation	41
	12	2.3.1	Properties	41
	12	.3.2	Syntax	41
	12.4	Rur	n Recommendations	41
	12	2.4.1	Properties	42
	12	.4.2	Syntax	42
	12.5	Rur	AllRecommendations	42
	12	2.5.1	Properties	42
	12	.5.2	Syntax	42
	12.6	Orc	lers Output	42
	12	2.6.1	Properties	42
	12	.6.2	Syntax	42
	12.7	Rec	ommendations Output	42
	12	2.7.1	Properties	42
	12	.7.2	Syntax	43
	12.8	Orc	lers Load	43
	12	.8.1	Properties	43
	12	.8.2	Syntax	43
	12.9	Cal	culate Cl Constraints	
	12	2.9.1	Properties	
		.9.2	Syntax	
	12.10	Ru	n Forecast	
		.10.1		
	12	2.10.2		
	12.11		n Commercial Consolidation	
		.11.1		
		.11.2		
			st Calculation	
	12	.12.1	Properties	45

12.12.2	Syntax	45
12.13 Purg	ge Application File Data	45
12.13.1	Properties	45
12.13.2	Syntax	45
12.14 Purg	ge Cashpoint Costs	45
12.14.1	Properties	46
12.14.2	Syntax	46
12.15 Purg	ge Calendar Events	46
12.15.1	Properties	46
12.15.2	Syntax	46
12.16 Purg	ge Forecast Adjustments	46
12.16.1	Properties	46
12.16.2	Syntax	46
12.17 Pur	ge CI CAP/OBMH	47
12.17.1	Properties	47
12.17.2	Syntax	47
12.18 Pur	ge Audit Records	47
12.18.1	Properties	47
12.18.2	Syntax	47
12.19 Pur	ge History	47
12.19.1	Properties	47
12.19.2	Syntax	47
12.20 Pur	ge Recommendations	48
12.20.1	Properties	48
12.20.2	Syntax	48
12.21 Purg	ge Orders	48
12.21.1	Properties	48
12.21.2	Syntax	48
12.22 Casł	hpoint Synchronization	48
12.22.1	Properties	48
12.22.2	Syntax	49
12.23 Cale	endar Refresh	49
12.23.1	Properties	49
12.23.2	Syntax	49
12.24 Exte	end Event Dates	49
12.24.1	Properties	49
12.24.2	Syntax	50
13 File Mair	ntenance	51

14	4 Redeploying the OptiVault Oracle Schema		
15	Prevent	ting Access to System Maintenance	53
16	Additio	nal Dependencies for OptiVault in Tomcat	54
	16.1.1	Tomcat 7	54
	16.1.2	Tomcat 8	55
	16.1.3	Tomcat 9	55
17	IMPORT	ΓΑΝΤ NOTE	57
18	EPSS Int	tegration	58

#### **Preface**

#### **Document conventions**

#### **Typographical conventions**

The following typographical conventions are used:

Typographical conventions

Style	Indicating
Bold	An option that you can select, for example, Insert > Bookmark
BoldItalic	Emphasis, for example, "This partition <i>must not</i> be modified." A physical key, for example, <i>Shift+F9</i>
Code	Text displayed on-screen  Commands or data entered by the user  Code text and examples
<u>Hyperlink</u>	Links to Internet sites Internal cross-references
Italic	The first reference to a keyword The title of a publication, for example, <i>Product Overview</i> A file or folder name, for example, <i>C:\Program Files\NCR</i>

#### **Admonition conventions**

Notes and cautions alert you to important/critical information. Each is displayed in a different way:

**Note:** Notes contain information that has special importance, to which the reader should pay close attention, or tips with useful advice for the user on tasks or procedures.

△ **Caution:** Cautions alert you to procedures or conditions that could damage equipment or data.

Notes and cautions in tables		
<b>Note:</b> Notes contain information that has special importance.	<b>Caution:</b> Cautions alert you to procedures or conditions that could damage equipment or data.	

#### 1 Introduction

The purpose of this document is to provide basic installation instructions for the OptiVault application. The particular architecture and environment of the installation may require additional configuration.

Although the installation media provides components for both Windows and UNIX, this document will provide samples and syntax based on the Windows operating system. The main modification for UNIX will be the file path name syntax.

The recommended process for installing OptiVault is:

- 1. **Oracle Database Configuration** (It is the responsibility of the client to ensure Oracle 12.2 or 19c is installed and running correctly PRIOR to the onsite product installation.)
- 2. **Application and Web Server** Configuration (It is the responsibility of the client to ensure the application & web servers are running correctly and readily accessible PRIOR to the on-site product installation).
- 3. Create **New User** in Oracle
- 4. Create **New Schema** in Oracle (NCR Cash Management provides a database dump file, or schema creation script)
- 5. Generate OptiVault license file
- 6. Deploy OptiVault WAR File
- 7. Define **OptiVault System** Settings
- 8. Batch Process Setup

OptiVault requires a base of version 8 JDK. Most Application Servers already come with the required JDK (e.g. IBM WebSphere or Apache Tomcat).

A clear understanding of Oracle and Application Server technology is required on the part of the user performing the installation.

# **2 Application Distribution**

#### 2.1 Application Component Checklist

Depending upon the client environment, the **Application Server** and **Oracle Database Server** could reside on the same physical machine or on different machines. The exact nature of this configuration should be agreed upon between NCR Cash Management and the client prior to installation. It is required that **JDBC** access is available between the Application Server and Oracle Database Server (as defined by the JDBC URL, which typically runs through port **1521**).

In a split-server example, the Application Server would house the Web Components (e.g. OptiVault WAR file) on one machine, and a different machine will house the Oracle components.

The following are the required components for the OptiVault installation:

- Oracle 12.2 or 19c and the latest patches relevant to the applicable O/S:
   It is the responsibility of the client to ensure the Oracle database is running correctly and readily accessible PRIOR to the on-site installation.
- OptiVault Schema Dump File or Schema DDL: NCR Cash Management will
  provide the Oracle schema dump or data-pump file for installation OR the
  database structure command SQL file for all required tables, views, and
  constraints.
- Java Application server, e.g. IBM WebSphere or Apache Tomcat: It is the responsibility of the client to ensure the Application Server is running correctly and readily accessible PRIOR to the on-site installation.

Note: Version 8 JDK is required for OptiVault.

- OptiVault WAR File: NCR Cash Management will provide the WAR file for deployment.
- **License File:** NCR Cash Management will provide a license SQL file based on the client's **OptiVault.log**

# 3 Oracle Setup

**Note:** It is the client's responsibility to have Oracle installed and running correctly and readily accessible PRIOR to the on-site installation performed by NCR Cash Management.

Additionally, it is the client's responsibility to prepare and agree with NCR Cash Management on the Oracle environment prior to the on-site installation. The *Technical Overview document* (separate) provides relevant information and shall serve as a basis for architectural consideration.

#### 3.1 Configuration

- 1. Verify the Oracle memory settings are correctly defined and do not fall below the minimum memory requirements i.e., necessary for running OptiVault. Kindly coordinate with Oracle System Administrator to ensure that memory settings are also taken into consideration for any other databases used in this Oracle environment.
- 2. The OptiVault application's Queries use many joins in the SQL statements. These joins usually exceed the default sort\_area\_size. Change the Oracle sort\_area\_size from 524288 to 1524288 on both the Running and SPFile pages (check on the radio button within the "Memory" tab of the Oracle DB Management Console). The sort\_area\_size must be changed in both the Running and SPFile tabs for enough memory to be allocated for some of the bigger SQL queries in OptiVault. When it is only changed in the Running tab, it will reset back to the default whenever Oracle is restarted.

#### 3.2 Tablespaces

The following assumes steps are being performed in the **Oracle DB Management** Console. Similar actions may of course be performed with the tool and interface per DBA choice.

It is recommended that the OptiVault Tables and Indexes/Constraints be separated into different tablespaces. If you already have your tablespaces available, you may continue to the next section.

- 1. From the *Oracle Enterprise Manager* Console, click on the **Object Menu** and select *Create*.
- 2. Select **Tablespace** and click the **Create** button.

- 3. The next window allows you to specify the table space. Recommended table space names are **OPTIVAULT\_DAT** for OptiVault data and the name **OPTIVAULT\_IDX** for the OptiVault indexes.
- 4. Type in the desired tablespace name. In the **"Size"** column, enter the anticipated size of your OptiVault data. This will depend upon the number of cashpoints, etc., but a minimum of 1-2GB is recommended for both the data and index table spaces.

**Note:** The **OptiVault Schema Definition Script** (DDL) will have tables and constraints defined such that:

5. Tables, Foreign Keys, and Views are defined in the Schema User's default tablespace. (e.g. **OPTIVAULT\_DAT**).

Primary Keys and Indexes are defined in the **OPTIVAULT\_IDX** tablespace.

You may modify the DDL script prior to execution as needed (e.g. changing the index tablespace, etc.).

#### 3.3 Schema User

- 1. Choose a name similar to the schema you want to create, e.g. OptiVault, client name, etc. Make sure to select the appropriate *Default Tablespace* for the user. This would typically be the **OPTIVAULT\_DAT** tablespace.
- 2. Select **"Connect"** and **"Resource"** from the Role list for the user. The user will need these roles to connect to the database and access database functions.
- 3. Select "UNLIMITED\_TABLESPACE" from the System list for the user.

#### 3.4 Schema Definition

The following files should be used to create a new schema base on the new user created in the previous step:

- <cli><cli>t name>.dmp (Oracle Schema Data Dump as provided by NCR Cash Management)
- Master\_Schema\_Creation\_Script\_build<build\_number>.sql

NCR Cash Management will provide these files to the client.

- You will first need to create the schema objects, per the Master\_Schema\*.sql script. This script can be modified as needed to reflect the desired tablespaces, etc.
- 2. Once completed, verify that there were no errors in the process, and the appropriate objects are created within the user schema for the appropriate

Tablespaces. (You may do this from the Oracle Enterprise Manager Console or your DBA tool of choice.)

- 3. Execute the various par file imports, ensuring there are no errors.
- 4. Once completed, verify that there were no errors in the process, and the data has been loaded into the user's tables. (You may do this from the Oracle Enterprise Manager Console or your DBA tool of choice.)

It is strongly recommended to analyse the tables and indexes for the newly imported data immediately after import.

# **4 SQL Server Setup**

# 4.1 Configuration

Verify the *SQL Server* memory settings are correctly defined and do not fall below the minimum memory requirements i.e., necessary for running OptiSuite (refer to SQL Server Installation document for more information on minimum memory requirements). Kindly coordinate with *System Administrator* to ensure that memory settings are also taken into consideration with other databases used by the bank in the SQL Server environment.

#### 4.2 Schema User

- 1. Choose a name similar to the schema you want to create, e.g. OptiVault, client name, etc. and password accordingly in the *General tab*
- 2. Select "public" and "dbcreator" from the Role list for the user. The user will need these roles to connect to the database and access database functions.
- 3. Select the respective database in the *user mapping tab* for that particular user. Select Grant permission to connect to the database engine and login enabled in the *Status tab*.

#### 4.3 Schema Definition

The following files may be used to create a new schema base on the new user created in the previous step:

- Minimum of 2 DDL scripts to define tables, indexes, and default data records.
  - e.g.: sqlserver-schema/data.sql

NCR Cash Management will provide these files to the client. Make sure to save these files in the same directory.

The User will have two options to create the data schema:

- 1. Run the provided **DDL SQL** files.
  - a. You will first need to create the schema objects, per the **sqlserver-schema.sql** script. This script can be modified as needed to reflect the desired tables etc.
  - b. Once completed, verify that there were no errors in the process, and the appropriate objects are created within the user schema followed by running the sqlserver-data.sql script to add default data records to the created tables.

It is strongly recommended to analyse the tables and indexes for the newly imported data immediately after import.

#### 5 JDK

Most Application Servers (e.g. IBM WebSphere or Apache Tomcat) already come with the JDK required for running the application server. The OptiVault application requires the installation of the **Java Development Toolkit** (JDK) version 8.

This document does not detail the installation of the JDK, since this is identified as a client's direct responsibility. The following provides a brief overview of specific scenarios that might be used for JDK Installation.

**Note**: The Runtime equivalent (JRE) is not sufficient since runtime compiling is required by the web application.

#### 5.1 Single Application / Database Server Scenario

The critical thing in this scenario (the recommended scenario) is simply to ensure the JDK has been installed on the machine and is in use by the Application Server.

#### 5.2 Split Application / Batch Server Scenario

In some client installations, the Application Server (e.g. WebSphere) and Batch Server reside on two different machines. In this example, WebSphere will house the Web Component (e.g. OptiVault WAR file) on one machine, and another machine would house the batch jobs.

The IDK will still need to be installed on the Batch Server.

**Note:** The entire Application Server need not be installed on the batch machine, only the JDK is required. This can be important to clients looking to reduce 3<sup>rd</sup> party Application Server licensing on two servers.

# 5.3 All Scenarios - Setting the JAVA\_HOME Environment Variable

Once the JDK is installed, create a **WINDOWS ENVIRONMENT VARIABLE** for **JAVA\_HOME** that corresponds to the location of the JDK.

e.g. Open up the *Control Panel > System,* "Advanced" tab. Choose "Environment Variables". Add a "System Variable" for:

- Variable Name: JAVA\_HOME
- **Variable Value :** C:\Java\jdk1.8 (or the appropriate location of the JDK on the hard drive).

This will allow the system execution of the **OptiVault Batch job Services**, which will be installed later. If you are running on another Operating System, you will need to follow similar steps, but with the **"setenv"** command instead (assuming UNIX).

# **6 Application Server**

**Note:** It is the responsibility of the client to ensure the Application Server is running correctly and readily accessible PRIOR to the on-site installation to be performed by NCR Cash Management.

Additionally, the **Application Server** must be installed in a directory structure without spaces, e.g. **C:\IBM\WebSphere**.

It is also strongly recommended that the application server be deployed in the root directory (or close to the root directory).

# 7 OptiVault Deployment (Application Server)

# 7.1 WAR File Deployment

- 1. WAR files are readily deployable web-application containers, complete with supporting jars. Recommendation and forecast engines are also inside the WAR file.
- 2. The default deployment of OptiVault will be to a web application and URL called "OptiVault". Many Application Servers (WebSphere, etc.) provide an application assembly tool to allow you to change the default context prior to deployment. Refer to the specifics of your Application Server for this. Additionally, you may change this by directly editing the application.xml file inside the WAR file.
- 3. The precise deployment technique for the installation WAR file depends on the Application Server chosen, e.g. *IBM WebSphere* or *Apache Tomcat*.
- 4. If you are deploying on WebSphere, it is strongly recommended to enable the option "Show me all installation options and parameters" for deployment, unless you are already comfortable using a custom OptiVault deployment script specific to your institution.
- 5. DO NOT select "pre-compile JSPs" if that is an option when deploying the WAR file for your given Application Server.
- 6. OptiVault contains security roles within the WAR file (the **web.xml** file), which permit you to match authenticated users to application access. These roles are:
  - a. NormalRole (conventional cash analyst who logs into OptiVault)
  - b. MaintenanceRole (typically an App Server or IT administrator who configures the application with the JDBC access, input/output directories, log directories, etc.). This user would access the sub maint/ URL and associated pages.
- 7. You may choose to give any user access to these URLs of the application, and if so, simply enable the applicable options in accordance with your application server.
  - a. <u>Example 1</u>: In the case of WebSphere, this is handled in the "*Map security roles to users or groups*" step of WAR deployment, where you can *Look Up* Users or Groups based upon your applicable access directory plug-in. You can also grant these two roles to "*Everyone*".
  - b. <u>Example 2:</u> In the case of Sun Java, these *user-to-URL* restrictions must be handled pre-deployment in the XML configuration files. To grant to "*Everyone*" simply remove the <security-constraint>, <login-config>, and <security-role> sections from the web.xml file prior to deployment.


- 8. If applicable, make sure to save the configuration post-deployment.
- 9. If applicable, make sure to regenerate the plug-in configuration for proper communication between the *Web Server* and the *Application Server*.

# 8 OptiVault Deployment (Using WebLogic Server)

#### 8.1 WAR File Deployment

- After logging in to the Weblogic console using valid credentials which were set at the time of installation in the left side pane under Domain structure click on Deployments
- Click on the Install button under the Configuration tab an Install
   Application Assistant will be displayed using this the required .war file can be imported into Weblogic
- On the next page, of *Install application Assistant* select the installation type as application and click on next
- Select the available target types like admin server and managed servers
  if any depending on the requirement i.e. in how many servers the
  application should be deployed
- Click on the **Finish** button to finish the setup, Weblogic will automatically
  display the deployed application in the dashboard with the status of the
  deployment like active for successful and errors if the deployment failed

Below is the dashboard view of Weblogic



#### 9 OptiVault System Configuration

After the WAR file is deployed following the instructions in the previous steps, the following will indicate additional configurations that need to be defined.

 Update the <application-path>/WEB-INF/Log4j.properties file to point to the optivault.log to the desired location.

**Log4J** is a Java logging utility that logs the usage activity in the application.

**Note:** This should be the full path to the log file.

• Open the **<application-path>/WEB-INF/Log4j.properties** file and edit line 16

(by default)

```
log4j.appender.R.File=C:\\jrun\\servers\\default\\OptiVault
\\WEB-INF\\OptiVault.log
```

**Note:** The path below is not necessarily correct for your specific installation, rather it is for illustration purposes.)


```
log4j.appender.R.File=
C:/IBM/WebSphere/AppServer/profiles/default/installedApps/M
IRAGENode01Cell/OptiVault.ear/OptiVault.war/WEB-
INF/OptiVault.log
```

**Note:** Each time changes are made to any of the property files user needs to restart the Application Server where the WAR file was deployed so that the changes are applied. (Reconfigure the plug-in, as well, between your App Server and Web Server, if necessary.)

**NOTE**: The following lines are to suppress excessive DEBUG logging coming from Jasper Reports:

```
# Suppress Jasper Reports Debug data
log4j.logger.net.sf.jasperreports=INFO, R
log4j.logger.org.apache.commons.digester=INFO, R
log4j.logger.org.apache.commons.beanutils.MethodUtils=INFO, R
```

Browse to <a href="http://<server\_address>:<port>/optivault/maint/index.jsp">http://<server\_address>:<port>/optivault" was not changed in the application.xml</a> file. Select the "System Setup" link, which takes you to <a href="http://<server\_address>:<port>/optivault/maint/setup.jsp">http://<server\_address>:<port>/optivault/maint/setup.jsp</a>



- 3. The JNDI **Context** and **Name** should be filled in with the applicable JNDI information. If you are NOT using JNDI, then make sure these fields are empty.
- 4. The **'Driver Class'** field should be left as it is. The Connection URL should indicate the following:

**jdbc:oracle:thin@<server\_name>:1521:<oracle\_db\_name>**The example above is: jdbc:oracle:thin:@demo:1521:orcl

- 5. Indicate the user name and password as in the schema created for the OptiVault database. In the example above it is 'DEMO\_OV' and '\*\*\*\*\*\*'.
- 6. You may leave the Authentication Method as "Legacy Internal" until the installation is complete and verified. After that time, switch to the authentication method of choice. Remote User authentication is recommended to utilize the inherent authentication method of the Web server.

Authentication Method	Description
Basic	This is a simple authentication method where the password is the user name. This method should never be used in production.
Remote User	This authentication method accepts the <b>"remote_user"</b> header variable from the HTTP request. This works identically to the <b>"External"</b> authentication method in the previous OV versions and is the preferred production method.
WebSeal	This authentication method accepts the "iv_user" header variable from the HTTP request.

Legacy Internal	This authentication method, provided for compatibility with earlier releases, accepts a username and password from an HTML form and verifies them against the database.
	<b>Note</b> : If the <b>"exuser"</b> column is blank or null for an authenticated user, this class will copy the <b>"username"</b> column into it. Otherwise, it works exactly like the <b>"Internal"</b> authentication in the previous OV versions. Also, because it uses the OptiVault database and database classes, it is not part of OptiCore. Instead, it is part of OptiVault itself. Variations of it must be produced for the other products.
	It is not recommended to use this authentication method in production.
Legacy Custom	This authentication method is provided for compatibility with earlier releases and expects a legacy <b>CustomAuthenticator</b> subclass as its parameter. Once configured that way, it works exactly like the " <b>Custom</b> " authentication in previous versions. Also, because it uses OptiVault classes, it is not part of OptiCore. Instead, it is part of OptiVault itself. Variations of it must be produced for the other products. It is not recommended to use this method for new installations.
Microsoft AD Authentication	Microsoft ActiveDirectory Authentication. This method requires Authenticator Parameters in the following format: FACTORY{LDAPfactory};PROVIDER{myURL};METHOD{value};DOMAIN{myDom
	ain};DN{value}  Example:
	FACTORY{com.sun.jndi.ldap.LdapCtxFactory};PROVIDER{ldap://server1:389}; METHOD{simple};DOMAIN{home.myinstitution.com};DN{DC=home,DC=myin stitution,DC=com}
	This method uses LDAP to authenticate with an existing Microsoft ActiveDirectory installation. It is assumed that that installation will accept credentials in the form "username@domain" where the username is supplied by the user, and the domain is the parameter configured here. The other Authenticator Parameters are used to create the context.
	<b>Note:</b> When using Microsoft AD Authentication, users will likely have to be created with the External Auth. User field in this format: //LDAP/username@domain
File Authorizer	FileAuthorizer is a simple external authentication method where the "external" part is a file. The Sample file can be found in. <optivault directory="">\WEB-INF\classes This can be used for demo or test environments, or as an example for those developing a customized external authentication method but is not suitable for production environments.</optivault>
Database Table Authentication	This authentication references a database to authenticate users. Often this is its own database, but can be a separate authentication database if desired. If the <b>Database Table Authentication</b> option is selectedyou will also need to

configure additional parameters in **<OptiCash directory>\WEB-INF\DBAuthorizer-OV.properties** file as follows.

**Note:** You will see some options in the file not listed here (query definition, etc). Those should not be changed from the default.

**dbAuthorizer.database.dsn**: JNDI database connection name. Similar to section 3 above, this is a connection to the database. If desired to use JDBC connection then this field should be empty.

**dbAuthorizer.database.url**: URL to authorization database, example: jdbc:oracle:thin:@server:1521:serverdb

**dbAuthorizer.database.username**, **dbAuthorizer.database.password**: Schema username and password if using JDBC connection. Can be blank if using JNDI connection.

**dbAuthorizer.digest.length**: Length of the password after encryption. Longer is more secure but cannot exceed the maximum size of your target database's password field.

**dbAuthorizer.digest.algorithm**: Algorithm to be used when encrypting the password.

**dbAuthorizer.digest.seed**: Character string used to seed the encryption algorithm. It is recommended to change this away from the default.

**dbAuthorizer.option.quiet**: "true" or "false". Quiet mode allows a password that was unencrypted to be encrypted without the user having to change that password. If false, then users are forced to change the password in that situation. This can be relevant when migrating from another auth method or in a case where the administrator previously reset a user's password.

**Note**: If you plan to use Database Table Authentication, also known as **DBAuthorizer**, from multiple OptiSuite applications and point to the same single database for user management, then the digest "length", "algorithm", and "seed" settings above must be the same between all applications.

- Select "User Interface Language" as "English\_US".
- 8. Leave "Calendar length" as provided by default. Do not change this field.
- 9. The Import Path typically reflects the existing <application-path>/import directory as it exists under the deployment on the Application Server. However, this could be a location outside of the deployed application path. OptiVault load processes that use an input file will assume that the file is found in this location. If you point this to a location other than the typical <application-path>/import directory, then you will also need to create 2 subdirectories within that directory with the same names as subdirectories found in <application-path>/import.
- △ **Caution**: The import directory is used to copy files that are being loaded to OptiVault (daily load files, order files, etc). When loading such files via



interface it is recommended that the original path of the load files is other than the import directory. This is to avoid potential issues when the loaded files are replaced by the previously copied files in the import directory. Also, there may be issues associated with loading files of bigger size when the load files are reduced in size while executing the load process via interface directly from the import directory.

- 10. The Output Path typically reflects the existing **<application-path>/output** directory as it exists under the deployment on the Application Server. However, this could be a location outside of the deployed application path. OptiVault processes that produce an output file will put it in this location.
- 11. The Logs Path typically reflects the existing **<application-path>/logs** directory as it exists under the deployment on the Application Server. However, this could be a location outside of the deployed application path.

**Note:** It is recommended for this path to be the same path as that defined in **log4j.properties** for easy locating of the various job and application logs. Log files produced by OptiVault during normal operation will be put into this location.

12. CarrierWeb Service URL is a connection used to retrieve some data from **OptiVLM-CarrierWeb** application. Leave blank if you are not connecting to CarrierWeb.

**Example:** http://host.com:9080/CarrierWeb/

- 13. Define the "Mail Host Name", which is the SMTP mail host server IP address or server name. This is used to email the daily load log files to an appropriate business analyst for review.
- 14. Click Update to save the changes. At the bottom of the screen in the "Connection Status" table, you should see the message indicating that a connection to Oracle is established.

#### **Example:**




15. Once you are sure you have a working connection with Oracle for the OptiVault database, next point OptiVault to the OptiCash database. OptiVault uses information from OptiCash, so it is necessary to grant select privileges on various OptiCash tables to OptiVault.

**Note:** These items are only applicable if you are sharing data between OptiCash and OptiVault. Stand-alone OptiVault installations can skip this section.

In the "Set Up OptiCash" table, enter the Driver Class and Connection URL for OptiCash.

#### **Example:**



- Enter the **OptiCash Schema/User** and the **OptiCash schema** password.
- Click the **Grant OptiCash Privilege** button.

**Note:** It is necessary to review the **OptiVault.log** to verify this process completed successfully. You should see log entries similar to the following:

```
INFO -- Running Query : GRANT SELECT ON MYBANK OC.CASHPNT
TO MYBANK OV
INFO -- Running Query : GRANT SELECT ON MYBANK OC.CAL LIST
TO MYBANK OV
INFO -- Running Query : GRANT SELECT ON MYBANK OC. EVENTS
TO MYBANK OV
INFO -- Running Query : GRANT SELECT ON MYBANK OC. EVNTDATE
TO MYBANK OV
INFO -- Running Query : GRANT SELECT ON MYBANK OC.CALENDAR
TO MYBANK OV
INFO -- Running Query : GRANT SELECT ON MYBANK OC.DENOMDEF
TO MYBANK OV
INFO -- Running Query : GRANT SELECT ON MYBANK OC. SRVDEPOT
TO MYBANK OV
INFO -- Running Query : GRANT SELECT ON MYBANK OC.ORDERS
TO MYBANK OV
INFO -- Running Query : GRANT SELECT ON MYBANK OC.ORDERDEN
TO MYBANK OV
INFO -- Running Query : GRANT SELECT ON MYBANK OC.CP DENOM
TO MYBANK OV
INFO -- Running Query : GRANT SELECT ON MYBANK OC.ATORDRTR
TO MYBANK OV
INFO -- Running Query : GRANT SELECT ON MYBANK OC.ATMHIST
TO MYBANK OV
INFO -- Running Query : GRANT SELECT ON MYBANK OC.RECOMTOT
TO MYBANK OV
INFO -- Running Query : GRANT SELECT ON MYBANK OC.RECOMDEN
TO MYBANK OV
INFO -- Running Query : GRANT SELECT ON
MYBANK OC.RECOMSTATE TO MYBANK OV
INFO -- Running Query : GRANT SELECT ON MYBANK OC. VABRECON
TO MYBANK OV
INFO -- Running Query : GRANT SELECT ON MYBANK OC.ATMFREC
TO MYBANK OV
```

```
INFO -- Running Query : GRANT SELECT ON MYBANK_OC.CP_RPROC
TO MYBANK_OV
INFO -- Running Query : GRANT SELECT ON MYBANK_OC.CRNCYDEF
TO MYBANK_OV
INFO -- Running Query : GRANT SELECT ON MYBANK_OC.CP_LINK
TO MYBANK_OV
INFO -- Running Query : GRANT SELECT ON MYBANK_OC.QUALITIES
TO MYBANK_OV
INFO -- Running Query : GRANT SELECT ON
MYBANK_OC.CRNCY_EXCHANGE TO MYBANK_OV
INFO -- Running Query : GRANT SELECT ON
MYBANK_OC.CRNCY_INTEREST TO MYBANK_OV
INFO -- Running Query : GRANT SELECT ON
MYBANK_OC.ORDERS_MASTER TO MYBANK_OV
INFO -- Grant OptiCash select to OptiVault finished!
```

- Informing the process was successful. The tables mentioned above are the **OptiCash tables** read by **OptiVault**.
- 16. Browse back to the **/maint/index.jsp**, by clicking the blue house icon at the top of the page. (taking the user back to **<OptiVault URL>/maint/index.jsp**)
- 17. For Brazilian users, you may wish to turn on the CDI interest calculations (for holding cost). This is an alternative method to calculate compound interest rather than simple interest and no interest on Saturdays, Sundays, or Holidays.

**Note**: This applies only during Recommendations generation and will be inconsistent with other features (like Cost reports). To turn this on, find file <application-path>/WEB-INF/optivault.properties and modify the values of the following parameters:

```
cdi_interest_calculation=on
cdi_interest_calculation_calendar_id=CDI_CALENDAR
```

CDI\_CALENDAR here may be replaced with a different calendar ID if desired. A Calendar with the same ID must be created within OptiCash and Events associated with that calendar that represent the holidays during which interest will not accrue.

Optionally, the email "From" address for notifications sent by OptiVault may be altered in file {OptiVault directory}/WEB-INF/optivault.properties by changing the "JobSender" variable.

#### **Example:**

JobSender=optivault@mybank.com

18. After the OptiVault setup is completed, it may be necessary to update your local java security to grant permissions, which will allow OptiVault to directly execute various OptiVault Java classes. If so, the following line should be added to the **java.policy** file:

```
grant {
permission java.security.AllPermission;
};
```

# 10OptiVault Licensing

- To receive an OptiVault license, you will need to provide the **OptiVault.log** file to NCR Cash Management after an attempted login, which captures the needed information to generate a license. We have defined the location of the **OptiVault.log** file earlier in your **<application-path>/WEB-INF/Log4j.properties** file.
- 2. NCR Cash Management will create a license SQL script and relay that back to you.
- 3. To apply the SQL script, Go to http://<hostname>/optivault/maint/testsql.jsp
- 4. Copy and paste the new license script to the SQL editor and click Run SQL.
- 5. You should now be able to login to OptiVault successfully.
- ▲ **Warning**: This should only be carried out by a system administrator or database administrator as incorrect use of the SQL editor could cause corruption of the data.

# 11OptiVault Customization

The most common customization you will perform is to the look of the user interface or language file edits.

#### 11.1 Making Changes to the Language File

- 1. For instance, if you want to change the word *"recommendation"* to the word *"suggestion"*, open the following file with a text editor (assuming English):
- <application-path>WEB-INF\classes\transoft\_optivault\_LanguageSet\_English.properties
- 3. Search for the string **'=recommendation'**. Edit to **'=suggestion"**. Make sure to search for all occurrences of this word or string.
- Save the file.
- 5. Restart the Application Server where the WAR file was deployed.

Note: OptiVault contains individualized properties files for text elements used in Reports. These files are found in the following location: <application-path>WEB-INF\lib\optivault<version-number>.jar\transoft\optivault\reports\ . Files will be named like AuditReport\_es.properties where "AuditReport" is the report name and "\_es" indicates the Spanish language. Other languages can be substituted instead of "es" – just use the same language abbreviation as found in "locale.language" in <application-path>WEB-INF\classes\transoft\_optivault\_LanguageSet\_<yourlanguage>.propertie s



Customized language files are the client's responsibility to maintain. Before editing, save the original file (i.e.

transoft\_optivault\_LanguageSet\_English.orig.properties). In the future, with each OptiVault upgrade, the edited version will need to be saved PRIOR to installing a new WAR file. Once the WAR file has been deployed, then restore the edited version.

#### 11.2 Making Changes to the Styles and Logos

- 1. All images are stored in the **<application-path>/WEB-INF/images** directory.
- 2. The main OptiVault style sheet is found at <application-path>/styles/main.css



Customized styles and logos are the client's responsibility to maintain. Before editing, save off the original style sheet and image files. In the future, with

each OptiVault upgrade, the edited version will need to be saved PRIOR to installing a new WAR file. Once the WAR file has been deployed, then restore the edited version.

#### 11.3 Making Changes to the Report Styles and Text

Changes to the styles and text within OptiVault PDF and CSV reports are maintained separately per report.

- 1. Style definitions are maintained within each report **JRXML** file. e.g. The Vault Horizon report style can be found in VaultHorizonReport.jrxml. All styles are contained within the **<style>** and **<style name>** tags.
- 2. Textual elements are contained within the OptiVault.jar file under the **transoft/optivault/reports/** path, with an extension of **"properties"**. e.g., The Vault Horizon text can be found in **VaultHorizonReport.properties**

#### 11.4 Setting Custom Order Fields

OptiVault allows the addition of up to 10 customizable fields to the ordering interface. These fields are configured in OptiVault under *System > Order Settings > Custom Field Definitions*.

The option called **"SQL Query"** allows to add a menu to ordering screens with a dynamic list of options. If you intend to use this type of field, then the queries must be predefined during the OptiVault setup.

- In the <application-path>/WEB-INF/classes directory, find the file "transoft\_optivault\_custom\_QueryString.properties". If it does not already exist, create it as a blank text file. This will be known as the "custom query file".
- Open the custom query file with a text editor. Enter the queries on separate
  rows in the following format: <reference>=<SQL query> where 'reference' is
  what the user will type on System > Order Settings > Custom Field Definitions
  page and 'SQL query' determines what options will be displayed when placing
  an order.

#### **Example:**

CustomField.active\_date=?select actvdate from cashpnt where cashp\_id \= '\:cashp\_id\:';

3. Notice the segment '\:cashp\_id\:' in the above example. This is a dynamic parameter being passed into the query at the time of opening an order creation screen. You may use the following parameters:

CASHP_ID	The cashpoint for which this order is being placed.
_	The cashpoint type of the cashpoint for which this order is being placed. Possible values are VAULT.
ACTN_ID	The type of order being placed.
	01=Delivery, 02=Return
SCHED_ID	Indicates if this order is an emergency (unplanned) or not.
	01=Normal, 02=Unplanned
ORD_DATE	The date on which the order is being placed (current date usually).

Note: Customized query files are the client's responsibility to maintain. Typically, this means saving an outside copy of the existing custom query file prior to an OptiCash upgrade, and then replacing that copy in the <application-path>/WEB-INF/classes directory after the upgrade is complete.

Additionally, writing queries requires some knowledge of SQL (Structured Query Language) and the OptiCash database structure. NCR Cash Management support personnel are available to help with specific inquiries regarding this.

#### 11.5 Audit Settings

The Auditing feature creates and stores a record of users' actions. Settings allow the system administrator to determine which actions to record and to what level of detail.

- Open settings file: <application-path>WEB-INF\classes\transoft\_optivault\_audit.properties
- 2. Set auditing to 'none', 'partial', or 'full' for each function. See the table below for the meaning of each function ID number.
  - **None:** No recording occurs when this function is used.
  - Partial: Basic record is saved (statement parameters omitted).
  - **Full:** All available info is recorded when this function is used.
- 3. After making changes, save the file, and start (or restart) the OptiVault application.

Function ID	Description
0	Unknown  Note: The Unknown category includes many secondary records (things that take place invisibly when the action noted in the main record occurs). It is the most common record type. It may be advantageous to set Unknown to 'partial' logging to reduce the total amount of data logged by auditing.
1001	Updated Cashpoint Details
1002	Updated Vault Parameters
1003	Updated Vault Denomination
1004	Inserted Vault Requirements
1005	Import Vault Balance
1006	Saved Provisional Credit
1007	Linked Cashpoint to Vault
1008	Inserted Transit Time Setting
1009	Updated Vault Service Days
1010	Deleted Service Costs
1011	Updated Teller Verification
1012	Updated Vault Denomination Split
1013	Deleted Vault Sorter
1014	Updated Sort Capacity Utilization
1015	Created Denomination Definition
1016	Updated Denomination Definition
1017	Deleted Denomination Definition
1018	Updated Order
1019	Deleted Order
1020	Added Forecast Adjustment
1021	Inserted Forecast Horizon
1022	Updated Forecast Adjustment
1023	Deleted Job Message
1024	Inserted Job Message
1025	Updated Vault History

Function ID	Description
1026	Updated Vault Forecast Toggle Values
1027	Updated Horizon
1028	Import Vault Balance
1029	Deleted Cashpoint
1030	Updated Vault Denomination Quality Yield Split
1031	Updated Cross Shipping Yield
1032	Inserted Order
1033	Updated Commercial Service Days
1034	Updated Transit Time Setting
1035	Added Denomination to Cashpoint
1036	Removed Denomination from Cashpoint
1037	Updated Vault Requirement
1038	Deleted Vault Requirement
1039	Removed CP from Vault
1040	Add Sorter to Vault
1041	Update Vault Sorter
1042	Accept Recommendation
1043	Inserted Service Cost
1044	Removed Service Cost
1045	Removed Forecast Adjustment
1046	Exclude Commercial History
1047	Update Cl Service Days
1048	Update CI History
1049	Delete CI
1050	Remove External Funding Source
2001	Inserted Commercial History
2002	Deleted Job
2003	Inserted Job
2004	Deleted Job Message
2005	Inserted Job Message

Function ID	Description
2006	Deleted User Job Message
2007	Deleted Horizon
2008	Deleted Setting
2009	Saved Setting
2010	Updated Constraint Calculation Set
2011	Created Constraint Calculation Set
2012	Deleted Constraint Calculation Set
2013	Deleted Cost Table
2014	Inserted Horizon for Projected Cost
2015	Updated Cost Options
2016	Inserted Cost Options
2017	Inserted Orders Sum and Details From Load File
2018	Inserted Orders Denomination Details From Load File
2019	Updated Orders Sum and Details From Load File
2020	Updated Orders Denomination Details From Load File
3001	Created Cashpoint
3002	Created Depot
3003	Updated Depot
3004	Deleted Depot
3005	Created Group
3006	Updated Group
3007	Removed Group Cashpoints
3008	Deleted Group
3009	Created Order Constraint
3010	Deleted Order Constraint
3011	Updated Sorters
3012	Deleted Sorters
3013	Mass Assign Funding Source
3014	Mass Assign Overnight Earn. Rate
3015	Mass Assign Insurance Rate

Function ID	Description
3016	Mass Assign Max Hold
3017	Mass Assign Max Pallets
3018	Mass Assign Bulk Order
3019	Mass Assign Aggregate Emergencies
3020	Mass Assign Clearance Time
3021	Mass Assign Packaging Time
3022	Mass Assign Minimum Delivery
3023	Mass Assign Minimum Return
3024	Mass Assign Minimum Unplanned
3025	Mass Assign Delivery Handling Cost
3026	Mass Assign Return Handling Cost
3027	Mass Assign Delivery Days
3028	Mass Assign Return Days
3029	Mass Assign Unplanned Days
3030	Mass Assign Delete Service Cost
3031	Mass Assign Insert Service Cost Amount
3032	Mass Assign Insert Service Cost Range
3033	Mass Assign Insert Service Unit Size
3034	Mass Assign Update Service Cost
3035	Created Sorter
3036	Updated Cross Shipping Zone
3037	Created Cross Shipping Zone
3038	Deleted Cross Shipping Zone
4001	Created Calendars
4002	Deleted Calendars
4003	Created Event List
4004	Added Event to Event List
4005	Associated Calendar with Event
4006	Dissociated Calendar with Event
4007	Deleted Cashpoint from Calendar

Function ID	Description
4008	Updated Calendar
4009	Deleted Event Definition
4010	Updated Event
4011	Updated Event Date
4012	Updated Event List
4013	Add Cashpoint to the calendar
4014	Removed Event from Event List
4015	Updated Event List
4016	Deleted Event List
4017	Created an Event
5001	Updated Institution Parameters
5002	Updated Override Reason
5003	Deleted Override Reason
5004	Created User
5005	Updated User Info
5006	Inserted into Access Control List
5007	Deleted from Access Control List
5008	[Currently not used]
5009	Cloned Commercial
5010	Cloned Vault
5011	Renamed Vault ID
5012	Delete Vault History
5013	Replaced Vault Last Load Information
5014	Delete Commercial History
5015	Delete CI History
5016	Replaced CI Last Load Information
5017	Deleted Forecast Queue
5018	Deleted Unused Calendars
5019	Deleted Recommendations
5020	Deleted Orders

Function ID	Description
5021	Created Override Reason
5022	Deleted User
5023	Deleted Business Unit
5024	Rename CI ID
5025	Rename Commercial ID
5026	Update All Used Calendars
5027	Insert All New Calendars

## **12Batch Processes**

The purpose of batch process execution is to provide more time-efficient execution of regular OptiVault processes. The jobs can be scheduled to run overnight.

All the batch process files will be located under the deployment directory of the OptiVault Web Application in the **'batch'** directory. The batch files will be available after the OptiVault WAR File is deployed.

#### **Example:**

 $\label{lem:continuous} C:\label{lem:continuous} C:\label{lem:continuous} IBM\webSphere\appServer\profiles\default\installed\Apps\MIRAGENode01Cell\OptiVault.ear\OptiVault.war\Batch$ 



**Note**: Each time a WAR file is deployed or upgraded to a newer version, batch files will need to be backed up to save the environment settings. For that reason, the batch directory should be moved to a different location during installation, from where the processes will be run on an ongoing basis.

#### The batch files:

- 1. Intended to be used by the customer to implement their own production-quality batch processing schedule.
- 2. Can be executed in their current form to carry out the basic processing steps, however, the expectation is that the customer will either modify/wrap or rewrite the scripts to meet the banks internal batch standards and to closely integrate with the bank environment, considering issues such as file transfers, on-call alerts, standard scheduling packages and/or programming languages etc.

NCR Cash Management recommends the customer to first run the process in its basic form using the batch process and then, as necessary, make the changes to meet the local institution's requirements.



**Note**: NCR Cash Management does not provide ongoing support for the batch files due to integration requirements to existing customer systems, specific customer procedures in relation to data file interface a variety of scheduling capabilities and security concerns.

Therefore, it is the responsibility of the client to review, understand and support these batch files.

## 12.1 Ant Based Execution of Batch

Commencing with OptiSuite version 8, it is recommended to execute our batch processes via ANT, although other methods may be possible. The java standard Apache ANT package is used to execute the custom export framework, and it is

available for free for any operating system. ANT is available at <a href="http://ant.apache.org">http://ant.apache.org</a>. The custom export requires ANT version 1.7 at minimum.

ANT will need to be downloaded onto the computer which is running the custom output. Since ANT is java-based, you may simply unzip the Ant directory structure, and add the underlying "bin" directory to the system path so that calls to execute "ant" are found. If ANT is not added to the system path, simply call the fully-loaded path to the ANT executable instead.

Since ANT is a Java-based utility, **%JAVA\_HOME%** must also be defined, but this should have been done earlier in the installation process and if so, no additional action is necessary.

There are three files of importance for executing the batch process:

- **build.properties** This file contains the properties associated with each batch process.
- build.xml This file contains the configuration and calls to each underlying batch process, using the parameters defined in the build.properties file.
- ant\_execution\_samples This file contains sample calls to execute each process via ant

#### 12.1.1 General Parameters

These parameters must be set in the **build.properties** file

- optivault.dir=The directory path of the OptiCash war file. e.g.
   C:/IBM/WebSphere/AppServer/profiles/AppSrv01/installedApps/ironhide
   Node01Cell/OptiVault.ear/OptiVault.war/
- optivault.lib.dir=The directory path to the application server jar files. e.g. C:/IBM/WebSphere/AppServer/lib
- optivault.oracle.dir=The directory oracle ojdbc jar file.
- optivault.user=A valid user in OptiVault who has rights to the given batch functions and cashpoints.

## 12.2 Load Balance

The Load\_Balance batch will load daily load file(s), i.e. the file(s) that supply the activity and balance figures for the VAULT and COMMERCIAL cashpoints. Refer to the document *OptiVault Input/Output Formats* for more information about this load format.

#### 12.2.1 Properties

- Load\_Balance.fileName=Name of the file to be loaded. The File must be in the applicable defined import directory (e.g.
   C:\OptiSuite\optivault\import). Supply only the Basic Filename No path is necessary. If loaded from ETL, put 'none' or 'na'.
- Load\_Balance.cashpointType=Valid Cashpoint Types: VAULT, COMMERCIAL
- Load\_Balance.delim=Supported separators comma, tab. If load from ETL, put 'none' or 'na'.
- Load\_Balance.mailaddr=Email addresses, where the log file is sent once the process is completed
- Load\_Balance.source=Data source: file, ETL

## **12.2.2** Syntax

ant -f build.xml Load\_Balance

## 12.3 First Level Aggregation

• The First\_Level\_Aggregation batch will run the first-level aggregation between OptiCash and OptiVault.

## 12.3.1 Properties

- First\_Level\_Aggregation.startDate=Starting date of the aggregation. The Format should be yyyy-mm-dd
- First\_Level\_Aggregation.endDate=End date of the aggregation. The Format should be yyyy-mm-dd
- First\_Level\_Aggregation.HorizonLen=Length of desired Horizon
- First\_Level\_Aggregation.CurrencyID=Currency ID to be aggregated

## **12.3.2** Syntax

ant -f build.xml First\_Level\_Aggregation

## 12.4 Run Recommendations

• The Run\_Recommendations batch will run the OptiVault recommendation process.

#### 12.4.1 Properties

- Run\_Recommendations.Group=valid group in OptiVault
- Run\_Recommendations.OVSetId=Valid Recommendation Job Process ID (e.g. 1, 2, 3, etc.)

#### 12.4.2 **Syntax**

ant -f build.xml Run\_Recommendations

## 12.5 Run AllRecommendations

• The Run\_AllRecommendations batch will run all of the OptiVault recommendation processes which are marked as "Recurring".

## 12.5.1 Properties

This job requires no parameters.

## 12.5.2 Syntax

ant -f build.xml Run\_AllRecommendations

## 12.6 Orders Output

• The Output\_Orders batch will output OptiVault orders.

## 12.6.1 Properties

- Output\_Orders.delim=Supported separators comma
- Output\_Orders.mailaddr=Email addresses, where the log file is sent once the process is completed
- Output\_Orders.jobID=Valid Orders Order Job Process ID (e.g. 1, 2, 3, etc.)

## 12.6.2 Syntax

ant - f build.xml Output\_Orders

## 12.7 Recommendations Output

• The Output\_Recommendations batch will output OptiVault orders.

## 12.7.1 Properties

Output\_Recommendations.fileName=Name of the file to be output.

- Output\_Recommendations.delim=Supported separators comma
- Output\_Recommendations.startDate=Starting date of recommendations
- Output\_Recommendations.endDate=Endign date of recommendations
- Output\_Recommendations.mailaddr=Email addresses, where the log file is sent once the process is completed

#### **12.7.2** Syntax

ant -f build.xml Output\_Recommendations

## 12.8 Orders Load

The Load\_Orders batch will load VAULT orders.

## 12.8.1 Properties

- Load\_Orders.loadfile=Name of the file to be loaded
- Load\_Orders.delim=Supported separators comma
- Load\_Orders.mailaddr=Email addresses, where the log file is sent once the process is completed
- Load\_Orders.overwrite=Overwrite existing order records in the data- yes,
   no
- Load\_Orders.optld=Write invalid records to a file yes, no
- Load Orders.datchk=Validate order & due date yes, no

## **12.8.2** Syntax

ant -f build.xml Load\_Orders

## 12.9 Calculate CI Constraints

• The Calculate\_Constraints batch will run the CI CAP/OBMH calculations.

## 12.9.1 Properties

- Calculate\_Constraints.setID=Calculation Settings ID
- Calculate\_Constraints.mailaddr=Email addresses, where the log file is sent once the process is completed
- Calculate\_Constraints.integerStart=Start at date relative to today; 0 is today, -1 is yesterday, 4 is four days in future

- Calculate\_Constraints.integerEnd=End at date relative to today; 0 is today,
   -1 is yesterday, 4 is four days in future
- Calculate\_Constraints.from=from
- Calculate\_Constraints.to=to
- Calculate\_Constraints.day=day

#### 12.9.2 **Syntax**

ant -f build.xml Calculate\_Constraints

## 12.10 Run Forecast

• The Run\_Forecast batch will run the forecast in batch.

## 12.10.1 Properties

- Run\_Forecast.ForecastType=batch
- Run\_Forecast.Horizon=Valid Forecast Definition ID
- Run\_Forecast.FilterType=Filter type. Method of selecting cashpoints. I = institution (all cashpoints). G = group. V = cashpoint (vault or commercial)
- Run\_Forecast.Filter=The ID of the filter based on the filter type. Used if the filter type IS NOT "I"
- Run\_Forecast.mailaddr=Email addresses, where the log file is sent once the process is completed

## 12.10.2 Syntax

ant -f build.xml Run\_Forecast

## 12.11 Run Commercial Consolidation

 The ComConsolidation batch will run merge the commercial forecast into the associated vault's forecast.

## 12.11.1 Properties

• ComConsolidation.setID=Valid Commercial Consolidation Setting ID from within OptiVault.

## 12.11.2 Syntax

ant -f build.xml ComConsolidation

#### 12.12 Cost Calculation

 The Cost Calculation batch process will determine the costs of actual or projected activity in vaults. The resulting values will be available in OptiVault reports.

## 12.12.1 Properties

- Cost\_Calculation.cashGroup\_id= ID of the group of cashpoints for which cost calculation will run.
- Cost\_Calculation.model\_id= "none" not used in this version of OptiVault
- Cost\_Calculation.startDate=YYYY-MM-DD costs will be calculated for activity beginning on this date
- Cost\_Calculation.endDate = YYYY-MM-DD costs will be calculated for activity ending on this date
- Cost\_Calculation.calcType = "ACTUAL" or "PROJECTED"

#### 12.12.2 Syntax

ant -f build.xml Cost\_Calculation

## 12.13 Purge Application File Data

• The Process to delete temporary files (usually report document files and generated graph images)

## 12.13.1 Properties

- Purge\_ApplicationFile\_Data.daysInPast= Delete files which were created more than this number of days in past.
- Purge\_ApplicationFile\_Data.mailaddr= Email addresses, where the log file is sent once the process is completed

## 12.13.2 Syntax

ant -f build.xml Purge\_ApplicationFile\_Data

## 12.14 Purge Cashpoint Costs

The Process to delete cashpoint cost records.

#### 12.14.1 Properties

- Purge\_Cashpoint\_Cost.monthsInPast= Delete data more than this number of months in the past
- Purge\_Cashpoint\_Cost.mailaddr= Email addresses, where the log file is sent once the process is completed

#### 12.14.2 Syntax

ant -f build.xml Purge\_Cashpoint\_Cost

## 12.15 Purge Calendar Events

• The Process to delete calendar Event records.

## 12.15.1 Properties

- Purge\_Event.monthsInPast= Delete data more than this number of months in the past
- Purge\_Event.mailaddr= Email addresses, where the log file is sent once the process is completed

## 12.15.2 Syntax

ant -f build.xml Purge\_Event

## **12.16** Purge Forecast Adjustments

• The Process to delete Forecast Adjustment records which were only applicable in the past.

## 12.16.1 Properties

- Purge\_Forecast\_Adjustment.monthsInPast= Delete data more than this number of months in the past
- Purge\_Forecast\_Adjustment.mailaddr= Email addresses, where the log file is sent once the process is completed

## 12.16.2 Syntax

ant -f build.xml Purge\_Forecast\_Adjustment

## 12.17 Purge CI CAP/OBMH

 The Process to delete Custodial Inventory CAP and OBMH (On Book Minimum Holding) records.

## 12.17.1 Properties

- Purge\_Obmh\_Cap.daysInPast= Delete data more than this number of days in the past
- Purge\_Obmh\_Cap.mailaddr= Email addresses, where the log file is sent once the process is completed

## 12.17.2 Syntax

ant -f build.xml Purge\_Obmh\_Cap

## 12.18 Purge Audit Records

• The Process to delete records of OptiVault user activity.

## 12.18.1 Properties

- Purge\_Audit.daysInPast= Delete data more than this number of days in the past
- Purge\_Audit.mailaddr= Email addresses, where the log file is sent once the process is completed

## 12.18.2 Syntax

ant -f build.xml Purge\_Audit

# 12.19 Purge History

• The Process to delete cashpoint history data.

## 12.19.1 Properties

- Purge\_History.monthsInPast= Delete data more than this number of months in the past
- Purge\_History.mailaddr= Email addresses, where the log file is sent once the process is completed

## 12.19.2 Syntax

ant -f build.xml Purge\_History

## 12.20 Purge Recommendations

The Process to delete recommendation records.

## 12.20.1 Properties

- Purge\_Recommendations.daysInPast= Delete data more than this number of days in the past
- Purge\_Recommendations.mailaddr= Email addresses, where the log file is sent once the process is completed

## 12.20.2 Syntax

ant -f build.xml Purge\_Recommendations

## **12.21** Purge Orders

The Process to delete order records.

## 12.21.1 Properties

- Purge\_Orders.daysInPast= Delete data more than this number of days in the past
- Purge\_Orders.mailaddr= Email addresses, where the log file is sent once the process is completed

## 12.21.2 Syntax

ant -f build.xml Purge Orders

## 12.22 Cashpoint Synchronization

• The Process to bring OptiCash cashpoint details into OptiVault. Create, update and delete cashpoints as well as ensure relationships between cashpoints are the same as OptiCash.

## 12.22.1 Properties

- Batch\_Cashpoint\_Synchronization.insertFlag= "yes" or "no". New cashpoints in OptiCash will be added into OptiVault.
- Batch\_Cashpoint\_Synchronization.updateFlag= "yes" or "no". Cashpoint details from OptiCash will overwrite the same that already exists in OptiVault.

- Batch\_Cashpoint\_Synchronization.deleteFlag= "yes" or "no". Cashpoints already removed from OptiCash will be removed from OptiVault.
- Batch\_Cashpoint\_Synchronization.mailaddrPurge\_Orders.mailaddr= Email addresses, where the log file is sent once the process is completed

#### 12.22.2 Syntax

ant -f build.xml Batch\_Cashpoint\_Synchronization

## 12.23 Calendar Refresh

 The Process to bring OptiCash system settings into OptiVault. Calendars, Events, Currency and Denomination Definitions, Service Depots, and Exchange Rates are all made to be the same as OptiCash.

## 12.23.1 Properties

 Batch\_Calendar\_Refresh.mailaddr= Email addresses, where the log file is sent once the process is completed

## 12.23.2 Syntax

ant -f build.xml Batch\_Calendar\_Refresh

## 12.24 Extend Event Dates

 The Process for automatically extending Event date definition. "Events" in OptiVault are defined like rules: for example, Event "X" happens the on 4<sup>th</sup> Thursday of November. "Event Dates" are that rule translated to specific calendar days: for example, 28-Nov-2013, 27-Nov-2014, 26-Nov-2015, 25-Nov-2016. Event Dates need to exist for the Forecast process, so occasionally there is a need to extend further into the future. This process does that in an automatable fashion.

## 12.24.1 Properties

- ExtendEventDates.startDate= YYYY-MM-DD or "default" or "all". If a specific date is given, Event date generation begins then. If "default" is specified, Event date generation begins at end of existing Event Dates and goes to the current date + 5 years. If "all" is specified, Event dates are generated for 2 years in the past, the current year, and 2 years beyond.
- ExtendEventDates.mailaddr= Email addresses, where the log file is sent once the process is completed

ExtendEventDates.overwrite= "yes" or "no". If "yes" is specified, existing
event dates are removed and replaced with newly generated Event dates.
If "no", then newly generated Event dates are added to whatever existed
before.

## 12.24.2 Syntax

ant -f build.xml ExtendEventDates

## **13File Maintenance**

The following directories should regularly be purged in the deployed instance of OptiVault:

- dynimages\ (Kavachart images (pie charts, forecast graphs, etc.) as generated by the UI)
- dynreports\ (old CSV and PDF reports)

User institutions should purge these directories weekly. Deleting files from these directories should have no negative impact on the application.

Process logs (i.e. Recommendation logs, Forecast logs, Orders Output logs, etc.) should be purged occasionally, as well. The directory location for these log files will be the logs directory of the deployed instance. The interval for purging these logs will vary upon how much the client decides to keep archived, but it is not recommended to keep these files for more than a month, at most, unless there are compelling reasons.

# 14Redeploying the OptiVault Oracle Schema

- 1. It is recommended to have nightly backups of the OptiVault Oracle schema.
- 2. Users may backup the data using replication, a simple *Oracle EXP* command, or other tools of choice for the DBA.
- 3. You would reload data following the schema user create and import methods outlined earlier in the installation guide.

# **15Preventing Access to System Maintenance**

All system maintenance functions are stored in the maint sub-directory in the **OptiVault.war/ directory**.

If you choose to limit access to this directory, you may either:

- 1. Limit access to the URL using the provided security roles which can be mapped to plug-in Users and/or Groups (recommended).
- 2. Limit access to the URL at the web tier (recommended).
- 3. Move the directory to another location outside of the deployed instance once OptiVault is setup properly. You can always modify the **optivault.properties** file manually if needed.
- 4. Delete the directory once OptiVault is setup properly. You can always modify the **optivault.properties** file manually if needed.

# **16** Additional Dependencies for OptiVault in Tomcat

For clients deploying OptiVault on Apache Tomcat, you will need to configure the CSRF security properties to use the random number generator included with your app server (default refers to one for IBM WebSphere). Find file **{root directory}\WEB-INF\classes\Owasp.CsrfGuard.properties** and modify the following two properties:

- org.owasp.csrfguard.PRNG=SHA1PRNG
- org.owasp.csrfguard.PRNG.Provider=SUN

This example shows a typical Apache Tomcat setup. Similar lines referring to the IBM generator will need to be removed or commented out.

Also, you will need to deploy the following additional dependencies (jar files) under Tomcat "lib" directory (IBM WebSphere typically comes with these already included). For example, if Tomcat is installed under

C:\apache-tomcat-7.0.35

Then the jar files mentioned in this document should be put in

C:\apache-tomcat-7.0.35\lib

**Note** The version of each depends on the version of Tomcat installed.

These files should be downloaded from a trusted internet source, such as <u>mvnrepository.com</u>.

#### 16.1.1 Tomcat 7

Following are dependencies that are required by OptiCash/OptiNet in Tomcat 7

File name	
el-api-2.2.jar	
el-impl-2.2.1-b05.jar	
geronimo-jpa_2.0_spec-1.1.jar	
javax.servlet.jsp-api-2.2.1.jar	
javax.servlet-api-3.0.1.jar	
jstl-1.2.jar	

jstl-api-1.2.jar
jstl-impl-1.2.jar
jta-1.1.jar
validation-api-1.0.0.GA.jar

#### 16.1.2 Tomcat 8

Following are dependencies that are required by OptiCash/OptiNet in Tomcat 8

File name	
javax.el-api-3.0.0.jar	
geronimo-jpa_2.0_spec-1.1.jar	
javax.servlet.jsp-api-2.3.1.jar	
javax.servlet-api-3.1.0.jar	
jstl-1.2.jar	
jstl-api-1.2.jar	
jstl-impl-1.2.jar	
jta-1.1.jar	
validation-api-1.0.0.GA.jar	

#### 16.1.3 Tomcat 9

Following are dependencies that are required by OptiCash/OptiNet in Tomcat 9

File name
geronimo-jpa_2.0_spec-1.1.jar
javax.servlet.jsp-api-2.3.3.jar
javax.servlet-api-4.0.1.jar

taglibs-standard-impl-1.2.5.jar

taglibs-standard-spec-1.2.5.jar

jta-1.1.jar

validation-api-1.0.0.GA.jar

#### **17IMPORTANT NOTE**

To upgrade the application version to 9.16 with SQL Server, below are the steps.

- 1. Customers having older versions (<9.16) must be upgraded to 9.16 without changing the DB server (Oracle).
  - a. This step is taken care by the application if 9.16 war with oracle properties is deployed into the webserver.
  - b. After deployment, the user is prompted to upgrade DB Schema. This is also specific to OC and OV. For VLM, products the upgrade is taken care by Liquibase.
- 2. Create Database and schema in SQL Server as mentioned in installation.
- 3. Migrate data from Oracle to SQLServer(taken care by NCR Team).
- 4. Update Oracle DB properties with SQLServer Details in 9.16 war and deploy.

# **18EPSS Integration**

- 1. After 10.x, the application must be integrated with EPSS for authentication and authorization.
- 2. User/Terminal Groups must be created in EPSS.
- 3. Kindly refer to CM apps Installation and *EPSS Integration guide10.0.pdf* for detailed steps.

**NOTE**: It is recommended to use Tomcat as the application server from 10.x for CM apps instead of websphere/weblogic.

From 10.1 onwards, the Role 'OV\_VIEWER' needs to be added to the Security Groups that have roles relating to OptiVault, the role will allow the user to be able to view and access the OptiVault Menu Items.

CXBanking, OptiVault 10.1, Installation Guide April 2023

www.ncr.com

