Part I " Calculating the Gradients for the Output Layer Weights 3E output for modes (0 or 1) put Layer Weights 3Wq = (z-t) × z (1-z) × outb1

U5 = (0.5934 - 0) × 0.5934(1-0.5934) × 0.7020 = 0.5934 × 0.5934(0.4066) × 0.7020 = 0.1005

W7 = (0.5934-0) × 0.5934 (1-0.5934) × 0.5841 = 0.5934 × 0.5934(0.4066) × 0.5841 = 0.0836

We = (0.7353-1) × 0.7353 (1-0.7353) × 0.7020 =-0.2647 × 0.7353 (0.2647) × 0.7020 =-0.0362

We = (0.7353+1) x 0.7353 (1-0.7353) x 0.5841 = -0.2647 x 0.7353 (0.2647) x 0.5841 = -0.0301

Part 2: Gradients for Output Layer Blas Weights,  $S_z = (z-t)z(1-z)$ 

= (0.5934-0) × 0.5934 (1-0.5934) = 0.5934 × 0.5934 (0.4066) = 0.1432

buy = (0.7353-1) x 0.7363 (1-0.7363) = -0.2647 x 0.7363 (0.2647) = -0.0515