COBOL· Common business oriented language

1958 codasyl - pentagon

Dr· Grace hopper

Application programming language

English like language

Add a to b giving c·

Divide a by b giving d remainder e·

Create a pds

HLQ·URNAME·REVAT·COBOL·PDS

LRECL=80, RECFM=FB,, DSORG=PDS

PQ=10, SQ=10, DB=10,

Create a member \rightarrow COMPJCL \rightarrow type the job mentioned in the chat·

Create another \rightarrow RUNJCL \rightarrow type the next job mentioned in the chat·

CREATE A LIBRARY

HLQ·URNAME·REVAT·COBOL·LOADLIB

LRECL=80, RECFM=U, DSORG=LIBRARY

PQ=10, SQ=10, DB=10,

- 1. Write the cobol pgm
- 2. Submit a compile job on behalf of the cobol pgm.
 - a· Step1 → check syntax errors in cobol stmnts
 - b. Step2→ convert the cobol codes in loda modules/object code

3. Submit another the job that will run the load module.

PROGRAM STRUCTURE:

4 DIVISIONS.

1.IDENTIFICATION DIVISION: (mandatory)

Note: identifies the program.

PROGRAM-ID. Entry. mandatory

[AUTHOR. Entry].

[INSTALLATION Entry].

[DATE-WRITTEN. Entry].

[DATA-COMPILED. Entry].

[SECURITY Entry

[REMARKS. Entry.]

2. ENVIRONMENT DIVISION. (optional)

CONFIGURATION SECTION.

SOURCE-COMPUTER. ZOS.

OBJECT COMPUTER. 390.

INPUT-OUTPUT SECTION.

FILE CONTROL: \rightarrow where the files are linked:

Note: Files and other external resources are linked here.

logical name for the file is given here.

Accessing mode

Organization

3.DATA DIVISION. (optional)

Note: all the variables are declared

FILE SECTION.

FD - FILE'S FIELD DISCRIPTION (FILE LAYOUT/FILE VARIABLES)

WORKING-STORAGE SECTION.

ALL THE COMMONLY USED VARIABLES

LOCAL-STORAGE SECTION.

REPORTS

LINKAGE SECTION.

SUB PROGRAMS AND to which the values can be received from the user dynamically

PROCEDURE DIVISION · (Mandatory)

Has no predefined sections or paragraphs. Executable statements are written/verbs Must be ended by 'stop run'.

COLUMN DISCRIPTION OF COBOL PROGRAM

1-6 - SEQNUM

7 -INDICATOR \cdot SPACE \rightarrow executable sentence

'*' → comment

'-' \rightarrow continuation of string from previous sentence·

8-11 AREA/MARIGIN A

DIVISIONS, SECTIONS, PARAGRAPHS, FD, SD 01,77 ENTERIES.

12-72 -AREA/MARIGIN B

02-49,66,88 LEVEL NUMBERS. ALL EXECUTABLE SENTANCE IN PROCEDURE DIVISION(VERBS).

73-80 - IDENTIFIER - USERS DISCRETION.

Data types:

- 1. Char → A
- 2. Numeric > 9
- 3. Alphanumeric $\rightarrow X$

DECLARE A VARIABLE

SYNTAX:

LEVEL-NUMBER SPACE NAME-VAR SPACES PICTURE-CLAUSE DATATYPE(SIZE) VALUE-CLAUSE

LEVEL NUMBER → 01,77,02-49,66,88

VAR-NAME (MAX 36). ALPHANUMERIC, -, FIRST CHAR MUST BE ALPHABET.

(let the name tell the story)

PIC MANDATORY

DATATYPE(SIZE)

 $A(05) \rightarrow left$ justified with auto spaces on the suffix

 $9(05) \rightarrow right$ justified with auto zeros prefixed

 $X(10) \rightarrow$ left justified with auto spaces on the suffix

 $VALUE(OPTIONAL) \rightarrow$ the user can assign the variable with some initial values.

Date: 29:09-2023

Topics to be covered:

Singed variables

Figurative constants

Decimal variables

Move statement

Reference Modification

Group items

Arithmetic operations

Conditions

Conditional statements

Loops.

Task of the day:

Max digits· Max chars → alphabetic, max chars → alphanumeric

Singed variables. Numeric.

Pic $9(03) \rightarrow no sign$

01 WS01-A PIC 59(03) VALUE +123. A23.

Note: Signed variable, by default is sign leading. The sign will be combined with the leading digit with the below convention.

01 W501-A PIC 59(03) sign leading VALUE +123. A23

The sign will be combined with the leading digit with the below convention.

01 WS01-B PIC 59(03) sign trailing VALUE +123. 12C.

Convention \rightarrow +1 \rightarrow A, +2 \rightarrow B... +9 \rightarrow I, -1 \rightarrow J, -2 \rightarrow K... -9 \rightarrow R· +0 \rightarrow {, -0 \rightarrow }

01 WS01-STS PIC 59(03) sign trailing Separate VALUE +123.

→ 123+

01 WS01-SLS PIC S9(03) sign leading Separate VALUE +123. → +123

Figurative constants

Space, spaces, O, zero, zeros, zeroes

Decimal variables.

Virtual \rightarrow numeric \rightarrow arithmetic operation. The decimal point will not be displayed. 123.456 \rightarrow 123456

01 ws01-vd PIC 9(03)V(02) value 123.45

But when you display → 12345

- Physical (alphanumeric) → no arithmetic operation allowed on this Variable.
- no value clause is allowed.
- Move statement is allowed

01 W501-PD PIC 9(03)·9(02)

MOVE

Allocation of a value to a variable can be done 2 ways.

- 1. Value clause- data division.
- 2. Move statement in Procedure division.

Syntax:

Move source to dest-variables

Move 10 to ws01-var1

Move 'ca7' to ws05-name

Move ws01-a to ws05-b (provided their data type are same)

Move 10 to ws01-a, ws05-b, ws05-c

Move ws05-d to ws01-a, ws05-b, ws05-c

Move corresponding grp1 to grp2

It willmove the values from source members to the dest members, ONLY IF THEIR NAME MATCHES, irrespective of their sequence:

Move grp1 to grp2

→ It moves values in the sequence.

Source → single· Value/literal or variables

Destination → single or multiple variables·

Reference Modification.

A technique by which parts of a variable can be handled individually.

Syntax: var(stpos:length)

01 ws01-a pic a(05) value 12345.

01 ws01-b pic 9(05) value 00000.

1 2 3 4 5

Move ws01-a(2:3) to ws01-b(3:3)

0 0 2 3 4

Group items.

01 - level \rightarrow 1page-4kb 01 ws01-A pic x(03)

77 level number - elementary data item·
The number bytes allocated is the number bytes mentioned in the size clause·

Suggest: Declare one variable at O1 level number and declare all the other variables in the same page/under that O1 level number variable.

A group item is a variable which has member variables defined 01 ws01-vars

02 ws02-var1 pic 9(03).
02 ws02-var2 pic X(04).
02 ws02-var3 pic A(15).

Note: level numbers 02 - 49 must be mentioned in marigin b

Rules of group item.

- It cannot have picture clause.
- It CAN HAVE value clause. Value are considered to alphanumeric.
- A group item is identified as a group item, if it has variables with higher level number.
- The member items can have their own different pic clauses and sizes.
- The size of a group item is calculated by adding the sizes of its members.

Rules of a member item.

- Must have a level number higher than its group item.
- Any higher level number is the member of its immediate previous lower level number.
- A member item can be a SUB GROUP item.

01 ws01-vars VALUE "TOMMY007USANJK991111".

05 WS05-NAME PIC A(05).

05 WS05-ID PIC X(03).

05 WS05-ADDRESS.

10 WS10-COUNRTY PIC A(3).

10 W510-STATE PIC A(3).
10 W510-PCODE PIC 9(02).

05 WS05-PHONE PIC 9(4).

Note: group move Move corresponding See video 02-10-2023.

Arithmetic operations:

Numeric data type.

1. ADD.

ADD 10 TO WS05-A
$$\rightarrow$$
 WS05-A = WS05-A + 10

ADD WS05-A TO WS05-B \rightarrow WS05-B = WS05-A + WS05-B

ADD WS05-A TO WS05-B WS05-C. \rightarrow

WS05-B = WS05-B + WS05-A

WS05-C = WS05-C + WS05-A

ADD 10 TO WS05-B GIVING WS05-C

WS05-C = WS05-B + 10.

2. SUBTRACT.

SUBTRACT 10 FROM WS05-A \rightarrow WS05-A = WS05-A - 10
SUBTRACT WS05-A FROM WS05-B \rightarrow WS05-B = WS05-B - WS05-A
SUBTRACT WS05-A FROM WS05-B GIVING WS05-C

3. MULTIPLY.

MULTIPLY WS05-A BY WS05-B MULTIPLY 10 BY WS05-B MUTLIPLY WS05-A BY WS05-B GIVING WS05-C

4. DIVIDE

DIVIDE WS05-A BY WS05-B \rightarrow WS05-B(QU0)= WS05-A / WS05-B DIVIDE WS05-A BY WS05-B GIVING WS05-C REMAINDER WS05-D

5. COMPUTE. (NATURAL ARITHMATIC OPERATORS.)

$$C = A * B / F (-23 + 2) **4$$
 $BODMAS RULE IS FOLLOWED$
 $COMPUTE C = A * B / F (-23 + 2) **4$
 $COMPUTE C ROUNDED = (A * B) / 2 * (-23 + 2) **4$
 $Note: a Space must be given before and after the operator.$

- Relation Condition
 - <, LESS THAN, >, GREATER THAN, EQUALS TO, =, <=,>=
- Sign Condition POSITIVE NEGATIVE, ZERO
- Class Condition -ALPHABETIC, NUMERIC, ALPHABETIC-LOWER, ALPHABETIC-UPPER
- Condition-Name 88 level number declaration.
- Negated Condition NOT
- Combined Condition LOGICAL OPERATORS: AND & OR

Conditional statements

IF (CONDITION) THEN

IMP STMNT

ELSE IF(CONDITION) THEN

IMP STMNTS

ELSE

IMP STMNTS

END-IF

END-IF.

Note: The number of end-if must be equal to the number of IF in the structure.

There MUST NOT BE A PERIOD ANYWHERE INBETWEEN IF AND END-IF

Evaluate

EVALUATE TRUE/FALSE/VARIABLE WHEN CONDITION

```
IMP
```

WHEN CONDITON

IMP

WHEN OTHER

IMP

END-EVALUATE.

EXAMPLE:

IF (WSO5-A > WSO5-B AND WSO5-A > WSO5-C) THEN DISPLAY 'A IS THE GREATEST'

ELSE IF (WS05-B > WS05-A AND WS05-B > WS05-C) THEN DISPLAY 'B IS THE GREATEST'

ELSE

DISPLAY ' C IS THE GREATEST'

END-IF

END-IF.

EVALUATE TRUE

WHEN (WS05-A > WS05-B AND WS05-A > WS05-C)

DISPLAY ' A IS THE GREATEST'

WHEN (WS05-B > WS05-A AND WS05-B > WS05-C)

DISPLAY ' B IS THE GREATEST'

WHEN OTHER

DISPLAY ' C IS THE GFREATEST'

END-EVALUATE.

LOOPS. ITERATION STATEMENTS.

PERFORM

1. CONDITIONAL

Until a condition is satisfied the loop run.

a. Inline perform

When the group of statements to be iterated lies between "perform' and 'end-perform.

WS05-A PIC 9(02) VALUE 5.

PERFORM UNTIL WS05-A > 10

DISPLAY 'HI'

Add 1 TO ws05-a

END-PERFORM.

Ans: 6 timed.

WS05-A PIC 9(02) VALUE 5.

PERFORM UNTIL WS05-A > 10

DISPLAY 'HI'

END-PERFORM.

Ans: infinite a· Infinity 722 abend Ws05-a pic 9(02) value 5·

PERFORM VARYING WS05-A FROM 1 BY 1 UNTIL WS05-A > 10
DISPLAY 'HI'
DISPLAY WS05-A
END-PERFORM.
ANS: 10

b. Out-of-the-line

When a perform statement performs/calls a paragraph that is/not in the sequence of the statements.

The perform statement jumps to the paragraph and executes the statements in the paragraph and after doing so it comes back to the next from where it went.

PROCEDURE DIVISION.

PERFORM PARA-A UNTIL WS05-A > 5

PERFORM PARA-B VARYING WS05-A FROM 1 BY 1 UNTIL WS05-A >10
PERFORM TERM-PARA.

TERMP-PARA.

STOP RUN.

PARA-A.

DISPLAY 'HI'.

ADD 1 TO WSO5-A

PARA-B.

DISPLAY 'HELLO'.

- 2. UNCONDITIONAL
- a. Inline perform

When the group of sentence that are to be iterated are written between perform and end-perform stmnts.

PERFORM 5 TIMES

DISPLAY ' HI'

END-PERFORM.

PERFORM

DISPLAY 'HI'

END-PERFORM.

PERFORM WSO5-A TIMES

DISPLAY 'HI'

END-PERFORM

ANS:ws05-a times

PERFORM WSO5-A TIMES

DISPLAY 'HI'

ADD 1 TO WSO5-A

DISPLAY WSO5-A

END-PERFORM

b. Out-of-the-line

Dosn't check any condition to be satisfied.

When a paragraph is performed.

The program can be executed out of sequence.

PROCEDURE DIVISION.

PERFORM PARA-A

PERFORM PARA-B 3 TIMES

PERFORM TERM-PARA.

TERMP-PARA.

STOP RUN.

PARA-A.

DISPLAY 'HI'.

PARA-B.

DISPLAY 'HELLO'.

CONTROL STATEMENTS.

CONTNIUE

Transfers the control to the next COBOL statement which come next in the program flow.

NEXT SENTENCE

Transfers control to the next COBOL statement, which is immediately after the sentence ending with period.

Copy:

A group reusable statements can be written in any pds member.

They can be COPied into any division of your program.

Note: we need to mention the PDS in which the copy member is kept, in the compile $jcl \rightarrow compile \cdot syslib \cdot$

The member is called COPY BOOK
The PDS is called copy library.

Syntax: copy memname

FILE HANDLING FILES TRANSACTION, MASTER, BATCH

Processing data from a dataset and sending it to another datasets.

1. Link the file with program. ENVIRONMENT DIVISION. INPUT-OUTPUT SECTION. FILE-CONTROL.

SELECT TIO01-PS ASSIGN TO DDNAME

ORGANIZATION IS SEQUENTIAL

ACCESS IS SEQUENTIAL

FILE STATUS IS WS05-FST-TIO01.

ORGANIZATION → SEQUENTIAL PS,ESDS

INDEXED - KSDS

RELATIVE - RRDS

LINEAR - LDS

ACCESS → SEQUENTIAL

RANDOM

DYNAMIC

2. File variables. File layout.

Declare variables for the fields in the file.

6090 TOMMY INDIA 03800.89

DATA DIVISION.

FILE SECTION.

FD T1001-P5.

01 TIOO1-PS-REC.

05 TI001-ID PIC 9(04).

05 FILLER PIC X(01).

05 TIO01-NAME PIC A(05).

05 FILLER PIC X(01).

05 T1001-LOC PIC A(09).

05 FILLER PIC X(01).

05 TI001-SAL PIC 9(05).9(02).

05 FILLER PIC X(51).

3. Open appropriate mode

PROCEDURE DIVISION.

SYNTAX: OPEN MODE LOGICAL-FILENAME

 $INPUT \rightarrow reading from it$

OUTPUT → Writing into it

 $I-O \rightarrow$ reading, rewriting from and into it

 $EXTEND \rightarrow Writing records by appending$

4. Read, write, rewrite, delete, start, read next

PROCEDURE DIVISION

READ FILENAME -> one record from the dataset is copied into the

file layout.

READ FILENAME

AT END

IMPERATIVE

NOT AT END

IMPERATIVE

END-READ.

WRITE RECORD-NAME \rightarrow The values in the layout are moved into the file.


DELETE FILE-NAME \rightarrow the matching record would be removed from the file.

REWRITE RECORD-NAME → MODIFIES THE RECORD START, READ-NEXT DYNAMIC ACCESS.

DATASETS AND ITS ALLOWED OPERATIONS AND MODES.

FILENAME	ORGANIZATI	ACCESS	OPERATIONS	DDNAME
	ON	MODES		IN CBL
PS	SEUQENTIAL	SEQUENTIAL	READ, WRITE	DDNAME
ESDS	SEQUENTIAL	SEQUENTIAL	READ, WRITE	AS-
				DDNAME
KSDS	INDEXED	SEQUENTIAL,	READ, WRITE,	DDNAME
		RANDOM,	DELETE, REWRITE,	
		DYNAMIC	START, READ-	
			NEXT	
RRDS	RELATIVE	SEQUENTIAL,	READ, WRITE	DDNAME
		RANDOM		
		DYNAMIC		

Movement of data from and to dataset and File layout



5. Close.

PROCEDURE DIVISION: CLOSE FILENAME:

6. File operation status.

STATUS CODE: 00 → OPERATION SUCCESS.

10 → END OF FILE IS REACHED

SCENARIO.

Sweep / read all the records from the ps and validate the records with the below validations.

The id MUST ONLY HAVE NUMBERS

The salary must number before and after decimal point.

The decimal point must be a period.

Display all the valid records.

Don't display the invalid records.

DATA FLOW:

OPEN THE FILE \rightarrow FAILURE \rightarrow KILL THE PROGRAM \rightarrow READ UNTIL EOF \rightarrow VALIDATION \rightarrow DISPLAY INVALID \rightarrow SKIP

CLOSE

PROCEDURE DIVISION
0000-MAIN-PARA

PERFORM 1000-INIT-PARA
PERFORM 3000-PROC-PARA
THRU 3000-PROC-PARA-EXIT
PERFOMR 9000-TERM-PARA

1000-INIT-PARA

EXIT

.

```
3000-PROC-PARA
    PERFORM 3100-OPEN-PARA
         THRU 3100-OPEN-PAR-EXIT
    PERFORM 3200-READ-PARA
         THRU 3200-READ-PARA-EXIT
         UNTIL WS05-FST-T1001 = 10
    PERFORM 3300-CLOSE-PARA
         THRU 3300-CLOSE-PARA-EXIT
3000-PROC-PARA-EXIT.
    EXIT
9000-TERM-PARA:
    STOP RUN
3100-OPEN-PARA.
    OPEN INPUT TIOOI-PS
    EVALUATE TRUE
    WHEN WS05-FS-T1001 = 00
         DISPLAY 'TIOOI OPEN SUCCESS '
    WHEN OTHER
         DISPLAY 'TIOOI OPEN FAILED :' WSO5-FST-TIOOI
         PERFORM 9000-TERM-PARA
    END-EVALUATE
3100-OPEN-PARA-EXIT.
    EXIT
3200-READ-PARA
    READ TIOO1-PS
    EVALUATE TRUE
    WHEN WS05-FS-T1001 = 00
         ADD 1 TO WSO5-REC-COUNT
```

PERFORM 3210-VALID-PARA

```
THRU 3210-VALID-PARA-EXIT
    WHEN WS05-FST-T1001 = 10
         IF WSO5-REC-COUNT = 0
              DISPLAY 'EMPTY INPUT FILE'
         ELSE
             DISPLAY ' ALL RECORDS PROCESSED'
         END-IF
    WHEN OTHER
         DISPLAY 'TIOOI- READ FAILED 'WSO5-FST-TIOOI
    END-EVALAUTE
3200-READ-PARA-EXIT-
    EXIT
3210-VALID-PARA.
    EVALAUTE TRUE
    WHEN TIOOI-ID IS NUMERIC AND
           TIOO1SAL(1:5) IS NUMERIC AND
           TIOO1-SAL(6:1) = '\cdot'
                                    AND
           TIO01-SAL(7:2) IS NUMERIC
                  PERFORM 3211-CAL-PARA
                       THRU 3211-CAL-PARA-EXIT
    WHEN OTHER
         DISPLAY ' INVALID RECORD : ' TIOO1-ID
    END-EVALUATE
3210-VALID-PARA-EXIT-
    EXIT
3300-CLOSE-PARA.
    CLOSE TIOO1-PS
```

```
3211-CAL-PARA.
    DISPLAY ' THE RECORD IS A VALID RECORD'
    DISPLAY 'THE ID : 'TIO01-ID
    DISPLAY 'THE NAME : 'TIOOI-NAME
    DISPLAY 'THE LOC : 'TIO01-LOC
    DISPLAY 'THE OLD SAL : 'TIOOI-SAL
    MOVE TIOOI-SAL TO WSO5-SAL
    IF (TIOO1-LOC = 'CHENNAI' OR
       TIO01-LOC = 'CHINA' )
         COMPUTE WS05-SAL = WS05-SAL * 1.15
    ELSE IF ( TIOO1-LOC = 'DETROIT' OR
             TIO01-LOC = 'MICHIGEN' )
         COMPUTE WS05-SAL = WS05-SAL * 1.20
    ELSE
         COMPUTE WS05-SAL = WS05-SAL * 1.30
    END-IF
    END-IF
    MOVE WSO5-SAL TO TIOOI-SAL
    DISPLAY ' THE NEW SAL :' TIOOI-SAL
3211-CAL-PARA-EXIT.
    EXIT
3300-CLOSE-PARA-EXIT.
    EXIT
```

1. EMPTY INPUT FILE HANDLING.

Define a counter and add 1 to it when the read is successful· In the read para, when EOF is checked, use if condition to check the rec counter· If the counter is $O \rightarrow$ empty file

Else → end file of reached.

id:

name:

loca:

old sal:10000

new sal: 11500

 $br \rightarrow$

if the location is in asia \rightarrow 15 % else if location US \rightarrow 20 % else \rightarrow 30%

SCENARIO. READ ALL RECORDS FROM THE INPUT DATSET AND VALIDATE THEM.

if the record is invalid → display invalid record

if the record is valid

display the fields of the record as well as new field.

VALIDTIONS CONDITIONS

New field logic is given

if the location is in asia \rightarrow 15 % else if location US \rightarrow 20 % else \rightarrow 30%

Thought process.

How do I link? Organization, access

What is the layout? > physical decimal point, and is there any requirement that expects me to perform arithmetic operation on that variable?

What mode do I open? input

Read until eof

- · Move spaces to the layout
- Reada filename
- Check the file status variable
 - If file status is 00
 Add 1 to rec-counter

Perform - valid-para

- Else if the file status = 10
 ****** check for empty file
- o Else

** read failed

Close

Valid - fails → display 'invalid

Passess → caluculation → display the record

Data flow

Open-para Read-para until eof Close-para

Read-para → valid-para → calc-para → display

Failed →

Data flow

Scenario 3:

Read records from ps,

Validate the records.

Calculate the new salary

Write the valid records into another ps.

The output ps layout is as below.

Id name loc old sal new sal

Pic9(04) pic a(05) pic a(09) pic $9(05)\cdot 9(02)$ pic $9(05)\cdot 9(02)$

With one filler between fields.

1. Link.

ENVIRONMENT DIVISION.

INPUT-OUTPUT SECTION.

FILE-CONTROL.

SELECT TIOOI-PS ASSIGN TO DDI

ORGANIZATION IS SEQUENTIAL

ACCESS IS SEQUENTIAL

FILE STATUS IS WS05-FST-TI001.

SELECT TOOOI-PS ASSIGN TO DD2

ORGANIZATION IS SEQUENTIAL

ACCESS IS SEQUENTIAL

FILE STATUS IS WS05-FST-T0001.

2. LAYOUT.

DATA DIVISION.

FILE SECTION.

FD T1001-PS.

01 TIOO1-PS-REC.

05 TI001-ID PIC 9(04).

05 FILLER PIC X(01).

05 TIO01-NAME PIC A(05).

05 FILLER PIC X(01).

05 TI001-LOC PIC A(09).

05 FILLER PIC X(01).

05 TI001-SAL PIC 9(05).9(02).

05 FILLER PIC X(51).

FD T0001-PS.

01 T0001-P5-REC.

05 T0001-ID PIC 9(04).

05 FILLER PIC X(01).

05 TO001-NAME PIC A(05).

05 FILLER PIC X(01).

05 T0001-LOC PIC A(09).

05 FILLER PIC X(01).

05 T0001-SAL PIC 9(05).9(02).

05 FILLER PIC X(01).

05 T0001-NEW-SAL PIC 9(05).9(02)

05 FILLER PIC X(41).

3. OPEN

OPEN INPUT TIOO1-PS

OPEN OUTPUT TOOOI-PS

4. READ→ VALID→ CAL→ WRITE

WRITE → PLACE THE VALUES IN THE OUTPUT LAYOUT, THAT YOU ARE PLANNING TO WRITE·(MOVE STATEMNTS)

WRITE TOOOI-PS-REC·

PROCEDURE DIVISION 0000-MAIN-PARA

PERFORM 1000-INIT-PARA
PERFORM 3000-PROC-PARA

THRU 3000-PROC-PARA-EXIT

PERFOMR 9000-TERM-PARA

1000-INIT-PARA·

.

```
3000-PROC-PARA
    PERFORM 3100-OPEN-PARA
         THRU 3100-OPEN-PAR-EXIT
    PERFORM 3200-READ-PARA
         THRU 3200-READ-PARA-EXIT
         UNTIL WS05-FST-T1001 = 10
    PERFORM 3300-CLOSE-PARA
         THRU 3300-CLOSE-PARA-EXIT
3000-PROC-PARA-EXIT.
    EXIT
9000-TERM-PARA:
    STOP RUN
3100-OPEN-PARA.
    OPEN INPUT TIOO1-PS
    EVALUATE TRUE
    WHEN WS05-FS-T1001 = 00
         DISPLAY 'TIOOI OPEN SUCCESS'
    WHEN OTHER
         DISPLAY 'TIOOI OPEN FAILED :' WSO5-FST-TIOOI
         PERFORM 9000-TERM-PARA
    END-EVALUATE
    OPEN OUTPUT TOOOI-PS
    EVALUATE TRUE
    WHEN WS05-FS-T0001 = 00
         DISPLAY ' TOOOI OPEN SUCCESS '
    WHEN OTHER
         DISPLAY ' TOOOI OPEN FAILED : WSO5-FST-TOOOI
         PERFORM 9000-TERM-PARA
    END-EVALUATE
```

```
3100-OPEN-PARA-EXIT.
    EXIT
3200-READ-PARA
    MOVE SPACES TO TIOOI-PS-REC TOOOI-PS-REC
    MOVE O WSO5-NEW-SAL
    READ TIOO1-PS
    EVALUATE TRUE
    WHEN WS05-FS-T1001 = 00
         ADD 1 TO WSO5-REC-COUNT
         PERFORM 3210-VALID-PARA
          THRU 3210-VALID-PARA-EXIT
    WHEN WS05-FST-T1001 = 10
         IF WSO5-REC-COUNT = 0
             DISPLAY 'EMPTY INPUT FILE'
         ELSE
             DISPLAY ' ALL RECORDS PROCESSED'
         END-IF
    WHEN OTHER
         DISPLAY 'TIOOI- READ FAILED 'WSO5-FST-TIOOI
    END-EVALAUTE
3200-READ-PARA-EXIT.
    EXIT
3210-VALID-PARA.
    EVALAUTE TRUE
    WHEN TIOO1-ID
                   IS NUMERIC AND
           TIOO1SAL(1:5) IS NUMERIC AND
           TIOO1-SAL(6:1) = '\cdot'
                                    AND
           TIOO1-SAL(7:2) IS NUMERIC
                  PERFORM 3211-CAL-PARA
                       THRU 3211-CAL-PARA-EXIT
```

WHEN OTHER

```
DISPLAY 'INVALID RECORD : 'TIOO1-ID
    END-EVALUATE
3210-VALID-PARA-EXIT.
    EXIT
3211-CAL-PARA.
     MOVE TIO01-ID TO TO001-ID
    MOVE TIOOI-NAME TO TOOOI-NAME
    MOVE TIO01-LOC TO TOO01-LOC
    MOVE TIOOI-SAL
                     TO TOO01-SAL
    MOVE TIOO1-SAL
                     TO WSO5-SAL
    IF (TIOO1-LOC = 'CHENNAI' OR
       TIO01-LOC = 'CHINA')
         COMPUTE WS05-SAL = WS05-SAL * 1.15
    ELSE IF ( TIOO1-LOC = 'DETROIT' OR
             TIO01-LOC = 'MICHIGEN' )
         COMPUTE WS05-SAL = WS05-SAL * 1.20
    ELSE
         COMPUTE WS05-SAL = WS05-SAL * 1.30
    END-IF
    END-IF
    MOVE WS05-SAL TO TO001-SAL
    WRITE TOOOI-PS-REC
    EVALUATE TRUE
    WHEN WS05-FST-T0001 = 00
         DISPLAY ' WRITE SUCCESS'
    WHEN OTHER
         DISPLAY ' TOOOI WRITR FAILED ' WSO5-FST-TOOOI
    END-EVALUATE
3211-CAL-PARA-EXIT.
    EXIT
```

3300-CLOSE-PARA

CLOSE TIO01-PS TO001-PS

•

3300-CLOSE-PARA-EXIT· EXIT

.

MOVEMENT OF DATA ACROSS FILES.

