ABC vn 1.4da: Guide to running the research modelling and data assimilation system

November 6, 2019

Ross Bannister, National Centre for Earth Observation, University of Reading, Reading, UK r.n.bannister@reading.ac.uk

1 Introduction

1.1 The ABC model

The ABC model and data assimilation system (vn 1.4da) is a combined 2D (longitude/height) convective-scale toy model (currently dry dynamics) and variational data assimilation system. The model equations are as follows:

$$\frac{\partial u}{\partial t} + B\mathbf{u} \cdot \nabla u + C \frac{\partial \tilde{\rho}'}{\partial x} - fv = 0, \tag{1a}$$

$$\frac{\partial v}{\partial t} + B\mathbf{u} \cdot \nabla v + fu = 0, \tag{1b}$$

$$\frac{\partial w}{\partial t} + B\mathbf{u} \cdot \nabla w + C \frac{\partial \tilde{\rho}'}{\partial z} - b' = 0, \tag{1c}$$

$$\frac{\partial \tilde{\rho}'}{\partial t} + B\nabla \cdot (\tilde{\rho}\mathbf{u}) = 0, \tag{1d}$$

$$\frac{\partial b'}{\partial t} + B\mathbf{u} \cdot \nabla b' + A^2 w = 0. \tag{1e}$$

The prognostic variables are as follows: u is the zonal wind, v is the meridional wind, w is the vertical wind, $\mathbf{u}=(u,v,w)$ is the wind vector, $\tilde{\rho}$ is a density-like variable (where $\tilde{\rho}'$ is the perturbation, $\tilde{\rho}=\tilde{\rho}_0+\tilde{\rho}'$, where in this model, $\tilde{\rho}_0=1$), and b' is a buoyancy-like variable (for meteorologists, b' is related to potential temperature, θ' , by $b'=g\theta'/\theta_{\rm R}$, where g is the acceleration due to gravity and $\theta_{\rm R}$ is the reference potential temperature of 273K). The dimension variables are as follows: x is longitudinal distance, z is vertical distance, and t is time. Constant parameters to be chosen by the user are as follows: A (units s^{-1}) is the static stability (equivalent to the pure gravity wave frequency), B (dimensionless) multiplies the advection and divergence terms, and C (units m^2s^{-2}) relates density perturbations to pressure perturbations, $p'=C\rho_0\tilde{\rho}'$, where ρ_0 is a reference density. The value of \sqrt{BC} is the pure acoustic wave speed). These parameters give the model its "ABC" name. The remaining constant is f, which is the Coriolis parameter.

There is also a tracer transport equation, which advects a tracer, q, with the wind vector \mathbf{u} , and not by the modified winds, $B\mathbf{u}$:

$$\frac{\partial q}{\partial t} + \mathbf{u} \cdot \nabla q = 0. \tag{2}$$

The model is run in a 2D slice (longitude/height) geometry. All variables are considered constant in the meridional direction. The model grid is an Arakawa-C grid in the horizontal and a Charney-Phillips grid in the vertical (Fig. 1). The horizontal resolution of the model is 1.5km, there are 360




Figure 1: The arrangement of variables on the toy model's grid: an Arakawa-C grid in the horizontal and a Charney-Phillips grid in the vertical. Note the abbreviations: FL=Full Level and HL=Half Level.

grid-points in the horizontal, and 60 vertical levels. The scientific rational for this model is given in (author?) [1].

The code is set-up as a number of master subroutines, each designed to do a particular job (such as running the model from specified initial conditions, to performing a data assimilation cycle; there are other routines, e.g. for calibrating the control variable transform, and generating synthetic observation). This guide comprises the following sections, in Sect. 2 we give the full list of master routines; in Sect. 3 we describe how the software is downloaded and installed (also stating which software libraries are required), and in Sect. 4 (which makes up the bulk of this documentation) we describe how each master routine is used.

1.2 Difference between this and the previous software version

Although the code for the ABC model is exactly the same as in the previous released version of this system (vn 1.0), the organisation of the code is different (e.g. the master program Main.f90 in vn 1.0 is only for running the model and doing linear analysis; these have separate master routines in vn 1.4da). Another difference is that, while vn 1.0 used NAG routine libraries for eigen analysis and fast Fourier transforms, vn 1.4da uses free software libraries as documented in Sect. 3.

2 List of master routines

The code is written in Fortran-90, and the master routines are run inside bash script wrappers. The recommeded operating system to run the code is Linux. Scientific documentation is provided on the model [1] and on the data assimilation (in preparation). Each of these master routines is associated with a top-level Fortran 90 subroutine (.f90), and for some a top-level python routine (.py) for plotting the results. There are also examples (labelled with the respective master routine name) available.

Master routine	Purpose
Master_prepareABC_InitState	Inputs a UM dump and generates a single 2D
(Sect. 4.1)	longitude/height slice set of fields that is suitable as a set
	of initial initialised initial conditions for the ABC model.
Master RunNLModel (Sect.	Makes a single run of the ABC model from a specified set
4.2)	of initial conditions.
Master_Linear_Analysis (Sect. 4.3)	Analyses the linear modes of the ABC model.
Master_Calibration (Sect. 4.4)	Runs any of the required stages of computation to
	compute data needed to specify the background error
	covariance matrix used in the data assimilation (specifies
	all aspects of the control variable transform according to
	implemented options). There are nominally five stages,
	and so this code is run five times in succession.
Master_TestSuite (Sect. 4.5)	Tests various aspects of the components of the data
	assimilation system (adjoint and inverse tests of the
	control variable transforms, and linearization tests of the
	ABC model and observation operators).
Master_ImpliedCov (Sect. 4.6)	Computes a selection of implied covariances (selected
	columns of $\mathbf{U}\mathbf{U}^{\mathrm{T}}$) between the model variables.
Master RawCov (Sect. 4.7)	Computes raw covariances from a population of states
	(can be compared to the implied covariances).
Master MakeBgObs (Sect. 4.8)	Generates a set of synthetic observations for assimilating
	(and outputs the associated 'truth' trajectory), and a
	synthetic background state.
Master Assimilate (Sect. 4.9)	Performs a variational data assimilation run.
_ ,	

3 Downloading and installing the software

3.1 Required libraries on host system

This sofware requires the following free software and libraries to be installed on the host system.

- Fortran compiler (f95). This is needed to compile the Fortran-90 code into executable files.
 - Net CDF library. This is needed to handle the input and output of fields.
 - FFTpack. This is needed to perform the fast Fourier transforms.
 - LApack.
 - tmglib.
 - refblas.
- Python v2. This is needed to manage the graphical diagnostics.
 - matplotlib.

3.2 Contents of ABC download

The following sets of files are included with this software in the respective directories.

- ABCvn1.4/src
 - Fortran-90 source code (multiple .f90 files).
 - Interface files for subroutines that have optional arguments (multiple .interface files).
 - makefile (to manage the compilation of the software, depending upon the master routine to be run).
- ABCvn1.4/graphics
 - python source code (multiple .py files).
- ABCvn1.4/examples
 - Sample data and namelists, depending upon the master routine to be run.
- ABCvn1.4/docs
 - Documentation of the system.
- ABCvn1.4/scripts
 - Example bash scripts (one to allow assimilation cycles to be run, and another to generate ensembles from an existing calibrated assimilation system).

3.3 Compiling the code

Once the src directory is downloaded, go into this directory and type

make all

to compile all programs. Alternatively to compile just one master program (e.g. Master_Assimilate) and type

make Master Assimilate.out

Further guidance is given below.

4 Using the master routines

Each master routine is described in this section. This includes how to compile the master routine and dependent code, and how to run it. The namelist variables are defined, which includes mention of the required input files, the output files, and how the outputs can be inspected.

4.1 Master PrepareABC InitState

Inputs a UM dump and generates a single 2D longitude/height slice set of fields that is suitable as a set of initial initialised initial conditions for the ABC model.

To compile

Go to directory containing source code (ABC_SRC), and issue:

 $make\ Master_PrepareABC_InitState.out$

To run

Prepare namelist file UserOptions.nl, go to directory containing this file, and issue:

 $ABC_SRC/Master_PrepareABC_InitState.out$

Namelist variables

The namelist variables are described in UserOptions.nl, and should be placed in the directory where the above run command is issued. The variables are described in the following table, where blue entries describe the input directories/files, red entries describe the output directories/files, and purple entries describe the input/output directories/files. An example namelist is given in the file ABCvn1.4/examples/Master_PrepareABC_InitialState/UserOptions.nl.

Variable	Type	Description	Default	Notes
$\overline{\operatorname{Init} _\operatorname{ABC} _\operatorname{opt}}$	$_{ m integer}$	How to create ABC initial	No	1=take a slice of
		${ m conditions}.$	$\operatorname{default}$	${ m UM~data,~2=zero}$
				apart from pressure
				perturbation
				bubble, 3=sum of
				above
$\operatorname{datadir} \operatorname{UM}$	string	Directory containing UM data.	No	$Init_ABC_opt=1,3$
			default	
$\operatorname{init} _\operatorname{um} _\operatorname{file}$	string	UM data filename (expected in	No	$Init_ABC_opt=1,3$
		above directory).	default	
latitude	integer	Index of single latitude to	144	$Init_ABC_opt=1,3$
D 1		extract from UM file.	TRUE	
$Regular_vert_grid$	\log ical	Used to set a regularly-spaced	.TRUE.	
4	1 1.1	vertical grid.	0.00	_1
A	double · ·	Model parameter (pure gravity	0.02	s^{-1}
D	precision	wave frequency).	0.01	
B	double	Model parameter (modulation	0.01	
	precision	of the divergent and advection		
C	double	terms). Model parameter	100000.0	$\mathrm{m^2s^{-2}}$
C	precision	(proportionality constant for the	100000.0	III S
	Precision	equation of state).		
f	double	Model parameter (Coriolis	0.0001	s^{-1}
J	precision	parameter).	0.0001	ы
	Precision	parameter).		

$press_source_x$	integer	To specify horizontal grid box of centre of pressure perturbation.	180	${\rm Init_ABC_opt}{=}2{,}3$
$press_source_z$	integer	To specify vertical grid box of centre of pressure perturbation.	30	${\rm Init_ABC_opt}{=}2{,}3$
${\rm press_amp}$	double precision	Amplitude of pressure perturbation	0.01	${\rm Init_ABC_opt}{=}2{,}3$
${ m x_scale}$	integer	No. of horizontal grids to describe size of pressure perturbation.	80	$Init_ABC_opt{=}2{,}3$
${ m z_scale}$	integer	No. of vertical grids to describe size of pressure perturbation.	3	$\operatorname{Init} _\operatorname{ABC} _\operatorname{opt} = 2,3$
${ m Adv_tracer}$	logical	$ \begin{array}{c} {\rm Used\ to\ switch\ on/off\ tracer} \\ {\rm advection.} \end{array} $.FALSE.	Sets up a 4×5 grid of point initial tracer positions.
gravity_wave_switch	logical	Used to switch on/off setting of $u = 0$ to simulate gravity waves.	.FALSE.	
${f BoundSpread}$	double precision	No. of horizontal grid points to spread boundary discontinuity for periodic boundary conditions.	50.0	
$rac{ m datadir ABC_out}{ m init_ABC_file}$	$\begin{array}{c} \text{string} \\ \text{string} \end{array}$	Main output directory. Output filename (in above directory).		

Input and output files

• Inputs

- Suitable Unified Model (UM) dump for the Southern UK region (datadirUM/init_um_file). This is a netcdf file of fields of 360 longitudes, 287/288 latitudes, and 70/71 vertical levels. The file contains the following: u (zonal wind), v (meridional wind), dz_dt (vertical wind, w), unspecified (density, $\rho r_{\rm E}^2$, where $r_{\rm E}$ is the Earth's radius), theta (potential temperature, θ), field7 (exner pressure, Π), and ht (2D orographic height field). The dimension names are x (longitude axis for u), x_1 (longitude axis for v, w, $\rho r_{\rm E}^2$, θ , Π , and ht), y (latitude axis for u, v, and $\rho r_{\rm E}^2$), $hybrid_ht_1$ (vertical axis for θ), $hthybrid_ht_2$ (vertical axis for v), $hybrid_ht_3$ (vertical axis for v), $hybrid_ht_3$ (vertical axis for v), $hybrid_ht_3$ (vertical axis for v). The complete filename is datadirUM/init um file.

• Outputs

– Initial dump for the ABC model. This is a netcdf file of fields of 360 longitudes and 60 vertical levels (datadirABC_out/init_ABC_file). The file contains the following: $u, v, w, \rho', b', \rho = 1 + \rho', b_{\text{eff}}, tracer, geo_imbal$ (geostrophic imbalance), $hydro_imbal$ (hydrostatic imbalance), $wmom_source$ (vertical momentum source), $horiz_div$ (horizontal divergence), $horiz_vort$ (horizontal vorticity), E_k (total kinetic energy), E_b (total buoyant energy), E_e (elastic energy), and E (total energy, $E = E_k + E_b + E_e$). The dimension names are $longs_u$ (horizontal axis for u), $longs_v$ (horizontal axis for other fields), $half_level$ (vertical axis for u, v, ρ' , ρ , tracer, geo_imbal , $horiz_div$, and $horiz_vort$), $full_level$ (vertical axis for w, b', b_{eff} , $hydro_imbal$, and $wmom_source$.

The meanings of the symbols in the output file are described in **(author?)** [1]. In particular, the model equations are given as Eqs. (15) of that reference and the grid positions are shown in Fig. 1 of that reference.

Graphics tools

 \bullet The python code PlotModelFields.py can be used to plot the initial ABC model state.

4.2 Master RunNLModel

Makes a single run of the ABC model from a specified set of initial conditions. The model equations are given as Eqs. (15) of (author?) [1] (reproduced near the beginning of this document), the boundary conditions are specified in Sect. 3.2, and the numerical integration scheme is described in Sect. 3.3.

To compile

Go to directory containing source code (ABC_SRC), and issue: make Master RunNLModel.out

To run

Prepare namelist file UserOptions.nl, go to directory containing this file, and issue: ABC SRC/Master RunNLModel.out

Namelist variables

The namelist variables are described in UserOptions.nl, and should be placed in the directory where the above run command is issued. The variables are described in the following table, where blue entries describe the input directories/files, red entries describe the output directories/files, and purple entries describe the input/output directories/files. An example namelist is given in the file ABCvn1.4/examples/Master RunNLModel/UserOptions.nl.

Variable	Type	Description	Default	Notes
$\frac{\mathrm{datadirABC_in}}{\mathrm{datadirABC_in}}$	string	Input directory.		
$\operatorname{init} _\operatorname{ABC} _\operatorname{file}$	string	Input filename (in above		
		$\operatorname{directory}$).		
A	double	Model parameter (pure gravity	0.02	s^{-1}
	precision	wave frequency).		
B	double	Model parameter (modulation	0.005	
	precision	of the divergent and advection		
		m terms).		
C	double	Model parameter	100000.0	$\mathrm{m}^{2}\mathrm{s}^{-2}$
	precision	(proportionality constant for the		
		equation of state).		
f	double	Model parameter (Coriolis	0.0001	s^{-1}
	$\operatorname{precision}$	${ m parameter}).$		
dt	double	Model time step size.	4.0	\mathbf{s}
	precision			
$\operatorname{runlength}$	double	Length of integration.	60.0	\mathbf{s}
	precision			
ndumps	integer	The number of times to dump	10	
		the model state throughout		
		$\operatorname{runlength}.$		
$\operatorname{Adv_tracer}$	\log ical	Used to switch on/off tracer	.FALSE.	
		advection.		
$Lengthscale_diagnos$	sticslogical	Used to switch on/off	.FALSE.	
		computation of characteristic		
		lengthscales of variables at the		
		final time (and other		
		${\rm diagnostics}).$		
${\rm datadir ABC_out}$	string	Main output directory.		
datadirABU_out	string	Main output directory.		

$\operatorname{output}_{-}\operatorname{ABC}_{-}\operatorname{file}$	string	Output file (model trajectory, in
		above directory).
${ m diagnostics_file}$	string	Diagnostics file (in above
		directory).

Note that if runlength=0.0 and ndumps=0, the model is not run, and the output of the code (datadirABC_out/output_ABC_file) is formed from the initial conditions, i.e. the fields that comprise the last time in the input ABC file (datadirABC_in/init_ABC_file).

Input and output files

- Inputs
 - Suitable ABC dump (datadirABC_in/init_ABC_file, e.g. output by Master_PrepareABC_InitState in Sect. 4.1). The latest time present in this file is used as the initial conditions for the model.
- Outputs
 - Time sequence of ABC model trajectory (datadirABC_out/output_ABC_file). This is a netcdf file of fields as the initial dump, but with multiple times.
 - Diagnostics file (datadirABC_out/diagnostics_file). This contains a model-time-step-by-model-time-step output of each component of energy (time, $E_{\rm k}$, $E_{\rm b}$, $E_{\rm e}$, $E_{\rm e}$, see Sect. 4.1), followed by diagnostics for the last timestep (if Lengthscale diagnostics is set).

Graphics tools

- The python code *PlotModelFields.py* can be used to plot the ABC model state for a specified output time step.
- The python code *PlotEnergy.py* can be used to plot the total energy of the run, as a function of time.

4.3 Master Linear Analysis

Analyses the linear modes of the ABC model. A description of the linear analysis is given in Sect. 4 of (author?) [1].

To compile

Go to directory containing source code (ABC_SRC), and issue:

make Master_Linear_Analysis.out

To run

Prepare namelist file UserOptions.nl, go to directory containing this file, and issue:

\$ABC SRC/Master Linear Analysis.out

Namelist variables

The namelist variables are described in UserOptions.nl, and should be placed in the directory where the above run command is issued. The variables are described in the following table, where blue entries describe the input directories/files, red entries describe the output directories/files, and purple entries describe the input/output directories/files. An example namelist is given in the file ABCvn1.4/examples/Master Linear Analysis/UserOptions.nl.

Variable	Type	Description	Default	Notes
A	double	Model parameter (pure gravity	0.02	s^{-1}
	$\operatorname{precision}$	wave frequency).		
B	double	Model parameter (modulation	0.005	
	precision	of the divergent and advection		
		m terms) .		
C	double	Model parameter	100000.0	$\mathrm{m^2s^{-2}}$
	precision	(proportionality constant for the		
		equation of state).		
f	double	Model parameter (Coriolis	0.0001	s^{-1}
	precision	parameter).		
H	double	Model domain height.	14862.01	m
	precision			
${ m datadir Linear Anal}$	string	Output directory.		

Input and output files

- Inputs
 - No inputs.
- Outputs
 - Gravity wave frequencies file (datadirLinearAnal/grav_frequency.dat). Given as a function of horizontal and vertical wavenumbers.
 - Acoustic wave frequencies file (datadirLinearAnal/acou_frequency.dat). Given as a function
 of horizontal and vertical wavenumbers.
 - Gravity wave speed (in the horizontal) file (datadirLinearAnal/hori_grav_speed.dat). Given as a function of horizontal and vertical wavenumbers.

- Acoustic wave speed (in the horizontal) file (datadirLinearAnal/hori_acou_speed.dat). Given as a function of horizontal and vertical wavenumbers.
- Gravity wave speed (in the vertical) file (datadirLinearAnal/vert_grav_speed.dat). Given as a function of horizontal and vertical wavenumbers.
- Acoustic wave speed (in the vertical) file (datadirLinearAnal/vert_acou_speed.dat). Given as a function of horizontal and vertical wavenumbers.

Graphics tools

ullet The python code PlotWaveSpeeds.py can be used to plot the wave frequencies and wave group speeds.

4.4 Master Calibration

Runs any of the required stages of computation to compute data needed to specify the background error covariance matrix used in the data assimilation (specifies all aspects of the control variable transform according to implemented options). There are nominally five stages, and so this code is run five times in succession.

To compile

Go to directory containing source code (\$ABC_SRC), and issue: make Master Calibration.out

To run

Prepare namelist file UserOptions.nl, go to directory containing this file, and issue: $ABC_SRC/Master_Calibration.out$

Namelist variables

The namelist variables are described in UserOptions.nl, and should be placed in the directory where the above run command is issued. The variables are described in the following tables, where blue entries describe the input directories/files, red entries describe the output directories/files, and purple entries describe the input/output directories/files. An example namelist is given in the file ABCvn1.4/examples/Master_Calibration/x/UserOptions.nl, where x represents one of the calibration run stages.

Variable	Type	Description	Defaul	Notes
CalibRunStag	e Integer	Runs the	1	1=convert UM to ABC forecast ensemble,
		calibration stage.		2=compute forecast perturbations,
		Run serially 1 to 5.		3=determine the regression parameters,
				4=do parameter transform, 5=calibrate
				spatial statistics.

The namelist variables are given here separately for each stage.

$\begin{array}{ll} \textbf{4.4.1} & \textbf{CalibRunStage} = \textbf{1:} \ \textbf{Generating sample forecasts from UM data dumps (in the table below NYI=not yet implemented)} \\ \end{array}$

Variable for stage 1	Type	Description	Default	Notes
Nens	integer	Number of ensembles used for calibration.	50	0=Do not use ensembles to calibrate.
NEnsMems	integer	Number of ensemble members in each ensemble.	24	
EnsDirs(:)	string array	Names of directories containing ensembles.		Containing UM files Member001.nc, Member002.nc,
\overline{NNMC}	integer	Number of NMC forecast pairs.	0	0=Do not use NMC method to calibrate. NYI.
$\operatorname{NMCDirs}(:)$	$rac{ ext{string}}{ ext{array}}$	Names of directories containing NMC pairs.		NYI.
Nlats	integer	The number of latitude slices that are to be extracted from each ensemble member file.	1	${ m NEnsMems} imes { m Nlats} ext{ effective} $ ensemble members per ensemble
$\operatorname{latindex}(:)$	integer array	Specifies the latitude indices of the Nlats latitude slices.		
$\operatorname{BoundSpread}$	double preci- sion	No. of horizontal grid points to spread boundary discontinuity for periodic boundary conditions.	50.0	
A	double preci- sion	Model parameter (pure gravity wave frequency).	0.02	$ m s^{-1}$
B	double preci- sion	Model parameter (modulation of the divergent and advection terms).	0.005	
C	double preci- sion	Model parameter (proportionality constant for the equation of state).	100000.0	$\mathrm{m^2s^{-2}}$
f	double preci- sion	Model parameter (Coriolis parameter).	0.0001	s^{-1}
dt	double preci- sion	Model time step size.	4.0	S
$\operatorname{runlength}$	double preci- sion	Length of integration.	60.0	S
${\rm Adv_tracer}$	logical	Used to switch on/off tracer advection.	.FALSE.	Current implementation requires this to be .TRUE.
${\rm datadir ABCfcs}$	string	Output directory of ABC forecast ensemble members.		Output files FC Ens 001 Item 001.nc
${ m datadir CVT}$	string	Output directory of blank CVT file.		
$\mathrm{CVT}_{-}\mathrm{file}$	string	Name of blank CVT file to be output (in above directory).		

Variable for stage 1	Type	${\bf Description}$	Default	Notes
CVT%	integer	Order of the transforms.	1	1=as original MetO,
$\mathrm{CVT_order}$				2 = reversed horiz/vert,
				3=normal mode based
CVITO	. ,		1	(NYI).
CVT%	integer	Geostrophic balance option for the transform.	1	1=analytical geo balance,
CVT_param_op	ու_ցս	the transform.		$2 = ext{statistical balance NYI}, \ 3 = ext{no geo balance}.$
$\mathrm{CVT}\%$	integer	Hydrostatic balance option for	1	1=analytical hydro balance,
CVT_param_op	ot_hb	the transform.		2=statistical balance (NYI), 3=no hydro balance.
$\mathrm{CVT}\%$	integer	Anelastic balance option for the	1	1=analytical anel balance,
CVT_param_op	${ m pt_ab}$	${\it trans form.}$		2 =no anel balance.
$\mathrm{CVT}\%$	integer	Vertical regression option for	1	1=use vertical regression of
CVT_param_op	${ m pt_reg}$	the geostrophic balance field.		the gb r, $2=$ no vertical
GT ITTO				regression.
CVT%	integer	Symmetry option for vertical	1	1=non-symmetric transform,
$\begin{array}{c} \mathrm{CVT_vert_opt_} \\ \mathrm{CVT\%} \end{array}$	_	covariances.	2	2=symmetric transform. $1=$ stddev constant for each
CVI 70 CVT stddev oj	integer	Standard deviation option.	2	control variable, 2=level
Ovi_studev_of	pι			dependent only,
				3=Longitude and level
				dependent.
				1

Input and output files

- Inputs
 - Data from one or more suitable UM data files (EnsDir(i)/Member001.nc, etc.). For the specification of the UM data file, see Sect. 4.1.
- Outputs
 - Effective ensemble members (datadirABCfcs/FC_Ens_001_Item_001.nc, etc.; the first 001 is the ensemble number, and the second 001 is the item number e.g. for NEnsMems=2, and Nlats=3, for the first ensemble member, item=1,2,3, and for the second ensemble member, item=3,4,5). There are a total of Nens × NEnsMems × Nlats output forecast states in total.
 - A control variable transform file (datadirCVT/CVT_file) is a netcdf file, which is blank apart from containing the values A, B, C, f, CVT_order, CVT_param_opt_gb, CVT_param_opt_hb, CVT_param_opt_ab, CVT_param_opt_reg, CVT_vert_opt_sym, and CVT_stddev_opt.

Graphics tools

ullet The python code PlotEnsemblesABC.py can be used to plot the full ensemble members.

4.4.2 CalibRunStage = 2: Compute perturbations from the forecast data of stage 1

Variable for stage 2	Type	${f Description}$	Default	Notes
Nens	integer	Number of ensembles used for calibration (as stage 1).	50	0=Do not use ensembles to calibrate.
NEnsMems	integer	Number of ensemble members in each ensemble (as stage 1).	24	
${\rm datadir ABCfcs}$	$\begin{array}{c} \text{string} \\ \text{array} \end{array}$	Directory containing ensemble or NMC forecasts (as output in stage 1).		Containing FC_Ens_001_Item
NNMC	integer	Number of NMC forecast pairs (as stage 1).	0	0=Do not use NMC method to calibrate. Not yet implemented.
m Nlats	integer	The number of latitude slices (as stage 1).	1	NEnsMems × Nlats effective ensemble members for each ensemble
${ m datadir ABC perts}$	string	The name of the directory to output the ensemble means and perturbations.		The ensemble means output are MeanABC001.nc,, and the perturbations output are PertABC_Ens001_1
$rac{ m datadirCVT}{ m CVT_file}$	string string	Directory containing CVT file. Name of CVT file. Used to extract options (output to this file was done in stage 1).		

Input and output files

- Inputs
 - Forecast data from one or more forecasts from the ABC model (datadirABCfcs/FC_Ens_001_Item_001.nc, etc.). For the specification of the ABC data file, see Sect. 4.1.
 - Model specification data (A, B, C, f) output to the CVT file during stage 1 (datadirCVT/CVT_file).
- Outputs
 - Ensemble means for each ensemble (datadirABCperts/MeanABC001.nc, etc.).
 - Ensemble perturbations for each ensemble, and each member (datadirABCperts/PertABC_Ens001_Item001 etc.; the first 001 is the ensemble number, and the second 001 is the item number). The output perturbation file labelling corresponds to the input forecast file labelling.

Graphics tools

• The python code *PlotEnsemblesABC.py* can be used to plot the ensemble perturbations.

4.4.3CalibRunStage = 3: Compute vertical regression matrix for geostrophic balanced mass fields

Variable for	Type	Description	Default	Notes
${f stage} {f 3}$				
Nens	integer	Number of ensembles used for calibration (as stage 1).	50	0=Do not use ensembles to calibrate.
NEnsMems	integer	Number of ensemble members in each ensemble (as stage 1).	24	
${ m datadir}{ m ABCperts}$	$rac{ ext{string}}{ ext{array}}$	Directory containing ensemble perturbations (as output in stage 2).		$\begin{array}{c} {\rm Containing} \\ {\rm PertABC_Ens_001_I} \\ {\dots} \end{array}$
NNMC	integer	Number of NMC forecast pairs (as stage 1).	0	0=Do not use NMC method to calibrate. Not yet implemented.
Nlats	integer	The number of latitude slices (as stage 1).	1	NEnsMems × Nlats effective ensemble members for each ensemble
${\rm datadir}{\rm CVT}$	string	Directory containing CVT file.		
$\mathrm{CVT_file}$	string	Name of CVT file. Used to extract options, and to output vertical covariance matrix.		
${ m dat}$ ad ir ${ m Regression}$	string	Directory to containing sample files from this run.		r for the first ensemble/ensemble member, and its balanced version.

Input and output files

- Inputs
 - ABC model perturbations as output from stage 2 (datadirABCperts/PertABC Ens 001 Item 001.nc,
 - Model specification data (A, B, C, f), and covariance options output to the CVT file during stage 1 (datadirCVT/CVT file).
- Outputs (if CVT options allow)
 - Regression matrices to the covariance file (datadirCVT/CVT file.nc).
 - Sample fields for the first ensemble, and first ensemble member, namely r and the geostrophically balanced version of r (datadirRegression/r 001.nc, datadirRegression/psi 001.nc, and datadirRegression/rbal 001.nc). The output perturbation file labelling corresponds to the input forecast file labelling.

Graphics tools

• The python code *PlotRegressionMatrices.py* can be used to plot the matrices output by this run stage.

4.4.4 CalibRunStage = 4: Perform parameter transform (convert model perturbations to parameters)

Variable for	Type	Description	Default	Notes
${f stage} {f 4}$				
Nens	integer	Number of ensembles used for calibration (as stage 1).	50	0=Do not use ensembles to calibrate.
${ m NEnsMems}$	integer	Number of ensemble members in each ensemble (as stage 1).	24	
${\bf datadir ABC perts}$	$rac{ ext{string}}{ ext{array}}$	Directory containing ensemble perturbations (as output in stage 2).		Containing PertABC_Ens_001_Item
NNMC	integer	Number of NMC forecast pairs (as stage 1).	0	0=Do not use NMC method to calibrate. Not yet implemented.
Nlats	integer	The number of latitude slices (as stage 1).	1	NEnsMems × Nlats effective ensemble members for each ensemble
$rac{ m datadirCVT}{ m CVT_file}$	string string	Directory containing CVT file. Name of CVT file. Used to extract options, and to output vertical covariance matrix.		
datadirConParams	string	Directory to contain perturbations of control parameters (converted from perturbations of model variables).		PertParam_001_Item001 etc.

Input and output files

- Inputs
 - ABC model perturbations as output from stage 2 (datadirABCperts/PertABC_Ens_001_Item_001.nc, etc.).
 - ABC mean states as output from stage 2 (datadirABCperts/MeanABC001.nc, etc.).
 - Model specification data (A, B, C, f), covariance options output to the CVT file during stage 1, and regression data computed from stage 3 (datadirCVT/CVT file).
- Outputs
 - Ensemble of pertubations of control parameters (datadirConParams/PertParam_001_Item001.nc, etc).
 - Sample fields for the first ensemble, and first ensemble member, namely balanced b (datadirCon-Params/b_b.nc), balanced r pre-regression step (datadirConParams/r_b_preregress.nc), and balanced r post-regression step (datadirConParams/r b postregress.nc).

Graphics tools

• The python code *PlotParameterEnsembles.py* can be used to plot the parameter perturbations.

• The python code $Plot_rp_pre+post_regress.py$ can be used to plot the example pre- and pregression balanced r.	post-

4.4.5 CalibRunStage = 5: Perform calibration of each parameter (compute parameter standard deviations, and vertical and horizontal control variable transforms)

Variable for stage 5	Type	${f Description}$	Default	Notes
Nens	integer	Number of ensembles used for calibration (as stage 1).	50	0=Do not use ensembles to calibrate.
${ m NEnsMems}$	integer	Number of ensemble members in each ensemble (as stage 1).	24	
${\bf data} {\bf dir} {\bf ABC} {\bf perts}$	string array	Directory containing ensemble perturbations (as output in stage 2).		Read PertABC_Ens_001_ dimension information.
${ m datadir Con Params}$	string	Directory containing perturbations of control parameters.		Containing Pert- Param_001_Item001 etc.
NNMC	integer	Number of NMC forecast pairs (as stage 1).	0	0=Do not use NMC method to calibrate. Not yet implemented.
Nlats	integer	The number of latitude slices (as stage 1).	1	NEnsMems × Nlats effective ensemble members for each ensemble
VertSmoothPoints	integer	Number of points in vertical (in each direction) to average for standard dev.	0	0=No vertical smoothing of standard dev.
${ m ForizSmoothPoints}$	integer	Number of points in horizontal (in each direction) to average for standard dev.	0	0=No horizontal smoothing of standard dev.
$rac{ m datadirCVT}{ m CVT_file}$	$\begin{array}{c} \text{string} \\ \text{string} \end{array}$	Directory containing CVT file. Name of CVT file. Used to extract options.		

Input and output files

- Inputs
 - Parameter perturbations as output from stage 4 (datadirConParams/PertParam_001_Item_001.nc, etc.).
 - Sample ABC model perturbation for reading in dimension data (datadirABCperts/PertABC Ens 001 Item
 - Covariance options output to the CVT file during stage 1 (datadirCVT/CVT file).
- Outputs
 - A complete CVT definition file for the specification made in stage 1 (datadirCVT/CVT file).

Graphics tools

• The python code *PlotCVT.py* can be used to inspect the contents of the output CVT file.

4.5 Master TestSuite

Tests various aspects of the components of the data assimilation system (adjoint and inverse tests of the control variable transforms, and linearization tests of the ABC model and observation operators). The linear ABC model is not yet implemented.

To compile

Go to directory containing source code (ABC_SRC), and issue: make Master TestSuite.out

To run

Prepare namelist file UserOptions.nl, go to directory containing this file, and issue: $ABC_SRC/Master_TestSuite.out$

Namelist variables

The namelist variables are described in UserOptions.nl, and should be placed in the directory where the above run command is issued. The variables are described in the following table, where blue entries describe the input directories/files, red entries describe the output directories/files, and purple entries describe the input/output directories/files. An example namelist is given in the file ABCvn1.4/examples/Master_TestSuite/UserOptions.nl.

Variable	Type	Description	Default	Notes
${ m datadir ABCfcs}$	string	Directory containing an ABC		
- 0 0		model state.		
$\mathrm{LS_file}$	string	Name of a test ABC model		
		state.		
datadir ABC perts	string	Directory containing an ABC model perturbation.		RunInvTests = .TRUE.
Pert _file	string	$\begin{array}{c} {\rm Name~of~a~test~ABC} \\ {\rm perturbation~file.} \end{array}$		RunInvTests = .TRUE.
${ m datadir CVT}$	string	Directory containing a CVT file.		RunAdjTests_CVT=.' or RunIn- vTests=.TRUE.
$\mathrm{CVT}_{-}\mathrm{file}$	string	Name of a CVT file (as found from Master_Calibration).		RunAdjTests_CVT=.' or RunIn- vTests=.TRUE.
${ m datadir_Obs}$	string	Directory containing observations.		$RunAdjTests_obs=.TI$
${ m Obs_file}$	string	Observation file (in above directory).		$RunAdjTests_obs=.TI$
${ m datadirTestDA}$	string	Directory to output textual and field results of test suite.		
${ m diagnostics_file}$	string	File to output textual diagnostics (in above directory).		
$RunAdjTests_CVT$	logical	Set to perform adjoint tests on operators used in CVT	.FALSE.	
$RunAdjTests_obs$	logical	Set to perform adjoint tests on observation operators	.FALSE.	
RunInvTests	logical	Set to perform inverse tests	.FALSE.	

Input and output files

• Inputs

- A complete CVT definition file after running the complete calibration suite (stages 1 to 5) (datadirCVT/CVT file), needed when RunAdjTests CVT=.TRUE. or RunInvTests=.TRUE.
- An example ABC forecast file to act as a linearisation state for the parameter transform and observation operator (datadirABCfcs/LS file).
- An example ABC perturbations perturbation file (datadirABCperts/Pert_file), needed when RunInvTests=.TRUE.
- An observations file for doing adjoint test of observation operator (datadir_Obs/Obs_file), needed when RunAdjTests obs=.TRUE.

• Outputs

- The text file of diagnostic results datadirTestDA/diagnostics_file shows output of the adjoint and/or inverse tests.
- Fields associated with the inverse tests (output when RunInvTests=.TRUE.). The files output are datadirABCperts/uv2psi.nc, datadirABCperts/uv2chi.nc, datadirABCperts/psichi2u.nc, datadirABCperts/psichi2v.nc, datadirABCperts/fft_test.nc, and datadirABCperts/UpInvTest.nc. See below for descriptions of these files.
- The observations file datadirTestDA/Obs_processed.dat (when RunAdjTests_obs=.TRUE.). This is a version of the observations file which has been processed (to contain, e.g. model observations, innovations, etc see the observation file format in Sect. 4.8.

Graphics tools

There are currently no special utitities to analyse the output from this program. The output file datadirTestDA/diagnostics file contains some textual diagnostics.

Notes on the tests

Many of the mathematical transforms used in the DA system require an adjoint version, which appear in the expressions computing the gradient of the cost function, needed for the minimization alforithm. Even though it may not be explicitly coded as such, a linear transform is equivalent to the action of a matrix on an input vector to give an output vector. An adjoint version of a transform is essentially the equivalent to the transpose of this matrix (or in the case of complex values the combined adjoint and complex conjugate of this). To distinguish the transform from its adjoint, the transform itself is often called the forward transform. As with the forward transform, the adjoint is not necessarily written in an explicit matrix operation, but instead comprises a set of linear code. Mistakes often creep into the translation of code from the forward version to the adjoint version. An adjoint test is a reliable way of testing that this procedure has been done correctly.

In its basic form the adjoint test takes an arbitrary vector \mathbf{v} (e.g. a vector of random numbers), and checks that the following holds:

$$(\mathbf{A}\mathbf{v})^{\dagger} \mathbf{A}\mathbf{v} \stackrel{?}{=} (\mathbf{A}^{\dagger} \mathbf{A}\mathbf{v})^{\dagger} \mathbf{v},$$

or $\langle \mathbf{A}\mathbf{v}, \mathbf{A}\mathbf{v} \rangle_{\mathbf{I}} \stackrel{?}{=} \langle \mathbf{A}^{\dagger} \mathbf{A}\mathbf{v}, \mathbf{v} \rangle_{\mathbf{I}},$

where **A** is the forward operator and \mathbf{A}^{\dagger} is the adjoint operator. The above must be satisfied to machine precision. The above basic form assumes that the inner product metric is the identity matrix, i.e. that an inner product between two matrices \mathbf{u} and \mathbf{v} is $\langle \mathbf{u}, \mathbf{v} \rangle_{\mathbf{I}} = \mathbf{u}^{\dagger} \mathbf{I} \mathbf{v} = \mathbf{u}^{\dagger} \mathbf{v}$.

The following CVT operators are coded for adjoint tests in the current test suite:

• Boundaries (code to swap halos to satisfy boundary conditions in model fields)

- Boundaries CV (as above, but for control fields)
- LinearBal_r (computation of the linearly balanced r field from the streamfunction field)
- Anbalw (computation of the anelastically balanced w field from the u field)
- Helmholtz (computation of u and v from the streamfunction and velocity potential)
- INT HF (function to do vertical interpolation from half to full levels)
- INT FH (as above, but from full to half levels)
- HydroBal b (computation of the hydrostatically balanced b field from r)
- U p (the parameter transform)
- U v (the vertical transform)
- U stddev (the standard deviation transform)
- fft real2spec (FFT from real to spectral spaces)
- fft spec2real (FFT from spectral to real spaces)
- U_h (the horizontal transform)
- U_trans (the complete control variable transform, e.g. if using the traditional formulation this includes the horizontal, vertical, parameter, and standard deviation transforms).

The following observation operators are coded for adjoint tests in the current test suite:

- Interpolate1D
- Interpolate3D
- ModelObservations_linear

In order to do an adjoint test of the ModelObservations_linear operator, an observations file is required. The time dimension test is not currently implemented (only 3DFGAT is implemented). An observations file may be produced by running stages 1 and 2 of 4.8.

The inverse tests $\mathbf{A}^{-1}\mathbf{A}$ is performed on the following operators:

- InverseSymMat (where **A** is the auto-covariance balanced r, as found in the CVT file, and the outputs of $\mathbf{A}^{-1}\mathbf{A}$ [and also $\mathbf{A}\mathbf{A}^{-1}$] are sent to the diagnostics file, $\frac{\mathbf{datadirTestDA}}{\mathbf{diagnostics}}$ file).
- The u and v fields from datadirTestDA/Pert_file are transformed to ψ and χ (routine Helmholtz_inv) and output as datadirTestDA/uv2psi.nc and datadirTestDA/uv2chi.nc. These fields are then transformed back to u and v (routine Helmholtz) and output as datadirTestDA/psichi2u.nc and datadirTestDA/psichi2v.nc.
- The r field from datadirTestDA/Pert_file is transformed to spectral space (routine fft_real2spec), and then back to real space (routine fft_spec2real). The result is output to datadirTest-DA/fft_test.nc.
- The u, v, w, r, b, and tracer fields from datadirTestDA/Pert_file.nc are transformed to control variables (routine U_p_inv) and then trasformed back to the original fields (routine U_p). The result is output to datadirTestDA/UpInvTest.nc.

4.6 Master ImpliedCov

Computes a selection of implied covariances (selected columns of $\mathbf{U}\mathbf{U}^{\mathrm{T}}$) between the model variables.

To compile

Go to directory containing source code (ABC_SRC), and issue: make Master Implied Cov. out

To run

Namelist variables

The namelist variables are described in UserOptions.nl, and should be placed in the directory where the above run command is issued. The variables are described in the following table, where blue entries describe the input directories/files, red entries describe the output directories/files, and purple entries describe the input/output directories/files. An example namelist is given in the file ABCvn1.4/examples/Master ImpliedCov/UserOptions.nl.

Variable	Type	Description	Default	Notes
datadirABCfcs	string	Directory containing an ABC		
		model state.		
$\mathrm{LS}_\mathrm{file}$	string	Name of a test ABC model		
		${f state}.$		
$\operatorname{datadir}\operatorname{CVT}$	string	Directory containing a CVT file.		
$\mathrm{CVT}_\mathrm{file}$	string	Name of a CVT file (as found		
		$from \ Master_Calibration).$		
${ m datadir Implied Cov}$	string	Directory to output fields that		
		represent implied covariances.		
$\operatorname{ImplCov}_{-}\operatorname{npoints}$	$_{ m Integer}$	Number of source points to	0	
		compute implied covariances		
		with respect to.		
$\operatorname{longindex}(:)$	$_{ m integer}$	Specifies the longitude indices of		
	array	${ m the~ImplCov_npoints~source}$		
		points		
$\operatorname{levindex}(:)$	integer	Specifies the level indices of the		
	array	ImplCov_npoints source points		

Input and output files

• Inputs

- A complete CVT definition file after running the complete calibration suite (stages 1 to 5) (datadirCVT/CVT file).
- An example ABC forecast file to act as a linearisation state for the parameter transform (datadirABCfcs/LS file).

• Outputs

- Fields giving the implied covariances, $\mathbf{U}\mathbf{U}^{\mathrm{T}}$, associated with the source points. The files output are datadirImpliedCov/Point 001 deltau.nc, datadirImpliedCov/Point 001 deltav.nc,

datadirImpliedCov/Point_001_deltaw.nc, datadirImpliedCov/Point_001_deltar.nc, datadirImpliedCov/Point_001_deltab.nc, and datadirImpliedCov/Point_001_deltatracer.nc. where 001 is the point number. See below for descriptions of these files.

Graphics tools

• The python code *PlotCovs.py* can be used to inspect the contents of the output files mentioned above. The same code is used to plot raw covariances (i.e. covariances found from the data used to calibrate the control variable transform, computed from Master RawCov).

Notes on the implied covariances

The operator $\mathbf{U}\mathbf{U}^T$ is the background error covariance matrix (\mathbf{B}_{imp}) that is implied by the control variable transform. When $\mathbf{U}\mathbf{U}^T$ operates on a vector \mathbf{v} of zeros, apart from one particular unit element, the output $\mathbf{u} = \mathbf{U}\mathbf{U}^T\mathbf{v}$ is the column of \mathbf{B}_{imp} associated with where the unit element is located. For instance, if the unit element is placed in the field r near the centre of the domain, then \mathbf{u} is the set of fields that comprise the column of \mathbf{B}_{imp} associated with that single r point. If this spatial point's position is prescibed with longindex(1), levindex(1), then the output file is $\frac{\mathbf{datadirImpliedCov}}{\mathbf{Point}} = \frac{001}{\mathbf{deltar.nc}}$. The code systematically puts the unit point in each of the six fields in turn to give the six output files specified above.

4.7 Master RawCov

Computes a selection of raw covariances between the model variables.

To compile

Go to directory containing source code (ABC_SRC), and issue: make Master RawCov.out

To run

Prepare namelist file UserOptions.nl, go to directory containing this file, and issue:

\$ABC SRC/Master RawCov.out

Note that the input data needed to run this program is generated by stage

Namelist variables

The namelist variables are described in UserOptions.nl, and should be placed in the directory where the above run command is issued. The variables are described in the following table, where blue entries describe the input directories/files, red entries describe the output directories/files, and purple entries describe the input/output directories/files. An example namelist is given in the file ABCvn1.4/examples/Master RawCov/UserOptions.nl.

Variable	Type	Description	Default	Notes
${\rm datadir ABC perts}$	string	Directory containing ABC model state perturbations.		As output from run stage 2 of the calibration, 4.4.
${ m datadir}{ m Raw}{ m Cov}$	string	Directory to output fields that represent raw covariances.		
Nens	integer	Number of ensembles used.	50	0=Do not use ensembles to calibrate. Use as in run stage 2 of the calibration, 4.4.
${ m NensMems}$	integer	Number of ensemble members in each ensemble.	24	Use as in run stage 2 of the calibration, 4.4.
NNMC	integer	Number of NMC forecast pairs.	0	0=Do not use NMC method to calibrate. Not yet implemented.
Nlats	integer	The number of latitude slices.	1	Use as in run stage 2 of the calibration, 4.4.
${\rm ImplCov_npoints}$	integer	Number of source points to compute implied covariances with respect to.	0	
$\operatorname{longindex}(:)$	integer array	Specifies the longitude indices of the ImplCov_npoints source points		
$\operatorname{levindex}(:)$	integer array	Specifies the level indices of the ImplCov_npoints source points		

Input and output files

- Inputs
 - $ABC \ model \ perturbations \ (as \ output \ from \ stage \ 2 data dir ABC perts/Pert ABC_Ens_001_Item_001.nc, \\ etc.).$
- Outputs
 - Fields giving the raw covariances, associated with the source points. The files output are datadirRawCov/Point_001_deltau.nc, datadirRawCov/Point_001_deltav.nc, datadirRawCov/Point_001_deltav.nc, datadirRawCov/Point_001_deltar.nc, datadirRawCov/Point_001_deltab.nc, and datadirRawCov/Point_001_deltatracer.nc. where 001 is the point number.

Graphics tools

• The python code PlotCovs.py can be used to inspect the contents of the output files mentioned above. The same code is used to plot implied covariances (i.e. covariances found from $\mathbf{U}\mathbf{U}^{\mathrm{T}}$, computed from Master ImpliedCov).

4.8 Master MakeBgObs

Generates a set of synthetic observations for assimilating, and a synthetic background state.

To compile

Go to directory containing source code (ABC_SRC), and issue: make Master_MakeBgObs.out

To run

Prepare namelist file UserOptions.nl, go to directory containing this file, and issue: $ABC\ SRC/Master\ MakeBgObs.out$

Namelist variables

The namelist variables are described in UserOptions.nl, and should be placed in the directory where the above run command is issued. The variables are described in the following table, where blue entries describe the input directories/files, red entries describe the output directories/files, and purple entries describe the input/output directories/files. An example namelist is given in the file $ABCvn1.4/examples/Master_MakeBgObs/x/UserOptions.nl$, where x represents one of the run stages for this routine.

C 'C 1 1		
Specifies what data	1	1=generate a file that is used to specify obs
this routine should		times, positions, and types, etc., 2=generate
produce $(1-3)$.		obs consistent with some truth, 3=Generate
		a background state consistent with some
		${ m truth}.$
	this routine should	this routine should

The namelist variables are given here separately for each stage.

4.8.1 Generate_mode=1: Generate a file that is used to specify observation times, positions, and types, etc.

Variable	Type	Description	Default	Notes
datadir_ObsSpec	string	Directory to output observation		
ObsSpec file	string	specification file. Filename of observation		Format see below.
Obboped_me	501.1118	specification file (output to the		Torinae Bee Berow.
		above directory).		
${\rm ObsSpec\%year0}$	integer	Specification of $t = 0$ (year).	2000	
Obs Spec%month0	integer	(month, 1-12).	1	
ObsSpec%day0	integer	(day, 1-31).	1	
ObsSpec%hour0	\inf_{\cdot}	(hour, 0-23).	0	
ObsSpec%min0	integer	(minute, 0.59).	0	
ObsSpec%sec0	integer	(second, 0-59). Number of observation batches.	0	Each batch
${ m ObsSpec\%NumBatch}$	es mteger	Number of observation patches.	0	represents a
				particular obs type
				and time. The obs
				batch is distributed over space as
				specified below.
${ m ObsSpec\%batch}(:)$	integer	Batch number.	0	Not currently used,
0 000 F 00 / 000 000 (1)	array			but could be used
				to group batches
				together (with a
				common batch
				number) for
				possible later developments with
				correlated obs.
ObsSpec%seconds(1)	integer	Abolsute time of this	0	seconds since $t = 0$
• ()	array	observation batch.		
$Obs Spec\%ob_of_wh$	at (in)teger	What is to be observed.	0	$1{=}u,2{=}v,3{=}w,$
	array			$4 = r, \ 5 = b,$
				6=tracer,
				7=horizontal wind
				speed, 8=total wind speed.
ObsSpec%NumObs	loninatalger	Number of observations in the	0	wind speed.
0 8 6 8 P 6 0 7 0 1 1 4 1 1 1 0 8 5 _	array	longitude direction for this	Ü	
	v	batch		
$Obs Spec\%NumObs_$	heii ghte ger	Number of observations in the	0	
0. 0. ~.	array	height direction for this batch		
$ObsSpec\%long_min($		West-most extent of observation	0.0	
	precision	grid for this batch.		
ObsSpec%long max(array	East-most extent of observation	0.0	
Oppo Pec votong _ max/	precision	grid for this batch.	0.0	
	array	0		
$ObsSpec\%height_mis$		Lowest position of observation	0.0	
	precision	grid for this batch.		
	array			

$-{ m ObsSpec\%height_max}$	ıx(:double	Highest position of observation	0.0
	$\operatorname{precision}$	grid for this batch.	
	array		
ObsSpec%stddev(:)	double	Error standard deviation of this	0.0
	precision	batch.	
	array		

Input and output files

- Outputs
 - The observations to be made are specified in the file datadir_ObsSpec_ObsSpec_file, which has the format mentioned below. It is read by the code running with Generate_mode=2 to generate the actual observations. This file can be created separately, but the Generate_mode=1 mode has been provided as a convenient means of created this file. The file can also be edited if required before being read by the Generate_mode=2 mode (e.g. to modify an observation's error standard deviations, etc., etc.

Graphics tools

There are currently no special utitities to analyse the output from this program.

Notes on the output file

The format of the output file datadir ObsSpec / ObsSpec file is illustrated with the following example.

Observation specification file for ABC model

Ref year : 2010 Ref month : 1 Ref day : 1 Ref hour : 0 Ref minute : 0	
Ref day : 1 Ref hour : 0 Ref minute : 0	
Ref hour : 0 Ref minute : 0	
Ref minute : 0	
D f	
$\operatorname{Ref} \operatorname{second} : 0$	
Observation No : 1	
Batch ID : 1	
Time of obs (s) : 300	
Longitude (deg) : 10000.000	
H eight (m) : 1000.000	
Observation of : 5	
Err stddev : 0.001	
Observation No : 2	
Batch ID : 1	
Time of obs (s) : 300	
Longitude (deg) : 10000.000	
H eight (m) : 4666.667	
Observation of : 5	
Err stddev : 0.001	

. . .

The "observation of" refers to the quantity observed (see the key for $ObsSpec\%ob_of_what(:)$ in the table above).

4.8.2 Generate mode=2: Generate observations consistent with some truth

Variable	Type	Description	Default	Notes
$\overline{\mathrm{datadir}_{-}\mathrm{ObsSpec}}$	string	Directory containing		
		observation specification file.		
$ObsSpec_file$	string	Observation specification file (in above directory).		Format see above.
${ m datadir ABC_in}$	string	Directory containing the initial truth state.		End time present is used as init conds.
${\rm init_ABC_file}$	string	ABC model dump containing the truth (in above directory).		
dt	double	Time step of the model		
	precision	•		
dt_da	double	Time step of the data	60.0	Constraint:
	precision	assimilation system.		$dt_{-}da = ndt,$ $n = 1, 2, \dots$
t0	integer	Time of start dump.	0	seconds
$\operatorname{Runlength}$	double	Length of DA cycle	60.0	Carried through to
	precision			the DA via the Obs file (below)
${ m datadir_Obs}$	string	Directory containing observational data that can be later assimilated, and truth run.		-
${ m Obs_file}$	string	Observation file (in above directory).		Format see below.
${\rm output_ABC_file}$	string	Output truth trajectory file (in above directory).		
A	double precision	Model parameter (pure gravity wave frequency).	0.02	s^{-1}
B	double	Model parameter (modulation	0.005	
	precision	of the divergent and advection terms).		
C	double	Model parameter	100000.0	$\mathrm{m}^{2}\mathrm{s}^{-2}$
	precision	(proportionality constant for the equation of state).		
f	double	Model parameter (Coriolis	0.0001	s^{-1}
	precision	parameter).		
${\rm random_seed}$	integer	To seed the random number generator	0	

Input and output files

• Inputs

- Suitable truth input file (datadirABC_in/init_ABC_file). The latest time present in this file is used as the initial conditions for the model truth run.
- The observations to be made are specified in the file datadir_ObsSpec/ObsSpec_file, which
 has the format mentioned above.

• Outputs

- The synthetic observations themselves are output to the file datadir_Obs/Obs_file, which has the format mentioned below.
- The truth trajectory, output at every data assimilation time step, datadir_Obs/output_ABC_file.

Graphics tools

There are currently no special utitities to analyse the output from this program.

Notes on the output file

Observation file for ABC model

The format of the output file datadir_Obs/Obs_file is illustrated with the following example (comprising two observations).

```
Format version : 1
maxtime (s)
                         2400
Model ts (s)
                        0.400E+01
No model ts
                          600
                        0.600E + 02
DA ts (s)
                  :
No DA ts
                            40
Observation No :
                               1
Batch ID
                          1
Time of obs (s):
                          300
Longitude (deg) :
                        10000.000
Height (m)
                         1000.000
xbox lower
                               6
xbox lower ws
                               0
zbox_lower
                               4
zbox lower ws
                               0
tstep_lower
                               5
Observation of
                       1
                  : u
                  : T
y true known
y_true
                       -0.124E+00
                        0.152E+01
                  :
\operatorname{st}\operatorname{d}\operatorname{d}\operatorname{ev}
                        0.500E+00
                        0.000E+00
y_ref
d
                        0.000E+00
deltay_m
                        0.000E+00
                        0.000E+00
ymhx
deltay_m_hat
                        0.000E+00
                              2
Observation No
Batch ID
                          1
Time of obs (s):
                         1500
Longitude (deg):
                         1000.000
Height (m)
                          500.000
xbox lower
                               0
xbox lower ws
                               0
zbox lower
                               1
zbox_lower_ws
                               0
tstep lower
                              25
Observation of
                       5
                  :
                    b
y\_true\_known
                  : T
y\_true
                       -0.578E-03
                       -0.578E-03
У
stddev
                        0.000E+00
```

. . .

The "observation of" refers to the quantity observed (see the key for ObsSpec%ob_of_what(:) in the table for the Generate_mode=1 mode). The quantity that this corresponds to is also given in the line below this ("observation of" 1 corresponds to quantity u, and 5 corresponds to b in the example), although this textual description is not used by the software, only the "observation of" code.

The xbox_lower and zbox_lower are the grid box indices of the first point on the ABC model grid that is immediately below the observation position. (For example if the height of the observation is 55m, and the vertical grid has level heights 0, 10, 20, 30, 40, 50, 60, ..., then zbox_lower is 6 (the 6th level height is immediately below the 55m height). These indices are stored along with the observation for efficiency (since they are already computed when producing the observation file). If the observation file was produced by some other means, or if the user wishes to manually edit the observation positions, then these indixes may be set to zero – this will force the software to (re)compute these values when the observations are assimilated. Note that some observations need to have indices for more than one quantity (e.g. vertical wind speed, which is a function of a combination of u, v, and w values; since u and v are on different horizontal grid points, and u/v, and w are on different vertical levels (see Fig. 1), then two versions of the lower indices are required ([xbox_lower, zbox_lower] for u, [xbox_lower_ws, zbox_lower_ws, zbox_lower_ws, zbox_lower_ws] for v, and [xbox_lower_ws, zbox_lower_ws] for v. The extra indices xbox_lower_ws and zbox_lower_ws are zero if they are not needed.

There are some elements in the observation file that are not needed by the assimilation, and may be set to arbitrary values. These are y_true_known (T if the 'true' observation is known), y_true (the 'true' value of the observation), y_ref (the (potentially non-linear) model observation computed at the reference state), d (the difference between the observation, y, and y_ref), deltay_m (the perturbation to the modelled observation, computed using the linear operator on a perturbation state), ymhx (the difference between the observation, y, and the modelled observation, $y_ref + deltay_m$), and deltay_m_hat (the quantity $\partial J_O/\partial deltay_m$). These are included in the above file format as a version of the observation file may be output during or post assimilation for diagnostic purposes, where this information is known. This means that a single observation file format is used whether input or output to the data assimilation software.

Variable	\mathbf{Type}	Description	Default	Notes
$\overline{ m datadir ABC_in}$	string	Directory containing the 'truth'.		\mathbf{x}^{t}
$\operatorname{init} _\operatorname{ABC} _\operatorname{file}$	string	ABC model dump containing		End time present is
		the 'truth' (in above directory).		used as init conds.
$\operatorname{datadir} \operatorname{CVT}$	string	Directory containing a CVT file.		
$\mathrm{CVT_file}$	string	Name of a CVT file (as found		
		$from \ Master_Calibration).$		
${ m datadir_Bg}$	string	Directory containing the		
		background data.		
Pert _file	string	Background error selected (in		$\delta \mathbf{x}^{\mathrm{b}}$
		above directory).		
$_{ m Bg_file}$	string	Background state (in above		$\mathbf{x}^{\mathrm{b}} = \mathbf{x}^{\mathrm{t}} + \delta \mathbf{x}^{\mathrm{b}}$
		$\operatorname{directory}$).		
${\rm random_seed}$	$_{ m integer}$	To seed the random number	0	
		$\operatorname{generator}$		

Generate mode=3: Generate a background state consistent with some truth

Input and output files

- Inputs
 - Suitable truth input file (datadirABC_in/init_ABC_file). The latest time present in this file is used as the state that is perturbed by background error.
 - A complete CVT definition file after running the complete calibration suite (stages 1 to 5) (datadirCVT/CVT file).
- Outputs
 - A randomly chosen background error file (ABC model format, in file datadir_Bg/Pert_file) statistically consistent with the background error covariance as specified in the CVT file.
 - A background state (ABC model format, in file datadir_Bg/Bg_file) equal to the 'truth' read-in by this routine plus the above error.

Graphics tools

There are currently no special utitities to analyse the output from this program.

4.9 Master Assimilate

 $Inputs\ a\ background\ state,\ observations,\ and\ a\ CVT\ to\ give\ an\ analysis.\ Future\ options\ to\ include\ ensemble\ and\ hybrid\ methods.$

To compile

Go to directory containing source code (ABC_SRC), and issue: make Master_Assimilate.out

To run

Prepare namelist file UserOptions.nl, go to directory containing this file, and issue: $ABC_SRC/Master_Assimilate.out$

Namelist variables

The namelist variables are described in UserOptions.nl, and should be placed in the directory where the above run command is issued. The variables are described in the following table, where blue entries describe the input directories/files, red entries describe the output directories/files, and purple entries describe the input/output directories/files. An example namelist is given in the file ABCvn1.4/examples/Master Assimilate/UserOptions.nl.

Variable	Type	${\bf Description}$	Default	Notes
Vartype	integer	The type of data assimilation	3	3=3DVar,
				35 = 3D-FGAT,
				$4{=}4\mathrm{DVar}$
Hybrid opt	$_{ m integer}$	Type of hybrid (or if pure Var)	1	1 = standard B, 2
				= pure EnVar, $3=$
				hybrid EnVar, $4 =$
				reduced rank
				KF-type hybrid
				(2-4 currently not
L i P D		To the second second	NT	$\mathrm{implemented})$
${ m datadir_Bg}$	string	Directory containing	No	
D CI		background state.	$ \frac{\text{default}}{N} $	T ' ADC 11
${ m Bg_file}$	string	Background state (in above	No default	$Init_ABC_opt=1$
${ m datadir CVT}$	at nin a	directory).	deraurt No	
datadir C v 1	string	Directory containing a CVT file.	$rac{ m No}{ m default}$	
CVT flo	atrina	Name of a CVT file (in above	ueraum No	
$\mathrm{CVT_file}$	string	directory).	default	
datadir Obs	string	Directory containing	No	
datadii_Obs	string	observational data	default	
Obs file	string	Observation file (in above	No	
000_1110	5011116	directory).	default	
t0	integer	Time of start of this DA cycle	100000.0	\mathbf{S}
N outerloops	integer	Number of outer loops	1	
N innerloops max	$_{ m integer}$	Maximum number of inner loops	10	
$ \frac{1}{\text{crit}}$ $\frac{1}{\text{inner}}$	double	Stopping criterion for inner loop	0.01	$[\nabla J]_i/[\nabla J]_0 <$
-	precision			crit inner for
	-			$\stackrel{-}{\text{iteration}} i$
${ m datadir Anal}$	string	Data to contain the analysis		

anal file	string	Analysis file (put in above
		directory)
$\operatorname{analinc}$ _file	string	Analysis increment file (put in
		above directory)
diagnostics_file	string	Diagnostics file (put in above
		directory)

Input and output files

• Inputs

- The intput file datadir_Bg/Bg_file is a suitable background file. The latest time present in this file is read-in as the background state.
- The input file datadir_CVT/CVT_file contains information defining the control variable transform. This file contains many of the other things needed to define the way that the data assimilation is done (see Section 4.4).
- The input file datadir_Obs/Obs_file contains the observations. It also contains information that defines the length of the time window (it contains the number of model timesteps, the number of data assimilation timesteps, and the step lengths dt and dt_da. It has the same format as that specified in Sect. 4.8 (Generate_mode=2). Note that not all elements need to be specified to run the assimilation see notes accompanying the format specification detailing which are needed by the assimilation (unused elements may be set to zero as dummy values). A version of the observations file is output by the assimilation in which these elements gain meaningful values, which are useful for diagnostics and monitoring see output file descriptions below.

• Outputs

- The analysis is output to datadirAnal/anal_file. This is the background plus the analysis increment.
- The analysis increment is output to datadirAnal/analinc file.
- Diagnostics are output to datadirAnal/diagnostics_file. This contains values of the residuals, values of the cost function, and how different variables, like state energy, change with iteration.
- Linearisation state trajectories output to datadirAnal/LS_Oloop001_Iloop000.nc (the first number, 001 here, is the outer loop number, and the second number, 000 here, is the inner loop number). The first file, LS_Oloop001_Iloop000.nc, corresponds to the background trajectory, and the last file, e.g. LS_Oloop00n_Iloop000.nc, corresponds to the analysis trajectory, where n is N_outerloops + 1. Put in another way, LS_Oloop00i_Iloop000.nc is the LS trajectory at the start of the ith outer loop.
- $\frac{\text{datadirAnal/Delta_Oloop001_Iloop001.nc}}{\text{This is output only for the first inner loop of the first outer loop.}}$
- datadirAnal/GradJo_Oloop001_Iloop001.nc contains the fields describing the gradient of J_{Ω} .
- Versions of the observations file are output to datadirAnal/Obs_001_Iloop000.dat (the first number, 001 here, is the outer loop number, and the second number, 000 here, is the inner loop number). Each observation's time, location, value, and error standard deviation is identical to the respective values in the input file of observations, but other information is included. The extra information includes the model observation value at the particular reference value, the innovation (found with respect to the model reference), the innovation (found with respect to the perturbed model reference), the linear perturbation to the model observation, and the gradient of the observation term in the cost function with respect to the model observation.

The meanings of the symbols in the output file are described in **(author?)** [1]. In particular, the model equations are given as Eqs. (15) of that reference and the grid positions are shown in Fig. 1 of that reference.

Graphics tools

- The python code PlotAssimDiags.py (and the required subroutine contained in Routines4PlotAssimDiags.py) can be used to show the following diagnostics from the assimilation run.
 - Background trajectory.
 - Analysis trajectory.
 - Analysis increment at t = 0.
 - $\nabla_x J_{\rm O}$ trajectory.
 - Truth trajectory.
 - Background error trajectory.
 - Analysis error trajectory.
 - Cost function with iteration.
 - Energy with iteration.
 - $|\nabla_{\chi}J|$ with iteration.
 - Imbalance with iteration.
 - Histograms of O-B, O-A, O-T, B-T, A-T (O=observations, B=background, A=analysis, T=truth).

5 Data assimilation/forecast cycling

It is possible to cycle the data assimilation automatically with a suitable script. The commented bash script DAcycle001.sh is available (inside the script directory) for this purpose. The script assumes that the following have been prepared beforehand:

- CVT file (see Sect. (4.4) to generate this).
- Truth file (a valid ABC model state).
- An observation network specification file (see Sect. (4.8) to generate this). The way that the above script is written, this observation network is repeated every cycle, although the user may modify the script to allow the observation networks to change.
- Other variables required are documented in the script.

Here are some notes

- The true state is propagated from one cycle to the next and observations are simulated from it.
- The background state is a forecast from the previous analysis (except at the start of the cycling where it is a random perturbation from the truth).
- There is an option in the script to turn-on automatic plotting of the data assimilation results for each cycle using the python codes mentioned beforehand.
- When the cycling is finished the python code *PlotMultiCycleErrors.py* can be run, which shows assimilation diagnostics for the multiple cycles together.
- After they have run, two cycling experiments can be compared by running the python code Plot_MultiCycle_DiffExps.py. This will allow the errors of the two cycles to be compared. There are two sets of differences for each field:
 - The first set is the difference between the mean errors in the two experiments.
 - The second set is the difference between the *root-mean-squared-errors* in the two experiments.

6 Ensemble generation

It is possible to use the data assimilation cycling to generate an ensemble of ABC model states from a single dump. The commented bash script MakeEns001.sh is available (inside the script directory) for this purpose. The script assumes that the following have been prepared beforehand:

- CVT file (see Sect. (4.4) to generate this).
- Truth file (a valid ABC model state).
- An observation network specification file (see Sect. (4.8) to generate this). The way that the above script is written, this observation network is repeated every cycle, although the user may modify the script to allow the observation networks to change.
- Other variables required are documented in the script.

To generate an ensemble member, the script adds random background error to the truth file, and passes it through a specified number of assimilation cycles (with random observations). The forecast from the last cycle is taken as a forecast ensemble member.

References

[1] Ruth Elizabeth Petrie, Ross Noel Bannister, and Michael John Priestley Cullen. The ABC model: a non-hydrostatic toy model for use in convective-scale data assimilation investigations. *Geoscientific Model Development*, 10(12):4419, 2017.