
Interpretation of Bit Vectors

# Mapping signed ↔ unsigned

- The computer itself has no idea if a given bit pattern at a particular location in memory "signed" or "unsigned".
- The program interprets some given bit pattern according to the *type* that value has been assigned.
- Moreover, mappings between unsigned and two's complement numbers keep the same bit representations but are interpreted differently depending on type, which may yield a different value in your program.



Maintain Same Bit Pattern


# + Mapping signed ↔ unsigned *con't*

Bits
0000
0001
0010
0011
0100
0101
0110
0111
1000
1001
1010
1011
1100
1101
1110
1111

	1
Signed	
0	
1	
2	
3	4
4	
5	
6	
7	
-8	<b>←</b>
-7	
-6	
-5	
-4	
-3	
-2	
-1	

Unsigned	
0	
1	
2	
3	
4	
5	
6	
7	
8	
9	
10	
11	
12	
13	
14	
15	

# \*Insights into overflow



Lets say you have a signed char with the bit pattern...

#### 0111111

• What is its value in two's complement in decimal? How about unsigned?



# Insights into overflow



Lets say you have a signed char with the bit pattern...

0111111

• What is its value in two's complement in decimal? How about unsigned?

t: 127

u: 127

• Lets say 1 is added to 127. What is the bit pattern for 128?



## Insights into overflow



Lets say you have a signed char with the bit pattern...

#### 0111111

• What is its value in two's complement in decimal? How about unsigned?

t: 127

u: 127


• Lets say 1 is added to 127. What is the bit pattern for 128?

#### 1000000

• What is this bit pattern's value in two's complement in decimal? How about unsigned?



# Insights into overflow



Lets say you have a signed char with the bit pattern...

01111111

• What is its value in two's complement in decimal? How about unsigned?

t: 127

u: 127

• Lets say 1 is added to 127. What is the bit pattern for 128?

1000000

• What is this bit pattern's value in two's complement in decimal? How about unsigned?

t: -128

u: 128

• See *overflow.c* 

# It's all a matter of interpretation

- The key idea so far here is that a bit pattern is just a bit pattern!!
  - It has no intrinsic value or semantics.
- How that bit pattern is 'interpreted' determines its value in your program.
- Ok, so how are bit patterns interpreted in programs?

# + It's all a matter of interpretation

- The key idea so far here is that a bit pattern is just a bit pattern!!
  - It has no intrinsic value or semantics.
- How that bit pattern is 'interpreted' determines its value in your program.
- Ok, so how are bit patterns interpreted in programs?

# Datatypes!

+ Conversion & Casting with Integers

# Signed vs. unsigned in C

#### Constants

- By default are considered to be signed integers
- If you want unsigned you must add a "U" suffix

```
unsigned int x = 0U;
unsigned int y = 4294967259U;
```

#### Casting

• Explicit casting between signed & unsigned

```
int tx, ty;
unsigned int ux, uy;
tx = (int) ux;
uy = (unsigned) ty;
```

• *Implicit* casting also occurs during assignments and function calls

```
tx = ux;
uy = ty;
```

# \*Casting surprises

- If there is a mix of unsigned and signed in single expression, signed values are *implicitly cast to unsigned* 
  - Includes expressions with comparison operators: <, >, ==, <=, >=
  - See *casting\_surprise.c*
- There can also be unexpected results when working with array indices
  - See *array\_surprise.c* and *array\_surprise2.c*

# Casting signed ↔ unsigned: summary


- When the coercion takes place the bit pattern is *maintained* 
  - However the program will reinterpret its value!
  - Can have unexpected effects if not careful, as we just observed.
- Again, expressions containing signed and unsigned int...
  - signed integral is coerced to an unsigned integral!!

# Signed 'extension'

- When we do a 'widening conversion' of a value via casting, what happens?
- In other words, given w-bit signed typed integer value x, convert it to w+k-bit typed integer with same value.
  - w is the number of bits in the type of x
    - ex. short = 16
  - k is the number of bits difference between the two types
    - ex. k of short vs int = 16
- Moreover, what happens in cases like this?

```
short x = 15213;
int ix = (int) x;
short y = -15213;
int iy = (int) y;
```

# Signed 'extension' con't




#### Solution: make k copies of the sign bit

$$X = \mathbf{x}_{w-1} \ \mathbf{x}_{w-2} \dots \mathbf{x}_{1} \mathbf{x}_{0}$$

$$X' = \mathbf{x}_{w-1} \dots \mathbf{x}_{w-1} \mathbf{x}_{w-1} \ \mathbf{x}_{w-2} \dots \mathbf{x}_{1} \mathbf{x}_{0}$$

$$\stackrel{\mathsf{k times}}{\longleftarrow} X'$$



- Unsigned: zeros added
- Signed: sign bit extension
- Both yield intuitive and expected result

# Signed 'extension' con't



- Therefore, converting from smaller to larger integer data type C *automatically* performs sign extension
- Therefore, this code...

```
short x = 15213;
int ix = (int) x;
short y = -15213;
int iy = (int) y;
```

• ...has the values....

	Decimal	Hex	Binary
x	15213	3B 6D	00111011 01101101
ix	15213	00 00 3B 6D	00000000 00000000 00111011 01101101
У	-15213	C4 93	11000100 10010011
iy	-15213	FF FF C4 93	11111111 11111111 11000100 10010011

### Truncation

- When we do a 'narrowing conversion' of a value via coercion or casting, what happens? (i.e. from 32-bit int to 16-bit short)
- Higher-order bits are *truncated*. Value is altered, will be reinterpreted.
- Might yield reasonable result if value is 'small enough' to fit in smaller type...

• But what about something like this?


- This non-intuitive behavior can lead to buggy code!
- See *coercion.c*

# Summary

- Extension (e.g. short to int)
  - Unsigned: zeroes added
  - Signed: sign extension
  - Both yield expected results
- **Truncation** (e.g. unsigned short to unsigned int)
  - Unsigned/signed: Higher weighted bits are lopped off
  - Result must be reinterpreted
  - For 'small numbers' (e.g. int w/ value 16 into short), ok
  - For 'large numbers' (e.g. int w/ value 2<sup>20</sup> into short), problematic.

Negation & Addition

### Negation




- **Task**: given a bit-vector X compute -X
- **Solution**:  $-X = \sim X + 1$ 
  - Negating a value is done by computing its complement and adding 1

Example: 
$$X = 011001_2 = 25_{10}$$
  
 $\sim X = 100110_2 = -26_{10}$   
 $\sim X+1 = 100111_2 = -25_{10}$ 

- Notice, therefore, that for any signed integral type x,  $\sim x + x = -1$ 
  - See *negation.c*

#### Addition in base 2




- Very simple, works same as base 10, just remember...
  - -0+0=0
  - 0 + 1 = 1
  - -1+0=1
  - 1 + 1 = 10
- Examples:

$$\begin{array}{r}
 101 \\
 +101 \\
 \hline
 --- \\
 1010
 \end{array}$$
 $\begin{array}{r}
 1011 \\
 +1011 \\
 \hline
 \end{array}$ 
 $\begin{array}{r}
 1011 \\
 \end{array}$ 

• Note in the second example that in the  $2^1$  column, we have 1 + (1 + 1), where the first 1 is "carried" from the  $2^0$  column.

### Unsigned addition




• However since types have a limited number of bits, any carry bits after the MSB simply get truncated.

$$\begin{array}{rcl}
10010_{2} & = & 18_{10} \\
+ & 11011_{2} & = & 27_{10} \\
\hline
101101_{2} & = & 45_{10} \\
\hline
01101_{2} & = & 13_{10}
\end{array}$$

• See unsigned\_addition\_overflow.c

### Signed addition




■ TAdd and UAdd have identical bit-level behavior. If true sum requires w+1 bits, any carry bits after the MSB simply get truncated.

$$\begin{array}{rcl}
10010_{2} & = & -14_{10} \\
+ & 11011_{2} & = & -5_{10} \\
\hline
101101_{2} & = & -19_{10} \\
\hline
01101_{2} & = & 13_{10}
\end{array}$$

# + Signed addition con't

- One important notable difference!
  - If sum  $\geq 2^{w-1}$ , value becomes negative (overflow)
  - If sum  $< -2^{w-1}$ , value becomes positive (underflow)
- An now you can explain integer overflow to all your friends!!
- See *signed\_addition\_overflow.c*



#### + Summary

#### • Addition:

- Unsigned/signed: Normal addition followed by truncate, same operation on bit level
- Unsigned: addition mod 2<sup>w</sup>
  - Mathematical addition + possible subtraction of 2<sup>w</sup>
- Signed: modified addition mod 2<sup>w</sup> (result in proper range)
  - Mathematical addition + possible addition or subtraction of 2<sup>w</sup>