## SIMPLE HARMONIC MOTION


#### S.H.M.

$$F = -kx$$

General equation of S.H.M. is  $x = A \sin(\omega t + \phi)$ ; ( $\omega t + \phi$ ) is phase of the motion and  $\phi$  is initial phase of the motion.

$$\omega = \frac{2\pi}{T} = 2\pi f$$

$$T = \frac{2\pi}{\omega} = 2\pi \sqrt{\frac{m}{k}}$$



$$V = \omega \sqrt{A^2 - x^2}$$

$$a = -\omega^2 x$$

$$\frac{1}{2} mv^2 = \frac{1}{2} m\omega^2 (A^2 - x^2) = \frac{1}{2} k (A^2 - x^2)$$

$$\frac{1}{2}$$
 Kx<sup>2</sup>

**Total Mechanical Energy (TME)** 

= K.E. + P.E. = 
$$\frac{1}{2}$$
 k (A<sup>2</sup> - x<sup>2</sup>) +  $\frac{1}{2}$  Kx<sup>2</sup> =  $\frac{1}{2}$  KA<sup>2</sup> (which is constant)

## **SPRING-MASS SYSTEM**

$$T = 2\pi \sqrt{\frac{\mu}{K}}$$
, where  $\mu = \frac{m_1 m_2}{(m_1 + m_2)}$  known as reduced mass

## **COMBINATION OF SPRINGS**

Series Combination : 
$$1/k_{eq} = 1/k_1 + 1/k_2$$
  
Parallel combination :  $k_{eq} = k_1 + k_2$ 

Parallel combination: 
$$k_{eq} = k_1 + k_2$$

SIMPLE PENDULUM 
$$T = 2\pi \sqrt{\frac{\ell}{g}} = 2\pi \sqrt{\frac{\ell}{g_{eff.}}}$$
 (in accelerating Refer-

ence Frame); ger is net acceleration due to pseudo force and gravitational force.

#### COMPOUND PENDULUM / PHYSICAL PENDULUM

Time period (T): 
$$T = 2\pi \sqrt{\frac{I}{mg!}}$$


where, I =  $I_{CM}$  +  $m\ell^2$ ;  $\ell$  is distance between point of suspension and centre of mass.

## **TORSIONAL PENDULUM**

Time period (T): 
$$T = 2\pi \sqrt{\frac{I}{C}}$$
 where,  $C = Torsional constant$ 

# Superposition of SHM's along the same direction

$$x_{1} = A_{1} \sin \omega t \ & x_{2} = A_{2} \sin (\omega t + \theta)$$



If equation of resultant SHM is taken as  $x = A \sin(\omega t + \phi)$ 

$$A = \sqrt{A_1^2 + A_2^2 + 2A_1A_2\cos\theta}$$
 &  $\tan \phi = \frac{A_2\sin\theta}{A_1 + A_2\cos\theta}$ 

#### 1. **Damped Oscillation**

# Damping force

$$\vec{F} = -b\vec{v}$$

equation of motion is

$$\frac{mdv}{dt} = -kx - bv$$

•  $b^2$  - 4mK > 0 over damping

•  $b^2$  - 4mK = 0 critical damping

• b<sup>2</sup> - 4mK < 0 under damping

• For small damping the solution is of the form.

$$x = (A_0 e^{-bt/2m}) \sin [\omega^1 t + \delta], \text{ where } \omega' = \sqrt{\left(\frac{k}{m}\right) - \left(\frac{b}{2m}\right)^2}$$

For small b

• angular frequency  $\omega' \approx \sqrt{k/m}$ ,  $= \omega_0$ 

• Amplitude 
$$A = A_0 e^{\frac{-bt}{2m}}$$

• Energy E (t) = 
$$\frac{1}{2}$$
KA<sup>2</sup> e<sup>-bt/m</sup>

• Quality factor or Q value , Q = 
$$2\pi \frac{E}{|\Delta E|} = \frac{\omega'}{2\omega_Y}$$

where , 
$$\omega' = \sqrt{\frac{k}{m} \cdot \frac{b^2}{4m^2}}$$
 ,  $\omega_Y = \frac{b}{2m}$ 

# 2. Forced Oscillations And Resonance

External Force  $F(t) = F_0 \cos \omega_d t$  $x(t) = A \cos (\omega_d t + \phi)$ 

$$A = \frac{F_0}{\sqrt{\left(m^2 \left(\omega^2 - \omega_d^2\right)^2 + \omega_d^2 b^2\right)}} \text{ and } \tan \phi = \frac{-v_0}{\omega_d x_0}$$

(a) Small Damping 
$$A = \frac{F_0}{m(\omega^2 - \omega_d^2)}$$

(b) Driving Frequency Close to Natural Frequency 
$$A = \frac{F_0}{\omega_d b}$$