# Create Kubernetes cluster with Kubeadm

Including a master node and a worker node

#### Create virtual machines

- It is needed to create two virtual machines (one for each node)
- Ubuntu 20.04 TLS
- - Need to create two virtual machines with the normal process


•	OS	RAM	CPU
72.16.0.4*	Ubuntu 20.04 TLS	2Gb	2
72.16.0.5*	Ubuntu 20.04 TLS	1Gb	1
/	2.16.0.4*	'2.16.0.4* Ubuntu 20.04 TLS	72.16.0.4* Ubuntu 20.04 TLS 2Gb

- After creating VM, they must be started. Then, you use the Ubuntu 20.04 TLS ISO file to put the OS.
- Install Ubuntu with minimum requirements, nothing else needed. Give the VM names like master, worker, or easy identifiable names, as they will be much used in future.

<sup>\*</sup> The Ips are assigned automatically by the DHCP after we create a virtual box network (in next slide)


#### Create network for virtual machines

In virtual Box, a network must be created for the VMs to talk among them



## Create network for virtual machines (2)

 Need to access the settings of each VM (two in our case, which will be master node and worker node), and select in the network settings NAT network (in our case, TopGun)



#### Steps for both VM to work before installing Kubernetes

#### Execute commands:

- sudo apt install net-tools
   Install ifconfig commands and etc.
- sudo apt-get install openssh-server -> Install to allow to do ssh connections among VMs if needed (probably needed in future for testing purposes).

#### Check IP of VM

• Execute command ifconfig -> As a result, it gives several interfaces. The one with name epn0s3 is the IP of the VM.

```
enp0s3: flags=4163<UP,BROADCAST,RUNNING,MULTICAST> mtu 1500
inet 172.16.0.4 netmask 255.255.255.0 broadcast 172.16.0.255
inet6 fe80::ee0d:dcf:94d6:6d05 prefixlen 64 scopeid 0x20<link>
ether 08:00:27:41:17:d1 txqueuelen 1000 (Ethernet)
RX packets 6531 bytes 5927979 (5.9 MB)
RX errors 0 dropped 0 overruns 0 frame 0
TX packets 4522 bytes 1269596 (1.2 MB)
TX errors 0 dropped 0 overruns 0 carrier 0 collisions 0
```

# Test Ips, SSH

- - Try a SSH connection from one VM (master) to the other (worker), as a last step to check that the network is working fine
  - Execute command ssh user@ip\*
  - \*Ej. ssh mastervm@172.16.0.4
- In this moment, everything is ready to create Kubernetes cluster with Kubeadm.

# Steps for both VM (Master and worker)

- Log in as root user (every command from now on needs to be executed as root): sudo su (or putting sudo before every command, whichever you prefer)
- Disable Firewall: ufw disable
- Disable swap: swapoff -a; sed -i '/swap/d' /etc/fstab
- Update sysctl settings for Kubernetes networking: cat >>/etc/sysctl.d/kubernetes.conf<<EOF

net.bridge.bridge-nf-call-ip6tables = 1

net.bridge.bridge-nf-call-iptables = 1

**EOF** 

sysctl --system

# Install Docker Engine

- apt install -y apt-transport-https ca-certificates curl gnupg-agent software-properties-common
- curl -fsSL https://download.docker.com/linux/ubuntu/gpg | apt-key add -
- add-apt-repository "deb [arch=amd64] https://download.docker.com/linux/ubuntu \$(lsb\_release -cs) stable"
- apt update
- apt install -y docker-ce=5:19.03.10~3-0~ubuntu-focal containerd.io

### Install Kubernetes

- curl -s https://packages.cloud.google.com/apt/doc/apt-key.gpg | apt-key add -
- echo "deb https://apt.kubernetes.io/ kubernetes-xenial main" > /etc/apt/sources.list.d/kubernetes.list
- apt update && apt install -y kubeadm=1.18.5-00 kubelet=1.18.5-00 kubectl=1.18.5-00

\* Already installs kubectl, kubeadm and kubelet

- Initialize Kubernetes: sudo kubeadm init --pod-network-cidr=192.168.0.0/16
- Ejecutar los comandos que vienen a continuacion:

```
mkdir -p $HOME/.kube

sudo cp -i /etc/kubernetes/admin.conf $HOME/.kube/config

sudo chown $(id -u):$(id -g) $HOME/.kube/config
```

- Dowload Calico, yaml file from website <a href="https://docs.projectcalico.org/manifests/calico.yaml">https://docs.projectcalico.org/manifests/calico.yaml</a>
- Edit the Calico.yaml file. Since the BGP has a method that the pods connect to the first IP that is available and working, it can lead to errors when you have many interfaces in a machine. To solve this, we need to edit the Calico.yaml file and change the following values corresponding to section auto-detect the BGP IP address. Instead, the type (or name) should be "IP\_AUTODETECTION\_METHOD" and the value selected is "can-reach=172.16.0.4" which is the IP of my master node. That means, BGP will choose only an IP for the node that can connect to my master node.

```
# Auto-detect the BGP IP address.

3849 - name: IP
3850 - value: "autodetect"

Value by default: BAD
```

```
# Auto-detect the BGP IP address.
- name: IP_AUTODETECTION_METHOD
    value: "can-reach=172.16.0.4"

Personalized value: GOOD
```

- Once Calico.yaml file is edited, execute command: kubectl apply –f calico.yaml (file is supposed to be in same directory where command is executed)
- After a couple minutes, execute command: watch kubectl get pods -n kube-system (if OK, everypod is running with status 1/1)

root@crubio-VirtualBox:~# kubectl get pods	-n kube	-system -o	wide					
NAME	READY	STATUS	RESTARTS	AGE	IP	NODE	NOMINATED NODE	READINESS GATES
calico-kube-controllers-746f9d75cb-9j8zq	1/1	Running	1	81m	192.168.63.70	crubio-virtualbox	<none></none>	<none></none>
calico-node-6hklg Master	1/1	Running	1	81m	172.16.0.4	crubio-virtualbox	<none></none>	<none></none>
calico-node-7rskg Worker 1	1/1	Running	1	77m	172.16.0.5	worker	<none></none>	<none></none>
calico-node-mhcps Worker 2	1/1	Running	1	41m	172.16.0.6	worker2	<none></none>	<none></none>
coredns-66bff467f8-q55kj	1/1	Running	1	83m	192.168.63.68	crubio-virtualbox	<none></none>	<none></none>
coredns-66bff467f8-xh58w	1/1	Running	1	83m	192.168.63.69	crubio-virtualbox	<none></none>	<none></none>
etcd-crubio-virtualbox	1/1	Running	1	83m	172.16.0.4	crubio-virtualbox	<none></none>	<none></none>
kube-apiserver-crubio-virtualbox	1/1	Running	1	83m	172.16.0.4	crubio-virtualbox	<none></none>	<none></none>
kube-controller-manager-crubio-virtualbox	1/1	Running	1	83m	172.16.0.4	crubio-virtualbox	<none></none>	<none></none>
kube-proxy-5qtcx	1/1	Running	1	41m	172.16.0.6	worker2	<none></none>	<none></none>
kube-proxy-w6g9h	1/1	Running	1	83m	172.16.0.4	crubio-virtualbox	<none></none>	<none></none>
kube-proxy-x5brk	1/1	Running	1	77m	172.16.0.5	worker	<none></none>	<none></none>
kube-scheduler-crubio-virtualbox root@crubio-VirtualBox:~#	1/1	Running	1	83m	172.16.0.4	crubio-virtualbox	<none></none>	<none></none>

This picture is from the end, but it is only to show how columns "READY" and "STATUS" should look like

- Create Cluster join command (to create worker nodes for the master node): kubeadm token create --print-join-command
- It will generate something like this (it is the command needed to be executed in worker node to join to a master):

```
root@crubio-VirtualBox:~# <a href="kubeadm">kubeadm</a> token create --print-join-command

W0902 14:06:49.787789 36815 configset.go:202] WARNING: kubeadm cannot validate component configs for API groups [kubelet.config.k8s.io kubeproxy.config.k8s.io] kubeadm join 172.16.0.4:6443 --token u6w38m.zxq0h0b1rub5sh14 --discovery-token-ca-cert-hash sha256:7960f7074722ef522c00813db8f4e352ce0c0c43e9390f98e83712ca689f2f1c root@crubio-VirtualBox:~#
```

https://github.com/justmeandopensource/kubernetes/blob/master/docs/install-cluster-ubuntu-20.md

## Steps for each worker node

Copy that command in yellow (result of previous slide) and execute in each node (Virtual Machine) that you want to join the cluster.

```
root@crubio-VirtualBox:~# <a href="kubeadm">kubeadm</a> token create --print-join-command

W0902 14:06:49.787789 36815 configset.go:202] WARNING: kubeadm cannot validate component configs for API groups [kubelet.config.k8s.io kubeproxy.config.k8s.io]

kubeadm join 172.16.0.4:6443 --token u6w38m.zxq0h0b1rub5sh14 --discovery-token-ca-cert-hash sha256:7960f7074722ef522c00813db8f4e352ce0c0c43e9390f98e83712ca689f2f1c
root@crubio-VirtualBox:~#
```

Expected result is a success message saying that "Execute kubectl get nodes in your control-plane node (master node)" to view nodes in the cluster.

https://github.com/justmeandopensource/kubernetes/blob/master/docs/install-cluster-ubuntu-20.md

# Checking that cluster is up

Only from the master node, executing the command kubectl get nodes, the output should be:

```
root@crubio-VirtualBox:~# kubectl get nodes
NAME
                     STATUS
                              ROLES
                                        AGE
                                              VERSION
crubio-virtualbox
                    Ready
                                              v1.18.5
                              master
worker
                     Ready
                              <none>
                                              v1.18.5
                     Ready
                                              v1.18.5
                              <none>
root@crubio-VirtualBox:~#
```

If everything is good, after joining two nodes to the cluster, the command kubectl get pods –n kube-system – o wide should look like this:

```
root@crubio-VirtualBox:~# kubectl get pods -n kube-system -o wide
                                                    STATUS
                                                               RESTARTS
                                                                          AGE
                                                                                IΡ
                                                                                                                     NOMINATED NODE
                                                                                                                                      READINESS GATES
calico-kube-controllers-746f9d75cb-9j8zq
                                                                                192.168.63.70
                                                                                                crubio-virtualbox
                                                    Running
                                                              1
                                                                                                                     <none>
                                                                                                                                      <none>
calico-node-6hkla Master
                                                                                172.16.0.4
                                                                                                crubio-virtualbox
                                                    Running
                                                                                                                     <none>
                                                                                                                                      <none>
calico-node-7rskg Worker 1
                                            1/1
                                                                                172.16.0.5
                                                                                                worker
                                                    Running
                                                                                                                     <none>
                                                                                                                                      <none>
calico-node-mhcps Worker 2
                                                                                172.16.0.6
                                                                                                worker2
                                                    Running
                                                                                                                     <none>
                                                                                                                                      <none>
coredns-66bff467f8-q55kj
                                            1/1
                                                    Running
                                                                                192.168.63.68
                                                                                                crubio-virtualbox
                                                                                                                     <none>
                                                                                                                                      <none>
coredns-66bff467f8-xh58w
                                            1/1
                                                                                192.168.63.69
                                                                                                crubio-virtualbox
                                                    Running
                                                                                                                     <none>
                                                                                                                                      <none>
etcd-crubio-virtualbox
                                            1/1
                                                    Running
                                                                                172.16.0.4
                                                                                                crubio-virtualbox
                                                                                                                     <none>
                                                                                                                                      <none>
kube-apiserver-crubio-virtualbox
                                                    Running
                                                                                172.16.0.4
                                                                                                crubio-virtualbox
                                                                                                                     <none>
                                                                                                                                      <none>
kube-controller-manager-crubio-virtualbox
                                                    Running
                                                                                172.16.0.4
                                                                                                crubio-virtualbox
                                                                                                                     <none>
                                                                                                                                      <none>
kube-proxy-5qtcx
                                            1/1
                                                    Running
                                                                                172.16.0.6
                                                                                                worker2
                                                                                                                     <none>
                                                                                                                                      <none>
kube-proxy-w6q9h
                                            1/1
                                                    Running
                                                                                172.16.0.4
                                                                                                crubio-virtualbox
                                                                                                                     <none>
                                                                                                                                      <none>
kube-proxy-x5brk
                                            1/1
                                                    Running
                                                                                172.16.0.5
                                                                                                worker
                                                                                                                     <none>
                                                                                                                                      <none>
kube-scheduler-crubio-virtualbox
                                                    Running 1
                                                                               172.16.0.4
                                                                                                crubio-virtualbox
                                                                                                                     <none>
                                                                                                                                      <none>
root@crubio-VirtualBox:~#
```