MAXTIME(1) MAXTIME(1)

NAME

maxtime - run a command with a timeout

SYNOPSIS

```
maxtime [-g] [-k] [-v] [-w] [--] time command [arg1 \dots]
```

DESCRIPTION

maxtime allows for an external program to be run with a time limit. The argument *time* must be a positive number of seconds, and may be fractional. If the *command* terminates within this period, **maxtime** reports its exit status. If the command's real (wall clock) time exceeds the time limit, it will be killed with SIGTERM. **maxtime** will then return the value 106 to indicate the timeout (see below under RETURN VALUE).

OPTIONS

- **-g** The specified *command* will run in its own process group. If the command times out, the entire process group will be killed.
- **-k** If SIGTERM does not kill *command*, send SIGKILL after a short delay.
- -v Be verbose. If not specified, maxtime will not report what it is doing, even if it exits due to an error. However, the exit code will indicate the problem.
- -w Wait for termination of the child process, even if it timed out and was sent a SIGTERM and/or SIGKILL.

ENVIRONMENT

PATH

PATH is traversed in order to find the specified *command*.

RETURN VALUE

maxtime returns the exit status of the external command, unless an error condition occurs, in which case the exit code will be greater than 100.

0 The command completed successfully.

1 to 100

The command was unsuccessful. The exit status is the exit status of the external command.

- 101 Too few commandline arguments.
- 102 Invalid command line options.
- 103 Error while setting the alarm signal handler.
- 104 Error while forking child process.
- 105 Error during *exec()*. Probably the command specified is not in the **PATH**.
- 106 Either the *command* timed out and was killed, or some other process sent it a signal, causing it to terminate. The command did not return a useful exit status.
- 107 Insufficient memory to perform requested task.
- 108 The time specified was not a valid floating-point number.
- 109 The specified timer period was negative or zero.
- 110 The timer could not be set.
- 128 and up

The command was unsuccessful, and exited due to a signal (e.g. an interrupt was sent from the keyboard).

EXAMPLES

Request the status of a Baan shared memory segment, but do not lock up if shared memory is corrupt:

```
maxtime 2 $BSE/bin/shmmanager6.1 -s
```

Allow at most 10 minutes for stopping a Baan software environment:

2010-12-25

MAXTIME(1) MAXTIME(1)

maxtime 600 \$BSE/etc/rc.stop

BUGS

If the *time* argument is omitted and an *arg* argument is provided, **maxtime** might interpret its commandline arguments wrong. This will only be apparent if $-\mathbf{v}$ has been used, or if its exit status is tested for value 105.

On some platforms, **maxtime** might confuse options for the external command as options for itself. In these cases is necessary to indicate the end of **maxtime**'s options using --.

SEE ALSO

exit(3), setitimer(2), signal(7), wait(2).

VERSION

This manual pertains to version 0.35.

AUTHOR and COPYRIGHT

Copyright © 2004, René Uittenbogaard (ruittenb@users.sourceforge.net).

under the terms described by the GNU General Public License version 2.

maxtime is distributed without any warranty, even without the implied warranties of merchantability or fitness for a particular purpose.

2010-12-25