# **Computer Organization**

Instruction Set Architecture

B.Tech. II (CSE)

C code

A=b+c;

D=e+f;

Assembly Code

Add \$s3, \$s2, \$s1

Compiler Add \$s7, \$s5, \$s6



Machine Code

...0...1..

...0...1..

C code

A=b+c;

D=e+f;

Machine Independent

Defines Machine

Assembly Code

→ Add \$s3, \$s2, \$s1

Compiler Add \$s7, \$s5, \$s6





Encoding straight forward

Machine Code

...0...1..

...0...1.,





Assembly CodeAdd \$s3, \$s2, \$s1Add \$s7, \$s5, \$s6

Instruction set is the interface between hardware and software

#### **Instruction Set Design**

- Central part of any system design
- Allows abstraction, independence

# Why?

- Early days, new computer having its own new set of instructions
- Needed to allow backward compatibility

# **Topics**

- Instruction Set Architecture
- Key of ISA using MIPS
  - Design Principles
  - Instructions
  - Instruction formats
  - Addressing modes

## ISA or Instruction Set

- The level between the high-level languages and the hardware
- When new hardware architecture comes along ...
  - Can add new features to exploit new hardware capabilities
  - Need to maintain backward compatibility



ISA-level code is what a compiler outputs

- ISA-level code is what a compiler outputs
- Compiler writer needs to know
  - \* Memory model
  - Types of registers are available
  - What instructions are available
    - Instruction formats
    - Opcodes
  - Exceptional conditions

- An ISA includes a specification of the set of opcodes (machine language), the native commands implemented by a particular processor
- Related to programming includes
  - Native data types, instructions, registers, addressing modes, memory architecture, interrupt and exception handling, and external I/O

- Distinguished from the microarchitecture
  - \* MAL which is the set of processor design techniques used to implement the instruction set
- Computers with different microarchitectures can share a common instruction set
- For example:
  - The IntelThe Intel Pentium The Intel Pentium and the AMD The Intel Pentium and the AMD Athlon The Intel Pentium and the AMD Athlon implement nearly identical versions of the x86 instruction set, but have radically different internal designs

- Stored Program Concept
  - Fetch & Execute Cycle
    - Instructions are fetched and put into a special register
    - Bits in the register control the subsequent actions (= execution)
    - Fetch the next instruction and repeat
- Instructions
  - Encoded in binary, called machine code

## **ISA Instructions**

- More primitive than higher level languages,
  - \* e.g., no sophisticated control flow such as while or for loops
- Different computers have different instruction sets
  - But with many aspects in common
- Computers have very simple instruction sets
  - \* Makes the Implementation Simple

## Instruction Set

- The complete collection of instructions that are understood by a CPU
  - Can be considered as a functional spec for a CPU
    - Implementing the CPU in large part is implementing the machine instruction set
- Machine Code is rarely used by humans
  - Binary numbers / bits
  - Usually represented by human readable assembly codes
  - In general, one assembler instruction equals one machine instruction

### Elements of an Instruction

- Operation code (Op code)
  - Do this
- Source Operand reference
  - \* To this
- Result Operand reference
  - Put the result here
- Next Instruction Reference
  - When you have done that, do this...
  - Next instruction reference often implicit (sequential execution)

## **Operands**

- Main memory (or virtual memory or cache)
  - Requires address
- CPU register
- I/O device
  - Several forms:
    - Specify I/O module and device
    - Specify address in I/O space
    - Memory-mapped I/O just another memory address

# Sample Instruction Format

N bits

X bits Y bits Z bits

# Key of ISA

#### **Operations**

• What operations are provided??

#### **Operands**

- How many? how big?
- How are memory addresses computed?

#### How many registers?

#### Where do operands reside?

e.g., can you add contents of memory to a register?

#### Instruction length

• Are all instructions of the same length?

#### Instruction format

Which bits designate for what purpose??

## **Operations OR Instruction Types**

- Data processing
  - \* Arithmetic and logical instructions
- Data storage (main memory)
- Data movement (I/O)
- Program flow control
  - Conditional and unconditional branches
  - Call and Return

## **ISA Architecture Types**

Classification according to,

- Type of INTERNAL STORAGE in CPU
- Type and no. of OPERANDS

## **ISA Architecture Types**

- In the CPU, type of INTERNAL STORAGE is the most basic differentiation in ISA
  - Stack, Accumulator or Set of registers
- Accordingly architectures are named:
  - Stack architecture
  - Accumulator architecture
  - Register architecture

# **ISA Architecture Types**

- Operands may be named explicitly or implicitly
  - Stack architecture
    - Implicitly on the top of the stack
  - \* Accumulator architecture
    - One operand is implicitly the accumulator
  - General-purpose register architectures
    - Only explicit operands—either registers or memory locations
    - Operands may be accessed directly from memory or may need to be first loaded into temporary storage, depending on the class of instruction and choice of specific instruction

- Classification of Register Architecture according to the type of operands
  - \* Load-store or register-register machines
    - With no memory reference per ALU instruction
  - Register-memory
    - Instructions with one memory operands per typical ALU instruction
  - \* Memory-memory
    - Instructions with one or more than one memory operand

# ISA ISA Architecture Types

- Code C=A+B,
- On these three classes of instruction sets where A, B and C all belong in Memory

		3. Register	
1. Stack	2. Accumulator	Register-Memor y	Load-Store

# ISA ISA Architecture Types

- Code C=A+B,
- On these three classes of instruction sets where A, B and C all belong in Memory

		3. Register	
1. Stack	2. Accumulator	Register-Memor	Load-Store
		у	
Push A			
Push B			
Add			
Pop C			

# ISA ISA Architecture Types

- Code C=A+B,
- On these three classes of instruction sets where A, B and C all belong in Memory

		3. Register	
1. Stack	2. Accumulator	Register-Memor	Load-Store
Push A Push B Add Pop C	Load A Add B Store C	-	

#### Classes of register architecture

- 3.1 Register-memory architecture

  Can access memory as part of any instruction
- 3.2 Load-store or register-register architecture
- 3.3 Memory-memory architecture

		3. Register	
1. Stack	2. Accumulator	Register-Memor y	Load-Store
Push A Push B Add Pop C	Load A Add B Store C	Load R1, A Add R1, B Store C, R1	

#### Classes of register architecture

- 3.1 Register-memory architecture
  Can access memory as part of any instruction
- 3.2 Load-store or register-register architecture

  Can access memory only with load and store instructions
- 3.3 Memory-memory architecture

		3. Register	
1. Stack	2. Accumulator	Register-Memor y	Load-Store
Push A Push B Add	Load A Add B Store C	Load R1, A Add R1, B Store C, R1	Load R1, A Load R2, B Add R3, R1, R2
Pop C	Store C	Store C, KT	Store C, R3

- Third class of register architecture
  - 3.3 Memory-Memory architecture
    - Keeps all operands in memory
    - Not found in today's machines

		3. Register	
1. Stack	2. Accumulator	Register-Memor y	Load-Store
Push A Push B Add Pop C	Load A Add B Store C	Load R1, A Add R1, B Store C, R1	Load R1, A Load R2, B Add R3, R1, R2 Store C, R3

#### General Two classes of Register Architecture

- 3.1 Register-memory architecture
  - Can access memory as part of any instruction
- 3.2 Load-store or register-register architecture
  - Can access memory only with load and store instructions

		3. Register	
1. Stack	2. Accumulator	Register-Memor y	Load-Store
Push A Push B Add Pop C	Load A Add B Store C	Load R1, A Add R1, B Store C, R1	Load R1, A Load R2, B Add R3, R1, R2 Store C, R3

Utilized in today's machine

- Example Code (A\*B)–(C\*D)–(E\*F)
- On a stack architecture
  - Must be evaluated left to right, unless special operations or swaps of stack positions are done
  - A stack cannot be accessed randomly
- On an accumulator architecture
  - Creating lots of bus traffic
- On a register architecture
  - May be evaluated by multiplying in any order, which may be more efficient because of the location of the operands or because of pipelining

- Most Early Machines used
  - Stack or Accumulator-style architectures
  - Dedicating components / registers for special uses
    - Less number of general-purpose registers
    - Trying to allocate variables to registers will not be profitable

## ISA-Load-Store Reg. Architecture

- Machines designed after 1980 uses a load-store register arch., the registers are used for variables
  - \* To reduce memory traffic
  - To speed up the program
    - As registers are faster than memory
  - \* To improve the code density
    - Fewer bits are needed to represent the register than the memory location
  - Registers are easier for a compiler to use and can be used more effectively than other forms of internal storage

# ISA-Load-Store Reg. Architecture

- How many registers are sufficient?
  - \* Answer depends on how they are used by the compiler
- Most compilers reserve
  - Some registers for expression evaluation
  - Some for parameter passing
  - Remainder to be allocated to hold variables

# ISA

- GPR's major concern-the no. of operands for a typical arithmetic or logical instruction
  - 1. Whether ALU instruction has two or three operands
    - 3-operand instruction format
      - Instruction contains a result and two source operands
    - 2-operand instruction format
      - One of the operands is both a source and a result for the operation
  - 2. How many of the operands may be memory addresses in ALU instructions
    - May vary from none to three

### ISA

 Summary of Classification of Architectures according to the type of operands

#### **ISA** – GPR Architecture

- 1) Register-register (0-Memory + 3-Reg = Total 3)
  - \* Advantage
    - Simple, fixed-length instruction encoding
    - Simple code-generation model
    - Instructions take similar numbers of clocks to execute
  - Disadvantage
    - Higher instruction count than architectures having memory references in instructions
    - Some instructions are short and bit encoding may be wasteful
  - \* Example SPARC, MIPS, PowerPC, ALPHA

### **ISA** – GPR Architecture

- 2) Register memory (1- Memory + 1-Reg= Total 2)
  - \* Advantage
    - Data can be accessed without loading first
    - Instruction format tends to be easy to encode and yields good density
  - \* Disadvantage
    - Operands are not equivalent since a source operand in a binary operation is destroyed
    - Encoding a register number and a memory address in each instruction may restrict the number of registers
    - Clocks per instruction varies by operand location
  - Example Intel 80x86, Motorola 68000

### **ISA** – GPR Architecture

- 3) Memory-memory (3-Memory + 0-Reg = Total-3)
  - Advantage
    - Most compact
    - Doesn't waste registers for temporaries
  - Disadvantage
    - Large variation in instruction size, especially for three-operand instructions
    - Also, large variation in work per instruction
    - Memory accesses create memory bottleneck
  - Example VAX

### ISA

- Summary, In general,
  - Machines with fewer alternatives make the compiler's task simpler since there are fewer decisions for the compiler to make
  - Machines with a wide variety of flexible instruction formats reduce the number of bits required to encode the program
  - A machine that uses a small number of bits to encode the program is said to have good instruction density—a smaller number of bits do as much work as a larger number on a different architecture
  - The no. of registers also affects the instruction size

# **Operands**

- How many operands are supported?
  - \* 3 operands
  - \* 2 operands
  - \* 1 operand
  - \* 0 operand

- 3 operands
  - \* Operand 1, Operand 2, Result
  - \* a = b + c;
  - \* add ax, bx, cx
  - May be a fourth address next instruction (usually implicit)[not common]
- Instructions are long because 3 or more operands have to be specified

#### 2 Operands

- One address doubles as operand and result
- \* a = a + b
- \* add ax, bx
- \* Reduces length of instruction over 3-address format
- Requires some extra work by processor
- Temporary storage to hold some results

- 1 Operand
  - Implicit second address
  - Usually a register (accumulator)
  - Common on early machines
- Used in some Intel x86 instructions with implied operands
  - \* mul ax
  - \* idiv ebx

- 0 (zero) Operand
  - \* All addresses implicit
  - ★ Uses a stack- X87 example c = a + b:
    - push a
    - push b
    - fadd //a+b, pop stack
    - store and pop c
- Can reduce to 3 instructions:
  - push a
  - push b
  - faddp c; //add and pop

#### Computation of Y = (a-b) / (c + (d \* e))

- Three Operands instructions
- Two Operandsinstructions
- One Operand instructions

#### Computation of Y = (a-b) / (c + (d \* e))

- Three Operands instructions
  - \* sub y,a,b
  - \* mul t,d,e
  - \* add t,t,c
  - \* div y,y,t
- Two Operands instructions
  - \* mov y,a
  - sub y,b
  - mov t,d
  - \* mul t,e
  - \* add t,c
  - div y,t

#### Computation of Y = (a-b) / (c + (d \* e))

- One Operand instructions
  - load d
  - \* mul e
  - \* add c
  - store y
  - \* load a
  - \* sub b
  - \* div y
  - store y

# **How Many Operands?**

- More Operands
  - More complex instructions
  - More registers
    - Inter-register operations are quicker
  - Fewer instructions per program
  - More complexity in processor
- Fewer Operands
  - Less complex instructions
  - One address format however limits you to one register
  - More instructions per program
  - Less complexity in processor
    - Faster fetch/execution of instructions

- Viewed as a large single-dimension array with access by address
- A memory address is an index into the memory array
- Two views of Memory
  - Byte Addressing
    - The index points to a byte of memory, and that the unit of memory accessed by a load/store is a byte
  - Word Addressing

0	8 bits of
1	data 8 bits of data
2	8 bits of data
3	8 bits of data
4	8 bits of data
5	8 bits of data
6	8 bits of data

. . .

- How many bytes (8 bits) and words (32 bits) can be accessed for 4 GB Memory?
  - \* 2<sup>32</sup> bytes with byte addresses from 0 to 2<sup>32</sup>-1
  - \*  $2^{30}$  words with byte addresses 0, 4, 8, ...  $2^{32}$ -4
    - Words are aligned

- Why Word alignment?
  - Memories operate more efficiently this way
- Consider 8-byte (64-bit) words

- Bytes in a word can be numbered in two ways:
  - Big Endian
    - Most-significant byte at least address of a word
      - MIPS is Big Endian
  - Little Endian
    - Least-significant byte at least address
      - ? Is Little Endian

Example: Store the number 12 in 32 bits
 There will be 28 zeroes and then 1100
 (MSB) 00000000 00000000 00000000 00001100 (LSB)

	Big-endian	Little-endian
Byte 0:	0000 0000	0000 1100
1:	0000 0000	0000 0000
2:	0000 0000	0000 0000
3:	0000 1100	0000 0000

The big-endian system 1100 is in **byte 3** The little-endian system 1100 is in **byte 0** 

### ISA

- Example ISA's:
  - Digital's <u>VAX</u> (1977)
  - Intel's x86 (1978), but successful (IBM PC)
  - MIPS focus of text, used in assorted machines
  - PowerPC used in Mac's, IBM supercomputers, ...
- VAX and x86 are <u>CISC</u> ("Complex Instruction Set Computers")
  - Started in 70's
- MIPS and PowerPC are <u>RISC</u> ("Reduced Instruction Set Computers")
  - \* Almost all machines of 80's and 90's are RISC
    - Including VAX's successor, the DEC Alpha

### RISC vs. CISC

#### **RISC**

- Instructions in Instruction set of processor are simple and few in number
- Instructions to access memory
- only **LOAD/STORE**
- Instruction length Fixed
- Addressing modes Few
- Complexity in compiler
- Achieves shorten execution time by reducing the clock cycles per instruction (i.e. simple instructions take less time to interpret)

#### CISC

Many complex instructions

- Instructions to access memory many instructions can access
- Instruction length Variable
- Addressing modes Many
- Complexity in microcode
- Achieves shorten execution time by reducing the number of instructions per program

And many more as discussed in class...

# Example for RISC vs. CISC

#### Multiplication:

CISC: Mov ax,10 RISC: Mov ax,0

Mov bx,5

Mul bx, ax Mov cx, 5

Begin: Add ax,bx

Loop begin

The total clock cycles for the CISC version might be:
 (2 movs × 1 cycle) + (1 mul × 30 cycles)
 = 32 cycles

While the clock cycles for RISC version is:
 (3 movs × 1 cycle) + (5 adds × 1 cycle) + (5 loops × 1 cycle)
 = 13 cycles

# ISA

#### Design goals:

- Maximize performance
- Minimize cost
- Reduce design time

# The MIPS

Microprocessor without Interlocked Pipeline Stages

- RISC instruction set architecture (ISA)
- Large share of embedded core market
  - \* Applications in consumer electronics, network / storage equipment, cameras, printers, ...
- Typical of many modern ISAs

#### MIPS Instruction Set

- What should be considered?
  - Operations (MIPS Arithmetic)
  - MIPS Operand
    - Register
    - Memory

# **Operations (MIPS Arithmetic)**

#### Example:

- C code: A = B + C
- $\blacksquare$  C code: A = B + C + D + E
- C code: F = (G + H) (I + J)
- C code: G = H + A[8];

# **Operations (MIPS Arithmetic)**

#### Example:

- C code: A = B + C
- All MIPS arithmetic instructions have 3 operands
- Operand order is fixed (e.g., destination first)
- MIPS code: Add A, B, C

#### Example:

 $\blacksquare$  C code: A = B + C + D + E

#### MIPS code:

Add A, B, C

Add A, A, D

Add A, A, E

#### Example:

• C code: F = (G + H) - (I + J)

#### MIPS code:

Add F, G, H Sub F, I, J

#### Example:

- C code: F = (G + H) (I + J)
- MIPS code: //Use of temporary variables

Add \$t0, G, H

Add \$t1, I, J

Sub F, \$t0, \$t1

#### **Design Principle 1**:

- Simplicity favors regularity.
  - \* i.e. Regularity makes implementation simpler

 Simplicity enables higher performance at lower cost

# **MIPS Operand**

- Arithmetic instructions use register operands
- MIPS has a 32 × 32-bit register file
  - Use for frequently accessed data
  - 32-bit data called a "word"

# **MIPS Registers and Memory**

# **MIPS Operand**

- Arithmetic instructions use register operands
- MIPS has a 32 × 32-bit register file
  - Use for frequently accessed data
  - 32-bit data called a "word"
- Assembler names
  - \* \$t0, \$t1, ..., \$t9 for temporary values
  - \* \$s0, \$s1, ..., \$s7 for saved variables // C variables

# **MIPS Operand**

Only 32 Registers?

#### Design Principle 2:

- Smaller is faster.
- Why?
  - \* Electronic signals have to travel further on a physically larger chip increasing clock cycle time
  - Smaller is also cheaper!

# **MIPS Register Operand**

C code:

$$f = (g + h) - (i + j);$$

Compiled MIPS code:

```
* f, ..., j in $s0, ..., $s4
Add $t0, $s1, $s2
Add $t1, $s3, $s4
Sub $s0, $t0, $t1
```

# MIPS Register Operand

- Arithmetic instructions operands must be in registers
  - MIPS has only 32 registers
- Compiler associates variables with registers
- What about programs with lots of variables (arrays, etc.)?

# **MIPS Memory Operands**

- Main memory used for composite data
  - \* Arrays, structures, dynamic data
- To apply arithmetic operations
  - \* Load values from memory into registers
  - Store result from register to memory

# **MIPS Registers and Memory**

# **MIPS Memory Organization**

- Memory is byte addressed
- Each address identifies an 8-bit byte
- \* A word is 32 bits or 4 bytes
- \* Address must be a multiple of 4
- Words are aligned in memory
- Follows Big-Endian Ordering

<u>Instruction</u>	<u>Meaning</u>
Add \$s1, \$s2, \$s3	\$s1 = \$s2 + \$s3
Sub \$s1, \$s2, \$s3	\$s1 = \$s2 - \$s3
Lw \$s1, 100(\$s2)	s1 = Memory[s2+100]
Sw \$s1, 100(\$s2)	Memory[\$s2+100]= \$s1

## **Instruction Format: R Type**

### **MIPS Operand - Register**

Register 1, called \$at, is reserved for the assembler; registers 26-27, called \$k0 and \$k1 are reserved for the operating system

\*Require 5 bits to select one register

# **Instruction Format: R Type**

Opcode and Operand

3 Registers Operands

15 bits for Register Operands

Opcode

## **Instruction Format: R Type**

op rs	rt rd s	hamt f	unct			
opcode - operation		source	register destin- ation operand	amount 00000 for	function fi selects va of operation extends o	riant on
6 bits	5 bits	5 bits	5 bits	5 bits	6 bits	

# R Type Format Example

op rs	rt rd s	hamt f	ınct			
opcode - operation		source	register destin- ation operand	amount 00000 for	function fideselects varied of operation extends of	riant on
6 bits	5 bits	5 bits	5 bits	5 bits	6 bits	
Add	\$ <b>t0</b> , \$s	s1, \$s2	2	\$t8 - \$	t9: Registers	s are: 8 – 15 s are: 24 – 25 s are: 16 – 23
special	\$s1	\$s2	\$t0	0	add	
0 1	L <sub>7</sub>	18	8 (	)	32	
000000	10001	10010	01000	00000	100000	

 $00000010\ 00110010\ 01000000\ 00100000_2 = 02\ 32\ 40\ 20_{16}$ 

# R Type Format Example

Sub \$t0, \$s1, \$s2

\$t0 - \$t7: Registers are: 8 - 15 \$t8 - \$t9: Registers are: 24 - 25 \$s0 - \$s7:Registers are: 16 - 23

special	\$s1	\$s2	\$t0	0	sub
0 1	.7	18	8 (		34
000000	10001	10010	01000	00000	100010

 $00000010 \ 00110010 \ 01000000 \ 00100000_2 = 02 \ 32 \ 40 \ \underline{22}_{16}$ 

#### **MIPS Instructions**

#### **Design Principle 3:**

- Good design demands good compromises
  - Different formats complicate decoding
  - \* Keep formats as similar as possible

### **Immediate Operands**

- Small constants are used quite frequently (50% of operands)
- Make operand part of instruction itself!
- Introduce a new type of instruction format with Immediate operands
- Design Principle 4: Make the common case fast
- Example:
- addi \$sp, \$sp, 4 # \$sp = \$sp + 4, \$sp=29
- addi \$t0, \$t0, -5
  # \$t0 = \$t0 5

### **Immediate Operands**

- For example:
  - Constant data specified in an instruction
  - \* Addi \$s3, \$s3, 4 # \$s3 = \$s3 + 4
  - \* Addi \$sp, \$sp, 4 # \$sp = \$sp + 4

- No subtract immediate instruction
  - Just use a negative constant
  - \* Addi \$s2, \$s1, -1

# **Instruction Format: I Type**

op rs	rt co	nstant o	address
6 bits	5 bits	5 bits	16 bits
opcode – operation		second register source operand	constant: -2 <sup>15</sup> to +2 <sup>15</sup> - 1 address: offset added to base address in rs

### **Immediate Operands**

ор	rs	rt	16 bit number
6 bits	5 bits	5 bits	16 bits

■ Example: addi \$sp, \$sp, 4 # \$sp = \$sp + 4, \$sp=29

001000	11101	11101	000000000000100
6 bits	5 bits	5 bits	16 bits

#### **Instruction Format**

- Load Instruction
  - \* Lw \$s1, 100(\$s2)
    - Two Registers
    - A Constant
      - If consider, the third register to store this
      - Would be limited to 5 bits only i.e. upto 32
      - This may be larger than 32
      - So, 5-bit field is too small

- Load word has destination first
- Store has destination last
- MIPS arithmetic operands are registers, not memory locations
  - \* Therefore, words must first be moved from memory to registers using loads before they can be operated on; then result can be stored back to memory

C code:

```
G = H + A[8];
G in $s1, H in $s2, base address of A in $s3
```

Compiled MIPS code:

Index 8 requires offset of 32, due to 4 bytes/word

```
Value Offset Base address
Lw $t0, 32($s3) # load word
Add $s1, $s2, $t0
```

C code:

$$A[12] = H + A[8];$$

MIPS code:

?

Load : Lw \$t0, 32(\$s3)

Arithmetic: Add \$t0, \$s2, \$t0

Store : Sw \$t0, 48(\$s3)

# **Instruction Format: I Type**

op rs	rt co	nstant o	address		
6 bits	5 bits	5 bits	16 bits		
opcode - operation		second register source operand	constant: -2 <sup>15</sup> to +2 <sup>15</sup> - 1 address: offset added to base address in rs		
lw \$t0	\$t0 - \$t7: Registers are: 8 - \$t8 - \$t9: Registers are: 24 - \$s0 - \$s7: Registers are: 16 -				
100011	10010	01000	0000001111101010		

# **Example: I Type Format**

C code:

```
A[300] = H + A[300];
```

- MIPS code:
  - \* Lw \$t0, 1200(\$t1)
  - \* Add \$t0, \$s2, \$t0
  - \* Sw \$t0, 1200(\$t1)

# **Example: I Type Format**

ор	rs	rt	rd	shan addre	nt/ fund ss	ŧ	
35	9	8		1200			
0	1	8	8	8		<b>)</b>	32
43	9	8	<u> </u>	1200			

```
$t0 - $t7: Registers are: 8 - 15
$t8 - $t9: Registers are: 24 - 25
$s0 - $s7:Registers are: 16 - 23
```

```
Lw $t0, 1200($t1)
Add $t0, $s2, $t0
Sw $t0, 1200($t1)
```

# **Logical Operations**

Instructions for bitwise manipulation

Operation	С	MIPS
Shift Left	<<	sll
Shift Right	>>	srl
Bitwise AND	&	and, andi
Bitwise OR		or, ori
Bitwise NOT	~	nor

 Useful for extracting and inserting groups of bits in a word

# **Shift Operations**

op rs	rt rd	shamt	funct		
6 bits	5 bits	5 bits	5 bits	5 bits	6 bits

- shamt: how many positions to shift
- Shift left logical
  - Shift left and fill with 0 bits
  - \* SII by i bits multiplies by 2i
- Shift right logical
  - Shift right and fill with 0 bits
  - Srl by i bits divides by 2i (unsigned only)

# **AND Operations**

- Useful to mask bits in a word
  - Select some bits, clear others to 0
- Example:

```
And $t0, $t1, $t2 # $t0 = $t1 & $t2
```

# **OR Operations**

- Useful to include bits in a word
  - Select some bits to 1, leave others unchanged
- Example:

```
Or $t0, $t1, $t2 # $t0 = $t1 | $t2
```

#### The Constant Zero

- MIPS register 0 (\$zero) is the constant 0
  - Cannot be overwritten
- Useful for common operations
  - \* E.g., move between registers:
    - Value of \$s1 to \$t2
    - Add \$t2, \$s1, \$zero

# **NOT Operations**

- Useful to invert bits in a word
  - Change 0 to 1, and 1 to 0
  - MIPS has NOR 3-operand instruction
  - \* a NOR b == NOT ( a OR b )
- Example:

Nor \$t0, \$t1, \$zero # Register 0: always read as zero

```
$t1 = 0000\ 0000\ 0000\ 00011\ 11\ 00\ 0000\ 0000
$t0 = 1111\ 1111\ 1111\ 1111\ 1111\ 1111
```

### **Conditional Operations**

- Decision making instructions
  - \* alter the control flow,
    - i.e., change the next instruction to be executed

### MIPS conditional instructions

- Branch to a labeled instruction if a condition is true
- Otherwise, continue sequentially
  - Beq rs, rt, L1
    - if (rs == rt) branch to instruction labeled L1;
  - Bne rs, rt, L1
    - if (rs != rt) branch to instruction labeled L1;
  - \* J L1
    - unconditional jump to instruction labeled L1

# **Compiling If Statements**

C code:

```
if (i==j) f = g+h;
else f = g-h;
* f, g, ... in $s0, $s1, ...
```

Compiled MIPS code:

```
Bne $s3, $s4, Else
Add $s0, $s1, $s2
J Exit
Else: Sub $s0, $s1, $s2
Exit: ...
```

Assembler calculates addresses

# **Compiling Loop Statements**

C code: (with Variable Array Index)
 Loop: g = g + A[i];
 i = i + j;
 if (i!= h) goto Loop;
 Variables g, h, i and j to the registers \$\$1, \$\$2, \$\$3 and \$\$4
 Assume A is an array of 100 elements and its base address is in \$\$5

#### C code to MIPS code

#### C Code:

$$g = g + A[i];$$

- Assume A is an array of 100 elements and its base address is in \$s3
- Variables g and i to the registers \$s1 and \$s4

Array A of 100 elements and its base address is in \$s3 Variables G and i to the registers \$s1 and \$s4

Load A[i] into a temporary register
Due to Byte Addressing, Must multiply i by 4

```
i.e. i + i = 2i and then 2i + 2i = 4i
```

#### MIPS Code:

```
add $t1, $s4, $s4 # $t1 = 2 * i
add $t1, $t1, $t1 # $t1 = 4 * i
```

Array A of 100 elements and its base address is in \$s3 Variables G and i to the registers \$s1 and \$s4

■To get the address of A[i],
Need to add \$t1 and the base of A in \$s3
i.e., add \$t1, \$t1, \$s3
# \$t1=address of A[i] (4 \* i + \$s3)

■Now use Load A[i] into a temporary register i.e., lw \$t0, 0(\$t1)

$$# $t0 = A[i]$$

Final Instruction adds A[i] and g, and places the sum in g:

i.e., add \$s1, \$s1, \$t0

$$#g = g + A[i]$$

#### MIPS Code:

```
add $t1, $s4, $s4  # $t1 = 2 * i
add $t1, $t1, $t1  # $t1 = 4 * I
add $t1, $t1, $s3  # $t1=address of A[i] (4 * i + $s3)
lw $t0, 0($t1)  # $t0 = A[i]
add $s1, $s1, $t0  # g = g + A[i]
```

## **Compiling Loop Statements**

- C code: (with Variable Array Index)
   Loop: g = g + A[i]; i = i + j; if (i!= h) goto Loop;
   Variables g, h, i and j to the registers \$s1, \$s2, \$s3 and \$s4
   Array A of 100 elements and its base address is in \$s5
- Compiled MIPS code:

```
Loop: add $t1, $s3, $s3 # Temp reg $t1 = 2 * i add $t1, $t1, $t1 # Temp reg $t1 = 4 * i add $t1, $t1, $s5 # $t1 = address of A[i] lw $t0, 0($t1) add $s1, $s1, $t0 # g = g +A[i] add $s3, $s3, $s4 # i = i + j bne $s3, $s2, Loop
```

#### **Compiling While Loop**

C code:

```
while (save[i] == k)
i = i + j;
```

- i in \$s3, j in \$s4, k in \$s5, base address of save in \$s6
- Compiled MIPS code: ?

```
while: add $t1,$s3,$s3;
  add $t1,$t1,$t1;
  add $t1,$t1,$s6;
  Iw $t0,0($t1);
  Beq $t0,$s5,here;
here:add $s3,$s3,$s4;
Exit:
```

```
while: add $t1,$s3,$s3;
  add $t1,$t1,$t1;
  add $t1,$t1,$s6;
  Iw $t0,0($t1);
  Beq $t0,$s5,here;
exit
here:add $s3,$s3,$s4:
  J while
```

```
add t1,s3,s3
   add t1,t1,t1
   add t0,s4,s4
   add t0,t0,t0
   add t0,t0,s4
loop: load s1,0(t1)
      bnq s1,s5 exit
      add t1,t1,t0
      j loop
```

```
while: add $t1,$s3,$s3 // Address
     add $t1,$t1,$t1
     add $t1,$t1,$s4 // $s4=Base Addr
     Iw $t0, 0($t1)
     Beq $t0, $s5, body // Equality Check
    J Exit
body: add $s3,$s3,$s4
    J while
Fxit:...
```

#### **Compiling Loop Statements**

```
C code:
while (save[i] == k) i = i + j;
    * i in $s3, j in $s4, k in $s5, base address of save in $s6
```

Compiled MIPS code:

```
Loop: add $t1, $s3, $s3 \# Temp reg $t1 = 2 * i
     add $t1, $t1, $t1 # Temp reg $t1 = 4 * i
      add $t1, $t1, $s6 # $t1 = address of save[i]
     Iw $t0, 0($t1) # Temp reg $t0 = save[i]
     bne $t0, $s5, Exit # Go to Exit if save[i] != k
     add $3, $3, $4 # i = i + j
     j Loop # Go to loop
```

Exit:

## **More Conditional Operations**

- Set result to 1 if a condition is true
  - \* Otherwise, set to 0
- slt rd, rs, rt
  - \* if (rs < rt) rd = 1; else rd = 0;
- slti rt, rs, constant
  - # if (rs < constant) rt = 1; else rt = 0;</pre>
- Use in combination with beq, bne
  - slt \$t0, \$s1, \$s2 # if (\$s1 < \$s2)</p>
  - bne \$t0, \$zero, L # branch to L

#### **Compiling Loop Statements**

C code:

```
while (save[i] == k) i += 1;
```

- \* i in \$s3, k in \$s5, address of save in \$s6
- Compiled MIPS code:

?

#### **Tutorial Question**

```
C code:
switch (k){
case 0: f = i + j; break;
case 1: f = g + h; break;
case 2: f = g - h; break;
case 3: f = i - j; break;
Six variables f through k correspond to six registers $s0 through $s5
```

Compiled MIPS code: ?

#### **Branch Instruction Format**

- Instructions:
  - beq rs, rt, L1
  - bne rs, rt, L1
  - Specify:
    - Opcode, two registers, target address

op rs	rt co	nstant o	r address
6 bits	5 bits	5 bits	16 bits

16 bit Address ?

#### **Branch Addressing**

 16 bits is too small a reach in a 2<sup>32</sup> address space

#### Solution:

- Principle of locality
  - Most branch targets are near branch
  - Forward or backward Direction
- \* Use PC (= program counter), called PC-relative addressing based on Principle of Locality
- PC-relative addressing
  - Target address = PC + offset × 4
  - PC already incremented by 4 by this time

#### C code:

```
while (save[i] == k)
i = i + j;
```

//i in \$s3, j in \$s4, k in \$s5, base address of save in \$s6

Assume Loop at location 80000

C code: while (save[i] == k) i = i + j; i in \$s3, j in \$s4, k in \$s5, base address of save in \$s6

#### Compiled MIPS code:

Loop: add \$t1, \$s3, \$s3	80000	0	19	19	9	0	32
add \$t1, \$t1, \$t1	80004	0	9	9	9	0	32
add \$t1, \$t1, \$s6	80008	0	9	21	9	0	32
Iw \$t0, 0(\$t1)	80012	35	9	8		0	
bne \$t0, \$s5, Exit	80016	5	8	21		?	
add \$s3, \$s3, \$s4	80020	0	19	20	19	0	32
j Loop	80024	2			?		
Exit:	80028						
Assume Loop at location 80000	80012	35	9	8		0	


C code: while (save[i] == k) i = i + j; i in \$s3, j in \$s4, k in \$s5, base address of save in \$s6

Compiled MIPS code:

Loop: add \$t1, \$s3, \$s3 add \$t1, \$t1, \$t1 add \$t1, \$t1, \$s6 lw \$t0, 0(\$t1) bne \$t0, \$s5, Exit add \$s3, \$s3, \$s4 j Loop

#### Exit:

Assume Loop at location 80000



C code: while (save[i] == k) i = i + j; i in \$s3, j in \$s4, k in \$s5, base address of save in \$s6

80000

80004

80008

80012

80016

80020

80024

80028

80012

35

9

8

0

Compiled MIPS code:

Loop: add \$t1, \$s3, \$s3 add \$t1, \$t1, \$t1 add \$t1, \$t1, \$s6 lw \$t0, 0(\$t1) bne \$t0, \$s5, Exit add \$s3, \$s3, \$s4 j Loop

#### Exit:

Assume Loop at location 80000

0	19	19	9	0	32
0	9	9	9	0	32
0	9	21	9	0	32
35	9	8		0	
5	8	21		8	X
0	19	20	19	0	32
2			80000		

C code: while (save[i] == k) i = i + j; i in \$\$3, j in \$\$ As the PC-Relative addressing refers the number of words to Compiled MIPS code: 8000 the next instruction instead of Loop: add \$t1, \$s3, \$s3 the number of bytes. 8000 add \$t1, \$t1, \$t1 So, 8 bytes is replaced by add \$t1, \$t1, \$s6 8000 2 words/ Iw \$t0, 0(\$t1) 80012 35 9 bne \$t0, \$s5, Exit 80016 8 21 add \$s3, \$s3, \$s4 19 19 80020 0 20 0j Loop 80024 80000 Exit: 80028 Assume Loop at location 80000 80012 35 9 8 0

#### **Jump Addressing**

- Jump (j) targets could be anywhere in text segment
  - Encode full address in instruction

ор	address	
6 bits	26 bits	

- Pseudo-Direct jump addressing
  - \* 26 bit address is concatenated with the upper bits of the PC
  - Target address = PC31...28 : (address × 4)

#### **Jump Addressing**

- MIPS jump j instruction replaces lower 28 bits of the PC with A00 where A is the 26 bit address; it never changes upper 4 bits
  - \* Example:

```
if PC = 1011X (where X = 28 bits), it is replaced with 1011A00
```

- Why Not upper 4 bits?
- \* Address space size = 2<sup>32</sup>
  - There are 16(=2<sup>4</sup>) partitions of memory, each partition of size 256 MB (=2<sup>28</sup>), such that, in each partition the upper 4 bits of the address is same.
- If a program crosses an address partition, then a j that reaches a different partition has to be replaced by jr with a full 32-bit address first loaded into the jump register
- \* Therefore, OS should always try to load a program inside a single partition

## **Jump Addressing**

Example:

```
J Label # Address of Label = 100
```

• 26-bit Pseudodirect address is 100/4 = 25

ор	26 bit number		
6 bits	26 bits		
000010	0000000000000000001100	'	
	1		

1

C code: while (save[i] == k) i = i + j; i in \$s3, j in \$s4, k in \$s5, base address of save in \$s6

80012

35

9

Compiled MIPS code:

Loop: add \$t1, \$s3, \$s3 add \$t1, \$t1, \$t1 add \$t1, \$t1, \$s6 lw \$t0, 0(\$t1) bne \$t0, \$s5, Exit add \$s3, \$s3, \$s4 j Loop

Exit:

Assume Loop at location 80000

80000	0	19	19	9	0	32
80004	0	9	9	9	0	32
80008	0	9	21	9	0	32
80012	35	9	8		0	
80016	5	8	21		2	
80020	0	19	20	19	0	32
80024	2			80000		
80028						

8

0


C code: while (save[i] == k) i = i + j; i in \$s3, j in \$s4, k in \$s5, base address of save in \$s6

Compiled MIPS code:

Loop: add \$t1, \$s3, \$s3 add \$t1, \$t1, \$t1 add \$t1, \$t1, \$s6 lw \$t0, 0(\$t1) bne \$t0, \$s5, Exit add \$s3, \$s3, \$s4 j Loop

#### Exit:

Assume Loop at location 80000



#### **More Conditional Operators**

- Signed vs. Unsigned
- Signed comparison: slt, slti
- Unsigned comparison: sltu, sltui
- Example

  - slt \$t0, \$s0, \$s1 # signed
    - $-1 < +1 \square \$t0 = 1$
  - \* sltu \$t0, \$s0, \$s1 # unsigned
    - $+4,294,967,295 > +1 \square $t0 = 0$

#### **Immediate Operands**

- Small constants are used quite frequently (50% of operands)
- Make operand part of instruction itself!
- Design Principle 4: Make the common case fast
- Example: addi \$sp, \$sp, 4 # \$sp = \$sp + 4, \$sp=29

001000	11101	11101	000000000000000000000000000000000000000
6 bits	5 bits	5 bits	16 bits
ор	rs	rt	16 bit number

What If Constants are LARGER than 16-bits?


#### How about larger constants?

- First we need to load a 32 bit constant into a register
- Must use two instructions for this: first new load upper immediate instruction for upper 16 bits

```
lui $t0, 10101010101010
```

#### How about larger constants?

To load \$t0 with 1010... upto 32 bits



Then get lower 16 bits in place:

Now the constant is in place, use register-register arithmetic

#### **Larger Constants**

#### Example:

Load the register \$s0 with the value:

```
40000010 = 3D090016
```

= 0000 0000 0011 1101 0000 1001 0000 00002

#### MIPS Code:

```
lui $$0 61<sub>10</sub> # 61<sub>10</sub> = 0000 0000 0011 1101<sub>2</sub> addi $$0, $$0, 2304<sub>10</sub> # 2304<sub>10</sub> = 0000 1001 0000 0000<sub>2</sub>
```

# MIPS Addressing Modes

#### So far

Instruction Format Meaning

```
add \$s1,\$s2,\$s3 R \$s1 = \$s2 + \$s3

sub \$s1,\$s2,\$s3 R \$s1 = \$s2 - \$s3

lw \$s1,100(\$s2) I \$s1 = \$s2 + \$s3

sw \$s1,100(\$s2) I \$s1 = \$s2 + \$s3

hemory[\$s2+100] = \$s1

bne \$s4,\$s5,Lab1 Next instr. is at Lab1 if \$s4 != \$s5

heq \$s4,\$s5,Lab2 Next instr. is at Lab2 if \$s4 = \$s5

j Lab3 J Next instr. is at Lab3
```

- Formats:
- Simple instructions all 32 bits wide, Very structured no unnecessary baggage, Only three instruction formats

R	op	rs	rt	rd shamt funct
I	op	rs	rt	16 bit address
J	op	26	bit ad	dress

#### **Summarize MIPS:**

- Simplicity favors regularity
  - Fixed size instructions
  - Small number of instruction formats
  - \* Keep the register fields in the same place
    - Opcode always the first 6 bits

- Simplicity favors regularity
  - Fixed size instructions
  - Small number of instruction formats
  - Keep the register fields in the same place
    - Opcode always the first 6 bits

#### Smaller is faster

- Limited instruction set
- \* Limited number of registers in register file
- Limited number of addressing modes

- Simplicity favors regularity
  - Fixed size instructions
  - Small number of instruction formats
  - Keep the register fields in the same place
    - Opcode always the first 6 bits
- Smaller is faster
  - Limited instruction set
  - Limited number of registers in register file
  - \* Limited number of addressing modes
- Good design demands good compromises
  - Compromise between providing for larger addresses and constants in instructions
  - Keep all instructions of the same length

- Simplicity favors regularity
  - Fixed size instructions
  - Small number of instruction formats
  - Keep the register fields in the same place
    - Opcode always the first 6 bits
- Smaller is faster
  - Limited instruction set
  - Limited number of registers in register file
  - Limited number of addressing modes
- Good design demands good compromises
  - Compromise between providing for larger addresses and constants in instructions
  - Keep all instructions of the same length
- Make the common case fast
  - Arithmetic operands from the register file (load/store machine)
  - \* Allow instructions to contain immediate operands

#### **Animating the Datapath**

lw rt, offset(rs)

R[rt] <- MEM[R[rs] + s\_extend(offset)];



## **Animating the Datapath**

sw rt, offset(rs)

**MEM**[R[rs] + sign\_extend(offset)] <- R[rt]

End of Presentation