# Module Interface Specification for Software Engineering

Team #13, ARC
Avanish Ahluwalia
Russell Davidson
Rafey Malik
Abdul Zulfiqar

 $January\ 17,\ 2025$ 

# 1 Revision History

Date Version		Notes
2025-01-18	1.0	Initial Version
2025-03-28	1.1	Modifications based on review

# 2 Symbols, Abbreviations and Acronyms

See SRS Documentation here.

# Contents

1	Rev	vision I	History				i	
2	Syn	nbols,	Abbreviations and Acronyms			i	i	
3	Introduction							
4	Notation							
5	5 Module Decomposition						2	
6	MIS	S of Se	ettings Module				3	
	6.1		ıle				3	
	6.2	Uses					3	
	6.3	Syntax	NX				3	
		6.3.1	Exported Constants				3	
		6.3.2	Exported Access Programs				3	
	6.4	Seman	ntics				3	
		6.4.1	State Variables				3	
		6.4.2	Environment Variables				4	
		6.4.3	Assumptions				4	
		6.4.4	Access Routine Semantics				4	
		6.4.5	Local Functions			. !	5	
7	MIS	of He	Telp Module			(	6	
	7.1	Modul	ıle				6	
	7.2	Uses				. (	6	
	7.3	Syntax	NX			. (	6	
		7.3.1	Exported Constants			. (	6	
		7.3.2	Exported Access Programs			. (	6	
	7.4	Seman	ntics			. (	6	
		7.4.1	State Variables			. (	6	
		7.4.2	Environment Variables			. (	6	
		7.4.3	Assumptions			. '	7	
		7.4.4	Access Routine Semantics				7	
		7.4.5	Local Functions		•	. '	7	
8	MIS	S of Co	ollision Hazard Detection Module			8	3	
	8.1	Modul	ıle			. 8	8	
	8.2	Uses				. 8	8	
	8.3	Syntax	nx			. 8	8	
		8.3.1	Exported Constants			. 8	8	
		8.3.2	Exported Access Programs			. 8	8	

	8.4	Seman	ntics	. 8
		8.4.1	State Variables	. 8
		8.4.2	Environment Variables	. 9
		8.4.3	Assumptions	. 9
		8.4.4	Access Routine Semantics	. 9
		8.4.5	Local Functions	. 9
9	MIS	of To	our Proximity Detection Module	10
	9.1	Modul	le	. 10
	9.2	Uses		. 10
	9.3	Syntax	x	. 10
		9.3.1	Exported Constants	. 10
		9.3.2	Exported Access Programs	. 10
	9.4	Seman	ntics	. 10
		9.4.1	State Variables	. 10
		9.4.2	Environment Variables	. 11
		9.4.3	Assumptions	. 11
		9.4.4	Access Routine Semantics	. 11
		9.4.5	Local Functions	. 11
10	MIS	of No	otifications Module	12
	10.1	Modul	le	. 12
	10.3	Syntax	X	. 12
		10.3.1	Exported Constants	. 12
		10.3.2	Exported Access Programs	. 12
	10.4	Seman	ntics	. 12
		10.4.1	State Variables	. 12
		10.4.2	Environment Variables	. 12
		10.4.3	Assumptions	. 13
		10.4.4	Access Routine Semantics	. 13
		10.4.5	Local Functions	. 13
11	MIS	of Au	uthentication Module	14
	11.1	Modul	le	. 14
	11.3	Syntax	X	. 14
		11.3.1	Exported Constants	. 14
			Exported Access Programs	
	11.4		ntics	
			State Variables	
		11.4.2	Environment Variables	. 15
		11.4.3	Assumptions	. 15

		11.4.4 Acces	ss Routine S	Semantics	 		 	 	 				. 15
		11.4.5 Local	Functions		 		 	 	 				. 16
<b>12</b>	MIS	of Object	Render M	odule									17
		Module											
		Uses											
		Syntax											
	12.0	12.3.1 Expo											
		12.3.1 Expo											
	19.4	Semantics .											
	12.4												
		12.4.1 State											
		12.4.2 Envir											
		12.4.3 Assur											
		12.4.4 Acces											
		12.4.5 Local	Functions		 		 	 	 	•	 •	•	. 19
<b>13</b>	MIS	of Touring	Module										20
		Module			 		 	 	 				. 20
	13.2	Uses			 		 	 	 				. 20
	13.3	Syntax			 		 	 	 				. 20
		13.3.1 Expo	rted Consta	ants	 		 	 	 				. 20
		13.3.2 Expo											
	13.4	Semantics .											
		13.4.1 State											
		13.4.2 Envir											
		13.4.3 Assur											
		13.4.4 Acces	-										
		10.1.1 11000	is recurring t	)CIIIaII0ICS	 	• •	 	 • •	 	•	 •	•	. 20
		of Tour Li											22
		Module											
		Uses											
	14.3	Syntax			 		 	 	 				. 22
		14.3.1 Expo	rted Consta	ints	 		 	 	 				. 22
		14.3.2 Expo	rted Access	Programs	 		 	 	 				. 22
	14.4	Semantics .			 		 	 	 				. 22
		14.4.1 State	Variables		 		 	 	 				. 22
		14.4.2 Envir	conment Var	riables	 		 	 	 				. 22
		14.4.3 Assur	mptions		 		 	 	 				. 22
		14.4.4 Acces											
1 5	NATE	of Tour M	anagemen.	t Madula									<b>2</b> 4
τŋ		Module	_										
	10.2	Uses			 		 	 	 				. Z <sup>z</sup>

	15.3	Syntax	24
		15.3.1 Exported Constants	24
		15.3.2 Exported Access Programs	24
	15.4	Semantics	24
		15.4.1 State Variables	24
		15.4.2 Environment Variables	24
		15.4.3 Assumptions	24
		15.4.4 Access Routine Semantics	24
<b>16</b>	MIS	of Maps	26
	16.1	Module	26
	16.2	Uses	26
	16.3	Syntax	26
		16.3.1 Exported Constants	26
		16.3.2 Exported Access Programs	26
	16.4	Semantics	26
		16.4.1 State Variables	26
		16.4.2 Environment Variables	26
		16.4.3 Assumptions	26
		16.4.4 Access Routine Semantics	27
		16.4.5 Local Functions	27
<b>17</b>	MIS	of Object Interaction Module	28
<b>17</b>		of Object Interaction Module  Module	_
<b>17</b>	17.1		_
17	$17.1 \\ 17.2$	Module	28
<b>17</b>	$17.1 \\ 17.2$	Module	28 28
<b>17</b>	$17.1 \\ 17.2$	Module	28 28 28
<b>17</b>	17.1 17.2 17.3	Module	28 28 28 28
17	17.1 17.2 17.3	Module	28 28 28 28 28
17	17.1 17.2 17.3	Module	28 28 28 28 28 28
17	17.1 17.2 17.3	Module	28 28 28 28 28 28 28
17	17.1 17.2 17.3	Module	28 28 28 28 28 28 28 28
17	17.1 17.2 17.3	Module	28 28 28 28 28 28 28 28 28
	17.1 17.2 17.3 17.4	Module	28 28 28 28 28 28 28 28 28 29
	17.1 17.2 17.3 17.4 MIS	Module	28 28 28 28 28 28 28 28 29 29
	17.1 17.2 17.3 17.4 MIS 18.1	Module Uses Syntax 17.3.1 Exported Constants 17.3.2 Exported Access Programs Semantics 17.4.1 State Variables 17.4.2 Environment Variables 17.4.3 Assumptions 17.4.4 Access Routine Semantics 17.4.5 Local Functions of Local Database Manager	28 28 28 28 28 28 28 28 28 29 29
	17.1 17.2 17.3 17.4 MIS 18.1 18.2	Module	28 28 28 28 28 28 28 28 28 28 29 29 30 30
	17.1 17.2 17.3 17.4 MIS 18.1 18.2	Module Uses Syntax 17.3.1 Exported Constants 17.3.2 Exported Access Programs Semantics 17.4.1 State Variables 17.4.2 Environment Variables 17.4.3 Assumptions 17.4.4 Access Routine Semantics 17.4.5 Local Functions  of Local Database Manager Module Uses	28 28 28 28 28 28 28 28 29 29 30 30
	17.1 17.2 17.3 17.4 MIS 18.1 18.2	Module . Uses . Syntax . 17.3.1 Exported Constants . 17.3.2 Exported Access Programs . Semantics . 17.4.1 State Variables . 17.4.2 Environment Variables . 17.4.3 Assumptions . 17.4.4 Access Routine Semantics . 17.4.5 Local Functions .  of Local Database Manager . Module . Uses . Syntax .	28 28 28 28 28 28 28 28 28 28 29 29 30 30 30 30
	17.1 17.2 17.3 17.4 MIS 18.1 18.2 18.3	Module Uses Syntax 17.3.1 Exported Constants 17.3.2 Exported Access Programs Semantics 17.4.1 State Variables 17.4.2 Environment Variables 17.4.3 Assumptions 17.4.4 Access Routine Semantics 17.4.5 Local Functions  of Local Database Manager Module Uses Syntax 18.3.1 Exported Constants	28 28 28 28 28 28 28 28 29 29 30 30 30 30

	18.4.2 Environment Variables	30
	18.4.3 Assumptions	30
	18.4.4 Access Routine Semantics	31
	18.4.5 Local Functions	32
	v	33
19.		33
19.		33
19.	V	33
	•	33
	19.3.2 Exported Access Programs	33
19.	4 Semantics	33
		33
	19.4.2 Environment Variables	33
	19.4.3 Assumptions	33
	19.4.4 Access Routine Semantics	33
	19.4.5 Local Functions	34
		35
20.		35
		35
20.		35
	±	35
		35
20.		35
	20.4.1 State Variables	35
	20.4.2 Environment Variables	35
	20.4.3 Assumptions	35
	20.4.4 Access Routine Semantics	36
	20.4.5 Local Functions	37
		38
		38
		38
21.		38
	•	38
	1	38
21.		38
		38
		38
	*	38
		36
	21.4.5. Local Functions	40

<b>22</b>	MIS of Object Importer Module
	22.1 Module
	22.2 Uses
	22.3 Syntax
	22.3.1 Exported Constants
	22.3.2 Exported Access Programs
	22.4 Semantics
	22.4.1 State Variables
	22.4.2 Environment Variables
	22.4.3 Assumptions
	22.4.4 Access Routine Semantics
	22.4.5 Local Functions
<b>23</b>	MIS of Realm Interface Module
	23.1 Module
	23.2 Uses
	23.3 Syntax
	23.3.1 Exported Constants
	23.3.2 Exported Access Programs
	23.4 Semantics
	23.4.1 State Variables
	23.4.2 Environment Variables
	23.4.3 Assumptions
	23.4.4 Access Routine Semantics
	23.4.5 Local Functions
0.4	NATION C.A. III I
24	MIS of AccessHardware
	24.1 Module
	24.2 Uses
	24.3 Syntax
	24.3.1 Exported Constants
	24.3.2 Exported Access Programs
	24.4 Semantics
	24.4.1 State Variables
	24.4.2 Environment Variables
	24.4.3 Assumptions
	24.4.4 Access Routine Semantics
	24.4.5 Local Functions
25	MIS of Inventory
_0	25.1 Module
	25.2 Uses
	25.3 Syntax

		25.3.1	Exported Constants			 					48
		25.3.2	Exported Access Programs			 					48
	25.4	Semant	$\mathrm{tics}$			 					49
			State Variables								49
		25.4.2	Environment Variables			 					49
			Assumptions								49
			Access Routine Semantics								49
			Local Functions								50
		20.1.0	Booth Fallottone	•		 	•	•	•	•	
<b>26</b>	MIS	of Ob	jectPlacement								50
	26.1	Module	e			 					50
	26.2	Uses .				 					51
											51
			Exported Constants								51
			Exported Access Programs								51
	26.4		tics								51
	20.1		State Variables								51
			Environment Variables								51
			Assumptions								52
			Access Routine Semantics								$\frac{52}{52}$
			Local Functions								53
		20.4.0	Local Pulicions			 	•	•		•	96
<b>27</b>	MIS	of Res	${f stricted Area Detect}$								<b>5</b> 4
<b>27</b>						 					<b>5</b> 4
<b>27</b>	27.1	Module	e								
<b>27</b>	27.1 27.2	Module Uses .	e			 					54
<b>27</b>	27.1 27.2	Module Uses . Syntax	e			 					54 54 54
<b>27</b>	27.1 27.2	Module Uses . Syntax 27.3.1	Exported Constants		· · ·	  					54 54 54 54
27	27.1 27.2 27.3	Module Uses . Syntax 27.3.1 27.3.2	Exported Constants		  	   					54 54 54 54
27	27.1 27.2 27.3	Module Uses . Syntax 27.3.1 27.3.2 Semant	Exported Constants			 					54 54 54 54 54
27	27.1 27.2 27.3	Module Uses . Syntax 27.3.1 27.3.2 Semant 27.4.1	Exported Constants	· · · · · · · · · · · · · · · · · · ·		 					54 54 54 54 54 54
27	27.1 27.2 27.3	Module Uses . Syntax 27.3.1 27.3.2 Semant 27.4.1 27.4.2	Exported Constants  Exported Access Programs  tics  State Variables  Environment Variables			 					54 54 54 54 54 54
27	27.1 27.2 27.3	Module Uses . Syntax 27.3.1 27.3.2 Semant 27.4.1 27.4.2 27.4.3	Exported Constants  Exported Access Programs  tics  State Variables  Environment Variables  Assumptions			 					54 54 54 54 54 54 54
27	27.1 27.2 27.3	Module Uses . Syntax 27.3.1 27.3.2 Semant 27.4.1 27.4.2 27.4.3 27.4.4	Exported Constants Exported Access Programs tics State Variables Environment Variables Assumptions Access Routine Semantics								54 54 54 54 54 54 54 54
27	27.1 27.2 27.3	Module Uses . Syntax 27.3.1 27.3.2 Semant 27.4.1 27.4.2 27.4.3 27.4.4	Exported Constants  Exported Access Programs  tics  State Variables  Environment Variables  Assumptions								54 54 54 54 54 54 54
	27.1 27.2 27.3 27.4	Module Uses . Syntax 27.3.1 27.3.2 Semant 27.4.1 27.4.2 27.4.3 27.4.4	Exported Constants Exported Access Programs tics State Variables Environment Variables Assumptions Access Routine Semantics								54 54 54 54 54 54 54 54
	27.1 27.2 27.3 27.4 MIS	Module Uses . Syntax 27.3.1 27.3.2 Semant 27.4.1 27.4.2 27.4.3 27.4.4 27.4.5	Exported Constants Exported Access Programs tics State Variables Environment Variables Assumptions Access Routine Semantics Local Functions  eatherHazardDetect								544 544 544 544 544 545 545 555 555
	27.1 27.2 27.3 27.4 <b>MIS</b> 28.1	Module Uses . Syntax 27.3.1 27.3.2 Semant 27.4.1 27.4.2 27.4.3 27.4.4 27.4.5 of We Module	Exported Constants Exported Access Programs tics State Variables Environment Variables Assumptions Access Routine Semantics Local Functions  eatherHazardDetect	· · · · · · · · · · · · · · · · · · ·							54 54 54 54 54 54 54 54 55 55 55
	27.1 27.2 27.3 27.4 <b>MIS</b> 28.1 28.2	Module Uses . Syntax 27.3.1 27.3.2 Semant 27.4.1 27.4.2 27.4.3 27.4.4 27.4.5 of We Module Uses .	Exported Constants Exported Access Programs tics State Variables Environment Variables Assumptions Access Routine Semantics Local Functions  eatherHazardDetect								54 54 54 54 54 54 54 55 55 55 55
	27.1 27.2 27.3 27.4 <b>MIS</b> 28.1 28.2	Module Uses Syntax 27.3.1 27.3.2 Semant 27.4.1 27.4.2 27.4.3 27.4.4 27.4.5 S of We Module Uses Syntax	Exported Constants Exported Access Programs tics State Variables Environment Variables Assumptions Access Routine Semantics Local Functions  eatherHazardDetect								54 54 54 54 54 54 54 54 55 55 55 55
	27.1 27.2 27.3 27.4 <b>MIS</b> 28.1 28.2	Module Uses Syntax 27.3.1 27.3.2 Semant 27.4.1 27.4.2 27.4.3 27.4.4 27.4.5 Sof We Module Uses Syntax 28.3.1	Exported Constants Exported Access Programs tics State Variables Environment Variables Assumptions Access Routine Semantics Local Functions  eatherHazardDetect  Exported Constants								54 54 54 54 54 54 54 54 55 55 55 55 55
	27.1 27.2 27.3 27.4 MIS 28.1 28.2 28.3	Module Uses Syntax 27.3.1 27.3.2 Semant 27.4.1 27.4.2 27.4.3 27.4.5 of We Module Uses Syntax 28.3.1 28.3.2	Exported Constants Exported Access Programs tics State Variables Environment Variables Assumptions Access Routine Semantics Local Functions  eatherHazardDetect								54 54 54 54 54 54 54 54 55 55 55 55

28.4.2	Environment Variables	56
28.4.3	Assumptions	56
28.4.4	Access Routine Semantics	56
28.4.5	Local Functions	56

# 3 Introduction

The following document details the Module Interface Specifications for the mobile AR application, Realm. The application is designed to provide users with an interactive and immersive experience of the world of AR. The application will be developed using the Unity game engine and will be compatible with both iOS and Android devices. The MIS will provide a detailed description of the modules that will be implemented in the application on both the client and server sides. The modules are decomposed into the hardware-hiding, behavior-hiding, and software decision modules. The hardware-hiding modules are used to abstract the hardware components of the system. The behavior-hiding modules are used to provide the functional requirements of the system. The software decision modules are used to provide the algorithms and data structures that will be used in the system.

Complementary documents include the SRS (System Requirement Specifications) and Module Guide. The full documentation and implementation can be found here.

# 4 Notation

The following table summarizes the primitive data types used by the *Realm* application.

Data Type	Notation	Description
character	char	a single symbol or digit
string	$\operatorname{str}$	a sequence of characters
integer	$\mathbb{Z}$	a number without a fractional component in $(-\infty, \infty)$
natural number	N	a number without a fractional component in $[1, \infty)$
real	$\mathbb{R}$	any number in $(-\infty, \infty)$
boolean	$\mathbb{B}$	{True, False}
array	$\Theta[\ ]$	Collection of data of type $\Theta$ . Fixed size can be mentioned within the brackets. Example: $\mathbb{R}[\ ]$
AR object	AR	a binary blob containing information to read and view the AR object

# 5 Module Decomposition

The following table is taken directly from the Module Guide document for this project.

Level 1	Level 2
Hardware-Hiding Module	Hardware Module
Behaviour-Hiding Module	Inventory Module Touring Module Tour List Module Tour Management Module Settings Module Help Module Maps Module Realm Interface Module Object Importer Module Object Placement Module Object Interaction Module Object Render Module Collision Detection Module Restricted Area Detection Module Weather Detection Module
	Tour Proximity Detection Module Notifications Module REST API Connection Module
Software Decision Module	Local Database Manager Module Data Sync Module Server Database Manager Module Authentication Module

Table 1: Module Hierarchy

# 6 MIS of Settings Module

# 6.1 Module

Settings Module

# 6.2 Uses

- Database/Network Manager Module
- Error Manager Module
- Authentication Module

# 6.3 Syntax

# 6.3.1 Exported Constants

• None

# 6.3.2 Exported Access Programs

Name	In	Out	Exceptions
UpdateSettings	Dictionary of key-	Bool - Success or Fail	InvalidKeyException
	value pairs		
FetchSettings	-	Dictionary of current	-
		settings	
ResetToDefaults	-	Bool - Success or Fail	-
UpdateProfileDetails	Dictionary of profile-	Bool - Success or Fail	InvalidKeyException
	related key-value pairs		
FetchProfileDetails	-	Dictionary of profile-	-
		related data	
ChangePassword	Old password, new	Bool - Success or Fail	AuthenticationException
	password		

# 6.4 Semantics

## 6.4.1 State Variables

- settings: A dictionary containing user-configurable settings and their current values.
- profileDetails: A dictionary storing user profile-related data (e.g., name, avatar, bio).

#### 6.4.2 Environment Variables

- Device Storage: Used to persist settings and profile details.
- Encryption Mechanism: Ensures sensitive data like passwords and privacy settings are encrypted during storage and transmission.

## 6.4.3 Assumptions

- The device has sufficient storage for saving and retrieving settings and profile details.
- All keys provided for updates are predefined and valid.
- The user is authenticated before accessing this module.

#### 6.4.4 Access Routine Semantics

UpdateSettings(newSettings):

- Transition: Updates the corresponding entries in the settings dictionary with the provided key-value pairs.
- Output: Returns true if all updates succeed, false otherwise.
- Exception: Throws InvalidKeyException if an invalid key is provided.

FetchSettings():

- Output: Returns the current settings dictionary.
- Exception: None

ResetToDefaults():

- Transition: Resets all settings in the dictionary to their default values.
- Output: Returns true if the reset succeeds, false otherwise.
- Exception: None

UpdateProfileDetails(newProfileDetails):

- Transition: Updates the corresponding entries in the profileDetails dictionary with the provided key-value pairs.
- Output: Returns true if all updates succeed, false otherwise.
- Exception: Throws InvalidKeyException if an invalid key is provided.

FetchProfileDetails():

• Output: Returns the current profileDetails dictionary.

• Exception: None

ChangePassword(oldPassword, newPassword):

- Transition: Validates the old password and updates the password to the new one if valid.
- Output: Returns true if the password is successfully changed, false otherwise.
- Exception: Throws AuthenticationException if the old password is incorrect or the user session is invalid.

- ValidateKey(key): Ensures the provided key is predefined and valid for the settings or profileDetails dictionaries.
- EncryptData(data): Applies encryption to sensitive data before storage or transmission.

# 7 MIS of Help Module

## 7.1 Module

Help Module

#### 7.2 Uses

- User Interface Manager Module
- Content Storage Module

# 7.3 Syntax

# 7.3.1 Exported Constants

• None

## 7.3.2 Exported Access Programs

Name	In	Out	Exceptions
ViewHelpTopics	-	List of help topics	-
SearchHelp	Query string	Relevant help content	InvalidQueryException
FetchFAQ	-	List of frequently	-
		asked questions	
ContactSupport	User message, user	Confirmation of mes-	MessageDeliveryException
	contact info	sage sent	
SubmitFeedback	Feedback message	Bool - Success or Fail	FeedbackSubmissionException

## 7.4 Semantics

#### 7.4.1 State Variables

- helpSections: A collection of predefined help sections, each identified by a unique ID and containing text, images, or links.
- searchIndex: An index to facilitate quick searches within help content.

#### 7.4.2 Environment Variables

- Content Storage: Stores the help documentation (e.g., FAQs, guides).
- Device Network: Used for fetching online help content if local content is not available.

#### 7.4.3 Assumptions

- All help content is preloaded in the Content Storage or accessible via a network connection.
- The section identifiers used are valid and correspond to existing help sections.

#### 7.4.4 Access Routine Semantics

FetchHelpContent(sectionID):

- Transition: None
- Output: Returns the help content associated with the given section identifier.
- Exception: Throws ContentNotFoundException if the sectionID is invalid or not found.

SearchHelpContent(query):

- Transition: None
- Output: Returns a list of section identifiers that are relevant to the search query.
- Exception: None

NavigateToHelpSection(sectionID):

- Transition: Updates the displayed help section in the user interface to the section corresponding to the given identifier.
- Output: Returns true if navigation is successful, false otherwise.
- Exception: Throws InvalidSectionException if the sectionID is invalid.

- ValidateSectionID(sectionID): Ensures the section identifier is valid and corresponds to an existing help section.
- PerformSearch(query): Matches the search query against the searchIndex and returns relevant section identifiers.

# 8 MIS of Collision Hazard Detection Module

# 8.1 Module

Collision Hazard Detection Module

## 8.2 Uses

- AR Object Manager Module
- Device Sensors Module (e.g., Camera, LiDAR)
- Notification Module

# 8.3 Syntax

# 8.3.1 Exported Constants

• None

## 8.3.2 Exported Access Programs

Name	In	Out	Exceptions
DetectCollision	User's current	Boolean (Col-	$\underline{ Sensor Data Unavailable Exception}$
	position, AR	lision De-	
	object positions	tected/Not	
		Detected)	
FetchHazardDetails	Collision ID	Hazard details	HazardNotFoundException
		(Type, Severity,	
		Location)	
LogCollisionEvent	Collision details	Bool - Success or	LoggingException
	(Position, Time,	Fail	
	Severity)		
ClearHazardAlerts	-	Bool - Success or	AlertClearanceException
		Fail	
UpdateDetectionSettings	s Dictionary of de-	Bool - Success or	InvalidSettingsException
	tection settings	Fail	

## 8.4 Semantics

#### 8.4.1 State Variables

• collisionEvents: A log of detected collisions, including timestamps, object data, and resolutions.

#### 8.4.2 Environment Variables

- Device Sensors: Provides real-time data for collision detection (e.g., LiDAR, camera).
- Notification System: Sends alerts when collisions are detected.
- Storage System: Logs collision events for future analysis.

#### 8.4.3 Assumptions

- Device sensors are operational and capable of providing accurate real-time data.
- The system has access to sufficient storage for logging collision events.
- All objects in the AR environment are registered and have defined collision boundaries.

#### 8.4.4 Access Routine Semantics

DetectCollision(sensorData):

- Transition: None
- Output: Returns true if a collision is detected based on sensor data, false otherwise.
- Exception: Throws SensorUnavailableException if real-time data cannot be accessed.

ResolveCollision(collisionData):

- **Transition:** Attempts to resolve the collision by adjusting object positions or notifying the user.
- Output: Returns true if the collision is successfully resolved, false otherwise.
- Exception: Throws CollisionNotResolvableException if the collision cannot be resolved.

LogCollisionEvent(eventData):

- **Transition:** Records the collision event in the system log.
- Output: Returns true if the event is successfully logged, false otherwise.
- Exception: Throws LogWriteException if the log cannot be updated.

- AnalyzeSensorData(sensorData): Processes real-time data to determine if a collision is imminent.
- NotifyUserOfCollision(collisionData): Sends an alert to the user about a detected collision.

# 9 MIS of Tour Proximity Detection Module

# 9.1 Module

Tour Proximity Detection Module

## 9.2 Uses

- GPS Module
- Notification Module
- AR Object Manager Module

# 9.3 Syntax

# 9.3.1 Exported Constants

• None

# 9.3.2 Exported Access Programs

Name	In	Out	Exceptions
DetectNearbyTours	User's current	List of tours	${\color{blue}\textbf{Location}} \textbf{Data} \textbf{Unavailable} \textbf{Exception}$
	location, reg-	within proxim-	
	istered tour	ity	
	locations		
NotifyTourProximity	User's proximity	Notification	NotificationFailureException
	to a specific tour	message	
UpdateTourProximity	Updated user lo-	Bool - Success or	UpdateFailedException
	cation, updated	Fail	
	tour locations		
FetchProximityDetails	User ID, tour ID	Details of prox-	DataFetchException
		imity data	

## 9.4 Semantics

## 9.4.1 State Variables

- proximityEvents: A log of detected proximity events, including timestamps, tour data, and notifications sent.
- currentLocation: The user's most recently reported GPS coordinates.

#### 9.4.2 Environment Variables

- GPS System: Provides the user's real-time location.
- Notification System: Sends alerts when a user is near a tour location.
- Storage System: Logs proximity detection events for future analysis.

### 9.4.3 Assumptions

- The GPS system is operational and capable of providing accurate location data.
- The system has sufficient storage for logging proximity detection events.
- All tours in the system have clearly defined geographical boundaries.

#### 9.4.4 Access Routine Semantics

DetectNearbyTour(currentLocation):

- Transition: None
- Output: Returns a list of tours within proximity to the user's current location.
- Exception: Throws LocationUnavailableException if GPS data cannot be accessed.

TriggerTourNotification(tourData):

- Transition: Sends a notification to the user about the nearby tour.
- Output: Returns true if the notification is successfully sent, false otherwise.
- Exception: Throws NotificationSendException if the notification fails to send.

LogProximityEvent(eventData):

- Transition: Records the proximity event in the system log.
- Output: Returns true if the event is successfully logged, false otherwise.
- Exception: Throws LogWriteException if the log cannot be updated.

- AnalyzeLocationData(locationData): Processes the current GPS location to identify nearby tours.
- NotifyUserOfProximity(tourData): Sends an alert to the user about a detected nearby tour.

# 10 MIS of Notifications Module

## 10.1 Module

Notifications Module

## 10.2 Uses

- User Interface Manager Module
- Database Manager Module

# 10.3 Syntax

# 10.3.1 Exported Constants

• None

# 10.3.2 Exported Access Programs

Name	In	Out	Exceptions
SendNotification	User ID, notifi-	Bool - Success or	NotificationSendException
	cation message	Fail	
FetchNotifications	User ID	List of notifica-	DataFetchException
		tions	
MarkNotificationRead	Notification ID	Bool - Success or	NotificationNotFoundException
		Fail	
DeleteNotification	Notification ID	Bool - Success or	DeleteFailedException
		Fail	
UpdateNotificationSettings	User ID, settings	Bool - Success or	InvalidSettingsException
	data	Fail	

## 10.4 Semantics

#### 10.4.1 State Variables

• notifications: A list of notifications associated with each user, including their status (read/unread).

#### 10.4.2 Environment Variables

- Notification System: Handles the actual delivery of notifications to users.
- Database: Stores notifications for retrieval and management.

#### 10.4.3 Assumptions

- The notification delivery service is operational and capable of sending notifications in real-time.
- All user identifiers and notification identifiers are valid and exist in the database.

#### 10.4.4 Access Routine Semantics

SendNotification(notificationData):

- Transition: Adds the notification to the database and attempts to deliver it to the specified user.
- Output: Returns true if the notification is successfully sent, false otherwise.
- Exception: Throws NotificationSendException if the delivery fails.

FetchNotifications(userID):

- Output: Returns a list of notifications for the specified user.
- Exception: Throws UserNotFoundException if the user ID is not found.

MarkNotificationAsRead(notificationID):

- Transition: Updates the status of the specified notification to "read" in the database.
- Output: Returns true if the status update is successful, false otherwise.
- Exception: Throws NotificationNotFoundException if the notification ID is not found.

DeleteNotification(notificationID):

- **Transition:** Removes the specified notification from the database.
- Output: Returns true if the notification is successfully deleted, false otherwise.
- Exception: Throws NotificationNotFoundException if the notification ID is not found.

- ValidateNotificationData(notificationData): Ensures the notification data is valid before sending.
- NotifyUser(notificationData): Sends the notification to the user using the delivery system.

# 11 MIS of Authentication Module

## 11.1 Module

Authentication Module

# 11.2 Uses

- Database Manager Module
- Encryption Module
- Notification Module (for two-factor authentication)

# 11.3 Syntax

## 11.3.1 Exported Constants

• None

# 11.3.2 Exported Access Programs

Name	In	Out	Exceptions
SendNotification	User ID, notifi-	Bool - Success or	NotificationSendException
	cation message	Fail	
FetchNotifications	User ID	List of notifica-	DataFetchException
		tions	
MarkNotificationRead	Notification ID	Bool - Success or	Notification Not Found Exception
		Fail	
DeleteNotification	Notification ID	Bool - Success or	DeleteFailedException
		Fail	
UpdateNotificationSettings	User ID, settings	Bool - Success or	InvalidSettingsException
	data	Fail	

## 11.4 Semantics

#### 11.4.1 State Variables

- users: A collection of user data, including credentials, authentication settings, and two-factor status.
- activeSessions: A list of currently authenticated user sessions.

#### 11.4.2 Environment Variables

- Database: Stores user credentials and authentication-related data.
- Encryption System: Encrypts sensitive user information like passwords.
- Notification System: Sends two-factor authentication codes or password reset links.

### 11.4.3 Assumptions

- All usernames and passwords are stored securely and hashed using industry-standard encryption.
- The system has access to a functional notification system for delivering codes and reset links.
- Users provide valid inputs during registration and login attempts.

#### 11.4.4 Access Routine Semantics

AuthenticateUser(username, password):

- **Transition:** Verifies the username and password against stored credentials.
- Output: Returns true if the credentials are valid, false otherwise.
- Exception: Throws AuthenticationFailedException if the credentials do not match.

RegisterUser(registrationData):

- Transition: Adds a new user to the database with the provided registration data.
- Output: Returns true if the registration is successful, false otherwise.
- Exception: Throws RegistrationFailedException if the registration fails due to invalid data or duplication.

ResetPassword(emailOrUsername):

- Transition: Sends a password reset link or code to the associated email.
- Output: Returns true if the reset link/code is sent successfully, false otherwise.
- Exception: Throws UserNotFoundException if the email or username is not found.

EnableTwoFactorAuth(userID):

- Transition: Enables two-factor authentication for the specified user.
- Output: Returns true if the feature is enabled successfully, false otherwise.

• Exception: Throws UserNotFoundException if the user ID is invalid.

ValidateTwoFactorCode(userID, code):

- Transition: Validates the two-factor authentication code provided by the user.
- Output: Returns true if the code is valid, false otherwise.
- Exception: Throws InvalidCodeException if the code is incorrect or expired.

- HashPassword(password): Generates a secure hash for the given password.
- GenerateTwoFactorCode(userID): Creates a time-sensitive code for two-factor authentication.
- SendNotification(userID, message): Sends a notification to the specified user with relevant authentication details.

# 12 MIS of Object Render Module

# 12.1 Module

Object Render Module

## 12.2 Uses

- Maps Module
- Object Placement Module

# 12.3 Syntax

# 12.3.1 Exported Constants

- RENDER\_RESOLUTION\_DEFAULT: Default resolution for rendering objects.
- RENDER\_FPS\_LIMIT: Frame-per-second limit for rendering.
- RENDER\_QUALITY\_OPTIONS: Preset quality levels (e.g., low, medium, high).

# 12.3.2 Exported Access Programs

Name	In	Out	Exceptions
RenderObject	Object ID, Position,	Rendered Object	RenderingException
	Orientation		
AdjustRenderSettings	Dictionary of key-	Bool - Success or Fail	InvalidSettingException
	value pairs		
FetchRenderSettings	-	Dictionary of current	-
		render settings	
PauseRendering	-	Bool - Success or Fail	RenderingException
ResumeRendering	-	Bool - Success or Fail	RenderingException

#### 12.4 Semantics

### 12.4.1 State Variables

- currentRenderSettings: Stores the current rendering settings, such as resolution and FPS.
- renderQueue: A queue of objects to be rendered.

#### 12.4.2 Environment Variables

- Graphics Processing Unit (GPU)
- Rendering Library (e.g., OpenGL, Vulkan, Unity Renderer)

### 12.4.3 Assumptions

- Objects to be rendered are correctly formatted and preprocessed.
- The rendering hardware meets the minimum requirements.

#### 12.4.4 Access Routine Semantics

RenderObject(Object ID, Position, Orientation):

- transition: Adds the object to the render queue and renders it based on the given parameters.
- output: The rendered object appears in the virtual environment.
- exception: Throws RenderingException if the rendering fails due to hardware or software issues.

AdjustRenderSettings(Dictionary of key-value pairs):

- transition: Updates the currentRenderSettings variable with the provided values.
- output: Returns a success or failure boolean.
- exception: Throws InvalidSettingException if the provided settings are invalid.

#### FetchRenderSettings():

- transition: None.
- output: Returns the currentRenderSettings.
- exception: None.

#### PauseRendering():

- transition: Pauses the rendering process.
- output: Returns a success or failure boolean.
- exception: Throws Rendering Exception if pausing fails.

#### ResumeRendering():

- transition: Resumes the rendering process.
- output: Returns a success or failure boolean.
- exception: Throws RenderingException if resuming fails.

- ValidateRenderSettings(settings): Ensures that the given render settings are within acceptable ranges.
- $\bullet$   ${\bf Optimize Render Queue}():$  Reorders the render queue to improve performance.

# 13 MIS of Touring Module

## 13.1 Module

Touring Module

#### 13.2 Uses

Realm Interface Module, Maps Module, Notifications Module

# 13.3 Syntax

## 13.3.1 Exported Constants

• **DEFAULT\_TOUR\_RADIUS:** The default radius for proximity detection during tours.

## 13.3.2 Exported Access Programs

Name	In	Out	Exceptions
StartTour	Tour ID	Bool - Success or Fail	InvalidTourIDException
PauseTour	-	Bool - Success or Fail	-
EndTour	Tour ID	Bool - Success or Fail	InvalidTourIDException
FetchTourDetails	Tour ID	Tour Object	InvalidTourIDException

### 13.4 Semantics

## 13.4.1 State Variables

• CurrentTour: Stores the details of the ongoing tour.

#### 13.4.2 Environment Variables

GPS and Maps API for location tracking.

# 13.4.3 Assumptions

It is assumed that GPS and Maps API services are functional.

#### 13.4.4 Access Routine Semantics

#### StartTour:

- transition: Initializes the tour with the given Tour ID and marks it as active.
- output: Returns success if the tour starts successfully.

• exception: Throws InvalidTourIDException if the Tour ID does not exist.

## PauseTour:

- transition: Pauses the current active tour.
- output: Returns success if the tour is paused successfully.

#### **EndTour**:

- transition: Ends the current active tour and updates its status.
- output: Returns success if the tour is ended successfully.
- exception: Throws InvalidTourIDException if the Tour ID does not exist.

# 14 MIS of Tour List Module

## 14.1 Module

Tour List Module

# 14.2 Uses

Touring Module, Maps Module

# 14.3 Syntax

## 14.3.1 Exported Constants

• MAX\_TOUR\_ENTRIES: The maximum number of tours that can be displayed in the list.

## 14.3.2 Exported Access Programs

Name	In	Out	Exceptions
FetchTourList	None	Array of Tours	-
SearchTours	Search Query	Array of Tours	-
SortTours	Sorting Criteria	Array of Tours	-

# 14.4 Semantics

#### 14.4.1 State Variables

• TourList: Stores a list of available tours.

#### 14.4.2 Environment Variables

Database connection to retrieve available tours.

#### 14.4.3 Assumptions

It is assumed that the database is functional and contains valid tour data.

## 14.4.4 Access Routine Semantics

## FetchTourList:

- transition: Retrieves all available tours from the database.
- output: Returns an array of available tours.

# SearchTours:

- transition: Filters the available tours based on the search query.
- output: Returns an array of tours matching the search criteria.

## **SortTours**:

- transition: Sorts the available tours based on the specified criteria.
- output: Returns an array of tours sorted by the given criteria.

# 15 MIS of Tour Management Module

#### 15.1 Module

Tour Management Module

#### 15.2 Uses

Realm Interface Module, Server Database Manager Module

# 15.3 Syntax

## 15.3.1 Exported Constants

• MAX\_TOUR\_POINTS: The maximum number of waypoints allowed in a single tour.

# 15.3.2 Exported Access Programs

Name	In	Out	Exceptions
CreateTour	Tour Object	Bool - Success or Fail	InvalidTourDataException
UpdateTour	Tour ID, Updated	Bool - Success or Fail	InvalidTourIDException
	Tour Data		
DeleteTour	Tour ID	Bool - Success or Fail	InvalidTourIDException

# 15.4 Semantics

#### 15.4.1 State Variables

• ManagedTours: Stores a list of tours created and managed by the organization.

#### 15.4.2 Environment Variables

Database connection to manage tour data.

#### 15.4.3 Assumptions

It is assumed that the database is functional and contains valid tour data.

#### 15.4.4 Access Routine Semantics

#### CreateTour:

• transition: Adds a new tour to the database.

- output: Returns success if the tour is created successfully.
- exception: Throws InvalidTourDataException if the tour data is invalid.

# **UpdateTour**:

- transition: Updates the details of an existing tour in the database.
- output: Returns success if the tour is updated successfully.
- exception: Throws InvalidTourIDException if the Tour ID does not exist.

## DeleteTour:

- transition: Removes a tour from the database.
- output: Returns success if the tour is deleted successfully.
- exception: Throws InvalidTourIDException if the Tour ID does not exist.

# 16 MIS of Maps

### 16.1 Module

Maps

### 16.2 Uses

Local Database Manager, Maps API (external)

### 16.3 Syntax

### 16.3.1 Exported Constants

N/A

### 16.3.2 Exported Access Programs

Name	In	Out	Exceptions
getMapData	N	MapData	LocationNotFound
addMarker	N, Location, De-	-	-
	tails		
removeMarker	N, Location	-	MarkerNotFound
updateMarker	N, Location, De-	_	MarkerNotFound
	tails		
displayMap	$\mathbb{N}$	${\bf RenderedMap}$	LocationNotFound

### 16.4 Semantics

#### 16.4.1 State Variables

- markers: A collection of markers, where each marker includes its *Location* and associated *Details*.
- mapViews: A mapping from  $\mathbb{N}$  (view IDs) to rendered map states.

### 16.4.2 Environment Variables

- Access to the Google Maps API.
- Access to the local database for location details.

### 16.4.3 Assumptions

The Google Maps API and the local database are available and functioning properly.

getMapData(viewID):

- transition: N/A
- **output**: Returns MapData for the viewID, including all markers and details for the associated location.
- exception:  $viewID \notin mapViews$

addMarker(viewID, location, details):

- transition: If  $viewID \in mapViews$ , adds a marker to the map at *location* with the given details.
- output: N/A
- exception: None

removeMarker(viewID, location):

- transition: If  $location \in markers[viewID]$ , removes the marker at location from the map.
- output: N/A
- exception:  $location \notin markers[viewID]$

updateMarker(viewID, location, details):

- transition: If  $location \in markers[viewID]$ , updates the marker at location with new details.
- output: N/A
- exception:  $location \notin markers[viewID]$

displayMap(viewID):

- transition: Renders the map for the *viewID*, including all markers and relevant details.
- output: Returns RenderedMap, which is a visual representation of the map.
- exception:  $viewID \notin mapViews$

- fetchLocationDetails(Location): Communicates with the local database to retrieve detailed information for a given location.
- renderMap(viewID): Generates a visual representation of the map for the given *viewID* using the Google Maps API.

# 17 MIS of Object Interaction Module

### 17.1 Module

ObjectInteraction

### 17.2 Uses

Local Database Manager

### 17.3 Syntax

### 17.3.1 Exported Constants

N/A

### 17.3.2 Exported Access Programs

Name	In	Out	Exceptions
reportObject	N, Reason, Details	-	ObjectNotFound
reactToObject	$\mathbb{N}$ , Reaction	-	ObjectNotFound
fetchReactions	$\mathbb{N}$	Array (Reaction)	ObjectNotFound
fetchReports	N	Array(Report)	ObjectNotFound
resolve Report	N, ResolutionDetails	-	ReportNotFound

### 17.4 Semantics

### 17.4.1 State Variables

- objects: A collection of AR objects, each identified by a unique  $\mathbb{N}$ .
- reports: A collection of reports associated with AR objects, including Reason and Details.
- reactions: A collection of user reactions, associated with specific AR objects.

### 17.4.2 Environment Variables

- AR objects are rendered and interactable in the environment.
- The system must have a connection to the local database for storing reports and reactions.

#### 17.4.3 Assumptions

All AR objects are assigned unique identifiers and are interactable within the system. Users have access to a predefined set of reaction types (e.g., Like, Dislike).

reportObject(objectID, reason, details):

- transition: Adds a new report to reports for the object identified by object ID, with the specified reason and details.
- output: N/A
- exception:  $objectID \notin objects$

reactToObject(objectID, reaction):

- **transition**: Adds a reaction (e.g., Like, Dislike) to reactions for the object identified by object ID.
- output: N/A
- exception:  $objectID \notin objects$

fetchReactions(objectID):

- transition: N/A
- output: Returns all reactions associated with objectID.
- exception:  $objectID \notin objects$

fetchReports(objectID):

- transition: N/A
- output: Returns all reports associated with objectID.
- exception:  $objectID \notin objects$

resolveReport(reportID, resolutionDetails):

- transition: Marks the report identified by report ID as resolved and stores the resolution Details.
- output: N/A
- exception:  $reportID \notin reports$

- validateObject(objectID): Ensures objectID corresponds to a valid AR object in the system.
- notifyUser(reportID): Sends a notification to the user who submitted the report, indicating its resolution status.

# 18 MIS of Local Database Manager

### **18.1** Module

LocalDBM

### 18.2 Uses

Server Database Manager

### 18.3 Syntax

### 18.3.1 Exported Constants

N/A

### 18.3.2 Exported Access Programs

Name	In	Out	Exceptions
fetchData	Query	Data	DataNotFound
saveData	Key, Data	=	-
updateData	Key, Data	-	DataNotFound
deleteData	Key	-	DataNotFound
syncWithServer	-	-	ServerError
getCachedData	Key	Data	DataNotCached

### 18.4 Semantics

#### 18.4.1 State Variables

- *localCache*: A local in-memory or on-disk cache, keyed by unique *Key*, storing frequently accessed data.
- lastSyncTime: A timestamp of the last successful synchronization with the server database.

### 18.4.2 Environment Variables

- Access to the server database for retrieving and storing persistent data.
- A local caching mechanism (e.g., in-memory cache or local storage).

### 18.4.3 Assumptions

The server database is available and operational for syncing, and the local caching system has sufficient storage capacity.

fetchData(query):

- transition: N/A
- **output**: Executes *query* on the local cache or the server database if the data is not cached, and returns the *Data*.
- exception: Returns DataNotFound if the query does not match any records.

saveData(key, data):

- **transition**: Stores *data* in the *localCache* with the associated *key*. Also updates the server database asynchronously.
- output: N/A
- exception: None

updateData(key, data):

- **transition**: Updates *data* in *localCache* and synchronizes the change to the server database.
- output: N/A
- exception:  $key \notin localCache$

deleteData(key):

- transition: Removes data identified by key from localCache and the server database.
- output: N/A
- exception:  $key \notin localCache$

syncWithServer():

- **transition**: Synchronizes the *localCache* with the server database, updating any stale or missing records.
- output: N/A
- **exception**: ServerError if the server database is unavailable or the synchronization fails.

getCachedData(key):

- transition: N/A
- output: Returns data from localCache associated with key.
- exception:  $key \notin localCache$

- isCacheStale(key): Determines whether the cached data for *key* is outdated compared to the server database.
- resolveConflict(localData, serverData): Resolves discrepancies between *localCache* and server database data.

# 19 MIS of Data Sync Module

The Data Sync Module updates the common data on both the local and server databases based on whichever has the most up-to-date information. This will mostly just apply to locally stored AR Objects.

### 19.1 Module

DataSyncModule

### 19.2 Uses

Server Database Manager Module Local Database Manager Module

### 19.3 Syntax

### 19.3.1 Exported Constants

N/A

### 19.3.2 Exported Access Programs

Name	In	Out	Exceptions
Sync	-	-	SyncFailureException

### 19.4 Semantics

#### 19.4.1 State Variables

syncInProgress: B

#### 19.4.2 Environment Variables

N/A

### 19.4.3 Assumptions

N/A

### 19.4.4 Access Routine Semantics

Sync():

• transition: local\_obj.lastModified < server\_obj.lastModified == True \Rightarrow LocalDatabase-Manager.update(local\_obj, server\_obj)

 $\bullet$ exception: (Local DatabaseManager == null <br/>  $\vee$ ServerDatabaseManager == null)  $\Rightarrow$ SyncFailureException

### 19.4.5 Local Functions

N/A

# 20 MIS of Server Database Manager

### 20.1 Module

ServerDBM

### 20.2 Uses

Local Database Manager

### 20.3 Syntax

### 20.3.1 Exported Constants

N/A

### 20.3.2 Exported Access Programs

Name	In	Out	Exceptions
fetchData	Query	Data	DataNotFound,
			NetworkError
saveData	Key, Data	-	NetworkError
updateData	Key, Data	-	DataNotFound,
			NetworkError
deleteData	Key	-	DataNotFound,
			NetworkError
${\rm syncWithLocal}$	DataDiff	-	NetworkError

### 20.4 Semantics

#### 20.4.1 State Variables

- database: The server database that stores all permanent data associated with the app.
- lastSyncTime: A timestamp indicating the last synchronization with the local database.

### 20.4.2 Environment Variables

• Network connectivity must be available for communication between the server database and local database manager.

### 20.4.3 Assumptions

The server database is accessible, operational, and synchronized with the local database manager periodically.

### fetchData(query):

- transition: N/A
- output: Executes query on the server database and returns the corresponding Data.
- exception:
  - DataNotFound: If query does not match any records in the database.
  - NetworkError: If the network connection fails.

### saveData(key, data):

- transition: Adds data to the server database with the associated key.
- output: N/A
- exception:
  - NetworkError: If the network connection fails.

### updateData(key, data):

- transition: Updates data in the server database associated with key.
- output: N/A
- exception:
  - DataNotFound: If key does not exist in the database.
  - NetworkError: If the network connection fails.

### deleteData(key):

- transition: Removes the record associated with key from the server database.
- output: N/A
- exception:
  - DataNotFound: If key does not exist in the database.
  - NetworkError: If the network connection fails.

### syncWithLocal(dataDiff):

• transition: Synchronizes the database with changes provided in dataDiff from the local database manager.

• output: N/A

• exception:

- NetworkError: If the network connection fails during synchronization.

- $\bullet$  applyDataDiff(dataDiff): Applies the changes from dataDiff to the server database during synchronization.
- logSyncOperation(status): Logs the success or failure of the synchronization operation.

### 21 MIS of REST API Communication Module

### 21.1 Module

RESTAPICommunication

### 21.2 Uses

Server Database Manager, HTTP Client Library (external)

### 21.3 Syntax

### 21.3.1 Exported Constants

N/A

### 21.3.2 Exported Access Programs

Name	In		Out	Exceptions
sendRequest	Endpoint,	Method,	Response	APIError, Net-
	Params			workError
parseResponse	RawResponse	;	ParsedResponse	ResponseParsingError
setHeaders	Headers		-	-
handleAuthentication	AuthToken		-	AuthError
${\it checkServerStatus}$	=		ServerStatus	APIError, Net-
				workError

### 21.4 Semantics

#### 21.4.1 State Variables

- baseURL: The base URL for the REST API server.
- headers: Key-value pairs for HTTP headers, including authentication tokens and content type.

### 21.4.2 Environment Variables

• Network connectivity for sending HTTP requests to the REST API server.

### 21.4.3 Assumptions

The REST API server follows standard HTTP and REST conventions, and the API endpoints are well-documented and accessible.

sendRequest(endpoint, method, params):

- transition: Sends an HTTP request to the API server at baseURL + endpoint using the specified HTTP method (e.g., GET, POST, PUT, DELETE) and params as query parameters or request body.
- output: Returns the *Response* received from the API server.
- exception:
  - APIError: If the server responds with an error status code (e.g., 4xx or 5xx).
  - NetworkError: If the request fails due to network issues.

parseResponse(rawResponse):

- transition: N/A
- **output**: Converts rawResponse (raw HTTP response) into a structured ParsedResponse (e.g., JSON or XML object).
- exception:
  - Response Parsing Error: If the raw Response cannot be parsed due to invalid format.

setHeaders(headers):

- transition: Updates the *headers* used for subsequent HTTP requests.
- output: N/A
- exception: None

handleAuthentication(authToken):

- transition: Sets the authentication token in the *headers* for authorized requests.
- output: N/A
- exception:
  - AuthError: If the authToken is invalid or rejected by the server.

checkServerStatus():

• transition: N/A

• **output**: Returns the *ServerStatus* indicating whether the API server is reachable and operational.

### • exception:

- APIError: If the server responds with an error status code.
- NetworkError: If the request fails due to network issues.

- buildURL(endpoint, params): Constructs the complete URL for the API request by appending *endpoint* to *baseURL* and encoding *params* as query parameters.
- logRequest(requestDetails): Logs details of the outgoing API request for debugging purposes.
- retryRequest(requestDetails): Attempts to resend a failed request based on the retry policy.

# 22 MIS of Object Importer Module

### 22.1 Module

ObjectImporter

### 22.2 Uses

Local Database Manager

### 22.3 Syntax

### 22.3.1 Exported Constants

N/A

### 22.3.2 Exported Access Programs

Name	In	Out	Exceptions
importObject	FilePath	ObjectID	InvalidFileFormat,
			ImportError
validateObject	FilePath	Boolean	Invalid File Format
addObjectToInventory	ObjectID	-	ObjectAlreadyExists
listSupportedFormats	-	$Array\langle String \rangle$	-

### 22.4 Semantics

### 22.4.1 State Variables

- supportedFormats: A list of file formats (e.g., OBJ, FBX, GLTF) that the module can process.
- importedObjects: A mapping of ObjectID  $\rightarrow$  ObjectMetadata, representing all objects imported by the user.

### 22.4.2 Environment Variables

- File system access for reading 3D model files.
- Network connectivity for syncing imported objects with the server database.

### 22.4.3 Assumptions

The file paths provided are accessible, and the objects being imported are in formats supported by the module.

importObject(filePath):

- transition: Reads the 3D model file from *filePath*, parses it using the 3D Model Parser Library, and generates an *ObjectID*. The object is then stored locally and synced with the server database.
- output: Returns the ObjectID of the successfully imported object.
- exception:
  - InvalidFileFormat: If the file format is not supported.
  - ImportError: If the file cannot be read or parsed due to corruption or other issues.

validateObject(filePath):

- transition: N/A
- **output**: Returns true if the file at filePath is in a supported format and passes initial validation, false otherwise.
- exception:
  - InvalidFileFormat: If the file format is not supported.

addObjectToInventory(objectID):

- **transition**: Adds the object identified by *objectID* to the user's inventory and marks it as available for use within the app.
- output: N/A
- exception:
  - ObjectAlreadyExists: If the object is already present in the user's inventory.

listSupportedFormats():

- transition: N/A
- **output**: Returns the list of *supportedFormats*, indicating which file types can be imported.
- exception: None

- parseFile(filePath): Reads and parses the 3D model file to extract metadata and geometry.
- generateObjectID(metadata): Generates a unique identifier for the imported object based on its metadata.
- syncObjectWithServer(objectID): Uploads the imported object's metadata to the server database.

### 23 MIS of Realm Interface Module

### 23.1 Module

RealmInterface

### 23.2 Uses

16, 3D Renderer, AR Framework

### 23.3 Syntax

### 23.3.1 Exported Constants

N/A

### 23.3.2 Exported Access Programs

Name	In	Out	Exceptions
displayObjectsInRealm	N	-	-
navigate To Map	-	-	-
${\it update Displayed Objects}$	$\mathbb{N}, \operatorname{Array}\langle \mathbb{N} \rangle$	-	-

### 23.4 Semantics

#### 23.4.1 State Variables

• displayedObjects: A list of 3D objects being rendered in the current view.

### 23.4.2 Environment Variables

- 3D rendering engine for displaying AR objects.
- Maps module interface for quick navigation.

### 23.4.3 Assumptions

All objects in the realm are properly loaded.

### 23.4.4 Access Routine Semantics

displayObjectsInRealm():

- transition: Retrieves the 3D objects and displays them in the AR view.
- output: N/A

### navigateToMap():

• transition: Opens the Maps interface to display the map view.

• output: N/A

• exception: None

updateDisplayedObjects(objectIDs):

• transition: Updates the list of objects displayed in the AR view. Removes any previously displayed objects not in *objectIDs*.

• output: N/A

- loadObjects(): Loads 3D object data from the local or server database.
- renderObjects(objectList): Renders the provided list of 3D objects in the AR view.
- clearDisplay(): Removes all objects currently displayed in the AR view.

### 24 MIS of AccessHardware

The AccessHardware module is used to interface with the hardware components of the device. The module will be used to access the camera, GPS, and an array of device sensors on the mobile device.

### 24.1 Module

Short Name: AccHard

### 24.2 Uses

AccHard does not use any other modules.

## 24.3 Syntax

### 24.3.1 Exported Constants

- 1. CAM\_RES\_WIDTH = 1920 (Default width of the camera resolution)
- 2. CAM\_RES\_HEIGHT = 1080 (Default height of the camera resolution)

### 24.3.2 Exported Access Programs

Name	In	Out	Exceptions
getResH()	None	Resolution height: N	None
getResW()	None	Resolution width : $\mathbb{N}$	None
getFrameRate()	None	Frame rate : $\mathbb{N}$	None
getNextFrame()	None	Frame : $\mathbb{Z}[\ ]$	$\overline{\textbf{FrameNotFoundException}}$
getFrame()	$FrameID : \mathbb{N}$	Frame : $\mathbb{Z}[\ ]$	$\overline{\textbf{FrameNotFoundException}}$

### 24.4 Semantics

#### 24.4.1 State Variables

- 1. FRAME\_COUNT :  $\mathbb{N}$  (Number of frames captured by the camera)
- 2. FRAME\_BUFFER :  $\mathbb{Z}[\ ][\ ]$  (Buffer to store frames captured by the camera)
- 3. CAM\_PROG\_SCAN: B (Camera scans progressively if true, else scans using interlaced)
- 4. CAM\_ACC : B (Access to device camera)
- 5.  $GPS\_ACC : \mathbb{B}$  (Access to device GPS)

#### 24.4.2 Environment Variables

- 1. CAM\_RES\_WIDTH: N (Current width of the camera resolution)
- 2. CAM\_RES\_HEIGHT: N (Current height of the camera resolution)
- 3. FRAME\_RATE : N (Current frame rate of the camera)
- 4. CAM\_ON: B (Device camera turned on)

### 24.4.3 Assumptions

• Device provides the ability to access the camera and GPS through device applications

#### 24.4.4 Access Routine Semantics

getResH():

- transition: No transition
- output: Returns the camera resolution height
- exception: No exceptions

getResW():

- transition: No transition
- output: Returns the camera resolution width
- exception: No exceptions

getFrameRate():

- transition: No transition
- output: Returns the camera frame rate
- exception: No exceptions

getNextFrame():

- transition: No transition
- output: Returns the next frame as a buffer.
- exception: Raises **FrameNotFoundException** if the next frame cannot be returned. getFrame(FrameID):
  - transition: No transition
  - output: Returns the frame matching the given FrameID.
  - exception: Raises **FrameNotFoundException** if the specified frame cannot be found.

#### 24.4.5 Local Functions

1. ReqCamAccess(): None  $\rightarrow \mathbb{B}$ 

# 25 MIS of Inventory

The Inventory module is used to manage the user's inventory of 3D and 2D AR objects. The module will be used to add, remove, and view objects in the user's inventory. The module will also be used to access the user's inventory while placing objects in the AR environment.

### 25.1 Module

Short Name: Inventory

### 25.2 Uses

- RESTAPICommunication
- Object Render Module
- LocalDBM
- DataSyncModule

### 25.3 Syntax

### 25.3.1 Exported Constants

- 1. MAX\_OBJ\_COUNT = 100 (Maximum number of objects that can be stored in the user's inventory (except for application-provided objects))
- 2. FILTER\_OPTS = {Favorites, Oldest, Newest, Most Shared, Least Shared, Largest Size, Smallest Size} (Fixed list of filter options that can be applied to the user's inventory)

### 25.3.2 Exported Access Programs

Name	In	Out	Exceptions
getObjCount	None	N	None
addObj	Object : $\mathbb{AR}$	$\mathbb B$	${f ObjAddException}$
getObj	ObjectID : N	$\mathbb{AR}$	${\bf ObjNotFoundException}$
delObj	ObjectID : N	$\mathbb{B}$	${f ObjDelException}$
getObjList	ObjectIDs : N[]	Object List : $\mathbb{AR}[\ ]$	${\bf ObjNotFoundException}$
setBackColor	Color code : $\mathbb{N}[3]$	None	None

### 25.4 Semantics

### 25.4.1 State Variables

- 1. OBJ\_SYNCED: B (true if objects that are synced with the server, else false)
- 2. TOTAL\_OBJ\_COUNT: N (Total number of objects in the user's inventory)
- 3. 3D\_OBJECT\_COUNT : N (Number of 3D objects in the user's inventory)
- 4. 2D\_OBJECT\_COUNT : N (Number of 2D objects in the user's inventory)
- 5. BACKGROUND\_COLOR: str (Color code of the background of the inventory)

### 25.4.2 Environment Variables

No environment variables for this module.

### 25.4.3 Assumptions

No assumptions are made for this module.

#### 25.4.4 Access Routine Semantics

getObjCount():

- transition: No transition
- output: Returns the number of objects in the user's inventory.
- exception: No exceptions

addObj(Object : AR):

- transition: Adds the specified AR object to the user's inventory.
- output: Returns a boolean indicating whether the object was successfully added (true for success, false otherwise).
- exception: Raises **ObjAddException** if the object cannot be added.

 $getObj(ObjectID: \mathbb{N}):$ 

- transition: No transition
- output: Returns the AR object corresponding to the given ObjectID.
- exception: Raises **ObjNotFoundException** if the specified object cannot be found in the inventory.

 $delObj(ObjectID: \mathbb{N}):$ 

- transition: Removes the AR object corresponding to the given ObjectID from the user's inventory.
- output: Returns a boolean indicating whether the object was successfully removed (true for success, false otherwise).
- exception: Raises **ObjDelException** if the object cannot be deleted.

 $getObjList(ObjectIDs: \mathbb{N}[\ ]):$ 

- transition: No transition
- output: Returns a list of AR objects (AR[]) corresponding to the specified ObjectIDs
- exception: Raises **ObjNotFoundException** if any of the specified objects cannot be found in the inventory.

 $setBackColor(ColorCode: \mathbb{N}[3]):$ 

- transition: Updates the background color setting for the inventory view using the specified RGB color code ( $\mathbb{N}[3]$ ).
- output: None
- exception: None

#### 25.4.5 Local Functions

- 1. filterObj(): (Filter option : str, Objects :  $\mathbb{AR}[\ ]) \to \mathbb{AR}[\ ]$
- 2. syncObjs(): None  $\rightarrow \mathbb{B}$

## 26 MIS of ObjectPlacement

The Object Placement module is used to place 3D and 2D AR objects in the AR environment. The module will be used in the Realm interface to begin the object placement workflow. It will place objects from the user's inventory.

### **26.1** Module

Short Name: ObjPlacer

### 26.2 Uses

- RESTAPICommunication
- Object Render Module
- Inventory

## 26.3 Syntax

### 26.3.1 Exported Constants

There are no constants for this module.

### 26.3.2 Exported Access Programs

Name	In	Out	Exceptions
beginPlacement	None	$\mathbb{B}$	${\bf Placement Fail Exception}$
displayEditor	None	$\mathbb{B}$	None
hideEditor	None	$\mathbb{B}$	None
termPlacement	None	$\mathbb{B}$	PlacementFailException
endPlacement	None	$\mathbb{B}$	PlacementFailException
rotateObj	(Angle : $\mathbb{Z}$ , Axis :	Angle rotated : $\mathbb{Z}$	None
	char)		
translateObj	(Distance : $\mathbb{Z}$ , Axis :	Dist Translated : $\mathbb{Z}$	None
	char)		
placeObj	$ObjectID : \mathbb{N}$	$\mathbb{B}$	ObjPlaceException

### 26.4 Semantics

### 26.4.1 State Variables

- 1. PLACEMENT\_STATUS :  $\mathbb{B}$  (true if object placement is in progress, else false)
- 2. OBJ\_PLACED: B (true if object is placed in the AR environment, else false)
- 3.  $OBJ_ID : \mathbb{N}$  (ID of the object being placed)
- 4. OBJ\_POS :  $\mathbb{Z}[3]$  (XYZ position of the object in the AR environment)

### 26.4.2 Environment Variables

1. DEVICE\_LOCATION :  $\mathbb{Z}[3]$  (Current location of the device)

### 26.4.3 Assumptions

- The user is not located in a restricted area.
- The user has objects in their inventory.
- The weather is not hazardous.
- The user surroundings is large enough for the object to be placed.

#### 26.4.4 Access Routine Semantics

beginPlacement():

- transition: Initiates the object placement workflow in the AR environment.
- output: Returns a boolean indicating whether the workflow started successfully (true for success, false otherwise).
- exception: Raises **PlacementFailException** if the workflow cannot be initiated.

displayEditor():

- transition: Displays the object placement editor in the AR environment.
- output: Returns a boolean indicating whether the editor was displayed successfully (true for success, false otherwise).
- exception: No exceptions

hideEditor():

- transition: Hides the object placement editor from the AR environment.
- output: Returns a boolean indicating whether the editor was hidden successfully (true for success, false otherwise).
- exception: No exceptions

termPlacement():

- transition: Terminates the object placement workflow in the AR environment without finalizing the placement.
- output: Returns a boolean indicating whether the workflow was terminated successfully (true for success, false otherwise).
- exception: Raises **PlacementFailException** if the workflow cannot be terminated.

endPlacement():

- transition: Ends the object placement workflow, finalizing the placement in the AR environment.
- output: Returns a boolean indicating whether the workflow ended successfully (true for success, false otherwise).
- exception: Raises PlacementFailException if the workflow cannot be ended.

rotateObj(Angle:  $\mathbb{Z}$ , Axis: char):

- transition: Rotates the object in the AR environment by the specified angle (Angle) around the specified axis (Axis).
- output: Returns the total angle the object was rotated.
- exception: No exceptions

 $translateObj(Distance: \mathbb{Z}, Axis: char):$ 

- transition: Translates the object in the AR environment by the specified distance (Distance) along the specified axis (Axis).
- output: Returns the total distance the object is translated by.
- exception: No exceptions

placeObj(ObjectID: ℕ):

- transition: Places the specified object (identified by ObjectID) from the user's inventory into the AR environment.
- output: Returns a boolean indicating whether the object was placed successfully (true for success, false otherwise).
- exception: Raises **ObjPlaceException** if the object cannot be placed.

- 1.  $getObj(): None \rightarrow \mathbb{AR}$
- 2. checkRestrictArea(): None  $\rightarrow \mathbb{B}$
- 3. checkWeatherHaz(): None  $\rightarrow \mathbb{B}$
- 4. checkObjCollisions(): None  $\rightarrow \mathbb{B}$
- 5. getCoords(): None  $\to \mathbb{Z}[3]$

# 27 MIS of RestrictedAreaDetect

The Restricted Area Detection module is used to detect if the user is located in a restricted area. The module will be get the user's location and determine if they are present in a pre-defined restricted area.

### **27.1** Module

Short Name: RestrictAreaDet

### 27.2 Uses

- RESTAPICommunication
- Maps

### 27.3 Syntax

### 27.3.1 Exported Constants

The module does not have any constants.

### 27.3.2 Exported Access Programs

Name	In	Out	Exceptions
checkCurrAreaRestrict	None	$\mathbb{B}$	None

### 27.4 Semantics

### 27.4.1 State Variables

There are no state variables for this module.

### 27.4.2 Environment Variables

There are no environment variables for this module.

### 27.4.3 Assumptions

There are no assumptions for this module.

checkCurrAreaRestrict():

• transition: No transition

• output: Return a boolean indicating whether the user is in a restricted area (true if in a restricted area, otherwise false).

• exception: No exceptions

#### 27.4.5 Local Functions

1. getUserLocation(): None  $\to \mathbb{Z}[3]$ 

2. getRestrictedAreas(): None  $\rightarrow \mathbb{Z}[][3]$ 

### 28 MIS of WeatherHazardDetect

The Weather Hazard Detection module is used to detect if the user is in a hazardous weather condition. The module will get the current weather conditions and future warnings based on the user's current location. The module will determine if there is incoming or present hazardous weather conditions based on the information accessed.

### **28.1** Module

Short Name: WeatherHazDet

### 28.2 Uses

• RESTAPICommunication

### 28.3 Syntax

### 28.3.1 Exported Constants

DETECTION\_RADIUS = 30 (Radius in kilometers to detect weather hazards)

### 28.3.2 Exported Access Programs

Name	In	$\mathbf{Out}$	Exceptions
checkWeatherHaz	None	$\operatorname{str}$	-

### 28.4 Semantics

### 28.4.1 State Variables

LAST\_UPDATE :  $\mathbb{N}$  (Number of minutes passed since last time the weather data was updated) CURR\_WEATHER : str (Current weather conditions)

### 28.4.2 Environment Variables

There are no environment variables for this module.

### 28.4.3 Assumptions

There are no assumptions for this module.

#### 28.4.4 Access Routine Semantics

checkWeatherHaz():

• transition: No transition

• output: Returns a string indicating the current weather conditions and any hazardous weather warnings.

• exception: No exceptions

### 28.4.5 Local Functions

1. getUserLocation: None  $\to \mathbb{Z}[3]$ 

2. updateWeather: None  $\rightarrow \mathbb{B}$ 

3. determineHaz: None  $\rightarrow$  str

### References

# Appendix — Reflection

1. What went well while writing this deliverable?

The modules were distributed relatively well according to what each group member seems most comfortable and experienced with.

2. What pain points did you experience during this deliverable, and how did you resolve them?

Deciding the modules initially was a bit of a challenge, but after speaking with our TA, it helped us decide which modules to split and which ones to combine.

3. Which of your design decisions stemmed from speaking to your client(s) or a proxy (e.g. your peers, stakeholders, potential users)? For those that were not, why, and where did they come from?

Our design decisions came as a natural consequence of our requirements, many of which did stem from speaking to clients. So while indirectly influenced, our design decisions were mostly made to be the easiest way to meet the requirements we set out.

4. While creating the design doc, what parts of your other documents (e.g. requirements, hazard analysis, etc), it any, needed to be changed, and why?

We did not need to change any parts of other documents.

5. What are the limitations of your solution? Put another way, given unlimited resources, what could you do to make the project better? (LO\_ProbSolutions)

One of the key components of our design is the client server system for storing user data. If we had infinite resources, it would be beneficial to move more logic to the server to relieve the client from certain expensive computations. The reason our current design has them on the client side is to reduce the complexity of client server communication to simplify the implementation.

6. Give a brief overview of other design solutions you considered. What are the benefits and tradeoffs of those other designs compared with the chosen design? From all the potential options, why did you select the documented design? (LO\_Explores)

In our initial solution, user content generation was meant to be internal, and more components were designed to be on the server. This design would have been ideal for users, and more maintainable in the long run, but came at an exorbiant cost for compute for object generation, and a complex design that would be infeasible to build in the alloted time. The driving force behind our changes since then were to make our app easier to implement, and less expensive to run.