2019 02 06

Example

```
*p = arr[i] + y; // assume p is initialized properly # i \rightarrow \$s0, y \rightarrow \$s1, p \rightarrow \$s2, arr \rightarrow \$s3 add $t3, # t3 \leftarrow 2i add $t3, $t3, $t3 # t3 \leftarrow 4i add $t3, $t3, $t3 # t3 \leftarrow address\ of\ arr[i] lw $t3, 0($t3) # t3 \leftarrow arr[i] add $t3, $t3, $s1 # t3 \leftarrow arr[i] + y sw $t3, 0($s2) # *p \leftarrow arr[i] + y
```

Logical Instructions

```
rd, rt, shamt

sll # shift left Logical
srl # shift right logical

rd, rs, rt

# rd <- rs op rt
and
or
nor
xor

rt, rs, imm
andi
ori
```

imm needs to be converted from 16 bits to 32 bits. It uses 0-extended to do this.

Pseudo instructions

xori

```
not rt, rs # rt <- (rs)'
```

Pseudo instructions are kind of like a "mini-compiler" Don't use yet, may cause problems in the hardware side of things down the line.

Computers have 3 types of shifts: logical, arithmetic, and rotate.

Logical Shift L left <- o's, shift directly left

Arithmetic Shift L. same as logical shift, but does a special case for the sign bit rotate shift left, moves all bits left moving the leftmost to the right (for the counter-clockwise leftward rotation)

Example: split \$s0 into 4 bytes assume \$s0 is 16 bits \$s1 is Most Significant Byte. \$s4 is Least Significant Byte

```
# bytes stored is $s1, $s2, $s3, $s4

add $t0, $s0, $zero # t0 <- s0
andi $s4, $t0, 255 # s4 <- LSB of s0, 255 = 0x00FF (line 2)

srl $t0, $t0, 8 # t0 <- s0 >> 8
andi $s3, $t0, 255 # s3 <- 2nd LSB of s0
srl $t0, $t0, 8 # t0 <- s0 >> 16
andi $s2, $t0, 255 # s2 <- 2nd MSB of s0
srl $t0, $t0, 8 # t0 <- s0 >> 24
andi $s1, $t0, 255 # s1 <- MSB of s0

Line 2 explanation: Zero out all but the last 8 bits by anding

1100 1011 0010 1010 0011 0111 1110 1010 = $s0
& 0000 0000 0000 0000 0000 0000 1110 1010 -> $s4
```

0x00FF is operating as a bit mask. It zeros out all but the last 8 bits. What if we want to

Relevant identities for bit manipulation

Assume x is a bit.

```
x & 0 = 0
x & 1 = x
x | 1 = 1
x | 0 = x
x xor 0 = x
x xor 1 = ~x
```

```
x \wedge 0 = 0x \wedge 1 = xx \vee 1 = 1x \oplus 0 = xx \oplus 1 = \bar{x}
```

Ex: We want to do the following some bit manipulation. We can do this using the logical operations ori, andi, and xori. In this case, the i at the end of the command is short for integer. We're using the binary representations of the numbers as the underlying mechanism for the result.

- 1. set bits 3 & 8 of \$s5 (correspond to 0...0001 0000 1000)
- 2. clear bits 2 & 11 of \$s5
- 3. flip bits 0, 1, 7 of \$s5
- 4. don't care for bits 31..16

```
ori $s5, $s5, 0x0108 # set bits 3, 8 of s5
andi $s5, s5, 0xF7FB # clear bits 2, 4 of s5
xori $s5, $s5, 0x0083 # flip bits 0, 1, 7 of $s5
```

Use xor to flip bits. Or with 1 to set bit to 1.