HTMLDOC 1.9 Software Users Manual ESP-003-2009????

Easy Software Products
Copyright 1997-2009 Easy Software Products. All rights reserved.

<u>Introduction</u>	1
<u>History</u>	1
Organization of This Manual.	1
Support	2
Encryption Support.	2
Copyright, Trademark, and License Information	2
<u>Chapter 1 - Installing HTMLDOC</u>	
<u>Requirements</u>	
Installing HTMLDOC	
Installing HTMLDOC on Microsoft Windows	
Installing HTMLDOC on MacOS X.	
Installing HTMLDOC on Linux	
Installing HTMLDOC on Solaris	
<u>Licensing HTMLDOC</u>	
<u>Uninstalling HTMLDOC</u>	
<u>Uninstalling HTMLDOC on Microsoft Windows</u>	
Uninstalling HTMLDOC on MacOS X	
Uninstalling HTMLDOC on Linux.	
Uninstalling HTMLDOC on Solaris	1-4
Chapter 2 - Getting Started	
Starting HTMLDOC.	
Choosing a HTML File	
Setting the Output File	
Generating the Document	2-2
Chapter 3 - Generating Books	2 1
Overview.	
Choosing HTML Files.	
Selecting a Title File.	
Setting the Output Format.	
Setting the Output Format. Setting the Output File	
Generating the Document	
Saving Your Book	
Saving Your Book	3-2
Chapter 4 - HTMLDOC from the Command-Line	4.1
Getting to the Command-Line on Windows	
The Basics of Command-Line Access	
What Are All These Commands?	
Converting Multiple HTML Files.	
Generating Books.	
What are all these commands?	
Setting the Title File.	
Putting It All Together.	
rutung it An Together	4-3
Chapter 5 - Using HTMLDOC on a Web Server	5-1
The Basics.	
Using HTMLDOC as a CGI Program.	
Server-Side Preferences	

Chapter 5 - Using HTMLDOC on a Web Server	
Configuring HTMLDOC with Apache	5-2
Configuring HTMLDOC with Microsoft IIS	5-2
Additional Configuration for IIS 6.0	5-7
Using HTMLDOC From Server-Side Scripts and Programs	5-8
Calling HTMLDOC from a Shell Script	5-9
Calling HTMLDOC from Perl	5-10
Calling HTMLDOC from PHP	5-10
Calling HTMLDOC from C	5-12
Calling HTMLDOC from Java	5-13
Chapter 6 - HTML Reference	6-1
General Usage.	
Elements	6-1
Comments	
Header/Footer Strings.	
FONT Attributes	
Headings	
Numbered Headings.	6-8
Images.	
Links.	
META Attributes	
Page Breaks.	
Tables.	
Chapter 7 - GUI Reference.	7- 1
The HTMLDOC GUL	
Document File Operations	
<u>New</u>	7-1
<u>Open</u>	
<u>Save</u>	
Save As	
Generate	
<u>Close</u>	
The Input Tab	
Document Type.	
Input Files	
Add Files	7-2
Edit Files	7-2
Delete Files	7-2
Move Up	7-2
Move Down	7-3
Logo Image	7-3
Title File/Image.	7-3
The Output Tab.	
Output To	
Output Path	
Output Format	7-3
Output Options	7-3
Compression	7-4

oter 7 - GU	JI Reference	
	JPEG Quality.	7
The Pag	ge Tab.	
	Page Size	
	2-Sided.	
	<u>Landscape</u> .	
	Top, Left, Right, and Bottom.	
	Header and Footer.	
The TC	C Tab.	7-0
	Table of Contents.	
	Numbered Headings	
	Header and Footer.	
	<u>Title</u>	7-7
The Co	lors Tab	
	Body Color.	
	Body Image.	
	Text Color.	
	Link Color	
	Link Style.	
The For	nts Tab.	
1110 1 0	Base Font Size	
	Line Spacing	
	Body Typeface	
	Heading Typeface.	
	Header/Footer Size.	
	Header/Footer Font.	
	Character Set.	
	Options.	
The PS	Tab.	
1110 1 15	PostScript Level	
	Send Printer Commands.	
	Include Xerox Job Comments.	
The PD	F Tab.	
THETE	PDF Version.	
	Page Mode	
	Page Layout.	
	First Page	
	Page Effect.	
	Page Duration.	
	Effect Duration.	
The Sec	curity Tab.	
The Sec	Encryption.	
	Permissions Permissions	
	Owner Password	
	Options. User Password	
Th. O	<u>User Password</u>	
<u>rne Op</u>	tions Tab.	
	HTML Editor	
	Browser Width	
	Search Path.	/-1 .

<u>Chapter 7 - GUI Reference</u>	
Proxy URL	7-11
<u>Tooltips</u>	7-12
Modern Look	7-12
Strict HTML	7-12
Save Options and Defaults	7-12
The File Chooser.	7-12
<u>Show</u>	7-12
Favorites.	7-12
File List.	
Filename	
<u>Dialog Buttons</u>	7-13
Chapter 8 - Command-Line Reference	
Basic Usage.	
Options	8-1
<u>-d directory</u>	8-1
<u>-f filename</u>	8-1
<u>-t format</u>	8-1
<u>-V</u>	8-2
batch filename.book	
bodycolor color	8-2
bodyfont typeface	
bodyimage filename	
<u>book</u>	
bottom margin	
browserwidth pixels	
charset charset	
color	
compression[=level]	
continuous	
cookies 'name=\"value with space\"; name=value'	
datadir directory.	
-duplex	
effectduration seconds.	
embedfonts	
encryption.	
firstpage page	
fontsize size	
fontspacing spacing.	
footer lcr.	
<u>100ter fct</u>	
<u>gray</u>	
header lcr	
headfootfont font	
headfootsize size.	
headingfont typeface	
<u>help</u>	
helpdir directory.	
jpeg[=quality]	8-10

Chapter 8	<u>8 -</u>	Command-Line	Reference
-----------	------------	--------------	-----------

1 1	0.10
-landscape	
left margin	
linkcolor color	
links	
linkstyle style	
-logoimage filename	
-no-compression	
-no-duplex	
-no-embedfonts	
-no-encryption	
<u>no-jpeg</u>	
-no-links	
-no-localfiles	
-no-numbered	
-no-pscommands	
-no-strict	
-no-title	
-no-toc	
-no-xrxcomments.	
<u>-numbered</u> .	
-nup pages.	
-outdir directory	
outfile filename.	
-owner-password password	
-pageduration seconds.	
-pageeffect effect	
pagelayout layout	8-15
pagemode mode	8-15
path_dir1;dir2;dir3;;dirN	
-permissions permission[,permission,].	
<u>portrait</u>	
pscommands	8-16
<u>quiet</u>	8-17
<u>referer url</u>	8-17
right margin	8-17
size size	8-17
<u>strict</u>	8-17
-textcolor color	8-17
textfont typeface	8-18
<u>title</u>	8-18
titlefile filename	8-18
titleimage filename.	8-18
tocfooter lcr	8-18
tocheader lcr	8-18
toclevels levels	
toctitle string.	
top margin	
-user-password password.	
verbose	8-19

Chapt	er 8 - Command-Line Reference	
	version	8-19
	webpage	8-19
	xrxcomments	8-19
	Environment Variables	8-20
	HTMLDOC DATA	8-20
	HTMLDOC DEBUG	8-20
	HTMLDOC HELP	8-20
	HTMLDOC NOCGI	8-20
	<u>Messages</u>	8-2
	BYTES: Message.	8-2
	DEBUG: Messages	8-2
	ERRnnn: Messages.	8-2
	INFO: Messages.	8-2
	PAGES: Message.	8-2
	REMOTEBYTES: Message	8-22
	TIMING: Message.	8-22
Appen	dix A - License Agreement	A -1
	<u>Introduction</u> .	A-
	Source Code and the GNU GPL.	A-
	<u>Trademarks</u>	A-
	Binary Distribution Rights.	A-
	Binaries and Support.	A-
	End-User License Agreement	A-2
	TERMS AND CONDITIONS OF SOFTWARE LICENSE	A-2
	LIMITED WARRANTY AND DISCLAIMER OF WARRANTY; LIMITATION OF	
	<u>LIABILITY</u>	A-í
Appen	dix B - Book File Format	B-1
	<u>Introduction</u>	B-
	The Header	B-
	The Options	B-
	<u>The Files</u>	B-
	Putting It All Together.	B-2
Appen	dix C - Release Notes	C-1
	Changes in HTMLDOC v1.9b1.	C-
Appen	dix D - Compiling HTMLDOC from Source	1-1
	<u>Requirements</u>	1-
	Compiling under UNIX/Linux	
	Compiling on Windows Using Visual C++.	1-2
	<u>Installing with Visual C++</u>	1-2
Index.		1-1
	<u></u>	1-
	<u>A</u>	1-
	<u>B</u>	1-1
	C	1 '

Table of Contents

Index

<u>E</u>	1-
<u> </u>	1-
<u> </u>	1-1
<u>I</u>	
<u>O</u>	
<u>P</u>	
<u>S</u>	
<u>W</u>	1-0
<u></u>	

Introduction

This document describes how to use the HTMLDOC software, version 1.9. HTMLDOC converts Hyper-Text Markup Language ("HTML") input files into indexed HTML, Adobe® PostScript®, or Adobe Portable Document Format ("PDF") files.

HTMLDOC supports most HTML 4.01 elements, CSS1 and some CSS2 stylesheet properties, and can generate title, table of contents, and index pages.

HTMLDOC can be used as a standalone application, in a batch document processing environment, or as a web-based report generation application.

No restrictions are placed upon the output produced by HTMLDOC.

HTMLDOC is available both as open source software under the terms of the GNU General Public License version 2 and as commercial software under the terms of a traditional commercial End-User License Agreement.

History

Like many programs HTMLDOC was developed in response to a need our company had for generating high-quality documentation in printed and electronic forms. For a while we used FrameMaker® and a package from Sgi that generated "compiled" Standard Generalized Markup Language ("SGML") files that could be used by the Electronic Book Technologies ("EBT") documentation products; EBT was bought by INSO who was bought by StellentTM who apparently has dropped the whole product line. When Sgi stopped supporting these tools we turned to INSO, but the cost of their tools is prohibitive to small businesses.

In the end we decided to write our own program to generate our documentation. HTML seemed to be the source format of choice since WYSIWYG HTML editors are widely (and freely) available and at worst you can use a plain text editor. We needed HTML output for documentation on our web server, PDF for customers to read and/or print from their computers, and PostScript for our own printing needs.

The result of our efforts is the HTMLDOC software which is available for Linux®/UNIX®, MacOS® X, and Microsoft® Windows®. Among other things, this software users manual is produced using HTMLDOC.

Organization of This Manual

This manual is organized into tutorial and reference chapters and appendices:

- · Chapter 1 Installing HTMLDOC
- · Chapter 2 Getting Started
- · Chapter 3 Generating Books
- · Chapter 4 HTMLDOC from the Command-Line
- · Chapter 5 HTMLDOC from a Web Server
- · Chapter 6 HTML Reference
- · Chapter 7 GUI Reference
- · Chapter 8 Command-Line Reference
- · Appendix A GNU General Public License
- Appendix B Book File Format
- Appendix C Release Notes

Introduction 1

Appendix D - Compiling HTMLDOC from Source

Support

Limited commercial support is available from Easy Software Products when purchasing the commercial version of HTMLDOC. More information is available at the HTMLDOC web page at the following URL:

http://www.easysw.com/htmldoc/

Encryption Support

HTMLDOC includes code to encrypt PDF document files using the RC4 algorithm with up to a 128-bit key. While this software and code may be freely used and exported under current US laws, other countries may restrict your use and possession of this code and software.

Copyright, Trademark, and License Information

The Adobe Portable Document Format is Copyright 1985-2004 by Adobe Systems Incorporated. Adobe, FrameMaker, and PostScript are registered trademarks of Adobe Systems, Incorporated.

The Graphics Interchange Format is the copyright and GIFSM is the service mark property of CompuServe Incorporated.

Intel is a registered trademark of Intel Corporation.

IRIX and Sgi are registered trademarks of Silicon Graphics, Inc.

Linux is a registered trademark of Linus Torvalds.

MacOS is a registered trademark of Apple Computer, Inc.

Microsoft and Windows are registered trademarks of Microsoft Corporation.

Red Hat and RPM are registered trademarks of Red Hat, Inc.

Solaris is a registered trademark of Sun Microsystems, Inc.

SPARC is a registered trademark of SPARC International, Inc.

UNIX is a registered trademark of the X/Open Company, Ltd.

HTMLDOC is the trademark property of Easy Software Products.

HTMLDOC is copyright 1997-2006 by Easy Software Products. See <u>Appendix A - License Agreement</u> for the terms of use.

This software is based in part on the work of the Independent JPEG Group.

Chapter 1 - Installing HTMLDOC

This chapter describes the steps needed to install the commercial version of HTMLDOC on your system. If you are installing HTMLDOC from source code, please see <u>Appendix D, Compiling HTMLDOC from Source</u>.

Requirements

HTMLDOC requires approximately 4MB of disk space and one of the following environments:

- · Microsoft Windows® 2000 or higher
- · MacOS® X 10.2 or higher
- · Linux® 2.4 or higher
- · Solaris® 7 or higher

HTMLDOC may run on other platforms, however we do not provide packages for platforms other than those listed.

Installing HTMLDOC

The following instructions describe how to install the HTMLDOC software on your system.

Installing HTMLDOC on Microsoft Windows

HTMLDOC is provided as a Microsoft installer file under Windows. Insert the CD or double-click on the *htmldoc* icon in the *Explorer* window to install HTMLDOC under Windows using the Microsoft software installation wizard (Figure 1-1).




Figure 1-1: The Microsoft software installation wizard

Installing HTMLDOC on MacOS X

Double-click on the *Install* icon in the *Finder* window to start the software installation wizard (Figure 1-2) and follow the installer prompts.



Figure 1-2: The software installation wizard

Installing HTMLDOC on Linux

Double-click on the *htmldoc-linux-intel.rpm* icon or run the following command to install HTMLDOC on Linux:

rpm -i htmldoc-linux-intel.rpm

Installing HTMLDOC on Solaris

Run the following command to install HTMLDOC on Solaris SPARC:

pkgadd -d htmldoc-solaris-sparc.pkg

Run the following command to install HTMLDOC on Solaris Intel:

pkgadd -d htmldoc-solaris-intel.pkg

Licensing HTMLDOC

Before you can use HTMLDOC, you must license it. When you first run HTMLDOC, the license dialog (Figure 1-3) will appear.




Figure 1-3 - The HTMLDOC License Dialog

Click on the *Update License* button to show the license manager window (Figure 1-4).



Figure 1-4 - The HTMLDOC License Dialog

Enter the license key that was emailed to you or came on the inside of the HTMLDOC CD-ROM case and click on the *OK* button. Click on the *Close* button to start using the software.

Uninstalling HTMLDOC

The following instructions describe how to remove the HTMLDOC software from your system.

Uninstalling HTMLDOC on Microsoft Windows

Open the Control Panel window and double-click on the *Add/Remove Software* icon. When the available software list is displayed, select HTMLDOC and click on the *Remove* button.

Uninstalling HTMLDOC on MacOS X

Double-click on the *Uninstall* icon in the *Finder* and follow the prompts.

Uninstalling HTMLDOC on Linux

Run the following command to remove HTMLDOC from your Linux system:

rpm -e htmldoc

Uninstalling HTMLDOC on Solaris

Run the following command to remove HTMLDOC from Solaris:

pkgrm htmldoc

Chapter 2 - Getting Started

This chapter describes how to start HTMLDOC and convert HTML files into PostScript and PDF files.

Note:

HTMLDOC currently does not support HTML 4.0 features such as stylesheets or the STYLE, TB0DY, THEAD, or TF00T elements. For more information, please consult <u>Chapter 6 - HTML Reference</u>.

Starting HTMLDOC

For Windows click:

Start Menu->All Programs->HTMLDOC->HTMLDOC

For MacOS X click:

Applications Folder->HTMLDOC

For Linux click:

Applications Menu->Office->HTMLDOC

or type:

htmldoc

For Solaris click:

Applications Window->ESP->HTMLDOC

or type:

htmldoc

Choosing a HTML File

The HTMLDOC window (Figure 2-1) shows the list of input files that will be converted. Start by clicking on the *Web Page* radio button (1) to specify that you will be converting a HTML web page file.

Figure 2-1 - The HTMLDOC Window

Then choose a file for conversion by clicking on the *Add Files*... button (2). When the file chooser dialog appears (Figure 2-2), double-click on the HTML file (3) you wish to convert from the list of files. If you don't see the file you wish to add, then double click on the folder with ../ (4) to see more file options.

Figure 2-2 - The File Chooser Dialog

Setting the Output File

You've chosen your HTML files to be converted, now you need to save your file(s) somewhere. The output file is where you would do that. Click on the *Output* tab (5) to set the output file (Figure 2-3). You can either type the name of the output file into the *Output Path* field or click on the *Browse*... button (6) to find an acceptable output location. Clicking on browse allows you to put the new file in a specific folder for easy retrieval. When you click on a folder you will notice that the filename area and text is highlighted. Click a few times at the end of the file name path and add a slash (/) and the name of the new file. If you don't see the folder you want to put your document in, double click on the folder with ../ after it.

Figure 2-3 - The Output Tab

Generating the Document

You can generate the document by clicking on the *Generate* button (7) at the bottom of the HTMLDOC window. When the conversion is completed you can open the PDF file that is produced using Adobe Acrobat Reader or any other PDF viewing application.

Note:

The *Open* button at the bottom of the HTMLDOC GUI Open Window will not open the generated document for viewing. You will learn about the *Open* button in later chapters.

Chapter 3 - Generating Books

This chapter describes how to create a book using HTML files.

Overview

While HTMLDOC can convert web pages into PostScript and PDF files, its real strength is generating indexed HTML, PostScript, or PDF books.

HTMLDOC uses HTML heading elements to delineate chapters and headings in a book. The H1 element is used for chapters:

Sub-headings are marked using the H2 through H6 elements.

Note:

When using book mode, HTMLDOC starts rendering with the first H1 element. Any text, images, tables, and other viewable elements that precede the first H1 element are silently ignored. Because of this, make sure you have an H1 element in your HTML file, otherwise HTMLDOC will not convert anything.

Choosing HTML Files

Start by clicking on the *Book* radio button (1) to specify you'll be converting one or more HTML files into a book.

Your next step is to choose one or more files for conversion by clicking on the *Add Files*... button (2). When the file chooser dialog appears, pick the file(s) you wish to convert and then click on the *OK* button. As discussed in Chapter 2, if you don't see the file that you want, double click on the folder with .../ after it.

Also, having all files and images in one folder will make file retrieval much easier.

Figure 3-1: The Input Tab

Selecting a Title File

HTMLDOC can automatically create a title page for you. Fill in the *Title File/Image* field or click the *Browse...* button (3) to locate the file you want to use. If you don't see the file you want, double click on the folder with ../ after it.

Figure 3-2: The Output Tab

Setting the Output Format

The output format is set in the *Output* tab (4). Click on the *Output* tab and then click on the *HTML*, *PS*, or *PDF* radio buttons to set the output format.

Setting the Output File

Now that you've chosen an output format, type the name of the output file into the *Output Path* field or click on the *Browse*... button (5) to select the output file using the file chooser.

Generating the Document

Once you have chosen the output file you can generate it by clicking on the *Generate* button (6) at the bottom of the HTMLDOC window.

Saving Your Book

HTMLDOC can save the list of HTML files, the title file, and all other options to a special . B00K file so you can regenerate your book when you make changes to your HTML files.

Click on the *Save* button (7) to save the current book to a file.

Chapter 4 - HTMLDOC from the Command-Line

This chapter describes how to use HTMLDOC from the command-line to convert web pages and generate books.

Getting to the Command-Line on Windows

Do the following steps to access the command-line on Windows:

- 1. Click on Start at the bottom left corner of your screen
- 2. Click on All Programs
- 3. Click on Accessories
- 4. Click on Command Prompt

After you have clicked command prompt, your screen should look something like Figure 4-1.




Figure 4-1: Command prompt window

To see what's in this directory, type the following command:

dir ENTER

You now have a list of available files and directories that you can use. To access a different directory simply type cd and the name of the new directory. For example, type the following if you want to access a directory called *Steve*:

cd Steve

The Basics of Command-Line Access

To convert a single web page type:

htmldoc --webpage -f output.pdf filename.html

What Are All These Commands?

htmldoc is the name of the software.

- --webpage is the document type that specifies unstructured files with page breaks between each file.
- -f output.pdf is the file name that you will save all the documents into and also the type of file it is. In this example it is a PDF file.

filename.html is the name of the file that you want to be converted and the type of file it is. In this example it is a HTML file.

Try the following exercise: You want to convert the file *myhtml.html* into a PDF file. The new file will be called *mypdf.pdf*. How would you do this? (Don't worry, it's answered for you on the next line. But try first.)

To accomplish this type:

htmldoc --webpage -f mypdf.pdf myhtml.html

Converting Multiple HTML Files

To convert more than one web page with page breaks between each HTML file, type:

```
htmldoc --webpage -f output.pdf file1.html file2.html
```

All we are doing is adding another file. In this example we are converting two files: file1.html and file2.html.

Try this example: Convert *one.html* and *two.html* into a PDF file named *12pdf.pdf*. Again, the answer is on the next line.

Your line command should look like this:

```
htmldoc --webpage -f 12pdf.pdf one.html two.html
```

We've been using HTML files, but you can also use URLs. For example:

htmldoc --webpage -f output.pdf http://slashdot.org/

Generating Books

Type one of the following commands to generate a book from one or more HTML files:

```
htmldoc --book -f output.html file1.html file2.html
htmldoc --book -f output.pdf file1.html file2.html
htmldoc --book -f output.ps file1.html file2.html
```

What are all these commands?

htmldoc is the name of the sofware.

- -- book is a type of document that specifies that the input files are structured with headings.
- -f output.html is where you want the converted files to go to. In this case, we requested the file be a HTML file. We could have made it a PDF (-f output.pdf) or Postscript (-f ouput.ps), too. file1.html and file2.html are the files you want to convert.

HTMLDOC will build a table of contents for the book using the heading elements (H1, H2, etc.) in your HTML files. It will also add a title page using the document TITLE text (you're going to learn about title files shortly) and other META information you supply in your HTML files. See <u>Chapter 6 - HTML Reference</u> for more information on the META variables that are supported.

Note:

When using book mode, HTMLDOC starts rendering with the first H1 element. Any text, images, tables, and other viewable elements that precede the first H1 element are silently ignored. Because of this, make sure you have an H1 element in your HTML file, otherwise HTMLDOC will not convert anything!

Setting the Title File

The --titlefile option sets the HTML file or image to use on the title page:

```
htmldoc --titlefile filename.bmp ...
htmldoc --titlefile filename.gif ...
htmldoc --titlefile filename.jpg ...
htmldoc --titlefile filename.png ...
htmldoc --titlefile filename.html ...
```

HTMLDOC supports BMP, GIF, JPEG, and PNG images, as well as generic HTML text you supply for the title page(s).

Putting It All Together

```
htmldoc --book -f 12book.pdf 1book.html 2book.html --titlefile bookcover.jpg
```

Take a look at the entire command line. Dissect the information. Can you see what the new filename is? What are the names of the files being converted? Do you see the titlepage file? What kind of file is your titlefile?

Generating Books 4-3

Figure it out? The new file is 12book.pdf. The files converted were 1book.html and 2book.html. A title page was created using the JPEG image file bookcover.jpg.

Chapter 8 - Command Line Reference digs deeper into what you can do with the the command line prompt.

Chapter 5 - Using HTMLDOC on a Web Server

This chapter describes how to interface HTMLDOC to your web server using CGI and your own server-side scripts and programs.

The Basics

HTMLDOC can be used in a variety of ways to generate formatted reports on a web server. The most common way is to use HTMLDOC as a CGI program with your web server to provide PDF-formatted output of a web page. Examples are provided for Microsoft IIS and the Apache web servers.

HTMLDOC can also be called from your own server-side scripts and programs. Examples are provided for PHP and Java.

WARNING:

Passing information directly from the web browser to HTMLDOC can potentially expose your system to security risks. Always be sure to "sanitize" any input from the web browser so that filenames, URLs, and options passed to HTMLDOC are not acted on by the shell program or other processes.

Using HTMLDOC as a CGI Program

HTMLDOC 1.8.24 and higher supports operation as a CGI program. You can copy or symlink the *htmldoc* (all but Windows) or *htmldoc.exe* (Windows) executable to your web server's *cgi-bin* directory and then use it to produce PDF versions of your web pages.

The CGI converts a page on your local server to PDF and sends it to the client's web browser. For example, to convert a page called *superproducts.html* at the following URL:

http://servername/superproducts.html

and if you installed HTMLDOC in your server's *cgi-bin* directory, you would direct your clients to the following URL:

http://servername/cgi-bin/htmldoc/superproducts.html

The boldface portion represents the location of the HTMLDOC executable on the web server. You simply place that path before the page you want to convert.

Form data using the GET method can be passed at the end of the URL, for example:

http://servername/cgi-bin/htmldoc/superproducts.html?name=value

Server-Side Preferences

When run as a CGI program, HTMLDOC will try to read a book file to set any preferences for the conversion to PDF. For the *superproducts.html* file described previously, HTMLDOC will look at the following URLs for a book file:

http://servername/superproducts.html.book

http://servername/.book

http://servername/cgi-bin/.book

The first book file that is found will be used.

Configuring HTMLDOC with Apache

The Apache web server is easily configured to use HTMLDOC. The simplest way is to copy or symlink the *htmldoc* executable to the configured *cgi-bin* directory. For example, if your Apache installation is configured to look for CGI programs in the */var/www/cgi-bin* directory, the default for Apache on Red Hat Linux, then the command to install HTMLDOC on your web server would be:

ln -s /usr/bin/htmldoc /var/www/cgi-bin

If you are using Apache 2.0.30 or higher, you will also need to enable PATH_INFO support by adding the following line to your *httpd.conf* file:

AcceptPathInfo On

Apache also allows you to associate CGI programs with a specific extension. If you add the following line to your *httpd.conf* file:

```
AddHandler cgi-script .cgi
```

and enable CGI execution with the **Options** directive for a directory:

```
Options +ExecCGI
```

then you can copy or symlink the *htmldoc* executable to an alternate location. For example, if you have a web directory called */var/www/htdocs/products*, you can install HTMLDOC in this directory with the following command:

ln -s /usr/bin/htmldoc /var/www/htdocs/products/htmldoc.cgi

Configuring HTMLDOC with Microsoft IIS

The IIS web server is configured to run CGI programs by either modifying the permissions of an existing directory or by creating a new virtual directory that allows for execution of programs. Start by running the *Internet Services Manager* program (Figure 5-1):

- 1. Click on Start
- 2. Click on Settings
- 3. Click on Control Panel
- 4. Double-click on Administrative Tools
- 5. Double-click on Internet Services Manager

After the *Internet Services Manager* window (Figure 5-1) appears, perform the following steps to add a virtual folder for HTMLDOC:

- 1. Click on your server in the list to show the default web site service in the list (Figure 5-2)
- 2. Choose *New->Virtual Directory* from the *Action* menu (Figure 5-3)
- 3. Click *Next* when the *Virtual Directory Creation Wizard* window appears (Figure 5-4)
- 4. Enter the name htmldoc in the *Alias* field and click *Next* (Figure 5-5)
- 5. Enter the HTMLDOC program folder in the *Directory* field and click *Next* (Figure 5-6)
- 6. Check the Execute (such as ISAPI applications or CGI) box and click Next (Figure 5-7)
- 7. Click *Finish* to dismiss the wizard (Figure 5-8)

If you are using IIS 6.0, proceed to the next section titled, "Additional Configuration for IIS 6.0".




Figure 5-1: The Internet Services Manager Window




Figure 5-2: The Default Web Site Service




Figure 5-3: Adding a New Virtual Directory



Figure 5-4: The Virtual Directory Creation Wizard Window



Figure 5-5: Entering the Alias Name




Figure 5-6: Entering the HTMLDOC Program Folder




Figure 5-7: Enabling CGI Mode



Figure 5-8: Completion of IIS Configuration

Once configured, the *htmldoc.exe* program will be available in the web server directory. For example, for a virtual directory called *cgi-bin*, the PDF converted URL for the *superproducts.html* page would be as follows:

http://servername/cqi-bin/htmldoc.exe/superproducts.html

The boldface portion represents the location of the HTMLDOC program on the web server.

Additional Configuration for IIS 6.0

IIS 6.0 requires additional configuration steps due to its increased focus on security. Start by running the *Internet Services Manager* program (Figure 5-1):

- 1. Click on Start
- 2. Click on Settings
- 3. Click on Control Panel
- 4. Double-click on Administrative Tools
- 5. Double-click on *Internet Services Manager*

After the *Internet Services Manager* window (Figure 5-1) appears, perform the following steps to add a new Wed Service Extension for HTMLDOC:

- 1. Click on Web Service Extensions
- 2. Click Add a new Web Service Extension
- 3. Enter the name "HTMLDOC" when the Web Service Extension window appears
- 4. Click *Add...* and choose the *htmldoc.exe* file from the program folder, typically *C:\Program Files\Easy Software Products\HTMLDOC*
- 5. Check the Set extension status to Allowed box
- 6. Click OK to add the extension and dismiss the window

Finally, double-click the *My Computer* icon on the desktop or start the *Windows Explorer*. When the explorer window appears, perform the following steps to provide write access to the Windows temporary folder:

- 1. Open the windows temporary file folder, typically *C:\WINDOWS\TEMP*
- 2. Choose Properties from the File menu
- 3. Click on the *Security* tab
- 4. Click *Add...*, enter the username for the web server, typically "SERVER\IUSR_SERVER" where "SERVER" is the name you gave your server, and click *OK*
- 5. Click on the username you just added in the list
- 6. Check the *Read* and *Write* permissions
- 7. Click *OK* to save the changes

Using HTMLDOC From Server-Side Scripts and Programs

To make this work the CGI script or program must send the appropriate HTTP attributes, the required empty line to signify the beginning of the document, and then execute the HTMLDOC program to generate the HTML, PostScript, or PDF file as needed. Since HTMLDOC looks for CGI environment variables when it is run, you must also set the HTMLDOC_NOCGI environment variable to a value of 1 before running HTMLDOC from your CGI script or program.

Another way to generate PDF files from your reports is to use HTMLDOC as a "portal" application. When used as a portal, HTMLDOC automatically retrieves the named document or report from your server and passes a PDF version to the web browser. See the next sections for more information.

Calling HTMLDOC from a Shell Script

Shell scripts are probably the easiest to work with, but are normally limited to GET type requests. Here is a script called *topdf* that acts as a portal, converting the named file to PDF:

```
#!/bin/sh
# Sample "portal" script to convert the named HTML file to PDF on-the-fly.
# Usage: http://www.domain.com/path/topdf/path/filename.html
# Tell HTMLDOC not to run in CGI mode...
HTMLDOC NOCGI=1; export HTMLDOC NOCGI
#
# The "options" variable contains any options you want to pass to HTMLDOC.
options='-t pdf --webpage --header ... --footer ..."
# Tell the browser to expect a PDF file...
echo "Content-Type: application/pdf"
echo ""
# Run HTMLDOC to generate the PDF file...
htmldoc $options http://${SERVER NAME}:${SERVER PORT}$PATH INFO
```

Users of this CGI would reference the URL "http://www.domain.com/topdf.cgi/index.html" to generate a PDF file of the site's home page.

The *options* variable in the script can be set to use any supported command-line option for HTMLDOC; for a complete list see <u>Chapter 8 - Command-Line Reference</u>.

Calling HTMLDOC from Perl

Perl scripts offer the ability to generate more complex reports, pull data from databases, etc. The easiest way to interface Perl scripts with HTMLDOC is to write a report to a temporary file and then execute HTMLDOC to generate the PDF file.

Here is a simple Perl subroutine that can be used to write a PDF report to the HTTP client:

```
sub topdf {
    # Get the filename argument...
    my $filename = shift;

    # Make stdout unbuffered...
    select(STDOUT); $| = 1;

    # Tell HTMLDOC not to run in CGI mode...
    $ENV{HTMLDOC_NOCGI} = 1;

    # Write the content type to the client...
    print "Content-Type: application/pdf\n\n";

    # Run HTMLDOC to provide the PDF file to the user...
    system "htmldoc -t pdf --quiet --webpage $filename";
}
```

Calling HTMLDOC from PHP

PHP is quickly becoming the most popular server-side scripting language available. PHP provides a passthru() function that can be used to run HTMLDOC. This combined with the header() function can be used to provide on-the-fly reports in PDF format.

Here is a simple PHP function that can be used to convert a HTML report to PDF and send it to the HTTP client:

```
function topdf($filename, $options = "") {
    # Tell HTMLDOC not to run in CGI mode...
    putenv("HTMLDOC_NOCGI=1");

# Write the content type to the client...
    header("Content-Type: application/pdf");
    flush();

# Run HTMLDOC to provide the PDF file to the user...
    passthru("htmldoc -t pdf --quiet --jpeg --webpage $options '$filename'");
}
```

The function accepts a filename and an optional "options" string for specifying the header, footer, fonts, etc.

To prevent malicious users from passing in unauthorized characters into this function, the following function can be used to verify that the URL/filename does not contain any characters that might be interpreted by the shell:

```
function bad url($url) {
    // See if the URL starts with http: or https:...
    if (strncmp(\$url, "http://", 7) \stackrel{\cdot}{!=} 0 \&\&
        strncmp($url, "https://", 8) != 0) {
        return 1;
    }
    // Check for bad characters in the URL...
    $len = strlen($url);
    for (\$i = 0; \$i < \$len; \$i ++) {
        if (!strchr("~ *()/:%?+-&@;=,$.", $url[$i]) &&
             !ctype alnum($url[$i])) {
             return 1;
        }
    }
    return 0;
}
```

Another method is to use the escapeshellarg() function provided with PHP 4.0.3 and higher to generate a quoted shell argument for HTMLDOC.

To make a "portal" script, add the following code to complete the example:

```
global $SERVER NAME;
global $SERVER PORT;
global $PATH INFO;
global $QUERY STRING;
if ($QUERY STRING != "") {
    $url = "http://${SERVER NAME}:${SERVER PORT}${PATH INFO}?${QUERY STRING}
} else {
    $url = "http://${SERVER NAME}:${SERVER PORT}$PATH INFO";
}
if (bad url($url)) {
  print("<html><head><title>Bad URL</title></head>\n"
       ."<body><h1>Bad URL</<math>h1>\n"
       ."The URL <b><tt>$url</tt></b> is bad.\n"
       ."</body></html>\n");
} else {
  topdf($url);
```

Calling HTMLDOC from C

C programs offer the best flexibility and easily supports on-the-fly report generation without the need for temporary files.

Here are some simple C functions that can be used to generate a PDF report to the HTTP client from a temporary file or pipe:

```
#include <stdio.h>
#include <stdlib.h>
/* topdf() - convert a HTML file to PDF */
                                             /* I - HTML file to convert */
FILE *topdf(const char *filename)
{
                                        /* Command to execute */
 char command[1024];
 /*
  * Tell HTMLDOC not to run in CGI mode...
 putenv("HTMLDOC NOCGI=1");
  * Write the content type to the client...
 puts("Content-Type: application/pdf\n");
  * Run HTMLDOC to provide the PDF file to the user...
 */
 sprintf(command, "htmldoc --quiet -t pdf --webpage %s", filename);
 return (popen(command, "w"));
}
/* topdf2() - pipe HTML output to HTMLDOC for conversion to PDF */
FILE *topdf2(void)
{
 * Tell HTMLDOC not to run in CGI mode...
 putenv("HTMLDOC NOCGI=1");
  * Write the content type to the client...
```

```
*/
puts("Content-Type: application/pdf\n");

/*
 * Open a pipe to HTMLDOC...
 */
return (popen("htmldoc --quiet -t pdf --webpage -", "w"));
}
```

Calling HTMLDOC from Java

Java programs are a portable way to add PDF support to your web server. Here is a class called *htmldoc* that acts as a portal, converting the named file to PDF. It can also be called by your Java servlets to process an HTML file and send the result to the client in PDF format:

```
class htmldoc
 // Convert named file to PDF on stdout...
 public static int topdf(String filename)// I - Name of file to convert
                      String
   Process
   Runtime
   java.io.InputStream input;
   byte
                                       // Number of bytes
   int
                       bytes;
   // First tell the client that we will be sending PDF...
   System.out.print("Content-type: application/pdf\n\n");
   // Construct the command string
   command = "htmldoc --quiet --jpeg --webpage -t pdf --left 36 " +
             "--header .t. --footer .1. " + filename:
   // Run the process and wait for it to complete...
   runtime = Runtime.getRuntime();
   try
   {
     // Create a new HTMLDOC process...
     process = runtime.exec(command);
     // Get stdout from the process and a buffer for the data...
     input = process.getInputStream();
     buffer = new byte[8192];
     // Read output from HTMLDOC until we have it all...
     while ((bytes = input.read(buffer)) > 0)
       System.out.write(buffer, 0, bytes);
```

```
// Return the exit status from HTMLDOC...
    return (process.waitFor());
  catch (Exception e)
    // An error occurred - send it to stderr for the web server...
    System.err.print(e.toString() + " caught while running:\n\n");
    System.err.print(" " + command + "\n");
    return (1);
  }
}
// Main entry for htmldoc class
public static void main(String[] args)// I - Command-line args
                                       // SERVER NAME env var
  String server name,
         server_name, // SERVER_NAME env var
server_port, // SERVER_PORT env var
path_info, // PATH_INFO env var
query_string, // QUERY_STRING env var
                                       // QUERY STRING env var
         filename;
                                        // File to convert
  if ((server name = System.getProperty("SERVER NAME")) != null &&
      (server port = System.getProperty("SERVER PORT")) != null &&
      (path info = System.getProperty("PATH INFO")) != null)
    // Construct a URL for the resource specified...
    filename = "http://" + server name + ":" + server port + path info;
    if ((query string = System.getProperty("QUERY STRING")) != null)
      filename = filename + "?" + query string;
  }
  else if (args.length == 1)
    // Pull the filename from the command-line...
    filename = args[0];
  }
  else
    // Error - no args or env variables!
    System.err.print("Usage: htmldoc.class filename\n");
    return;
  }
  // Convert the file to PDF and send to the web client...
  topdf(filename);
}
```

}

Chapter 6 - HTML Reference

This chapter defines all of the HTML elements and attributes that are recognized and supported by HTMLDOC.

General Usage

There are two types of HTML files - structured documents using headings (H1, H2, etc.) which HTMLDOC calls "books", and unstructured documents that do not use headings which HTMLDOC calls "web pages".

A very common mistake is to try converting a web page using:

which will likely produce a PDF file with no pages. To convert web page files you **must** use the --webpage option at the command-line or choose *Web Page* in the input tab of the GUI.

Note:

HTMLDOC does not support HTML 4.0 elements, attributes, stylesheets, or scripting.

Elements

The following HTML elements are recognized by HTMLDOC:

Element	Version	Supported?	Notes
!DOCTYPE	3.0	Yes	DTD is ignored
A	1.0	Yes	See Below
ACRONYM	2.0	Yes	No font change
ADDRESS	2.0	Yes	
AREA	2.0	No	
В	1.0	Yes	
BASE	2.0	No	
BASEFONT	1.0	No	
BIG	2.0	Yes	
BLINK	2.0	No	
BLOCKQUOTE	2.0	Yes	
BODY	1.0	Yes	
BR	2.0	Yes	

HTMLDOC 1.9 Software Users Manual

	DUC 1.9		
CAPTION	2.0	Yes	
CENTER	2.0	Yes	
CITE	2.0	Yes	Italic/Oblique
CODE	2.0	Yes	Courier
DD	2.0	Yes	
DEL	2.0	Yes	Strikethrough
DFN	2.0	Yes	Helvetica
DIR	2.0	Yes	
DIV	3.2	Yes	
DL	2.0	Yes	
DT	2.0	Yes	Italic/Oblique
EM	2.0	Yes	Italic/Oblique
EMBED	2.0	Yes	HTML Only
FONT	2.0	Yes	See Below
FORM	2.0	No	
EDANGE	2.2		
FRAME	3.2	No	
FRAME Element	Version	No Supported?	Notes
			Notes
Element	Version	Supported?	Notes Boldface, <u>See Below</u>
Element FRAMESET	Version 3.2	Supported?	
Element FRAMESET H1	3.2 1.0	Supported? No Yes	Boldface, <u>See Below</u>
Element FRAMESET H1 H2	3.2 1.0 1.0	No Yes Yes	Boldface, <u>See Below</u> Boldface, <u>See Below</u>
Element FRAMESET H1 H2 H3	3.2 1.0 1.0 1.0	No Yes Yes Yes	Boldface, <u>See Below</u> Boldface, <u>See Below</u> Boldface, <u>See Below</u>
FRAMESET H1 H2 H3 H4	3.2 1.0 1.0 1.0	No Yes Yes Yes Yes	Boldface, <u>See Below</u> Boldface, <u>See Below</u> Boldface, <u>See Below</u> Boldface, <u>See Below</u>
FRAMESET H1 H2 H3 H4 H5	3.2 1.0 1.0 1.0 1.0	No Yes Yes Yes Yes Yes Yes	Boldface, <u>See Below</u>
Element FRAMESET H1 H2 H3 H4 H5 H6	Version 3.2 1.0 1.0 1.0 1.0 1.0 1.0	No Yes Yes Yes Yes Yes Yes Yes	Boldface, <u>See Below</u>
Element FRAMESET H1 H2 H3 H4 H5 H6 HEAD	Version 3.2 1.0 1.0 1.0 1.0 1.0 1.0 1.0	No Yes Yes Yes Yes Yes Yes Yes Yes	Boldface, <u>See Below</u>
Element FRAMESET H1 H2 H3 H4 H5 H6 HEAD HR	Version 3.2 1.0 1.0 1.0 1.0 1.0 1.0 1.0 1.0	No Yes	Boldface, <u>See Below</u>
Element FRAMESET H1 H2 H3 H4 H5 H6 HEAD HR HTML	Version 3.2 1.0 1.0 1.0 1.0 1.0 1.0 1.0 1.0 1.0	No Yes	Boldface, <u>See Below</u>
Element FRAMESET H1 H2 H3 H4 H5 H6 HEAD HR HTML I	Version 3.2 1.0 1.0 1.0 1.0 1.0 1.0 1.0 1.0 1.0 1.0	No Yes	Boldface, See Below See Below
FRAMESET H1 H2 H3 H4 H5 H6 HEAD HR HTML I IMG	Version 3.2 1.0 1.0 1.0 1.0 1.0 1.0 1.0 1.0 1.0 1.0 1.0	No Yes	Boldface, See Below See Below

6-2 Elements

HTMLDOC 1.9 Software Users Manual

			aci's Mariaar
ISINDEX	2.0	No	
KBD	2.0	Yes	Courier Bold
LI	2.0	Yes	
LINK	2.0	No	
MAP	2.0	No	
MENU	2.0	Yes	
META	2.0	Yes	See Below
MULTICOL	N3.0	No	
NOBR	1.0	No	
NOFRAMES	3.2	No	
OL	2.0	Yes	
OPTION	2.0	No	
P	1.0	Yes	
PRE	1.0	Yes	
S	2.0	Yes	Strikethrough
SAMP	2.0	Yes	Courier
SCRIPT	2.0	No	
Element	Version	Supported?	Notes
SELECT	2.0	No	
SMALL	2.0	Yes	
SPACER	N3.0	Yes	
STRIKE	2.0	Yes	
	2.0	168	
STRONG	2.0	Yes	Boldface Italic/Oblique
STRONG SUB			Boldface Italic/Oblique Reduced Fontsize
	2.0	Yes	
SUB	2.0	Yes Yes	Reduced Fontsize
SUB SUP	2.0 2.0 2.0	Yes Yes Yes	Reduced Fontsize Reduced Fontsize
SUB SUP TABLE	2.0 2.0 2.0 2.0	Yes Yes Yes Yes	Reduced Fontsize Reduced Fontsize
SUB SUP TABLE TD	2.0 2.0 2.0 2.0 2.0	Yes Yes Yes Yes Yes	Reduced Fontsize Reduced Fontsize
SUB SUP TABLE TD TEXTAREA	2.0 2.0 2.0 2.0 2.0 2.0	Yes Yes Yes Yes Yes No	Reduced Fontsize Reduced Fontsize See Below
SUB SUP TABLE TD TEXTAREA TH	2.0 2.0 2.0 2.0 2.0 2.0 2.0	Yes Yes Yes Yes Yes No Yes	Reduced Fontsize Reduced Fontsize See Below

Elements 6-3

HTMLDOC 1.9 Software Users Manual

TT	2.0	Yes	Courier
U	1.0	Yes	
UL	2.0	Yes	
VAR	2.0	Yes	Helvetica Oblique
WBR	1.0	No	

Comments

HTMLDOC supports many special HTML comments to initiate page breaks, set the header and footer text, and control the current media options:

<!-- F00TER LEFT "foo" -->

Sets the left footer text; the test is applied to the current page if empty, or the next page otherwise.

<!-- FOOTER CENTER "foo" -->

Sets the center footer text; the test is applied to the current page if empty, or the next page otherwise.

<!-- FOOTER RIGHT "foo" -->

Sets the right footer text; the test is applied to the current page if empty, or the next page otherwise.

<!-- HALF PAGE -->

Break to the next half page.

<!-- HEADER LEFT "foo" -->

Sets the left header text; the test is applied to the current page if empty, or the next page otherwise.

<!-- HEADER CENTER "foo" -->

Sets the center header text; the test is applied to the current page if empty, or the next page otherwise.

<!-- HEADER RIGHT "foo" -->

Sets the right header text; the test is applied to the current page if empty, or the next page otherwise.

<!-- MEDIA BOTTOM nnn -->

Sets the bottom margin of the page. The "nnn" string can be any standard measurement value, e.g. 0.5in, 36, 12mm, etc. Breaks to a new page if the current page is already marked.

<!-- MEDIA COLOR "foo" -->

Sets the media color attribute for the page. The "foo" string is any color name that is supported by the printer, e.g. "Blue", "White", etc. Breaks to a new page or sheet if the current page is already marked.

<!-- MEDIA DUPLEX NO -->

Chooses single-sided printing for the page; breaks to a new page or sheet if the current page is already marked.

<!-- MEDIA DUPLEX YES -->

Chooses double-sided printing for the page; breaks to a new sheet if the current page is already marked.

6-4 Comments

<!-- MEDIA LANDSCAPE NO -->

Chooses portrait orientation for the page; breaks to a new page if the current page is already marked.

<!-- MEDIA LANDSCAPE YES -->

Chooses landscape orientation for the page; breaks to a new page if the current page is already marked.

<!-- MEDIA LEFT nnn -->

Sets the left margin of the page. The "nnn" string can be any standard measurement value, e.g. 0.5in, 36, 12mm, etc. Breaks to a new page if the current page is already marked.

<!-- MEDIA POSITION nnn -->

Sets the media position attribute (input tray) for the page. The "nnn" string is an integer that usually specifies the tray number. Breaks to a new page or sheet if the current page is already marked.

<!-- MEDIA RIGHT nnn -->

Sets the right margin of the page. The "nnn" string can be any standard measurement value, e.g. 0.5in, 36, 12mm, etc. Breaks to a new page if the current page is already marked.

<!-- MEDIA SIZE foo -->

Sets the media size to the specified size. The "foo" string can be "Letter", "Legal", "Universal", or "A4" for standard sizes or "WIDTHxHEIGHTunits" for custom sizes, e.g. "8.5x11in"; breaks to a new page or sheet if the current page is already marked.

<!-- MEDIA TOP nnn -->

Sets the top margin of the page. The "nnn" string can be any standard measurement value, e.g. 0.5in, 36, 12mm, etc. Breaks to a new page if the current page is already marked.

<!-- MEDIA TYPE "foo" -->

Sets the media type attribute for the page. The "foo" string is any type name that is supported by the printer, e.g. "Plain", "Glossy", etc. Breaks to a new page or sheet if the current page is already marked.

<!-- NEED length -->

Break if there is less than length units left on the current page. The length value defaults to lines of text but can be suffixed by in, mm, or cm to convert from the corresponding units.

<!-- NEW PAGE -->

Break to the next page.

<!-- NEW SHEET -->

Break to the next sheet.

<!-- NUMBER-UP nn -->

Sets the number of pages that are placed on each output page. Valid values are 1, 2, 4, 6, 9, and 16.

<!-- PAGE BREAK -->

Break to the next page.

Header/Footer Strings

The HEADER and F00TER comments allow you to set an arbitrary string of text for the left, center, and right headers and footers. Each string consists of plain text; special values or strings can be inserted using the dollar sign (\$):

\$\$

Inserts a single dollar sign in the header.

\$CHAPTER

Inserts the current chapter heading.

\$CHAPTERPAGE

\$CHAPTERPAGE(format)

Inserts the current page number within a chapter or file. When a format is specified, uses that numeric format (1 = decimal, i = lowercase roman numerals, I = uppercase roman numerals, a = lowercase ascii, A = uppercase ascii) for the page numbers.

\$CHAPTERPAGES

\$CHAPTERPAGES(format)

Inserts the total page count within a chapter or file. When a format is specified, uses that numeric format (1 = decimal, i = lowercase roman numerals, I = uppercase roman numerals, a = lowercase ascii, A = uppercase ascii) for the page count.

\$DATE

Inserts the current date.

\$HEADING

Inserts the current heading.

\$LOGOIMAGE

Inserts the logo image; all other text in the string will be ignored.

\$PAGE

\$PAGE(format)

Inserts the current page number. When a format is specified, uses that numeric format (1 = decimal, i = lowercase roman numerals, I = uppercase roman numerals, a = lowercase ascii, A = uppercase ascii) for the page numbers.

\$PAGES

\$PAGES(format)

Inserts the total page count. When a format is specified, uses that numeric format (1 = decimal, i = lowercase roman numerals, I = uppercase roman numerals, a = lowercase ascii, A = uppercase ascii) for the page count.

\$TIME

Inserts the current time.

\$TITLE

Inserts the document title.

FONT Attributes

Limited typeface specification is currently supported to ensure portability across platforms and for older PostScript printers:

Requested Font	Actual Font
Arial	Helvetica
Courier	Courier
Dingbats	Dingbats
Helvetica	Helvetica
Monospace	DejaVu Sans Mono
Sans	DejaVu Sans
Serif	DejaVu Serif
Symbol	Symbol
Times	Times

All other unrecognized typefaces are silently ignored.

Headings

Currently HTMLDOC supports a maximum of 1000 chapters (H1 headings). This limit can be increased by changing the MAX_CHAPTERS constant in the *config.h* file included with the source code.

All chapters start with a top-level heading (H1) markup. Any headings within a chapter must be of a lower level (H2 to H15). Each chapter starts a new page or the next odd-numbered page if duplexing is selected.

Note:

Heading levels 7 to 15 are not standard HTML and will not likely be recognized by most web browsers.

The headings you use within a chapter must start at level 2 (H2). If you skip levels the heading will be shown under the last level that was known. For example, if you use the following hierarchy of headings:

```
<H1>Chapter Heading</H1>
...
<H2>Section Heading 1</H2>
...
<H2>Section Heading 2</H2>
...
<H3>Sub-Section Heading 1</H3>
...
```

FONT Attributes 6-7

```
<H4>Sub-Sub-Section Heading 1</H4>
...
<H4>Sub-Sub-Section Heading 2</H4>
...
<H3>Sub-Section Heading 2</H3>
...
<H2>Section Heading 3</H2>
...
<H4>Sub-Sub-Section Heading 3</H4>
```

the table-of-contents that is generated will show:

Chapter Heading

- · Section Heading 1
- Section Heading 2
 - Sub-Section Heading 1
 - · Sub-Sub-Section Heading 1
 - · Sub-Sub-Section Heading 2
 - Sub-Section Heading 2
 - Sub-Sub-Section Heading 3
- · Section Heading 3

Numbered Headings

When the numbered headings option is enabled, HTMLDOC recognizes the following additional attributes for all heading elements:

```
VALUE="#"

Specifies the starting value for this heading level (default is "1" for all new levels).

TYPE="1"

Specifies that decimal numbers should be generated for this heading level.

TYPE="a"

Specifies that lowercase letters should be generated for this heading level.

TYPE="A"

Specifies that uppercase letters should be generated for this heading level.

TYPE="1"

Specifies that lowercase roman numerals should be generated for this heading level.

TYPE="I"

Specifies that uppercase roman numerals should be generated for this heading level.
```

Images

HTMLDOC supports loading of BMP, GIF, JPEG, and PNG image files. EPS and other types of image files are not supported at this time.

6-8 Headings

Links

External URL and internal (#target and filename.html) links are fully supported for HTML and PDF output.

When generating PDF files, local PDF file links will be converted to external file links for the PDF viewer instead of URL links. That is, you can directly link to another local PDF file from your HTML document with:

```
<A HREF="filename.pdf">...</A>
```

META Attributes

HTMLDOC supports the following META attributes for the title page and document information:

Page Breaks

HTMLDOC supports four new <u>page comments</u> to specify page breaks. In addition, the older BREAK attribute is still supported by the HR element:

```
<HR BREAK>
```

Support for the BREAK attribute is deprecated and will be removed in a future release of HTMLDOC.

Tables

Currently HTMLDOC supports a maximum of 200 columns within a single table. This limit can be increased by changing the MAX_COLUMNS constant in the *config.h* file included with the source code.

HTMLDOC does not support HTML 4.0 table elements or attributes, such as TBODY, THEAD, TF00T, or RULES.

Links 6-9

7-10 Tables

Chapter 7 - GUI Reference

This chapter describes all of the GUI controls in HTMLDOC.

The HTMLDOC GUI

The HTMLDOC GUI (Figures 7-1 through 7-11) is contained in a single window showing the input, output, and generation options. At the bottom are buttons to load, save, and generate documents.

Document File Operations

HTMLDOC stores the HTML files, settings, and options in .B00K files. The buttons on the bottom of the HTMLDOC window allow you to manage these files and generate formatted documents.

New

The *New* button starts a new document. A confirmation dialog will appear if you have not saved the changes to the existing document.

Open...

The *Open...* button retrieves a document that you have saved previously. A <u>file chooser</u> dialog is displayed that allows you to pick an existing book file.

Save

The *Save* button saves the current document. A <u>file chooser</u> dialog is displayed if there is no filename assigned to the current document.

Note: Saving a document is not the same as *generating* a document. The book files saved to disk by the *Save* and *Save As.*.. buttons are **not** the final HTML, PDF, or PostScript output files. You generate those files by clicking on the *Generate* button.

Save As...

The *Save As...* button saves the current document to a new file. A <u>file chooser</u> dialog is displayed to allow you to specify the new document filename.

Note: Saving a document is not the same as *generating* a document. The book files saved to disk by the *Save* and *Save As.*.. buttons are **not** the final HTML, PDF, or PostScript output files. You generate those files by clicking on the *Generate* button.

Generate

The *Generate* button generates the current document, creating the specified HTML, PDF, or PostScript file(s) as needed. The progress meter at the bottom of the window will show the progress as each page or file is formatted and written.

Note: Generating a document is not the same as **saving** a document. To save the current HTML files and settings in the HTMLDOC GUI, click on the *Save* or *Save As.*.. buttons instead.

Close

The *Close* button closes the HTMLDOC window.

Figure 7-1 - The Input Tab

The Input Tab

The input tab (Figure 7-1) lists all of the HTML source files that are used to generate the document. You also specify the type of document (book or web page) and the title and logo images in this tab.

Document Type

The *Book* radio button specifies that the input files are structured with headings. The *Continuous* radio button specifies unstructured files without page breaks between each file. The *Web Page* radio button specifies unstructured files with page breaks between each file.

Input Files

The *Input Files* list shows all of the HTML input files that will be used to produce the document. Double-click on files to edit them.

Add Files...

The Add Files... button displays the <u>file chooser</u> dialog, allowing you to select one or more HTML files to include in the document.

Edit Files...

The *Edit Files*... button starts the specified editor program to edit the files selected in the *Input Files* list. Select one or more files in the *Input Files* list to enable the *Edit Files*... button.

Delete Files

The *Delete Files* button removes the selected files from the *Input Files* list. Select one or more files in the *Input Files* list to enable the *Delete Files* button.

The Delete Files button only removes the files from the Input Files list. The files are **not** removed from disk.

Move Up

The *Move Up* button moves the selected files in the *Input Files* list up one line in the list. To enable the *Move Up* button select one or more files in the *Input Files* list.

7-2 Close

Move Down

The *Move Down* button moves the selected files in the *Input Files* list down one line in the list. To enable the *Move Down* button select one or more files in the *Input Files* list.

Logo Image

The *Logo Image* field contains the filename for an image to be shown in the header or footer of pages, and in the navigation bar of HTML files.

Click on the *Browse...* button to select a logo image file using the <u>file chooser</u> dialog.

Title File/Image

The *Title File/Image* field contains the filename for an image to be shown on the title page, or for a HTML file to be used for the title page(s).

Click on the *Browse...* button to select a title file using the <u>file chooser</u> dialog.

Figure 7-2 - The Output Tab

The Output Tab

The output tab (Figure 7-2) specifies where your document will be generated, the output format, and some of the generic output options.

Output To

The *File* radio button selects output to a single file. The *Directory* radio button selects output to multiple files in the named directory.

Directory output is not available when generating PDF files.

Output Path

The *Output Path* field contains the output directory or filename. Click on the *Browse*... button to choose an output file using the <u>file chooser</u> dialog.

Output Format

The *HTML* radio button selects HTML output, the *Separated HTML* radio button selects HTML output that is separated into a separate file for each heading in the table-of-contents, the *PS* radio button selects PostScript output, and the *PDF* radio button selects PDF output.

Output Options

The *Grayscale* check box selects grayscale output for PostScript and PDF files. The *Title Page* check box specifies that a title page should be generated for the document. The *JPEG Big Images* check box specifies that JPEG compression should be applied to continuous-tone images.

Move Down 7-3

Compression

The *Compression* slider controls the amount of compression that is used when writing PDF or Level 3 PostScript output.

Note: HTMLDOC uses Flate compression, which is not encumbered by patents and is also used by the popular PKZIP and gzip programs. Flate is a lossless compression algorithm (that is, you get back exactly what you put in) that performs very well on indexed images and text.

JPEG Quality

The *JPEG Quality* slider controls the quality level used when writing continuous-tone images with JPEG compression.

7-4 Compression

Figure 7-3 - The Page Tab

The Page Tab

The page tab (Figure 7-3) defines the page header, footer, size, and margins for PostScript and PDF output.

Page Size

The *Page Size* field contains the current page size. Click on the arrow button to choose a standard page size.

HTMLDOC supports the following standard page size names:

- · Letter 8.5x11in (216x279mm)
- · A4 8.27x11.69in (210x297mm)
- Universal 8.27x11in (210x279mm)

Click in the *Page Size* field and enter the page width and length separated by the letter "x" to select a custom page size. Append the letters "in" for inches, "mm" for millimeters, or "cm" for centimeters.

2-Sided

Click in the 2-Sided check box to select 2-sided (duplexed) output.

Landscape

Click in the *Landscape* check box to select landscape output.

Top, Left, Right, and Bottom

Click in the *Top*, *Left*, *Right*, and *Bottom* fields and enter the new margin values to change them. Append the letters "in" for inches, "mm" for millimeters, or "cm" for centimeters.

Header and Footer

Select the desired text in each of the option buttons to customize the header and footer for the document/body pages. The left-most option buttons set the text that is left-justified, while the middle buttons set the text that is centered and the right buttons set the text that is right-justified. Each choice corresponds to the following text:

Choice	Description
Blank	The field should be blank.
Title	The field should contain the document title.
Chapter Title	The field should contain the current chapter title.
Heading	The field should contain the current heading.

IPEG Quality 7-5

Logo	The field should contain the logo image.
1,2,3,	The field should contain the current page number in decimal format (1, 2, 3,)
i,ii,iii,	The field should contain the current page number in lowercase roman numerals (i, ii, iii,)
I,II,III,	The field should contain the current page number in uppercase roman numerals (I, II, III,)
a,b,c,	The field should contain the current page number using lowercase letters.
A,B,C,	The field should contain the current page number using UPPERCASE letters.
Chapter Page	The field should contain the current chapter page number.
1/N,2/N,	The field should contain the current and total number of pages (n/N).
1/C,2/C,	The field should contain the current and total number of pages in the chapter (n/N).
Date	The field should contain the current date (formatted for the current locale).
Time	The field should contain the current time (formatted for the current locale).
Date + Time	The field should contain the current date and time (formatted for the current locale).

Figure 7-4 - The TOC Tab

The TOC Tab

The TOC tab (Figure 7-4) defines the table-of-contents options.

Table of Contents

Select the desired number of levels from the *Table of Contents* option button.

Numbered Headings

Click in the *Numbered Headings* check box to automatically number the headings in the document.

Header and Footer

Select the desired text in each of the option buttons to customize the header and footer for the tables-of-contents pages. The left-most option buttons set the text that is left-justified, while the middle buttons set the text that is centered and the right buttons set the text that is right-justified.

7-6 Header and Footer

Title

Enter the desired title for the table-of-contents in the *Title* field.

Figure 7-5 - The Colors Tab

The Colors Tab

The colors tab (Figure 7-5) defines the color and image information that is used for the entire document.

Body Color

The *Body Color* field specifies the default background color. It can be a standard HTML color name or a hexadecimal RGB color of the form #RRGGBB. Click on the *Lookup*... button to pick the color graphically.

Body Image

The *Body Image* field specifies the default background image. Click on the *Browse*... button to pick the background image using the <u>file chooser</u>.

Text Color

The *Text Color* field specifies the default text color. It can be a standard HTML color name or a hexadecimal RGB color of the form #RRGGBB. Click on the *Lookup*... button to pick the color graphically.

Link Color

The *Link Color* field specifies the default link color. It can be a standard HTML color name or a hexadecimal RGB color of the form #RRGGBB. Click on the *Lookup*... button to pick the color graphically.

Link Style

The *Link Style* chooser specifies the default link decoration.

Figure 7-6 - The Fonts Tab

The Fonts Tab

The fonts tab (Figure 7-6) defines the fonts and character set used by the document.

Base Font Size

The *Base Font Size* field specifies the size of normal text in the document in points (1 point = 1/72nd inch). Click on the single arrow buttons to decrease or increase the size by 1/10th point or on the double arrow buttons to decrease or increase the size by whole points.

Title 7-7

Line Spacing

The *Line Spacing* field specifies the spacing between lines as a multiple of the base font size. Click on the single arrow buttons to decrease or increase the size by 10ths or on the double arrow buttons to decrease or increase the size by whole numbers.

Body Typeface

The *Body Typeface* option button specifies the typeface to use for normal text. Click on the option button to select a typeface.

Heading Typeface

The *Heading Typeface* option button specifies the typeface to use for headings. Click on the option button to select a typeface.

Header/Footer Size

The *Header/Footer Size* field specifies the size of header and footer text in the document in points (1 point = 1/72nd inch). Click on the single arrow buttons to decrease or increase the size by 1/10th point or on the double arrow buttons to decrease or increase the size by whole points.

Header/Footer Font

The *Header/Footer Font* option button specifies the typeface and style to use for header and footer text. Click on the option button to select a typeface and style.

Character Set

The *Character Set* option button specifies the encoding of characters in the document. Click on the option button to select a character set.

Options

The *Embed Fonts* check box controls whether or not fonts are embedded in PostScript and PDF output.

Figure 7-7 - The PS Tab

The PS Tab

The PS tab (Figure 7-7) contains options specific to PostScript output.

PostScript Level

Click on one of the *Level* radio buttons to select the language level to generate. PostScript Level 1 is compatible with all PostScript printers and will produce the largest output files.

PostScript Level 2 is compatible with most PostScript printers and supports printer commands and JPEG image compression.

7-8 Line Spacing

PostScript Level 3 is compatible with only the newest PostScript printers and supports Flate image compression in addition to the Level 2 features.

Send Printer Commands

The *Send Printer Commands* check box controls whether or not the output files contain PostScript setpagedevice commands for the page size and duplex settings. Click in the check box to enable or disable printer commands.

Printer commands are only available with Level 2 and 3 output and may not work with some printers.

Include Xerox Job Comments

The *Include Xerox Job Comments* check box controls whether or not the output files contain Xerox job comments. Click in the check box to enable or disable the job comments.

Job comments are available with all levels of PostScript output.

Figure 7-8 - The PDF Tab

The PDF Tab

The PDF tab (Figure 7-8) contains settings specific to PDF output.

PDF Version

The *PDF Version* radio buttons control what version of PDF is generated. PDF 1.3 is the most commonly supported version. Click on the corresponding radio button to set the version.

Page Mode

The *Page Mode* option button controls the initial viewing mode for the document. Click on the option button to set the page mode.

The *Document* page mode displays only the document pages. The *Outline* page mode displays the table-of-contents outline as well as the document pages. The *Full-Screen* page mode displays the document pages on the whole screen; this mode is used primarily for presentations.

Page Layout

The *Page Layout* option button controls the initial layout of document pages on the screen. Click on the option button to set the page layout.

The *Single* page layout displays a single page at a time. The *One Column* page layout displays a single column of pages at a time. The *Two Column Left* and *Two Column Right* page layouts display two columns of pages at a time; the first page is displayed in the left or right column as selected.

PostScript Level 7-9

First Page

The *First Page* option button controls the initial page that is displayed. Click on the option button to choose the first page.

Page Effect

The *Page Effect* option button controls the page effect that is displayed in *Full-Screen* mode. Click on the option button to select a page effect.

Page Duration

The *Page Duration* slider controls the number of seconds that each page will be visible in *Full-Screen* mode. Drag the slider to adjust the number of seconds.

Effect Duration

The *Effect Duration* slider controls the number of seconds that the page effect will last when changing pages. Drag the slider to adjust the number of seconds.

Figure 7-9 - The Security Tab

The Security Tab

The security tab (Figure 7-9) allows you to enable PDF document encryption and security features.

Encryption

The *Encryption* buttons control whether or not encryption is performed on the PDF file. Encrypted documents can be password protected and also provide user permissions.

Permissions

The *Permissions* buttons control what operations are allowed by the PDF viewer.

Owner Password

The *Owner Password* field contains the document owner password, a string that is used by Adobe Acrobat to control who can change document permissions, etc.

If this field is left blank, a random 32-character password is generated so that no one can change the document using the Adobe tools.

Options

The *Include Links* option controls whether or not the internal links in a document are included in the PDF output. The document outline (shown to the left of the document in Acrobat Reader) is unaffected by this setting.

7-10 First Page

User Password

The *User Password* field contains the document user password, a string that is used by Adobe Acrobat to restrict viewing permissions on the file.

If this field is left blank, any user may view the document without entering a password.

Figure 7-10 - The Options Tab

The Options Tab

The options tab (Figure 7-10) contains the HTML file editor of your choice and allows you to save the settings and options that will be used in new documents.

HTML Editor

The *HTML Editor* field contains the name of the HTML editor to run when you double-click on an input file or click on the *Edit Files...* button. Enter the program name in the field or click on the *Browse...* button to select the editor using the <u>file chooser</u>.

The %S is added automatically to the end of the command name to insert the name of the file to be edited. If you are using Netscape Composer to edit your HTML files you should put "-edit" before the %S to tell Netscape to edit the file and not display it.

Browser Width

The *Browser Width* slider specifies the width of the browser in pixels that is used to scale images and other pixel measurements to the printable page width. You can adjust this value to more closely match the formatting on the screen.

The default browser width is 680 pixels which corresponds roughly to a 96 DPI display. The browser width is only used when generating PostScript or PDF files.

Search Path

The *Search Path* field specifies a search path for files that are loaded by HTMLDOC. It is usually used to get images that use absolute server paths to load.

Directories are separated by the semicolon (;) so that drive letters (and eventually URLs) can be specified.

Proxy URL

The *Proxy URL* field specifies a URL for a HTTP proxy server.

User Password 7-11

Tooltips

The *Tooltips* check button controls the appearance of tooltip windows over GUI controls.

Modern Look

The *Modern Look* check button controls the appearance of the GUI controls.

Strict HTML

The *Strict HTML* check button controls strict HTML conformance checking. When checked, HTML elements that are improperly nested and dangling close elements will produce error messages.

Save Options and Defaults

The Save Options and Defaults button saves the HTML editor and all of the document settings on the other tabs for use in new documents. These settings are also used by the command-line version of HTMLDOC.

Figure 7-11 - The File Chooser

The File Chooser

The file chooser (Figure 7-11) allows you to select one or more files and create files and directories.

Show

The *Show* option button (1) selects which files are displayed in the file list (3). Click on the option button to choose a different type of file.

Favorites

The *Favorites* button (2) allow you to view a specific directory or add the current directory to your list of favorites.

File List

The file list (3) lists the files and directories in the current directory or folder. Double-click on a file or directory to select that file or directory. Drag the mouse or hold the CTRL key down while clicking to select multiple files.

Filename

The *Filename* field contains the currently selected filename. Type a name in the field to select a file or directory. As you type, any matching filenames will be highlighted; press the TAB key to accept the matches.

The button bar along the top of the filename allows you to view each directory in the filename. Click on any of the segments to display the corresponding directory.

7-12 Tooltips

Dialog Buttons

The dialog buttons (5) close the file chooser dialog window. Click on the OK button to accept your selections or the Cancel button to reject your selections and cancel the file operation.

Dialog Buttons 7-13

8-14 Dialog Buttons

Chapter 8 - Command-Line Reference

This chapter describes all of the command-line options supported by HTMLDOC.

Basic Usage

The basic command-line usage for HTMLDOC is:

```
htmldoc options filename1.html ... filenameN.html
htmldoc options filename.book
```

The first form converts the named HTML files to the specified output format immediately. The second form loads the specified . book file and displays the HTMLDOC window, allowing a user to make changes and/or generate the document interactively.

If no output file or directory is specified, then all output is sent to the standard output file.

On return, HTMLDOC returns and exit code of 0 if it was successful and non-zero if there were errors.

Options

The following command-line options are recognized by HTMLDOC.

-d directory

The -d option specifies an output directory for the document files.

This option is not compatible with the PDF output format.

-f filename

The -f option specifies an output file for the document.

-t format

The -t option specifies the output format for the document and can be one of the following:

Format	Description
html	Generate one or more indexed HTML files.
htmlsep	Generate separate HTML files for each heading in the table-of-contents.
pdf	Generate a PDF file (default version - 1.3).
pdf11	Generate a PDF 1.1 file for Acrobat Reader 2.0.
pdf12	Generate a PDF 1.2 file for Acrobat Reader 3.0.
pdf13	Generate a PDF 1.3 file for Acrobat Reader 4.0.

HTMLDOC 1.9 Software Users Manual

pdf14	Generate a PDF 1.4 file for Acrobat Reader 5.0.
ps	Generate one or more PostScript files (default level - 2).
ps1	Generate one or more Level 1 PostScript files.
ps2	Generate one or more Level 2 PostScript files.
ps3	Generate one or more Level 3 PostScript files.

-V

The -V option specifies that progress information should be sent/displayed to the standard error file.

--batch filename.book

The --batch option specifies a book file that you would like to generate without the GUI popping up. This option can be combined with other options to generate the same book in different formats and sizes:

```
htmldoc --batch filename.book -f filename.ps
htmldoc --batch filename.book -f filename.pdf
```

--bodycolor color

The --bodycolor option specifies the background color for all pages in the document. The color can be specified by a standard HTML color name or as a 6-digit hexadecimal number of the form #RRGGBB.

8-2 -t format

--bodyfont typeface

The --bodyfont option specifies the default text font used for text in the document body. The typeface parameter can be one of the following:

typeface	Actual Font
Arial	Helvetica
Courier	Courier
Helvetica	Helvetica
Monospace	DejaVu Sans Mono
Sans	DevaVu Sans
Serif	DejaVu Serif
Times	Times

--bodyimage filename

The --bodyimage option specifies the background image for all pages in the document. The supported formats are BMP, GIF, JPEG, and PNG.

--book

The -- book option specifies that the input files comprise a book with chapters and headings.

--bottom margin

The --bottom option specifies the bottom margin. The default units are points (1 point = 1/72nd inch); the suffixes "in", "cm", and "mm" specify inches, centimeters, and millimeters, respectively.

This option is only available when generating PostScript or PDF files.

--browserwidth pixels

The --browserwidth option specifies the browser width in pixels. The browser width is used to scale images and pixel measurements when generating PostScript and PDF files. It does not affect the font size of text.

The default browser width is 680 pixels which corresponds roughly to a 96 DPI display. Please note that your images and table sizes are equal to or smaller than the browser width, or your output will overlap or truncate in places.

--charset charset

The --charset option specifies the 8-bit character set encoding to use for the entire document. HTMLDOC comes with the following character set files:

charset	Character Set
cp-874	Windows code page 874
cp-1250	Windows code page 1250
cp-1251	Windows code page 1251
cp-1252	Windows code page 1252
cp-1253	Windows code page 1253
cp-1254	Windows code page 1254
cp-1255	Windows code page 1255
ср-1256	Windows code page 1256
cp-1257	Windows code page 1257
cp-1258	Windows code page 1258
iso-8859-1	ISO-8859-1
iso-8859-2	ISO-8859-2
iso-8859-3	ISO-8859-3
iso-8859-4	ISO-8859-4
iso-8859-5	ISO-8859-5
iso-8859-6	ISO-8859-6
iso-8859-7	ISO-8859-7
iso-8859-8	ISO-8859-8
iso-8859-9	ISO-8859-9
iso-8859-14	ISO-8859-14
iso-8859-15	ISO-8859-15
koi8-r	KOI8-R
utf-8	Unicode (UTF-8)

8-4 --charset charset

--color

The --color option specifies that color output is desired.

This option is only available when generating PostScript or PDF files.

--compression[=level]

The --compression option specifies that Flate compression should be performed on the output file(s). The optional level parameter is a number from 1 (fastest and least amount of compression) to 9 (slowest and most amount of compression).

This option is only available when generating PDF or Level 3 PostScript files.

--continuous

The --continuous option specifies that the input files comprise a web page (or site) and that no title page or table-of-contents should be generated. Unlike the --webpage option described later in this chapter, page breaks are not inserted between each input file.

This option is only available when generating PostScript or PDF files.

--cookies 'name=\"value with space\"; name=value'

The --cookies option specifies one or more HTTP cookies that should be sent when converting remote URLs. Each cookie must be separated from the others by a semicolon and a space, and values containing whitespace or the semicolon must be placed inside double-quotes. When specifying multiple cookies, the entire cookie string must be surrounded by single quotes in order for the string to be processed correctly.

--datadir directory

The --datadir option specifies the location of data files used by HTMLDOC.

--duplex

The --duplex option specifies that the output should be formatted for two sided printing.

This option is only available when generating PostScript or PDF files. Use the --pscommands option to generate PostScript duplex mode commands.

--effectduration seconds

The --effectduration option specifies the duration of a page transition effect in seconds.

This option is only available when generating PDF files.

--color 8-5

--embedfonts

The --embedfonts option specifies that fonts should be embedded in PostScript and PDF output. This is especially useful when generating documents in character sets other than ISO-8859-1.

--encryption

The --encryption option enables encryption and security features for PDF output.

This option is only available when generating PDF files.

--firstpage page

The --firstpage option specifies the first page that will be displayed in a PDF file. The page parameter can be one of the following:

page	Description
p1	The first page of the document.
toc	The first page of the table-of-contents.
c1	The first page of chapter 1.

This option is only available when generating PDF files.

--fontsize size

The --fontsize option specifies the base font size for the entire document in points (1 point = 1/72nd inch).

--fontspacing spacing

The --fontspacing option specifies the line spacing for the entire document as a multiplier of the base font size. A spacing value of 1 makes each line of text the same height as the font.

8-6 --embedfonts

--footer Icr

The --footer option specifies the contents of the page footer. The lcr parameter is a three-character string representing the left, center, and right footer fields. Each character can be one of the following:

lcr	Description	
	A period indicates that the field should be blank.	
:	A colon indicates that the field should contain the current and total number of pages in the chapter (n/N).	
/	A slash indicates that the field should contain the current and total number of pages (n/N).	
1	The number 1 indicates that the field should contain the current page number in decimal format (1, 2, 3,)	
a	A lowercase "a" indicates that the field should contain the current page number using lowercase letters.	
A	An uppercase "A" indicates that the field should contain the current page number using UPPERCASE letters.	
c	A lowercase "c" indicates that the field should contain the current chapter title.	
С	An uppercase "C" indicates that the field should contain the current chapter page number.	
d	A lowercase "d" indicates that the field should contain the current date.	
D	An uppercase "D" indicates that the field should contain the current date and time.	
h	An "h" indicates that the field should contain the current heading.	
i	A lowercase "i" indicates that the field should contain the current page number in lowercase roman numerals (i, ii, iii,)	
I	An uppercase "I" indicates that the field should contain the current page number in uppercase roman numerals (I, II, III,)	
1	A lowercase "I" indicates that the field should contain the logo image.	
t	A lowercase "t" indicates that the field should contain the document title.	
Т	An uppercase "T" indicates that the field should contain the current time.	

Setting the footer to "..." disables the footer entirely.

--footer lcr 8-7

--format format

The -- format option specifies the output format for the document and can be one of the following:

Format	Description
html	Generate one or more indexed HTML files.
htmlsep	Generate separate HTML files for each heading in the table-of-contents.
pdf	Generate a PDF file (default version - 1.3).
pdf11	Generate a PDF 1.1 file for Acrobat Reader 2.0.
pdf12	Generate a PDF 1.2 file for Acrobat Reader 3.0.
pdf13	Generate a PDF 1.3 file for Acrobat Reader 4.0.
pdf14	Generate a PDF 1.4 file for Acrobat Reader 5.0.
ps	Generate one or more PostScript files (default level - 2).
ps1	Generate one or more Level 1 PostScript files.
ps2	Generate one or more Level 2 PostScript files.
ps3	Generate one or more Level 3 PostScript files.

--gray

The --gray option specifies that grayscale output is desired.

This option is only available when generating PostScript or PDF files.

--header Icr

The --header option specifies the contents of the page header. The lcr parameter is a three-character string representing the left, center, and right header fields. See the <u>--footer</u> option for the list of formatting characters.

Setting the header to "..." disables the header entirely.

8-8 --format format

--headfootfont font

The --headfootfont option specifies the font that is used for the header and footer text. The font parameter can be one of the following:

- · Courier
- · Courier-Bold
- · Courier-Oblique
- · Courier-BoldOblique
- Helvetica
- · Helvetica-Bold
- · Helvetica-Oblique
- · Helvetica-BoldOblique
- Monospace
- Monospace-Bold
- Monospace-Oblique
- Monospace-BoldOblique
- Sans
- · Sans-Bold
- · Sans-Oblique
- · Sans-BoldOblique
- Serif
- Serif-Roman
- · Serif-Bold
- · Serif-Italic
- Serif-BoldItalic
- · Times
- · Times-Roman
- · Times-Bold
- · Times-Italic
- · Times-BoldItalic

This option is only available when generating PostScript or PDF files.

--headfootsize size

The --headfootsize option sets the size of the header and footer text in points (1 point = 1/72nd inch).

This option is only available when generating PostScript or PDF files.

--headfootfont font 8-9

--headingfont typeface

The --headingfont options sets the typeface that is used for headings in the document. The typeface parameter can be one of the following:

typeface	Actual Font
Arial	Helvetica
Courier	Courier
Helvetica	Helvetica
Monospace	DejaVu Sans Mono
Sans	DevaVu Sans
Serif	DejaVu Serif
Times	Times

--help

The --help option displays all of the available options to the standard output file.

--helpdir directory

The --helpdir option specifies the location of the on-line help files.

--jpeg[=quality]

The -- jpeg option enables JPEG compression of continuous-tone images. The optional quality parameter specifies the output quality from 0 (worst) to 100 (best).

This option is only available when generating PDF or Level 2 and Level 3 PostScript files.

--landscape

The --landscape option specifies that the output should be in landscape orientation (long edge on top).

This option is only available when generating PostScript or PDF files.

--left margin

The --left option specifies the left margin. The default units are points (1 point = 1/72nd inch); the suffixes "in", "cm", and "mm" specify inches, centimeters, and millimeters, respectively.

This option is only available when generating PostScript or PDF files.

--linkcolor color

The --linkcolor option specifies the color of links in HTML and PDF output. The color can be specified by name or as a 6-digit hexadecimal number of the form #RRGGBB.

--links

The --links option specifies that PDF output should contain hyperlinks.

--linkstyle style

The --linkstyle option specifies the style of links in HTML and PDF output. The style can be "plain" for no decoration or "underline" to underline links.

--logoimage filename

The --logoimage option specifies the logo image for the HTML navigation bar and page headers and footers for PostScript and PDF files. The supported formats are BMP, GIF, JPEG, and PNG.

Note:

You need to use the --header and/or --footer options with the l parameter or use the corresponding HTML page comments to display the logo image in the header or footer.

The following example uses the --header option:

htmldoc --logoimage image.png --header lt. -f file.pdf file.html

--no-compression

The --no-compression option specifies that Flate compression should not be performed on the output files.

--no-duplex

The --no-duplex option specifies that the output should be formatted for one sided printing.

This option is only available when generating PostScript or PDF files. Use the --pscommands option to generate PostScript duplex mode commands.

--no-embedfonts

The --no-embedfonts option specifies that fonts should not be embedded in PostScript and PDF output.

--linkcolor color 8-11

--no-encryption

The --no-encryption option specifies that no encryption/security features should be enabled in PDF output.

This option is only available when generating PDF files.

--no-jpeg

The --no-jpeg option specifies that JPEG compression should not be performed on large images.

--no-links

The --no-links option specifies that PDF output should not contain hyperlinks.

--no-localfiles

The --no-localfiles option disables access to local files on the system. This option should be used when providing remote document conversion services.

--no-numbered

The --no-numbered option specifies that headings should not be numbered.

--no-pscommands

The --no-pscommands option specifies that PostScript device commands should not be written to the output files.

--no-strict

The --no-strict option turns off strict HTML conformance checking.

--no-title

The --no-title option specifies that the title page should not be generated.

--no-toc

The --no-toc option specifies that the table-of-contents pages should not be generated.

--no-xrxcomments

The --no-xrxcomments option specifies that Xerox PostScript job comments should not be written to the output files.

This option is only available when generating PostScript files.

--numbered

The -- numbered option specifies that headings should be numbered.

--nup pages

The --nup option sets the number of pages that are placed on each output page. Valid values for the pages parameter are 1, 2, 4, 6, 9, and 16.

--outdir directory

The --outdir option specifies an output directory for the document files.

This option is not compatible with the PDF output format.

--outfile filename

The --outfile option specifies an output file for the document.

--owner-password password

The --owner-password option specifies the owner password for a PDF file. If not specified or the empty string (""), a random password is generated.

This option is only available when generating PDF files.

--pageduration seconds

The --pageduration option specifies the number of seconds that each page will be displayed in the document.

This option is only available when generating PDF files.

--numbered 8-13

--pageeffect effect

The --pageeffect option specifies the page effect to use in PDF files. The effect parameter can be one of the following:

effect	Description			
none	No effect is generated.			
bi	Box Inward			
bo	Box Outward			
d	Dissolve			
gd	Glitter Down			
gdr	Glitter Down and Right			
gr	Glitter Right			
hb	Horizontal Blinds			
hsi	Horizontal Sweet Inward			
hso	Horizontal Sweep Outward			
vb	Vertical Blinds			
vsi	Vertical Sweep Inward			
vso	Vertical Sweep Outward			
wd	Wipe Down			
wl	Wipe Left			
wr	Wipe Right			
wu	Wipe Up			

This option is only available when generating PDF files.

--pagelayout layout

The --pagelayout option specifies the initial page layout in the PDF viewer. The layout parameter can be one of the following:

layout	Description			
single	A single page is displayed.			
one	A single column is displayed.			
twoleft	Two columns are displayed with the first page on the left.			
tworight	Two columns are displayed with the first page on the right.			

This option is only available when generating PDF files.

--pagemode mode

The --pagemode option specifies the initial viewing mode in the PDF viewer. The mode parameter can be one of the following:

mode	Description		
document	The document pages are displayed in a normal window.		
outline	The document outline and pages are displayed.		
fullscreen	The document pages are displayed on the entire screen in "slideshow" mode.		

This option is only available when generating PDF files.

--path dir1;dir2;dir3;...;dirN

The --path option specifies a search path for files that are loaded by HTMLDOC. It is usually used to get images that use absolute server paths to load.

Directories are separated by the semicolon (;) so that drive letters and URLs can be specified. Quotes around the directory parameter are optional. They are usually used when the directory string contains spaces.

--permissions permission[,permission,...]

The --permissions option specifies the document permissions. The available permission parameters are listed below:

Permission	Description			
all	All permissions			
annotate	User can annotate document			
copy	User can copy text and images from document			
modify	User can modify document			
print	User can print document			
no-annotate	User cannot annotate document			
no-copy	User cannot copy text and images from document			
no-modify	User cannot modify document			
no-print	User cannot print document			
none	No permissions			

The --encryption option must be used in conjunction with the --permissions parameter.

--permissions no-print --encryption

Multiple options can be specified by separating them with commas:

--permissions no-print, no-copy --encryption

This option is only available when generating PDF files.

--portrait

The --portrait option specifies that the output should be in portrait orientation (short edge on top).

This option is only available when generating PostScript or PDF files.

--pscommands

The --pscommands option specifies that PostScript device commands should be written to the output files.

This option is only available when generating Level 2 and Level 3 PostScript files.

--quiet

The --quiet option prevents error messages from being sent to stderr.

--referer url

The --referer option sets the URL that is passed in the Referer: field of HTTP requests.

--right margin

The -- right option specifies the right margin. The default units are points (1 point = 1/72nd inch); the suffixes "in", "cm", and "mm" specify inches, centimeters, and millimeters, respectively.

This option is only available when generating PostScript or PDF files.

--size size

The -- size option specifies the page size. The size parameter can be one of the following standard sizes:

size	Description
Letter	8.5x11in (216x279mm)
A4	8.27x11.69in (210x297mm)
Universal	8.27x11in (210x279mm)

Custom sizes are specified by the page width and length separated by the letter "x" to select a custom page size. Append the letters "in" for inches, "mm" for millimeters, or "cm" for centimeters.

This option is only available when generating PostScript or PDF files. Use the --pscommands option to generate PostScript page size commands.

--strict

The --strict option turns on strict HTML conformance checking. When enabled, HTML elements that are improperly nested and dangling close elements will produce error messages.

--textcolor color

The --textcolor option specifies the default text color for all pages in the document. The color can be specified by a standard HTML color name or as a 6-digit hexadecimal number of the form #RRGGBB.

--quiet 8-17

--textfont typeface

The --textfont options sets the typeface that is used for text in the document. The typeface parameter can be one of the following:

typeface	Actual Font	
Arial	Helvetica	
Courier	Courier	
Helvetica	Helvetica	
Monospace	DejaVu Sans Mono	
Sans	DevaVu Sans	
Serif	DejaVu Serif	
Times	Times	

--title

The --title option specifies that a title page should be generated.

--titlefile filename

The --titlefile option specifies a HTML file to use for the title page.

--titleimage filename

The --titleimage option specifies the title image for the title page. The supported formats are BMP, GIF, JPEG, and PNG.

--tocfooter Icr

The --tocfooter option specifies the contents of the table-of-contents footer. The lcr parameter is a three-character string representing the left, center, and right footer fields. See the <u>--footer</u> option for the list of formatting characters.

Setting the TOC footer to "..." disables the TOC footer entirely.

--tocheader Icr

The --tocheader option specifies the contents of the table-of-contents header. The lcr parameter is a three-character string representing the left, center, and right header fields. See the <u>--footer</u> option for the list of formatting characters.

Setting the TOC header to "..." disables the TOC header entirely.

--toclevels levels

The --toclevels options specifies the number of heading levels to include in the table-of-contents pages. The levels parameter is a number from 1 to 6.

--toctitle string

The --toctitle options specifies the string to display at the top of the table-of-contents; the default string is "Table of Contents".

--top margin

The --top option specifies the top margin. The default units are points (1 point = 1/72nd inch); the suffixes "in", "cm", and "mm" specify inches, centimeters, and millimeters, respectively.

This option is only available when generating PostScript or PDF files.

--user-password password

The --user-password option specifies the user password for a PDF file. If not specified or the empty string (""), no password will be required to view the document.

This option is only available when generating PDF files.

--verbose

The --verbose option specifies that progress information should be sent/displayed to the standard error file.

--version

The --version option displays the HTMLDOC version number.

--webpage

The --webpage option specifies that the input files comprise a web page (or site) and that no title page or table-of-contents should be generated. HTMLDOC will insert a page break between each input file.

This option is only available when generating PostScript or PDF files.

--xrxcomments

The --xrxcomments option specifies that Xerox PostScript job comments should be written to the output files.

This option is only available when generating PostScript files.

--toclevels levels 8-19

Environment Variables

HTMLDOC looks for several environment variables which can override the default directories, display additional debugging information, and disable CGI mode.

HTMLDOC DATA

This environment variable specifies the location of HTMLDOC's *data* and *fonts* directories, normally /usr/share/htmldoc or C:\Program Files\Easy Software Products\HTMLDOC.

HTMLDOC_DEBUG

This environment variable enables debugging information that is sent to stderr. The value is a list of keywords separated by spaces:

keyword	Information Shown			
links	Shows all of the links in a document			
memory	Shows memory usage statistics			
remotebytes	Shows the number of bytes that were transferred via HTTP			
table	Puts a box around each table, row, and cell			
tempfiles	Shows the temporary files that were created, and preserves them for debugging			
timing	Shows the load and render times			
all	All of the above			

HTMLDOC_HELP

This environment variable specifies the location of HTMLDOC's documentation directory, normally /usr/share/doc/htmldoc or C:\Program Files\Easy Software Products\HTMLDOC\doc.

HTMLDOC_NOCGI

This environment variable, when set (the value doesn't matter), disables CGI mode. It is most useful for using HTMLDOC on a web server from a scripting language or invocation from a program.

Messages

HTMLDOC sends error and status messages to stderr unless the --quiet option is provided on the command-line. Applications can capture these messages to relay errors or statistics to the user.

BYTES: Message

The BYTES: message specifies the number of bytes that were written to an output file. If the output is directed at a directory then multiple BYTES: messages will be sent.

DEBUG: Messages

The DEBUG: messages contain debugging information based on the value of the HTMLDOC_DEBUG environment variable. Normally, no DEBUG: messages are sent by HTMLDOC.

ERRnnn: Messages

The ERRnnn: messages specify an error condition. Error numbers 1 to 14 map to the following errors:

- 1. No files were found or loadable.
- 2. No pages were generated.
- 3. The document contains too many files or chapters.
- 4. HTMLDOC ran out of memory.
- 5. The specified file could not be found.
- 6. The comment contains a bad HTMLDOC formatting command.
- 7. The image file is not in a known format.
- 8. HTMLDOC was unable to remove a temporary file.
- 9. HTMLDOC had an unspecified internal error.
- 10. HTMLDOC encountered a networking error when retrieving a file via a URL.
- 11. HTMLDOC was unable to read a file.
- 12. HTMLDOC was unable to write a file.
- 13. A HTML error was found in a source file.
- 14. A table, image, or text fragment was too large to fit in the space provided.
- 15. A hyperlink in the source files was unresolved.
- 16. A header/footer string in the document contains a bad \$ command.

Error numbers 100 to 505 correspond directly to a HTTP status code.

INFO: Messages

The INFO: messages contain general information that is logged when HTMLDOC is running in CGI mode or when you use the --verbose option.

PAGES: Message

The PAGES: message specifies the number of pages that were written to an output file. If the output is directed at a directory then multiple PAGES: messages will be sent. No PAGES: messages are sent when generating HTML output.

Messages 8-21

REMOTEBYTES: Message

The REMOTEBYTES: message specifies the number of bytes that were transferred using HTTP. This message is only displayed if the HTMLDOC_DEBUG environment variable has the keyword remotebytes or all.

TIMING: Message

The TIMING: message specifies the load, render, and total time in seconds for the current command. This message is only displayed if the HTMLDOC_DEBUG environment variable has the keyword timing or all.

REMOTEBYTES: Message

Appendix A - License Agreement

Introduction

HTMLDOC is distributed in both source code and binary (executable) forms. The source code is provided under the terms of the GNU General Public License ("GPL") with a license exception for the OpenSSL toolkit. A copy of the source code license can be found in the file *COPYING.txt* in the source code distribution.

The binaries are provided under a typical commercial software end-user license agreement which is more restrictive than the GNU GPL.

Source Code and the GNU GPL

For those not familiar with the GNU GPL, the license basically allows you to:

- · Use the HTMLDOC software and source code at no charge.
- · Distribute verbatim copies of the software in source form or as binaries you create.
- · Sell verbatim copies of the software for a media fee, or sell support for the software.
- · Distribute or sell your own modified version of HTMLDOC so long as the source code is made available under the GPL.

What this license **does not** allow you to do is make changes or add features to HTMLDOC and then sell a binary distribution without source code. You must provide source for any changes or additions to the software, and all code must be provided under the GPL.

Trademarks

Easy Software Products has trademarked the HTMLDOC name. You may use the name in any direct port or binary distribution of HTMLDOC. Please contact Easy Software Products for written permission to use the name in derivative products. Our intention is to protect the value of this trademark and ensure that any derivative product meets the same high-quality standards as the original.

Binary Distribution Rights

Easy Software Products also sells rights to the HTMLDOC source code under a binary distribution license for vendors that are unable to release source code for their additions and modifications to HTMLDOC under the GNU GPL. For information please contact us at the address shown above.

Binaries and Support

Easy Software Products sells commercial HTMLDOC binaries and support. You can find out more at the HTMLDOC commercial home page:

http://www.easvsw.com/htmldoc/

End-User License Agreement

PLEASE READ THIS DOCUMENT CAREFULLY. THIS IS A LEGAL AGREEMENT BETWEEN YOU AND EASY SOFTWARE PRODUCTS ("ESP"). BY INSTALLING THIS PACKAGE, AND USING THE HTMLDOC SOFTWARE AND DOCUMENTATION ("SOFTWARE") CONTAINED IN THIS PACKAGE, YOU ARE AGREEING TO BECOME BOUND BY THE TERMS AND CONDITIONS OF THIS AGREEMENT. THIS AGREEMENT REPRESENTS THE ENTIRE AND SOLE AGREEMENT CONCERNING THE ESP SOFTWARE, AND IT SUPERSEDES ANY PRIOR PROPOSAL, REPRESENTATION OR UNDERSTANDING REGARDING THE SOFTWARE BETWEEN YOU AND ESP OR ANY OTHER PARTY. IF YOU (hereafter in this document referred to as "LICENSEE") ARE NOT WILLING TO BE BOUND BY THE TERMS OF THIS LICENSE AGREEMENT, PLEASE DO NOT INSTALL OR USE THIS SOFTWARE.

TERMS AND CONDITIONS OF SOFTWARE LICENSE

- 1. **GRANT OF LICENSE; USE RESTRICTIONS**. In consideration for the payment of a license fee, ESP grants to LICENSEE a personal, nontransferable (except as provided below) and nonexclusive right to use the SOFTWARE on one (1) computer system, solely for LICENSEE's internal business purposes. LICENSEE agrees that it shall not reverse compile or disassemble any portion of the SOFTWARE not already provided by ESP in source code form.
- 2. **OWNERSHIP OF SOFTWARE**. LICENSEE agrees that no title to the SOFTWARE, or the intellectual property in any of the SOFTWARE, or in any SOFTWARE copy, is transferred to LICENSEE, and that all rights not expressly granted to LICENSEE hereunder are reserved by ESP. This license is not a sale of the original SOFTWARE or any copy thereof.
- 3. **TRANSFER RESTRICTIONS**. If LICENSEE transfers ownership, or otherwise disposes, of a computer system for which a license for the SOFTWARE was purchased, provided that the transferee agrees to accept the terms and conditions of this AGREEMENT, LICENSEE may transfer the SOFTWARE and all licenses and rights in SOFTWARE granted under this AGREEMENT to such transferee, provided that all SOFTWARE copies are also transferred.
- 4. **DISCLOSURE RESTRICTIONS**. LICENSEE agrees to not disclose or otherwise disseminate software licensing information, including the so-called "license key" provided to LICENSEE by ESP, to third parties other than ESP or its official distributors. Should LICENSEE violate this restriction, LICENSEE shall comply with the termination clause of this license and pay a penalty fee of \$1000 US per offense or \$100,000 US, whichever is greater. This restriction does not apply if the license is being transferred according to the rules in paragraph 3.
- 5. **TERMINATION**. If licensee fails to fulfill any of LICENSEE's material obligations under this AGREEMENT, ESP may, at any time thereafter, and in addition to any other available remedies, terminate this AGREEMENT and all licenses and rights granted to LICENSEE under this AGREEMENT. Upon termination of this AGREEMENT, LICENSEE shall, within thirty (30) days after termination, deliver to ESP all removable media and documentation containing the SOFTWARE, and shall render unusable all copies of the SOFTWARE placed in any storage apparatus.
- 6. **GOVERNING LAW**. This License is governed by the laws of the State of Maryland, U.S.A., excluding choice of law rules. If any part of this License is found to be in conflict with the law, that part shall be interpreted in its broadest meaning consistent with the law, and no other parts of the License shall be affected.
- 7. **U.S. GOVERNMENT USERS**. This SOFTWARE is provided with RESTRICTED RIGHTS. If you are a unit or agency of the United States Government or are acquiring the Software for any such unit or agency, the following applies:

If the unit or agency is the Department of Defense ("DOD"), the SOFTWARE and its documentation are classified as "commercial computer software" and "commercial computer software documentation" respectively and, pursuant to DFAR Section 227.7202, the Government is acquiring the SOFTWARE and its documentation in accordance with the terms of this License. If the unit or agency is other than DOD, the SOFTWARE and its documentation are classified as "commercial computer software" and "commercial computer software documentation" respectively and, pursuant to FAR Section 12.212, the Government is acquiring the SOFTWARE and its documentation in accordance with the terms of this License.

LIMITED WARRANTY AND DISCLAIMER OF WARRANTY; LIMITATION OF LIABILITY

ESP warrants that it has the authority and right to license the SOFTWARE, and that the SOFTWARE will conform to the material printed specifications therefore which are in effect on the date of original delivery of such SOFTWARE. ESP's warranty and obligation shall extend for a period of ninety (90) days after the date of the original delivery of SOFTWARE to LICENSEE by ESP, and is solely for the benefit of LICENSEE, who has no authority to assign or pass through this warranty to any other person or entity.

Except as provided in this Section, the SOFTWARE is provided to LICENSEE on an "AS IS" basis, and ESP makes no other warranty of any kind, express or implied, with regard to the SOFTWARE licensed hereunder. ESP warrants that the SOFTWARE properly processes date and time information between the years 1970 and 2038. ESP does not warrant or represent that the SOFTWARE will operate uninterrupted or error free or that all defects in the SOFTWARE are correctable or will be corrected. This warranty shall not apply if SOFTWARE is used other than in accordance with ESP's written instructions, or if any of LICENSEE's hardware equipment or other software malfunctions. ESP's entire liability and LICENSEE's exclusive remedy for any defects in the SOFTWARE shall be to obtain ESP's SOFTWARE updates via the Internet or pay a media update fee for each copy of the SOFTWARE.

THE FORGOING WARRANTIES ARE IN LIEU OF, AND ESP DISCLAIMS, ALL OTHER WARRANTIES, EXPRESS OR IMPLIED, INCLUDING, WITHOUT LIMITATION, ANY WARRANTY OF MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow the exclusion of implied warranties, so the exclusion above may not apply to LICENSEE. This warranty gives LICENSEE specific legal rights, and LICENSEE may have other rights which vary from state to state.

IN NO EVENT SHALL ESP OR ESP'S LICENSORS BE LIABLE TO LICENSEE FOR ANY SPECIAL, CONSEQUENTIAL, INCIDENTAL OR INDIRECT DAMAGES OF ANY KIND (INCLUDING WITHOUT LIMITATION LOSS OF PROFITS OR DATA AND PERSONAL INJURY), WHETHER OR NOT ESP HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH LOSS, HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, ARISING OUT OF THIS AGREEMENT. THESE LIMITATIONS SHALL APPLY NOTWITHSTANDING THE FAILURE OF THE ESSENTIAL PURPOSE OF ANY LIMITED REMEDY. In no event will ESP be liable for any claim against LICENSEE by a third party, and LICENSEE hereby agrees to indemnify and hold ESP harmless for any claims for cost, damage, expense or liability arising out of or in connection with the installation, use and performance of the SOFTWARE licensed hereunder, whether alone or in combination with any other product or service. Some states do not allow the limitation or exclusion of liability for incidental or consequential damages, so the limitation above may not apply to LICENSEE.

Appendix B - Book File Format

This appendix describes the HTMLDOC .book file format.

Introduction

The HTMLDOC .book file format is a simple text format that provides the command-line options and files that are part of the document. These files can be used from the GUI interface or from the command-line using the --batch option:

```
htmldoc filename.book
htmldoc --batch filename.book
```

The first form will load the book and display the GUI interface, if configured. Windows users should use *ghtmldoc.exe* executable to show the GUI and *htmldoc.exe* for the batch mode:

```
ghtmldoc.exe filename.book
htmldoc.exe --batch filename.book
```

The Header

Each .book file starts with a line reading:

```
#HTMLDOC 1.8.17
```

The version number (1.8.17) is optional.

The Options

Following the header is a line containing the options for the book. You can use any valid command-line option on this line:

```
-f htmldoc.pdf --titleimage htmldoc.png --duplex --compression=9 --jpeg=90
```

Long option lines can be broken using a trailing backslash $(\)$ on the end of each continuation line:

```
-f htmldoc.pdf --titleimage htmldoc.png --duplex \
--compression=9 --jpeg=90
```

The Files

Following the options are a list of files or URLs to include in the document:

```
intro.html
1-install.html
2-starting.html
3-books.html
4-cmdline.html
5-cgi.html
6-htmlref.html
```

```
7-guiref.html
8-cmdref.html
a-license.html
b-book.html
c-relnotes.html
```

Putting It All Together

The following is the complete book file needed to generate this documentation:

```
#HTMLDOC 1.8.13
-f htmldoc.pdf --titleimage htmldoc.png --duplex --compression=9 --jpeg=90
intro.html
1-install.html
2-starting.html
3-books.html
4-cmdline.html
5-cgi.html
6-htmlref.html
7-guiref.html
8-cmdref.html
a-license.html
b-book.html
c-relnotes.html
```

B-2 The Files

Appendix C - Release Notes

This appendix provides the release notes for each version of HTMLDOC.

Changes in HTMLDOC v1.9b1

- The header and footer margins no longer include the logo image height if no image is used (STR #174)
- The table-of-contents code did not validate the current heading number (STR #183)
- · HTMLDOC no longer terminates comments when it sees only "->" on the end (STR #181)
- · Fixed handling of percent-encoded URLs (STR #186)
- · HTMLDOC now provides much better support for "wrapping" of text around images and new support for tables via the ALIGN attribute (STR #16)

Appendix D - Compiling HTMLDOC from Source

This chapter describes the steps needed to install HTMLDOC on your system from the source distributions.

Requirements

HTMLDOC requires ANSI C and C++ compilers - recent versions of GCC work fine. To build the GUI you'll also need:

- Fast Light Tool Kit ("FLTK"), version 1.1 or higher.
- · X11 libraries, R5 or higher (needed to build under UNIX/Linux only.)

Secure (https) URL support can be enabled via the OpenSSL library. You should use at least version 0.9.8j.

Compiling under UNIX/Linux

HTMLDOC uses a configuration script produced by GNU autoconf to configure itself for your system. If your ANSI C compiler is not called *cc* or *gcc*, set the CC environment variable to the name and path of your ANSI C compiler:

Similarly, if your C++ compiler is not called CC, gcc, c++, or g++, set the CXX environment variable to the name and path of your C++ compiler:

```
setenv CXX /path/to/compiler [C Shell]
CXX=/path/to/compiler; export CXX [Bourne/Korn Shell]
```

Then run the following command to configure HTMLDOC for installation in the default directories:

```
./configure
```

The default configuration will install HTMLDOC in the /usr/bin directory with the data files under /usr/share/htmldoc and the documentation and on-line help under /usr/share/doc/htmldoc. Use the --prefix option to change the installation prefix to a different directory such as /usr/local:

```
./configure --prefix=/usr/local
```

If the OpenSSL library is not installed in a standard location for your compilers, use the --with-openssl-includes and --with-openssl-libs options to point to the OpenSSL library:

```
./configure --with-openssl-libs=/path/to/openssl/lib \
    --with-openssl-includes=/path/to/openssl
```

HTMLDOC is built from a Makefile in the distribution's main directory. Simply run the "make" command to build HTMLDOC:

make

If you get any fatal errors, please report them on the htmldoc.general newsgroup at:

http://www.easysw.com/newsgroups.php

Please note the version of HTMLDOC that you are using as well as any pertinent system information such as the operating system, OS version, compiler, and so forth. Omitting this information may delay or prevent a solution to your problem.

Once you have compiled the software successfully, you may install HTMLDOC by running the following command:

make install

If you are installing in a restricted directory like /usr then you'll need to be logged in as root.

Compiling on Windows Using Visual C++

A Visual C++ 6.0 workspace file and associated project files are included in the source distribution under the "visualc" directory. Open the workspace file "htmldoc.dsw", adjust the FLTK include and project file locations, and then build the HTMLDOC target.

Note:

You also need to download the OpenSSL and FLTK libraries in order to compile HTMLDOC with Visual C++.

Installing with Visual C++

To install HTMLDOC with Visual C++, create an installation directory and copy the *ghtmldoc.exe* and *htmldoc.exe* executables, the *afm* directoryj, the *data* directory, and the *doc* directory to it.

Then use the *regedit* program to create the following two string entries:

HKEY_LOCAL_MACHINE\Software\Easy Software Products\HTMLDOC\data C:\installation\directory

HKEY_LOCAL_MACHINE\Software\Easy Software Products\HTMLDOC\doc C:\installation\directory\doc

Index

```
_
```

--book <u>4-3</u>, <u>8-3</u>,

--webpage <u>4-2</u>, <u>6-1</u>, <u>8-5</u>, <u>8-19</u>,

Α

Apache 5-1, 5-2,

В

book 1, 3-1, 3-2, 4-3, 5-2, 7-1, 7-2, 8-2, 8-3, B-1, B-2

C

CGI <u>5-1</u>, <u>5-2</u>, <u>5-3</u>, <u>5-6</u>, <u>5-7</u>, <u>5-8</u>, <u>5-9</u>, <u>8-20</u>, <u>8-21</u>

command-line <u>1</u>, <u>4-1</u>, <u>4-2</u>, <u>5-9</u>, <u>6-1</u>, <u>7-12</u>, <u>8-1</u>, <u>8-21</u>, <u>B-1</u>,

Ε

element 3-1, 4-3, 6-1, 6-2, 6-3, 6-9

encryption <u>2</u>, <u>7-10</u>, <u>8-6</u>, <u>8-12</u>

environment variables 5-8, 8-20,

Н

HTML <u>1</u>, <u>2-1</u>, <u>2-2</u>, <u>3-1</u>, <u>3-2</u>, <u>4-2</u>, <u>4-3</u>, <u>5-8</u>, <u>5-10</u>, <u>5-13</u>, <u>6-1</u>, <u>6-2</u>, <u>6-4</u>, <u>6-7</u>, <u>6-9</u>, <u>7-1</u>, <u>7-2</u>, <u>7-3</u>, <u>7-7</u>, <u>7-11</u>, <u>7-12</u>, <u>8-1</u>, <u>8-2</u>, <u>8-8</u>, <u>8-11</u>, <u>8-12</u>, <u>8-17</u>, <u>8-18</u>, <u>8-21</u>,

ı

IIS <u>5-1</u>, <u>5-2</u>, <u>5-3</u>, <u>5-7</u>,

install <u>1-1</u>, <u>1-2</u>, <u>1-3</u>, <u>5-2</u>, <u>A-2</u>, <u>1-1</u>, <u>1-2</u>,

J

Java <u>5-1</u>, <u>5-13</u>,

0

output file 2-2, 3-2, 7-3, 8-1, 8-5, 8-10, 8-13, 8-21,

Index 1-1

P

page comments <u>6-9</u>, <u>8-11</u>

PDF <u>1</u>, <u>2</u>, <u>2-1</u>, <u>2-2</u>, <u>3-1</u>, <u>3-2</u>, <u>4-2</u>, <u>4-3</u>, <u>5-1</u>, <u>5-2</u>, <u>5-7</u>, <u>5-8</u>, <u>5-9</u>, <u>5-10</u>, <u>5-12</u>, <u>5-13</u>, <u>6-1</u>, <u>6-9</u>, <u>7-1</u>, <u>7-3</u>, <u>7-4</u>, <u>7-5</u>, <u>7-8</u>, <u>7-9</u>, <u>7-10</u>, <u>7-11</u>, <u>8-1</u>, <u>8-2</u>, <u>8-3</u>, <u>8-5</u>, <u>8-6</u>, <u>8-8</u>, <u>8-9</u>, <u>8-10</u>, <u>8-11</u>, <u>8-12</u>, <u>8-13</u>, <u>8-14</u>, <u>8-15</u>, <u>8-16</u>, <u>8-17</u>, <u>8-19</u>,

Perl 5-10,

PHP <u>5-1</u>, <u>5-10</u>, <u>5-11</u>

PostScript <u>1</u>, <u>2</u>, <u>2-1</u>, <u>3-1</u>, <u>4-3</u>, <u>5-8</u>, <u>6-7</u>, <u>7-1</u>, <u>7-3</u>, <u>7-4</u>, <u>7-5</u>, <u>7-8</u>, <u>7-9</u>, <u>7-11</u>, <u>8-2</u>, <u>8-3</u>, <u>8-5</u>, <u>8-6</u>, <u>8-8</u>, <u>8-9</u>, <u>8-10</u>, <u>8-11</u>, <u>8-12</u>, <u>8-16</u>, <u>8-17</u>, <u>8-19</u>,

S

starting <u>2-1</u>, <u>6-8</u>

style <u>2-1</u>, <u>7-7</u>, <u>7-8</u>, <u>8-11</u>,

W

web server 1, 5-1, 5-2, 5-7, 5-8, 5-13, 8-20