Addressing Modes

2.1. DATA DECLARATION

The first instruction of our first assembly language program was "mov ax, 5." Here MOV was the opcode, AX was the destination operand, while 5 was the source operand. The value of 5 in this case was stored as part of the instruction encoding. In the opcode B80500, B8 was the opcode and 0500 was the operand stored immediately afterwards. Such an operand is called an immediate operand. It is one of the many types of operands available.

Writing programs using just the immediate operand type is difficult. Every reasonable program needs some data in memory apart from constants. Constants cannot be changed, i.e. they cannot appear as the destination operand. In fact placing them as destination is meaningless and illegal according to assembly language syntax. Only registers or data placed in memory can be changed. So real data is the one stored in memory, with a very few constants. So there must be a mechanism in assembly language to store and retrieve data from memory.

To declare a part of our program as holding data instead of instructions we need a couple of very basic but special assembler directives. The first directive is "define byte" written as "db."

db somevalue

As a result a cell in memory will be reserved containing the desired value in it and it can be used in a variety of ways. Now we can add variables instead of constants. The other directive is "define word" or "dw" with the same syntax as "db" but reserving a whole word of 16 bits instead of a byte. There are directives to declare a double or a quad word as well but we will restrict ourselves to byte and word declarations for now. For single byte we use db and for two bytes we use dw.

To refer to this variable later in the program, we need the address occupied by this variable. The assembler is there to help us. We can associate a symbol with any address that we want to remember and use that symbol in the rest of the code. The symbol is there for our own comprehension of code. The assembler will calculate the address of that symbol using our origin directive and calculating the instruction lengths or data declarations inbetween and replace all references to the symbol with the corresponding address. This is just like variables in a higher level language, where the compiler translates them into addresses; just the process is hidden from the programmer one level further. Such a symbol associated to a point in the program is called a label and is written as the label name followed by a colon.

2.2. DIRECT ADDRESSING

Now we will rewrite our first program such that the numbers 5, 10, and 15 are stored as memory variables instead of constants and we access them from there.

	Example 2.1
001 002 003	; a program to add three numbers using memory variables [org 0x0100]
003	mov ax, [num1] ; load first number in ax

```
004
                      mov
                           bx, [num2]
                                             ; load second number in bx
005
                      add
                           ax, bx
                                              ; accumulate sum in ax
006
                                              ; load third number in bx
                      mov
                           bx, [num3]
                           ax, bx
007
                      add
                                              ; accumulate sum in ax
008
                                             ; store sum in num4
                           [num4], ax
                      mov
009
010
                      mov
                           ax, 0x4c00
                                              ; terminate program
                          0x21
011
                      int
012
        num1:
013
                      dw
014
        num2:
                      dw
                           10
015
        num3:
                      dw
                           15
016
        num4:
                      dw
                           0
002
        Originate our program at 0100. The first executable instruction
        should be placed at this offset.
003
        The source operand is changed from constant 5 to [num1]. The
        bracket is signaling that the operand is placed in memory at address
        num1. The value 5 will be loaded in ax even though we did not
        specified it in our program code, rather the value will be picked from
        memory. The instruction should be read as "read the contents of
        memory location num1 in the ax register." The label num1 is a
        symbol for us but an address for the processor while the conversion
        is done by the assembler.
013
        The label num1 is defined as a word and the assembler is requested
        to place 5 in that memory location. The colon signals that num1 is a
        label and not an instruction.
```

Using the same process to assemble as discussed before we examine the listing file generated as a result with comments removed.

```
1
                                      [org 0x0100]
 3 00000000 A1[1700]
                                                          ax, [num1]
                                                     mov
 4 00000003 8B1E[1900]
                                                          bx, [num2]
                                                     mov
 5 00000007 01D8
                                                     add
                                                          ax, bx
 6 00000009 8B1E[1B00]
                                                          bx, [num3]
                                                     mov
 7 0000000D 01D8
                                                     add
                                                          ax, bx
 8 0000000F A3[1D00]
                                                     mov
                                                          [num4], ax
10 00000012 B8004C
                                                          ax, 0x4c00
                                                     mov
11 00000015 CD21
                                                          0x21
                                                     int
12
13 00000017 0500
                                      num1:
                                                     dw
14 00000019 0A00
                                      num2:
                                                     dw
                                                          10
                                                          15
15 0000001B 0F00
                                      num3:
                                                     dw
16 0000001D 0000
                                      num4:
                                                     dw
```

The first instruction of our program has changed from B80500 to A11700. The opcode B8 is used to move constants into AX, while the opcode A1 is used when moving data into AX from memory. The immediate operand to our new instruction is 1700 or as a word 0017 (23 decimal) and from the bottom of the listing file we can observe that this is the offset of num1. The assembler has calculated the offset of num1 and used it to replace references to num1 in the whole program. Also the value 0500 can be seen at offset 0017 in the file. We can say contents of memory location 0017 are 0005 as a word. Similarly num2, num3, and num4 are placed at 0019, 001B, and 001D addresses.

When the program is loaded in the debugger, it is loaded at offset 0100, which displaces all memory accesses in our program. The instruction A11700 is changed to A11701 meaning that our variable is now placed at 0117 offset. The instruction is shown as mov ax, [0117]. Also the data window can be used to verify that offset 0117 contains the number 0005.

Execute the program step by step and examine how the memory is read and the registers are updated, how the instruction pointer moves forward, and how the result is saved back in memory. Also observe inside the debugger code window below the code for termination, that the debugger is interpreting our data as code and showing it as some meaningless instructions. This is because the debugger sees everything as code in the code window and cannot differentiate our declared data from opcodes. It is our responsibility that we terminate execution before our data is executed as code.

Also observe that our naming of num1, num2, num3, and num4 is no longer there inside the debugger. The debugger is only showing the numbers 0117, 0119, 011B, and 011D. Our numerical machine can only work with numbers. We used symbols for our ease to label or tag certain positions in our program. The assembler converts these symbols into the appropriate numbers automatically. Also observe that the effect of "dw" is to place 5 in two bytes as 0005. Had we used "db" this would have been stored as 05 in one byte.

Given the fact that the assembler knows only numbers we can write the same program using a single label. As we know that num2 is two ahead of num1, we can use num1+2 instead of num2 and let the assembler calculate the sum during assembly process.

```
Example 2.2
001
        ; a program to add three numbers accessed using a single label
002
        [org 0x0100]
003
                      mov ax, [num1]
                                             ; load first number in ax
004
                      mov bx, [num1+2]
                                             ; load second number in bx
005
                      add
                           ax, bx
                                             ; accumulate sum in ax
006
                      mov bx, [num1+4]
                                             ; load third number in bx
007
                                             ; accumulate sum in ax
                      add
                           ax, bx
008
                      mov
                          [num1+6], ax
                                             ; store sum at num1+6
009
010
                      mov
                          ax, 0x4c00
                                             ; terminate program
011
                          0x21
                      int
012
013
        num1:
                      dw
014
                      dw
                          10
015
                      dw
                          15
016
                      dw
                           0
004
        The second number is read from num1+2. Similarly the third
        number is read from num1+4 and the result is accessed at num1+6.
013-016 The labels num2, num3, and num4 are removed and the data there
        will be accessed with reference to num1.
```

Every location is accessed with reference to num1 in this example. The expression "num1+2" comprises of constants only and can be evaluated at the time of assembly. There are no variables involved in this expression. As we open the program inside the debugger we see a verbatim copy of the previous program. There is no difference at all since the assembler catered for the differences during assembly. It calculated 0117+2=0119 while in the previous it directly knew from the value of num2 that it has to write 0119, but the end result is a ditto copy of the previous execution.

Another way to declare the above data and produce exactly same results is shown in the following example.

```
; accumulate sum in ax
005
                           ax, bx
                      add
006
                      mov
                           bx, [num1+4]
                                              ; load third number in bx
007
                           ax, bx
                                              ; accumulate sum in ax
                      add
008
                           [num1+6], ax
                                              ; store sum at num1+6
009
010
                      mov
                           ax, 0x4c00
                                              ; terminate program
011
                      int
                           0x21
012
                           5, 10, 15, 0
013
        num1:
013
        As we do not need to place labels on individual variables we can save
        space and declare all data on a single line separated by commas.
        This declaration will declare four words in consecutive memory
        locations while the address of first one is num1.
```

The method used to access memory in the above examples is called direct addressing. In direct addressing the memory address is fixed and is given in the instruction. The actual data used is placed in memory and now that data can be used as the destination operand as well. Also the source and destination operands must have the same size. For example a word defined memory is read in a word sized register. A last observation is that the data 0500 in memory was corrected to 0005 when read in a register. So registers contain data in proper order as a word.

A last variation using direct addressing shows that we can directly add a memory variable and a register instead of adding a register into another that we were doing till now.

```
Example 2.4
01
         ; a program to add three numbers directly in memory
02
         [org 0x0100]
03
                                               ; load first number in ax
                       mov
                            ax, [num1]
04
                      mov
                            [num1+6], ax
                                               ; store first number in result
05
                            ax, [num1+2]
                                               ; load second number in ax
                       mov
06
                       add
                            [num1+6], ax
                                               ; add second number to result
07
                            ax, [num1+4]
                                               ; load third number in ax
                       mov.
08
                       add [num1+6], ax
                                               ; add third number to result
09
10
                       mov
                            ax, 0x4c00
                                               ; terminate program
11
                            0x21
12
                            5, 10, 15, 0
13
        num1:
                       Мb
```

We generate the following listing file as a result of the assembly process described previously. Comments are again removed.

```
1
2
                                     [org 0x0100]
 3 00000000 A1[1900]
                                                   mov
                                                        ax, [num1]
 4 00000003 A3[1F00]
                                                   mov [num1+6], ax
5 00000006 A1[1B00]
                                                        ax, [num1+2]
                                                   mov
 6 00000009 0106[1F00]
                                                   add
                                                        [num1+6], ax
7 0000000D A1[1D00]
                                                        ax, [num1+4]
                                                   mov
8 00000010 0106[1F00]
                                                   add
                                                        [num1+6], ax
10 00000014 B8004C
                                                        ax, 0x4c00
                                                   mov
11 00000017 CD21
                                                   int
                                                        0x21
13 00000019 05000A000F000000
                                     num1:
                                                        5, 10, 15, 0
```

The opcode of add is changed because the destination is now a memory location instead of a register. No other significant change is seen in the listing file. Inside the debugger we observe that few opcodes are longer now and the location num1 is now translating to 0119 instead of 0117. This is done automatically by the assembler as a result of using labels instead of

hard coding addresses. During execution we observe that the word data as it is read into a register is read in correct order. The significant change in this example is that the destination of addition is memory. Method to access memory is direct addressing, whether it is the MOV instruction or the ADD instruction.

The first two instructions of the last program read a number into AX and placed it at another memory location. A quick thought reveals that the following might be a possible single instruction to replace the couple.

```
mov [num1+6], [num1] ; ILLEGAL
```

However this form is illegal and not allowed on the Intel architecture. None of the general operations of mov, add, sub etc. allow moving data from memory to memory. Only register to register, register to memory, memory to register, constant to memory, and constant to register operations are allowed. The other register to constant, memory to constant, and memory to memory are all disallowed. Only string instructions allow moving data from memory to memory and will be discussed in detail later. As a rule one instruction can have at most one operand in brackets, otherwise assembler will give an error.

2.3. SIZE MISMATCH ERRORS

If we change the directive in the last example from DW to DB, the program will still assemble and debug without errors, however the results will not be the same as expected. When the first operand is read 0A05 will be read in the register which was actually two operands place in consecutive byte memory locations. The second number will be read as 000F which is the zero byte of num4 appended to the 15 of num3. The third number will be junk depending on the current state of the machine. According to our data declaration the third number should be at 0114 but it is accessed at 011D calculated with word offsets. This is a logical error of the program. To keep the declarations and their access synchronized is the responsibility of the programmer and not the assembler. The assembler allows the programmer to do everything he wants to do, and that can possibly run on the processor. The assembler only keeps us from writing illegal instructions which the processor cannot execute. This is the difference between a syntax error and a logic error. So the assembler and debugger have both done what we asked them to do but the programmer asked them to do the wrong chore.

The programmer is responsible for accessing the data as word if it was declared as a word and accessing it as a byte if it was declared as a byte. The word case is shown in lot of previous examples. If however the intent is to treat it as a byte the following code shows the appropriate way.

```
Example 2.5
001
        ; a program to add three numbers using byte variables
002
        [org 0x01001
003
                      mov al, [num1]
                                              ; load first number in al
004
                           bl, [num1+1]
                                              ; load second number in bl
                      mov
                                              ; accumulate sum in al
005
                      add al, bl
                      mov bl, [num1+2]
006
                                              ; load third number in bl
                      add al, bl
007
                                              ; accumulate sum in al
                      mov [num1+3], al
008
                                              ; store sum at num1+3
009
                      mov ax, 0x4c00
010
                                              ; terminate program
011
                      int 0x21
012
        num1:
                           5, 10, 15, 0
013
                      db
003
        The number is read in AL register which is a byte register since the
        memory location read is also of byte size.
005
        The second number is now placed at num1+1 instead of num1+2
        because of byte offsets.
```

To declare data db is used instead of dw so that each data declared occupies one byte only.

Inside the debugger we observe that the AL register takes appropriate values and the sum is calculated and stored in num1+3. This time there is no alignment or synchronization error. The key thing to understand here is that the processor does not match defines to accesses. It is the programmer's responsibility. In general assembly language gives a lot of power to the programmer but power comes with responsibility. Assembly language programming is not a difficult task but a responsible one.

In the above examples, the processor knew the size of the data movement operation from the size of the register involved, for example in "mov ax, [num1]" memory can be accessed as byte or as word, it has no hard and fast size, but the AX register tells that this operation has to be a word operation. Similarly in "mov al, [num1]" the AL register tells that this operation has to be a byte operation. However in "mov ax, bl" the AX register tells that the operation has to be a word operation while BL tells that this has to be a byte operation. The assembler will declare that this is an illegal instruction. A 5Kg bag cannot fit inside a 1Kg bag and according to Intel a 1Kg cannot also fit in a 5Kg bag. They must match in size. The instruction "mov [num1], [num2]" is illegal as previously discussed not because of data movement size but because memory to memory moves are not allowed at all.

The instruction "mov [num1], 5" is legal but there is no way for the processor to know the data movement size in this operation. The variable num1 can be treated as a byte or as a word and similarly 5 can be treated as a byte or as a word. Such instructions are declared ambiguous by the assembler. The assembler has no way to guess the intent of the programmer as it previously did using the size of the register involved but there is no register involved this time. And memory is a linear array and label is an address in it. There is no size associated with a label. Therefore to resolve its ambiguity we clearly tell our intent to the assembler in one of the following ways.

```
mov byte [num1], 5
mov word [num1], 5
```

2.4. REGISTER INDIRECT ADDRESSING

We have done very elementary data access till now. Assume that the numbers we had were 100 and not just three. This way of adding them will cost us 200 instructions. There must be some method to do a task repeatedly on data placed in consecutive memory cells. The key to this is the need for some register that can hold the address of data. So that we can change the address to access some other cell of memory using the same instruction. In direct addressing mode the memory cell accessed was fixed inside the instruction. There is another method in which the address can be placed in a register so that it can be changed. For the following example we will take 10 instead of 100 numbers but the algorithm is extensible to any size.

There are four registers in iAPX88 architecture that can hold address of data and they are BX, BP, SI, and DI. There are minute differences in their working which will be discussed later. For the current example, we will use the BX register and we will take just three numbers and extend the concept with more numbers in later examples.

```
Example 2.6
001
         ; a program to add three numbers using indirect addressing
002
         [org 0x100]
                            bx, num1
003
                       mov
                                                ; point bx to first number
004
                       mov
                            ax, [bx]
                                                ; load first number in ax
005
                            bx, 2
                                                ; advance bx to second number
                       add
```

```
006
                          ax. [bx]
                     add
                                            ; add second number to ax
007
                      add
                          bx,
                                             ; advance bx to third number
                          ax, [bx]
008
                                             ; add third number to ax
                      add
009
                      add
                          bx, 2
                                             ; advance bx to result
010
                                             ; store sum at num1+6
                          [bx], ax
                      mov
011
012
                      mov
                          ax, 0x4c00
                                             ; terminate program
013
                          0x21
                      int
014
        num1:
                          5, 10, 15, 0
015
                     dw
        Observe that no square brackets around num1 are used this time.
        The address is loaded in bx and not the contents. Value of num1 is
        0005 and the address is 0117. So BX will now contain 0117.
004
        Brackets are now used around BX. In japx88 architecture brackets
        can be used around BX, BP, SI, and DI only. In iapx386 more
        registers are allowed. The instruction will be read as "move into ax
        the contents of the memory location whose address is in bx." Now
        since bx contains the address of num1 the contents of num1 are
        transferred to the ax register. Without square brackets the meaning
        of the instruction would have been totally different.
005
        This instruction is changing the address. Since we have words not
        bytes, we add two to bx so that it points to the next word in memory.
        BX now contains 0119 the address of the second word in memory.
        This was the mechanism to change addresses that we needed.
```

Inside the debugger we observe that the first instruction is "mov bx, 011C." A constant is moved into BX. This is because we did not use the square brackets around "num1." The address of "num1" has moved to 011C because the code size has changed due to changed instructions. In the second instruction BX points to 011C and the value read in AX is 0005 which can be verified from the data window. After the addition BX points to 011E containing 000A, our next word, and so on. This way the BX register points to our words one after another and we can add them using the same instruction "mov ax, [bx]" without fixing the address of our data in the instructions. We can also subtract from BX to point to previous cells. The address to be accessed is now in total program control.

One thing that we needed in our problem to add hundred numbers was the capability to change address. The second thing we need is a way to repeat the same instruction and a way to know that the repetition is done a 100 times, a terminal condition for the repetition. For the task we are introducing two new instructions that you should read and understand as simple English language concepts. For simplicity only 10 numbers are added in this example. The algorithm is extensible to any size.

```
Example 2.7
001
         ; a program to add ten numbers
002
         [org 0x01001
003
                       mov bx, num1
                                                ; point bx to first number
004
                            cx, 10
                                                ; load count of numbers in cx
                       mov
005
                       mov
                            ax, 0
                                                 ; initialize sum to zero
006
007
         11:
                                                ; add number to ax
                       add
                            ax, [bx]
008
                       add
                            bx, 2
                                                ; advance bx to next number
009
                       sub
                            cx, 1
                                                 ; numbers to be added reduced
                            11
                                                ; if numbers remain add next
010
                       jnz
011
012
                            [total], ax
                                                ; write back sum in memory
                       mov
013
014
                            ax, 0x4c00
                                                ; terminate program
                       mov
015
                            0x21
                       int
016
        num1:
                            10, 20, 30, 40, 50, 10, 20, 30, 40, 50
017
                       dw
```

018	total: dw 0
006	Labels can be used on code as well. Just like data labels they remember the address at which they are used. The assembler does not differentiate between code labels and data labels. The programmer is responsible for using a data label as data and a code label as code. The label 11 in this case is the address of the following instruction.
009	SUB is the counterpart to ADD with the same rules as that of the ADD instruction.
010	JNZ stands for "jump if not zero." NZ is the condition in this instruction. So the instruction is read as "jump to the location l1 if the zero flag is not set." And revisiting the zero flag definition "the zero flag is set if the last mathematical or logical operation has produced a zero in its destination." For example "mov ax, 0" will not set the zero flag as it is not a mathematical or logical instruction. However subtraction and addition will set it. Also it is set even when the destination is not a register. Now consider the subtraction immediately preceding it. If the CX register becomes zero as a result of this subtraction the zero flag will be set and the jump will be taken. And jump to l1, the processor needs to be told each and everything and the destination is an important part of every jump. Just like when we ask someone to go, we mention go to this market or that house. The processor is much more logical than us and needs the destination in every instruction that asks it to go somewhere. The processor will load l1 in the IP register and resume execution from there. The processor will blindly go to the label we mention even if it contains data and not code.

The CX register is used as a counter in this example, BX contains the changing address, while AX accumulates the result. We have formed a loop in assembly language that executes until its condition remains true. Inside the debugger we can observe that the subtract instruction clears the zero flag the first nine times and sets it on the tenth time. While the jump instruction moves execution to address 11 the first nine times and to the following line the tenth time. The jump instruction breaks program flow.

The JNZ instruction is from the program control group and is a conditional jump, meaning that if the condition NZ is true (ZF=0) it will jump to the address mentioned and otherwise it will progress to the next instruction. It is a selection between two paths. If the condition is true go right and otherwise go left. Or we can say if the weather is hot, go this way, and if it is cold, go this way. Conditional jump is the most important instruction, as it gives the processor decision making capability, so it must be given a careful thought. Some processors call it branch, probably a more logical name for it, however the functionality is same. Intel chose to name it "jump."

An important thing in the above example is that a register is used to reference memory so this form of access is called register indirect memory access. We used the BX register for it and the B in BX and BP stands for base therefore we call register indirect memory access using BX or BP, "based addressing." Similarly when SI or DI is used we name the method "indexed addressing." They have the same functionality, with minor differences because of which the two are called base and index. The differences will be explained later, however for the above example SI or DI could be used as well, but we would name it indexed addressing instead of based addressing.

2.5. REGISTER + OFFSET ADDRESSING

Direct addressing and indirect addressing using a single register are two basic forms of memory access. Another possibility is to use different combinations of direct and indirect references. In the above example we used BX to access different array elements which were placed consecutively in memory like an array. We can also place in BX only the array index and not the exact address and form the exact address when we are going to access the actual memory. This way the same register can be used for accessing different arrays and also the register can be used for index comparison like the following example does.

	Example 2.8								
001 002	; a program to [org 0x0100]	add	ten	numbers using	g reg	gister + offset addressing			
003 004 005		mov mov	,	10	;	initialize array index to z load count of numbers in cx initialize sum to zero			
006 007 008	11:	add add				add number to ax advance bx to next index			
009 010 011		sub jnz			;	numbers to be added reduced if numbers remain add next	Ĺ		
012 013		mov	-	tal], ax		write back sum in memory			
014 015 016		mov	ax, 0x2	0x4c00 L	i	terminate program			
017 018	num1: total:	dw dw	10,	20, 30, 40,	50, 1	10, 20, 30, 40, 50			
003	This time BX is initialized to zero instead of array base								
007	The format of memory access has changed. The array base is added to BX containing array index at the time of memory access.								
008	As the array is of words, BX jumps in steps of two, i.e. 0, 2, 4. Higher level languages do appropriate incrementing themselves and we always use sequential array indexes. However in assembly language we always calculate in bytes and therefore we need to take care of the size of one array element which in this case is two.								

Inside the debugger we observe that the memory access instruction is shown as "mov ax, [011F+bx]" and the actual memory accessed is the one whose address is the sum of 011F and the value contained in the BX register. This form of access is of the register indirect family and is called base + offset or index + offset depending on whether BX or BP is used or SI or DI is used.

2.6. SEGMENT ASSOCIATION

All the addressing mechanisms in iAPX88 return a number called *effective address*. For example in base + offset addressing, neither the base nor the offset alone tells the desired cell in memory to be accessed. It is only after the addition is done that the processor knows which cell to be accessed. This number which came as the result of addition is called the effective address. But the effective address is just an offset and is meaningless without a segment. Only after the segment is known, we can form the physical address that is needed to access a memory cell.

We discussed the segmented memory model of iAPX88 in reasonable detail at the end of previous chapter. However during the discussion of addressing modes we have not seen the effect of segments. Segmentation is there and it's all happening relative to a segment base. We saw DS, CS, SS, and ES inside the debugger. Everything is relative to its segment base, even though we have not explicitly explained its functionality. An offset alone is not complete without a segment. As previously discussed there is a default segment associated to every register which accesses memory. For example CS is associated to IP by default; rather it is tied with it. It cannot access memory in any other segment.

In case of data, there is a bit relaxation and nothing is tied. Rather there is a default association which can be overridden. In the case of register indirect memory access, if the register used is one of SI, DI, or BX the default segment is DS. If however the register used in BP the default segment used is SS. The stack segment has a very critical and fine use and there is a reason why BP is attached to SS by default. However these will be discussed in detail in the chapter on stack. IP is tied to CS while SP is tied to SS. The association of these registers cannot be changed; they are locked with no option. Others are not locked and can be changed.

To override the association for one instruction of one of the registers BX, BP, SI or DI, we use the segment override prefix. For example "mov ax, [cs:bx]" associates BX with CS for this one instruction. For the next instruction the default association will come back to act. The processor places a special byte before the instruction called a prefix, just like prefixes and suffixes in English language. No prefix is needed or placed for default association. For example for CS the byte 2E is placed and for ES the byte 26 is placed. Opcode has not changed, but the prefix byte has modified the default association to association with the desired segment register for this one instruction.

In all our examples, we never declared a segment or used it explicitly, but everything seemed to work fine. The important thing to note is that CS, DS, SS, and ES all had the same value. The value itself is not important but the fact that all had the same value is important. All four segment windows exactly overlap. Whatever segment register we use the same physical memory will be accessed. That is why everything was working without the mention of a single segment register. This is the formation of COM files in IBM PC. A single segment contains code, data, and the stack. This format is operating system dependant, in our case defined by DOS. And our operating system defines the format of COM files such that all segments have the same value. Thus the only meaningful thing that remains is the offset.

For example if BX=0100, SI=0200, and CS=1000 and the memory access under consideration is [cs:bx+si+0x0700], the effective address formed is bx+si+0700 = 0100 + 0200 + 0700 = 0A00. Now multiplying the segment value by 16 makes it 10000 and adding the effective address 00A00 forms the physical address 10A00.

2.7. ADDRESS WRAPAROUND

There are two types of wraparounds. One is within a single segment and the other is inside the whole physical memory. Segment wraparound occurs when during the effective address calculation a carry is generated. This carry is dropped giving the effect that when we try to access beyond the segment limit, we are actually wrapped around to the first cell in the segment. For example if BX=9100, DS=1500 and the access is [bx+0x7000] we form the effective address 9100 + 7000 = 10100. The carry generated is dropped forming the actual effective address of 0100. Just like a circle when we reached the end we started again from the beginning. An arc at 370 degrees is the same as an arc at 10 degrees. We tried to cross the segment boundary and it pushed us back to the start. This is called segment wraparound. The physical address in the above example will be 15100.

The same can also happen at the time of physical address calculation. For example BX=0100, DS=FFF0 and the access under consideration is [bx+0x0100]. The effective address will be 0200 and the physical address will

be 100100. This is a 21bit answer and cannot be sent on the address bus which is 20 bits wide. The carry is dropped and just like the segment wraparound our physical memory has wrapped around at its very top. When we tried to access beyond limits the actual access is made at the very start. This second wraparound is a bit different in newer processor with more address lines but that will be explained in later chapters.

2.8. ADDRESSING MODES SUMMARY

The iAPX88 processor supports seven modes of memory access. Remember that immediate is not an addressing mode but an operand type. Operands can be immediate, register, or memory. If the operand is memory one of the seven addressing modes will be used to access it. The memory access mechanisms can also be written in the general form "base + index + offset" and we can define the possible addressing modes by saying that any one, two, or none can be skipped from the general form to form a legal memory access

There are a few common mistakes done in forming a valid memory access. Part of a register cannot be used to access memory. Like BX is allowed to hold an address but BL or BH are not. Address is 16bit and must be contained in a 16bit register. BX-SI is not possible. The only thing that we can do is addition of a base register with an index register. Any other operation is disallowed. BS+BP and SI+DI are both disallowed as we cannot have two base or two index registers in one memory access. One has to be a base register and the other has to be an index register and that is the reason of naming them differently.

Direct

A fixed offset is given in brackets and the memory at that offset is accessed. For example "mov [1234], ax" stores the contents of the AX registers in two bytes starting at address 1234 in the current data segment. The instruction "mov [1234], al" stores the contents of the AL register in the byte at offset 1234.

Based Register Indirect

A base register is used in brackets and the actual address accessed depends on the value contained in that register. For example "mov [bx], ax" moves the two byte contents of the AX register to the address contained in the BX register in the current data segment. The instruction "mov [bp], al" moves the one byte content of the AL register to the address contained in the BP register in the current stack segment.

Indexed Register Indirect

An index register is used in brackets and the actual address accessed depends on the value contained in that register. For example "mov [si], ax" moves the contents of the AX register to the word starting at address contained in SI in the current data segment. The instruction "mov [di], ax" moves the word contained in AX to the offset stored in DI in the current data segment.

Based Register Indirect + Offset

A base register is used with a constant offset in this addressing mode. The value contained in the base register is added with the constant offset to get the effective address. For example "mov [bx+300], ax" stores the word contained in AX at the offset attained by adding 300 to BX in the current data segment. The instruction "mov [bp+300], ax" stores the word in AX to the offset attained by adding 300 to BP in the current stack segment.

Indexed Register Indirect + Offset

An index register is used with a constant offset in this addressing mode. The value contained in the index register is added with the constant offset to get the effective address. For example "mov [si+300], ax" moves the word contained in AX to the offset attained by adding 300 to SI in the current data segment and the instruction "mov [di+300], al" moves the byte contained in AL to the offset attained by adding 300 to DI in the current data segment.

Base + Index

One base and one index register is used in this addressing mode. The value of the base register and the index register are added together to get the effective address. For example "mov [bx+si], ax" moves the word contained in the AX register to offset attained by adding BX and SI in the current data segment. The instruction "mov [bp+di], al" moves the byte contained in AL to the offset attained by adding BP and DI in the current stack segment. Observe that the default segment is based on the base register and not on the index register. This is why base registers and index registers are named separately. Other examples are "mov [bx+di], ax" and "mov [bp+si], ax." This method can be used to access a two dimensional array such that one dimension is in a base register and the other is in an index register.

Base + Index + Offset

This is the most complex addressing method and is relatively infrequently used. A base register, an index register, and a constant offset are all used in this addressing mode. The values of the base register, the index register, and the constant offset are all added together to get the effective address. For example "mov [bx+si+300], ax" moves the word contents of the AX register to the word in memory starting at offset attained by adding BX, SI, and 300 in the current data segment. Default segment association is again based on the base register. It might be used with the array base of a two dimensional array as the constant offset, one dimension in the base register and the other in the index register. This way all calculation of location of the desired element has been delegated to the processor.

EXERCISES

- 1. What is a label and how does the assembler differentiates between code labels and data labels?
- 2. List the seven addressing modes available in the 8088 architecture.
- 3. Differentiate between effective address and physical address.
- 4. What is the effective address generated by the following instructions? Every instruction is independent of others. Initially BX=0x0100, num1=0x1001, [num1]=0x0000, and SI=0x0100
 - a. mov ax, [bx+12]
 - b. mov ax, [bx+num1]
 - c. mov ax, [num1+bx]
 - d. mov ax, [bx+si]
- 5. What is the effective address generated by the following combinations if they are valid. If not give reason. Initially BX=0x0100, SI=0x0010, DI=0x0001, BP=0x0200, and SP=0xFFFF
 - a. bx-si
 - b. bx-bp
 - c. bx+10
 - d. bx-10
 - e. bx+sp
 - f. bx+di
- 6. Identify the problems in the following instructions and correct them by replacing them with one or two instruction having the same effect.

- a. mov [02], [22]
- b. mov [wordvar], 20
- c. mov bx, al
- d. mov ax, [si+di+100]
- 7. What is the function of segment override prefix and what changes it brings to the opcode?
- 8. What are the two types of address wraparound? What physical address is accessed with [BX+SI] if FFFF is loaded in BX, SI, and DS.
- 9. Write instructions to do the following.
 - a. Copy contents of memory location with offset 0025 in the current data segment into AX.
 - b. Copy AX into memory location with offset OFFF in the current data segment.
 - c. Move contents of memory location with offset 0010 to memory location with offset 002F in the current data segment.
- 10. Write a program to calculate the square of 20 by using a loop that adds 20 to the accumulator 20 times.