Practical 6

AIM: Observe STP Topology Changes and Implement RSTP


- 1. Implement Advanced STP Modifications and Mechanisms
- 2. Implement MST

Implement Advanced STP Modifications and Mechanisms

What is STP?

- Spanning Tree Protocol (STP) is used to make a loop free network by monitoring the network to track all the links and shut down the least redundant ones.
- Root bridge is a switch in a single VLAN or whole topology (according to the type of STP standard used) which is responsible for distributing BPDUs and block the least redundant port.
- Networks are often configured with redundant paths when connecting network segments.
- Although redundancy can help protect against disaster, it can also lead to bridge or switch looping.
- Looping occurs when data travels from a source to a destination along redundant paths and the data begins to circle around the same paths, becoming amplified and resulting in a broadcast storm.
- STP can help prevent bridge looping on LANs that include redundant links. Without STP, it would be difficult to implement that redundancy and still avoid network looping. STP monitors all network links, identifies redundant connections, and disables the ports that can lead to looping.

Step 1: Design the network



Step 2: Configure the devices:

D1:

```
vI0S-L2-01>
vIOS-L2-01>enable
vIOS-L2-01#conf t
Enter configuration commands, one per line. End with CNTL/Z.
vIOS-L2-01(config)#hostname D1
D1(config)#spanning-tree mode pvst
D1(config)#banner motd #D1, STP Topology Changes and RSTP Lab#
D1(config)#line con 0
D1(config-line)#exec-timeout 0 0
D1(config-line)#logging synchronous
D1(config-line)#exit
D1(config)#interface range gi0/0-2
D1(config-if-range)#switchport trunk encapsulation dot1q
D1(config-if-range)#switchport mode trunk
D1(config-if-range)#no shutdown
D1(config-if-range)#exit
D1(config)#vlan 2
D1(config-vlan)#name SecondVLAN
D1(config-vlan)#exit
D1(config)#interface vlan 1
D1(config-if)#ip address 10.0.0.1 255.0.0.0
D1(config-if)#no shutdown
D1(config-if)#exit
D1(config)#
D1(config)#
```

D2:

```
VIOS-L2-01>
VIOS-L2-01#conf t
Enter configuration commands, one per line. End with CNTL/Z.
VIOS-L2-01(config)#hostname D2
D2(config)#banner motd #D2, STP Topology Changes and RSTP Lab#
D2(config)#spanning-tree mode pvst
D2(config)#line con 0
D2(config-line)#exec-timeout 0 0
D2(config-line)#exec-timeout 0 0
D2(config-line)#exit
D2(config-line)#exit
D2(config-line)#exit
D2(config-line)#exit
D2(config-line)#switchport trunk encapsulation dot1q
D2(config-if-range)#switchport mode trunk
D2(config-if-range)#no shutdown
D2(config-if-range)#mo shutdown
D2(config-if-range)#exit
D2(config-vlan)#name SecondVLAN
D2(config-vlan)#axit
D2(config-vlan)#axit
D2(config-if)#pi address 10.0.0.2 255.0.0.0
D2(config-if)#no shutdown
D2(config-if)#no shutdown
D2(config-if)#no shutdown
D2(config-if)#exit
*Jan 6 14:59:11.825: %LINEPROTO-5-UPDOWN: Line protocol on Interface Vlan1, changed state to down
D2(config-if)#exit
*Jan 6 14:59:14.756: %LINK-3-UPDOWN: Line protocol on Interface Vlan1, changed state to up
*Jan 6 14:59:16.496: %LINK-3-UPDOWN: Line protocol on Interface Vlan1, changed state to up
D2(config-if)#exit
*Jan 6 14:59:16.496: %LINEPROTO-5-UPDOWN: Line protocol on Interface Vlan1, changed state to up
D2(config-if)#exit
D2(config-if)#exit
D2(config-if)#exit
D2(config-if)#exit
D2(config-if)#exit
D2(config-if)#exit
```

A1:

```
VIOS-L2-01>
VIOS-L2-01>
VIOS-L2-01+conf t
Enter configuration commands, one per line. End with CNTL/Z.
VIOS-L2-01(config)#hostname A1
A1(config)#banner motd #A1, STP Topology Changes and RSTP Lab#
A1(config)#line con 0
A1(config)#line con 0
A1(config-line)#exec-timeout 0 0
A1(config-line)#exec-timeout 0 0
A1(config-line)#exit
A1(config-line)#exit
A1(config-line)#switchport trunk encapsulation dot1q
A1(config-if-range)#switchport mode trunk
A1(config-if-range)#switchport mode trunk
A1(config-if-range)#switchport mode trunk
A1(config-if-range)#switchport mode trunk
A1(config-if-range)#switchport
A1(config-if-range)#switchport
A1(config-if-range)#switchport
A1(config-if)#una
A1(config-if)#una
A1(config-vlan)#mame SecondVLAN
A1(config-vlan)#exit
A1(config-vlan)#exit
A1(config-if)#pi address 10.0.0.3 255.0.0.0
A1(config-if)#pi address 10.0.0.3 255.0.0.0
A1(config-if)#so shutdown
A1(config-if)#exit
Jan 6 14:46:43.960: %LINEPROTO-5-UPDOWN: Line protocol on Interface Vlan1, changed state to down
A1(config-if)#exit
*Jan 6 14:46:47.144: %LINK-3-UPDOWN: Line protocol on Interface Vlan1, changed state to up
A1(config-if)#exit
*Jan 6 14:46:47.144: %LINK-3-UPDOWN: Line protocol on Interface Vlan1, changed state to up
A1(config-if)#exit
```

Step 3: Discover the Default Spanning Tree.

1. Find the root bridge.

- The root bridge is elected based upon which switch has the highest Bridge ID (BID).
- The BID is made up of a configurable priority value (which defaults to 32768) and the base MAC address for the switch.
- Use the command show spanning-tree root to gather that information from your switches to support the root bridge decision.

Enter the command 'show spanning-tree root' and observe what the output tells you about the root bridge.

D1:

DI.									
D1#show spanning-tree root									
Vlan	Root ID	Root Cost	Hello Time	Max F Age [Root Port			
VLAN0001 VLAN0002 VLAN0100 VLAN0200 VLAN0300 D1#	32769 0c9d.c7a4.0000 32770 0c9d.c7a4.0000 32868 0c9d.c7a4.0000 32968 0c9d.c7a4.0000 33068 0c9d.c7a4.0000	4 4 4	2 2 2	20 20 20 20 20 20 20	15 15 15 15 15 15	Gi0/2 Gi0/2 Gi0/2 Gi0/2 Gi0/2			

D2:

-			OJIJ-J-CONI IU_								
			_		,			150 00	b) comsocc		
	D2#show spanning-tree root										
				Root		Hello	Max	Eud			
	Vlan		Root ID	Cost		Time	Age	Dly	Root Port		
	VLAN0001	22760	0c0d c7c4 000	a	0	2	20	15			
			0c9d.c7a4.000		U	_	20				
	VLAN0002	32770	0c9d.c7a4.000)	0	2	20	15			
	VLAN0100	32868	0c9d.c7a4.000	0	0	2	20	15		j	
					_						
	VLAN0200	32968	0c9d.c7a4.000	ש	0	2	20	15			
	VLAN0300	33068	0c9d.c7a4.000)	0	2	20	15		j	
	D2#										
	ח2#								<u>.</u>		

A1:

111									
A1#show spanning-tree root									
V2		D+ TD	Root		Hello			Deat Deat	
Vlan		Root ID 	Cost		ııme 	Age	DLY	Root Port	
VLAN0001	32769 0	0c9d.c7a4.0000		4	2	20	15	Gi0/2	
VLAN0002		0c9d.c7a4.0000		4	2	20	15	Gi0/2	
VLAN0100 VLAN0200		0c9d.c7a4.0000 0c9d.c7a4.0000		4 4	2 2	20 20	15 15	Gi0/2 Gi0/2	
VLAN0200 VLAN0300		0c9d.c7a4.0000 0c9d.c7a4.0000		4 4	2	20	15	Gi0/2	
A1#								, -	
A1#	360. 0.0	CVC E CONFTC T	. Configu	501	d from		2010	hy cancala	
*Jan 6 14:47:21. A1#	. 309; %3	SYS-5-CONFIG_I	: Conregu	rec	a iron	ı cor	isote	by console	

The root cost is the cost to go to root bridge and in D1 and A1 there is a cost of 4.

But in D2 there is no cost because D2 is our root bridge.

We will see it clearly in upcoming Screenshot

2. Find the Root Port for each switch

- As we saw in the previous output of show spanning-tree root on each switch, the Path Cost can be different amongst switches.
- In this case, the path cost from A1 to D2 is 4, reflecting connectivity via a Gigabit Ethernet port
- While the path cost from D1 to D2 is 4, reflecting connectivity via a Gigabit Ethernet port.
- While the path cost from D2 to D2 is 0 because it is root bridge.

D ±11					15 10 00 01100 500
D1#show spann	ing-tree root				
Vlan	Root ID	Root Cost		Max Fwd Age Dly	
VLAN0001	32769 0c9d.c7a4.0000	4	2	20 15	Gi0/2
VLAN0002	32770 0c9d.c7a4.0000	4	2	20 15	Gi0/2
VLAN0100	32868 0c9d.c7a4.0000	4	2	20 15	Gi0/2
VLAN0200	32968 0c9d.c7a4.0000	4	2	20 15	Gi0/2
VLAN0300	33068 0c9d.c7a4.0000	4	2	20 15	Gi0/2
D1#					

D2#show spanning		confitgured from c	onsole by console
Vlan	Root ID	Root Hello Ma Cost Time Ag	x Fwd e Dly Root Port
VLAN0002 VLAN0100 VLAN0200 VLAN0300 D2# D2#	32868 0c9d.c7a4.0000 32968 0c9d.c7a4.0000 33068 0c9d.c7a4.0000	0 2 2 0 2 2 0 2 2	0 15 0 15 0 15 0 15 0 15 0 15
A1#show spanning- Vlan	tree root Root ID	Root Hello Max Cost Time Age	
VLAN0002 VLAN0100 VLAN0200 VLAN0300 A1# A1#	32769 0c9d.c7a4.0000 32770 0c9d.c7a4.0000 32868 0c9d.c7a4.0000 32968 0c9d.c7a4.0000 33068 0c9d.c7a4.0000 369: %SYS-5-CONFIG_I:	4 2 20 4 2 20 4 2 20 4 2 20 4 2 20	15 Gi0/2

3. Changes in network:

A1: Issue 'show spanning-tree' in A1 and check the output

```
A1#show spanning-tree
VLAN0001
  Spanning tree enabled protocol ieee
  Root ID
                        32769
             Priority
             Address
                         0c9d.c7a4.0000
             Cost
             Port
                         3 (GigabitEthernet0/2)
             Hello Time 2 sec Max Age 20 sec Forward Delay 15 sec
                         32769 (priority 32768 sys-id-ext 1)
  Bridge ID Priority
                         0cbd.e307.0000
             Address
             Hello Time
                         2 sec Max Age 20 sec Forward Delay 15 sec
             Aging Time
                        300 sec
Interface
                    Role Sts Cost
                                       Prio.Nbr Type
Gi0/0
                    Desg FWD 4
                                       128.1
                                                Shr
                    Desg FWD 4
                                       128.2
Gi0/1
                                                Shr
Gi0/2
                    Root FWD 4
                                       128.3
                                                Shr
Gi0/3
                    Altn BLK 4
                                       128.4
                                                Shr
```

Our topology does not really illustrate the difference between port cost and path cost very well, so we will introduce a change in the network to achieve this. At D1, shutdown the g1/0/1 interface.

The result of this is that D2 will have to change the port it considers root, and we will then see the difference between port cost and path cost.

```
D1#conf t
Enter configuration commands, one per line. End with CNTL/Z.
D1(config)#interface gi0/2
D1(config-if)#shutdown
D1(config-if)#
*Jan 6 07:51:59.728: %LINK-5-CHANGED: Interface GigabitEthernet0/2, changed state to administrn
*Jan 6 07:52:00.962: %LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/2, changen
```

Now enter 'show spanning-tree' at root i.e. D2:

```
D2#show spanning-tree
VLAN0001
   Spanning tree enabled protocol ieee
                 Priority 32769
Address 0c9d.c7a4.0000
   Root ID
                  This bridge is the root
Hello Time 2 sec Max Age 20 sec Forward Delay 15 sec
                 Priority 32769 (priority 32768 sys-id-ext 1)
Address 0c9d.c7a4.0000
Hello Time 2 sec Max Age 20 sec Forward Delay 15 sec
Aging Time 15 sec
  Bridge ID Priority
Interface
                           Role Sts Cost
                                                     Prio.Nbr Type
                           Desg FWD 4
                                                      128.1
Gi0/0
                                                                  Shr
                            Desg FWD 4
                                                      128.2
128.3
Gi0/1
Gi0/2
                                                                  Shr
                            Desg FWD 4
```

4. Identify Designated Ports.

If you have not already done so, issue the no shutdown command for D1 interface g1/0/1.

This will restore our full topology and allow for the non-root attached segment to exist (the links between A1 and D2).

```
D1(config)#interface gi0/2
D1(config-if)#no shutdown
D1(config-if)#exit
D1(config)#
```

On D2, issue the show spanning-tree command, and you will see that there are two ports now identified as being in the Designated Port role.

```
D2#show spanning-tree
VLAN0001
   Spanning tree enabled protocol ieee
Root ID Priority 32769
                                     0c9d.c7a4.0000
                   Address
                   This bridge is the root
Hello Time 2 sec Max Age 20 sec Forward Delay 15 sec
                   Priority 32769 (priority 32768 sys-id-ext 1)
Address 0c9d.c7a4.0000
Hello Time 2 sec Max Age 20 sec Forward Delay 15 sec
Aging Time 15 sec
   Bridge ID Priority
Interface
                              Role Sts Cost
                                                          Prio.Nbr Type
Gi0/0
                                                          128.1
                             Desg FWD 4
                                                                        Shr
                             Desg FWD 4
Desg FWD 4
                                                          128.2
128.3
Gi0/1
Gi0/2
                                                                        Shr
```

And now look at the segments from the A1 side. Issue the show spanning-tree command on A1.

```
A1#show spanning-tree
VLAN0001
   Spanning tree enabled protocol ieee
                  Priority 32769
Address 0c9d.c7a4.0000
  Root ID
                  Address Uc90.C744.0000
Cost 4
Port 3 (GigabitEthernet0/2)
Hello Time 2 sec Max Age 20 sec Forward Delay 15 sec
  Bridge ID Priority 32769 (priority 32768 sys-id-ext 1)
Address 0cbd.e307.0000
Hello Time 2 sec Max Age 20 sec Forward Delay 15 sec
Aging Time 15 sec
                            Role Sts Cost
Interface
                                                        Prio.Nbr Type
                            Desg FWD 4
Desg FWD 4
Root FWD 4
Gi0/0
                                                        128.1
                                                                     Shr
Gi0/1
                                                       128.2
                                                                     Shr
Gi0/2
                                                       128.3
                                                                     Shr
                            Altn BLK 4
Gi0/3
                                                        128.4
                                                                     Shr
```

You may have noticed in the previous output that the two links from A1 to D1 were not being used.

Step 4: Implement and Observe Rapid Spanning Tree Protocol.

- We will implement Rapid Spanning Tree Protocol (RSTP) on all the switches. Using the same basic rules, RSTP speeds up convergence significantly.
- On D2, issue the debug spanning-tree events command, and then issue the shutdown command for interface g1/0/1 and observe the output.

```
D2#debug spanning Tree events
Spanning Tree event debugging is on
D2#conf t
Enter configuration commands, one per line. End with CNTL/Z.
D2(config)#interface gi0/2
D2(config-if)#shutdown
D3(config-if)#shutdown
D3(config-if)#shutd
```

On D1, change the spanning tree mode to rapid-pvst:

```
D1(config)#spanning-tree mode rapid-pvst
D1(config)#
```

On D1, issue the command show spanning-tree.

```
D1#show spanning-tree
VLAN0001
  Spanning tree enabled protocol rstp
                 Priority 32769
Address 0c9d.c7a4.0000
Cost 8
Port 1 (GigabitEthernet0/0)
  Root ID
                 Hello Time 2 sec Max Age 20 sec Forward Delay 15 sec
  Bridge ID Priority 32769 (priority 32768 sys-id-ext 1)
Address 0ceb.a4ba.0000
Hello Time 2 sec Max Age 20 sec Forward Delay 15 sec
Aging Time 300 sec
Interface
                           Role Sts Cost
                                                     Prio.Nbr Type
                          Root FWD 4
Altn BLK 4
Desg BLK 4
Gi0/0
                                                     128.1
                                                                 Shr Peer(STP)
                                                     128.2
Gi0/1
                                                                  Shr Peer(STP)
Gi0/2
                                                                  Shr
```

The type values tell the story. Rapid spanning tree is backwards compatible with common spanning tree.

We will not see the benefits of rapid spanning tree if only one switch is running it.

On D2 and A1, change the spanning tree mode to rapid spanning tree.

For D2:(Note that I have only enabled the debugging mode for D2, this is why the output for D2 is different from D1 and A1 when the spanning-tree mode is set to rstp.)

```
Set to rstp.)

D2(config)#
*Jan 6 15:07:20.079; setting bridge id (which=3) prio 32769 prio cfg 32768 sysid 1 (on) id 8001.0c9d.c7a4.0000
*Jan 6 15:07:20.080: RSTP(1): initializing port Gi0/0
*Jan 6 15:07:20.080: RSTP(1): initializing port Gi0/1
*Jan 6 15:07:20.080: RSTP(1): Gi0/0 is now designated
*Jan 6 15:07:20.083: RSTP(1): Gi0/1 is now designated
*Jan 6 15:07:20.083: RSTP(1): Gi0/1 is now designated
*Jan 6 15:07:20.083: RSTP(2): initializing port Gi0/0
*Jan 6 15:07:20.084: RSTP(2): initializing port Gi0/0
*Jan 6 15:07:20.085: RSTP(100): Gi0/0 is now designated
*Jan 6 15:07:20.085: RSTP(100): initializing port Gi0/0
*Jan 6 15:07:20.085: RSTP(100): initializing port Gi0/1
*Jan 6 15:07:20.085: RSTP(100): initializing port Gi0/1
*Jan 6 15:07:20.085: RSTP(100): Gi0/0 is now designated
*Jan 6 15:07:20.085: RSTP(200): initializing port Gi0/1
*Jan 6 15:07:20.085: RSTP(200): initializing port Gi0/0
*Jan 6 15:07:20.085: RSTP(200): initializing port Gi0/0
*Jan 6 15:07:20.085: RSTP(200): initializing port Gi0/1
*Jan 6 15:07:20.085: RSTP(200): initializing port Gi0/0
*Jan 6 15:07:20.085: RSTP(200): initializing port Gi0/1
*Jan 6 15:07:20.085: RST
```

```
D2(config)#
D2(config)#

*Jan 6 15:07:25.090: RSTP(1): transmitting a proposal on Gi0/0

*Jan 6 15:07:25.093: RSTP(1): transmitting a proposal on Gi0/1

*Jan 6 15:07:25.096: RSTP(2): transmitting a proposal on Gi0/0

*Jan 6 15:07:25.098: RSTP(2): transmitting a proposal on Gi0/1

*Jan 6 15:07:25.099: RSTP(100): transmitting a proposal on Gi0/0

*Jan 6 15:07:25.099: RSTP(100): transmitting a proposal on Gi0/1

*Jan 6 15:07:25.099: RSTP(200): transmitting a proposal on Gi0/0

*Jan 6 15:07:25.100: RSTP(200): transmitting a proposal on Gi0/1

*Jan 6 15:07:25.100: RSTP(300): transmitting a proposal on Gi0/0

*Jan 6 15:07:25.100: RSTP(300): transmitting a proposal on Gi0/1

*P2(config)#
D2(config)#
*Jan 6 15:07:26.547: RSTP(2): transmitting a proposal on Gi0/1
*Jan 6 15:07:26.551: RSTP(300): transmitting a proposal on Gi0/1
            6 15:07:26.551: RSTP(300): transmitting a proposal on Gi0/1 6 15:07:26.551: RSTP(100): transmitting a proposal on Gi0/1 6 15:07:26.552: RSTP(200): transmitting a proposal on Gi0/1 6 15:07:27.095: RSTP(1): transmitting a proposal on Gi0/1 6 15:07:27.101: RSTP(2): transmitting a proposal on Gi0/1 6 15:07:27.101: RSTP(100): transmitting a proposal on Gi0/1 6 15:07:27.101: RSTP(200): transmitting a proposal on Gi0/1 6 15:07:27.101: RSTP(300): transmitting a proposal on Gi0/1
*Jan
*Jan
*Jan
*Jan
*Jan
*Jan
*Jan 6 15:07:27.101: RSTP(300): transmitting a proposal on Gi0/1
D2(config)#
*Jan 6 15:07:27.480: RSTP(1): transmitting a proposal on Gi0/1
D2(config)#
\starJan 6 15:07:29.100: RSTP(1): transmitting a proposal on Gi0/1
*Jan 6 15:07:29.102: RSTP(2): transmitting a proposal on Gi0/1
              6 15:07:29.104: RSTP(100): transmitting a proposal on Gi0/1 6 15:07:29.105: RSTP(200): transmitting a proposal on Gi0/1
*Jan
*Jan 6 15:07:29.105: RSTP(300): transmitting a proposal on GiO/1
D2(config)#
```

For A1:


```
A1#conf t
Enter configuration commands, one per line. End with CNTL/Z.
A1(config)#spanning-tree mode rapid-pvst
A1(config)#
A1#show spanning-tree
VLAN0001
  Spanning tree enabled protocol ieee
                        32769
  Root ID
             Priority
                         0c9d.c7a4.0000
             Address
             Cost
             Port
                         3 (GigabitEthernet0/2)
             Hello Time 2 sec Max Age 20 sec Forward Delay 15 sec
  Bridge ID
             Priority
                         32769 (priority 32768 sys-id-ext 1)
             Address
                         0cbd.e307.0000
             Hello Time
                         2 sec Max Age 20 sec Forward Delay 15 sec
                         15 sec
             Aging Time
                    Role Sts Cost
Interface
                                       Prio.Nbr Type
                    Desg FWD 4
Gi0/0
                                       128.1
                                                Shr
                    Desg FWD 4
Root FWD 4
Gi0/1
                                       128.2
                                                Shr
                                        128.3
Gi0/2
                                                 Shr
Gi0/3
                    Altn BLK 4
                                       128.4
                                                Shr
```

Implement MST

What is MST?

- Multiple Spanning Tree Protocol (MSTP), initially defined in IEEE 802.1s and later included in IEEE 802.1Q, supports mapping of multiple VLANs onto a single spanning-tree instance.
- This reduces the number of spanning-tree instances required in a switched network with many VLANs.
- Although RSTP provides faster convergence time than STP does, it still does not solve a problem inherent in STP: all VLANs within a LAN must share the same spanning tree.
- To solve this problem, the QFX Series products use Multiple Spanning Tree Protocol (MSTP) to create a loop-free topology in networks with multiple spanning-tree regions.
- An MSTP region allows a group of bridges to be modeled as a single bridge. An MSTP region contains multiple spanning-tree instances (MSTIs).
- MSTIs provide different paths for different VLANs. This functionality facilitates more efficient load sharing across redundant links.
- An MSTP region can support up to 64 MSTIs, and each instance can support from 1 through 4094 VLANs.

Step 1: Design the network:



Step 2: Configure the switches:

Switch D1:

```
vIOS-L2-01>
vIOS-L2-01>en
vIOS-L2-01#conf t
Enter configuration commands, one per line. End with CNTL/Z.
vIOS-L2-01(config)#hostname D1
D1(config)#spanning-tree mode rapid-pvst
D1(config)#line con 0
D1(config-line)#exec-timeout 0 0
D1(config-line)#logging synchronous
D1(config-line)#exit
D1(config)#int range gi0/0-2
D1(config-if-range)#switchport trunk encapsulation dot1q
D1(config-if-range)#switchport mode trunk
D1(config-if-range)#no shut
D1(config-if-range)#ex
D1(config)#vlan 2
D1(config-vlan)#name SecondVLAN
D1(config-vlan)#ex
D1(config)#vlan 3
D1(config-vlan)#name ThirdVLAN
D1(config-vlan)#ex
D1(config)#vlan 4
D1(config-vlan)#name FourthVLAN
D1(config-vlan)#ex
D1(config)#vlan 5
D1(config-vlan)#name FifthVLAN
D1(config-vlan)#ex
D1(config)#end
D1#wr
Building configuration...
Compressed configuration from 5147 bytes to 2003 bytes
```

Switch D2:

```
vIOS-L2-01>
vIOS-L2-01>en
vIOS-L2-01#conf t
Enter configuration commands, one per line. End with CNTL/Z.
vIOS-L2-01(config)#hostname D2
D2(config)#spanning-tree mode rapid-pvst
D2(config)#line con 0
D2(config-line)#exec-timeout 0 0
D2(config-line)#logging synchronous
D2(config-line)#exit
D2(config)#int range gi0/0-2
D2(config-if-range)#switchport trunk encapsulation dot1q
D2(config-if-range)#switchport mode trunk
D2(config-if-range)#no shut
D2(config-if-range)#ex
D2(config)#vlan 2
D2(config-vlan)#name SecondVLAN
D2(config-vlan)#ex
D2(config)#vlan 3
D2(config-vlan)#name ThirdVLAN
D2(config-vlan)#ex
D2(config)#vlan 4
D2(config-vlan)#name FourthVLAN
D2(config-vlan)#ex
D2(config)#vlan 5
D2(config-vlan)#name FifthVLAN
D2(config-vlan)#ex
D2(config)#end'
% Invalid input detected at '^' marker.
D2(config)#end
Building configuration...

Compressed configuration from 5147 bytes to 2005 bytes[OK]
```

Switch A1:

```
vIOS-L2-01>
vIOS-L2-01>en
vIOS-L2-01#conf t
Enter configuration commands, one per line. End with CNTL/Z.
vIOS-L2-01(config)#hostname A1
A1(config)#spanning-tree mode rapid pvst
% Invalid input detected at '^' marker.
A1(config)#spanning-tree mode rapid-pvst
A1(config)#line con 0
A1(config-line)#exec-timeout 0 0
A1(config-line)#logging synchronous
A1(config-line)#exit
A1(config)#int range gi0/0-3
Al(config-if-range)#switchport trunk encapsulation dot1q
Al(config-if-range)#switchport mode trunk
A1(config-if-range)#no shut
A1(config-if-range)#ex
A1(config)#int gi1/0
A1(config-if)#no shut
A1(config-if)#ex
A1(config)#vlan 2
A1(config-vlan)#name SecondVLAN
A1(config-vlan)#ex
A1(config)#vlan 3
A1(config-vlan)#name ThirdVLAN
A1(config-vlan)#ex
A1(config)#vlan 4
A1(config-vlan)#name FourthVLAN
A1(config-vlan)#ex
A1(config)#vlan 5
A1(config-vlan)#name FifthVLAN
A1(config-vlan)#ex
A1(config)#end
A1#wr
Building configuration...
Compressed configuration from 5340 bytes to 2081 bytes
*Oct 31 13:29:26.076: %SYS-5-CONFIG_I: Configured from console by console[OK]
```

Step 3: Implement and Observe MST.

Configure MST on D1 and D2.

On D1 and D2, issue the command spanning-tree mode mst.

```
D1#conf t
Enter configuration commands, one per line. End with CNTL/Z.
D1(config)#spanning-tree mode mst

D2#conf t
Enter configuration commands, one per line. End with CNTL/Z.
D2(config)#spanning-tree mode mst
D2(config)#end
D2#config
```

- At this point, with no MST-specific configuration, MST Instance 0 is operational for all VLANs.
- Issue the command **show spanning-tree** and you will see in the output that the spanning tree information is about MST 0.
- Issue the command **show spanning-tree mst** and you will see the MST-specific STP information that is specific to MST 0 only.

• Take note of the information displayed for interfaces g1/0/5 and g1/0/6 because they are connected to a switch that is not running MST.

```
D1#show spanning-tree
MSTØ
  Spanning tree enabled protocol mstp
                Priority 32768
Address 0c76.bb6f.0000
  Root ID
                Cost 20000
Port 3 (GigabitEthernet0/2)
                Hello Time 2 sec Max Age 20 sec Forward Delay 15 sec
  Bridge ID Priority 32768 (priority 32768 sys-id-ext 0)
Address 0c8f.fc0c.0000
                Address
                Hello Time 2 sec Max Age 20 sec Forward Delay 15 sec
                       Role Sts Cost
                                                Prio.Nbr Type
Gi0/0 Altn BKN*20000 128.1 Shr Bound(PVST) *PVST_Inc
Gi0/1 Altn BLK 20000 128.2 Shr Bound(PVST)
Gi0/2 Root FWD 20000 128.3 Shr Bound(PVST)
D1#show spanning-tree mst
##### MST0 vlans mapped: 1-4094
Bridge address 0c8f.fc0c.0000 priority 32768 (32768 sysid 0)
Root address 0c76.bb6f.0000 priority 32768 (32768 sysid 0)
                 port Gi0/2
Regional Root this switch
Operational hello time 2 , forward delay 15, max age 20, txholdcount 6
Configured hello time 2 , forward delay 15, max age 20, max hops 20
Interface
                    Role Sts Cost
                                             Prio.Nbr Type
Gi0/0 Altn BKN*20000 128.1 Shr Bound(PVST) *PVST_Inc
Gi0/1 Altn BLK 20000 128.2 Shr Bound(PVST)
Gi0/2 Root FWD 20000 128.3 Shr Bound(PVST)
```

- The basic behaviour of MST is the same as spanning tree, where a root bridge must be selected, then root ports, and finally best paths to the root bridge from all non-root bridges.
- In the current network, we can see that D1 has been elected the root bridge. The bridge priority defaults to 32768, so the election is based on D1 having a lower base MAC address.
- The switch elected as root may be different but the rules for election remain the same.
- Issue the command show spanning-tree root on switch A1. Switch A1 is running five instances of spanning tree.

A1:

Al#show spanning	-tree ro	oot			3076	9	
Vlan	ļ	Root ID	Root Cost	Hello Time			Root Port
VLAN0001	32768 6	3c76.bb6f.0000	4	2	20	15	Gi0/2
VLAN0002	32768 6	0c76.bb6f.0000	4	2	20	15	Gi0/2
VLAN0003	32768 6	0c76.bb6f.0000	4	2	20	15	Gi0/2
VLAN0004	32768 6	ac76.bb6f.0000	4	2	20	15	Gi0/2
VLAN0005	32768 6	0c76.bb6f.0000	4	2	20	15	Gi0/2
VLAN0100	32768 6	0c76.bb6f.0000	4	2	20	15	Gi0/2
VLAN0200	32768	ac76.bb6f.0000	4	2	20	15	Gi0/2
VLAN0300	32768	0c76.bb6f.0000	4	2	20	15	Gi0/2

Issue the show spanning-tree root command on D2 and the output will be different.

This is because with MST, only one instance of the spanning-tree algorithm runs, regardless of the number of VLANs mapped to it.

D2:

```
POCT 31 13:30:49.793: %5YS-5-COMFIG_1: Configured from console by consolespann D2#show spanning-tree root

Root Hello Max Fwd

MST Instance Root ID Cost Time Age Dly Root Port

MST0 32768 0c76.bb6f.0000 0 2 20 15

D2#
```

Configure A1 to use MST.

```
A1#conf t
Enter configuration commands, one per line. End with CNTL/Z.
A1(config)#spanning-tree mode mst
```

Step 4: Configure, Tune and Verify Basic MST Operation.

In the last part, you configured all three switches to run MST. In this part, you will further configure, tune, and verify MST to support the unique topological requirements.

Create and verify an MST configuration.

Enter MST configuration mode using the command spanning-tree mst configuration.

```
*Oct 31 13:30:34.449: %SPANTREE-2-PVSTSIM_OK: PVST Simulation inco D1#conf t
Enter configuration commands, one per line. End with CNTL/Z.
D1(config)#spanning-tree mst configuration
```

Configure an MST region name. Our example will be CCNPv8.

```
D1(config-mst)#name CCNPv8
D1(config-mst)#
```

Configure an MST configuration revision number. Our example will be 1.

```
D1(config-mst)#
D1(config-mst)#revision 1
D1(config-mst)#
```

Configure instance 1 to include VLAN 2.

Configure instance 2 to include VLAN 4.

Commit the configuration by typing exit and returning to global configuration mode.

```
D1(config-mst)#instance 1 vlan 2
D1(config-mst)#
D1(config-mst)#
D1(config-mst)#
D1(config-mst)#
D1(config-mst)#ex
D1(config)#end
D1#
*Oct 31 13:31:30 221: %SVS-S-CONETG
```

Issue the command show spanning-tree mst to verify the configuration is in place.

```
D1#show spanning-tree mst
##### MST0
                   vlans mapped: 1,3,5-4094
          address 0c8f.fc0c.0000 priority
address 0c28.f7bd.0000 priority
                                                                       32768 (32768 sysid 0)
32768 (32768 sysid 0)
Bridge
Root
                    port Gi0/0
                                                      path cost
                                                                           20000
Regional Root this switch
Operational hello time 2 , forward delay 15, max age 20, txholdcount 6
Configured hello time 2 , forward delay 15, max age 20, max hops 20
                                                   Prio.Nbr Type
Interface
                       Role Sts Cost
            Root FWD 20000 128.1 Shr Bound(RSTP)
Altn BLK 20000 128.2 Shr Bound(RSTP)
Altn BLK 20000 128.3 Shr Bound(RSTP)
Gi0/0
Gi0/1
Gi0/2
##### MST1 vlans mapped: 2
Bridge address 0c8f.fc0c.0000 priority 32769 (32768 sysid 1)
Root this switch for MST1
Interface Role Sts Cost
                                                 Prio.Nbr Type
               Mstr FWD 20000 128.1 Shr Bound(RSTP)
Altn BLK 20000 128.2 Shr Bound(RSTP)
Altn BLK 20000 128.3 Shr Bound(RSTP)
Gi0/2
##### MST2 vlans mapped: 4
Bridge address 0c8f.fc0c.0000 priority 32770 (32768 sysid 2)
Root this switch for MST2
Interface
                    Role Sts Cost Prio.Nbr Type
Gi0/0 Mstr FWD 20000 128.1 Shr Bound(RSTP)
Gi0/1 Altn BLK 20000 128.2 Shr Bound(RSTP)
Gi0/2 Altn BLK 20000 128.3 Shr Bound(RSTP)
```

This configuration does not propagate to other switches. Each switch exchanges digest information summarizing the VLAN-to-Instance mappings it has configured. If a switch receives a BPDU with a different digest, it assumes that the sender is in a different MST region. The output below is what A1 shows in the topology used to create this lab.

```
Al#show spanning-tree mst
##### MST0 vlans mapped: 1-4094
Bridge address 0c28.f7bd.0000 priority
                                                            32768 (32768 sysid 0)
Root
                this switch for the CIST
Operational hello time 2 , forward delay 15, max age 20, txholdcount 6
Configured hello time 2 , forward delay 15, max age 20, max hops 20
Interface
                  Role Sts Cost
                                           Prio.Nbr Type
Gi0/0 Desg FWD 20000 128.1 Shr
Gi0/1 Desg FWD 20000 128.2 Shr
Gi0/2 Desg FWD 20000 128.3 Shr
Gi0/3 Desg FWD 20000 128.4 Shr
                    Desg FWD 20000
Gi1/0
                                           128.5
A1#show spanning-tree mst configuration digest
Al#show spanning-tree mst configuration digest
Name []
Revision 0
Digest
                   Instances configured 1
                   0xAC36177F50283CD4B83821D8AB26DE62
Pre-std Digest 0x8B3B6C15EF8D089BB55ED10D24DF44DE
A1#
      31 13:33:27.937: %PLATFORM-5-SIGNATURE VERIFIED: Image 'flash0:/vios
```

Enter digest command in D1:

```
D1#
D1#show spanning-tree mst configuration digest
Name [CCNPv8]
Revision 1 Instances configured 3
Digest 0x746D865FEAD726D8F401F9396B8B62DA
Pre-std Digest 0xDE5D7C8B79A99142EBC0A1C265ED7B05
D1#conf t
```

Configure MST on D1, change the revision number to 2 and add VLAN 3 to instance 1 and VLAN 5 to instance 2.

```
Enter configuration commands, one per line. End with CNTL/Z.
D1(config)#spanning-tree mst configuration
D1(config-mst)#show current
Current MST configuration
         [CCNPv8]
Revision 1
                 Instances configured 3
Instance Vlans mapped
          1,3,5-4094
D1(config-mst)#revision 2
D1(config-mst)#instance 1 vlan 3
D1(config-mst)#instance 2 vlan 5
D1(config-mst)#show pending
Pending MST configuration
Name [CCNPv8]
Revision 2 Instances configured 3
Instance Vlans mapped
          1,6-4094
          2-3
          4-5
D1(config-mst)#ex
D1(config)#end
D1#
```

Now configure D2 and A1 with the same configuration settings (name CCNPv8, revision2, instance 1 vlans 2-3, instance 2 vlans 4-5). After completing the configuration on D2 and A1, the output of show spanning-tree mst on A1 should be similar to the following output.

D2:

```
D2#conf t
Enter configuration commands, one per line. End with CNTL/Z.
D2(config)#spanning-tree mst configuration
*Oct 31 13:33:36.649: %PLATFORM-5-SIGNATURE_VERIFIED: Image 'flash0:/vios_l2-adventerprisek9-m' passed code signing verification
D2(config)#spanning-tree mst configuration
D2(config-mst)#name CCNPv8
D2(config-mst)#revision 2
D2(config-mst)#instance 1 vlan 2
D2(config-mst)#instance 1 vlan 2
D2(config-mst)#instance 2 vlan 4
D2(config-mst)#instance 1 vlan 3
D2(config-mst)#instance 2 vlan 5
D2(config-mst)#ex
D2(config-mst)#ex
D2(config)#end
D2#
```

A1:

```
A1#
A1#conf t
Enter configuration commands, one per line. End with CNTL/Z.
A1(config)#spanning-tree mst configuration
A1(config-mst)#name CCNPv8
A1(config-mst)#revision 2
A1(config-mst)#instance 1 vlan 2
A1(config-mst)#instance 2 vlan 4
A1(config-mst)#instance 1 vlan 3
A1(config-mst)#instance 2 vlan 5
A1(config-mst)#instance 2 vlan 5
A1(config-mst)#ex
A1(config-mst)#ex
A1(config-mst)#ex
A1(config)#end
A1#
A1#
A1#
```

```
Al#show spanning-tree mst
##### MST0 vlans mapped:
                                 1,6-4094
               address 0c28.f7bd.0000 priority
                                                            32768 (32768 sysid 0)
               this switch for the CIST
Root
Operational hello time 2 , forward delay 15, max age 20, txholdcount 6
Configured hello time 2 , forward delay 15, max age 20, max hops 20
Interface
                                         Prio.Nbr Type
                  Role Sts Cost
          Desg BLK 20000
Gi0/0
                                         128.1
               Desg BLK 20000
Desg BLK 20000
Desg BLK 20000
Gi0/1
                                         128.2
                                                   Shr
Gi0/2
                                         128.3
                                                   Shr
Gi0/3
                                         128.4
                                                   Shr
                  Desg BLK 20000
Gi1/0
                                         128.5
##### MST1 vlans mapped: 2-3
Bridge address 0c28.f7bd.0000 priority
Root this switch for MST1
                                                           32769 (32768 sysid 1)
Interface
                  Role Sts Cost
                                         Prio.Nbr Type
          Desg BLK 20000 128.1
Desg BLK 20000 128.2
Gi0/0
                                                   Shr
Gi0/1
                                                   Shr
Gi0/2
                 Desg BLK 20000
                                         128.3
                  Desg BLK 20000
Gi0/3
                                         128.4
                                                   Shr
##### MST2 vlans mapped: 4-5
Bridge address 0c28.f7bd.0000 priority 32770 (32768 sysid 2)
Root this switch for MST2
Interface
                                         Prio.Nbr Type
                  Role Sts Cost
           Desg BLK 20000 128.1
Gi0/0
                                                   Shr
Gi0/1
                  Desg BLK 20000
                                         128.2
                                                   Shr
                 Desg BLK 20000
                                                   Shr
Gi0/2
                                         128.3
                   Desg BLK 20000
                                                   Shr
Gi0/3
                                         128.4
```

Controlling the Root Bridge.

- Just like with PVST+ and Rapid PVST+, the current root bridge was elected based on the lowest Bridge ID (consisting of the Priority, extended system ID equal to the VLAN ID, and base MAC address values).
- With PVST+ or Rapid PVST+, root bridge selection is done for each VLAN. With MST, the root bridge is based on instances.

- There are two basic ways to manipulate the configuration to control the location of the root bridge:
 - The spanning-tree mst instance-id priority value command can be used to manually set a priority value.
 - The spanning-tree mst instance-id root { primary | secondary } command can be used to automatically set a priority value.
- You will need to make configuration changes on both D1 and D2. The commands used at D1:

D1:

```
D1#conf t
Enter configuration commands, one per line. End with CNTL/Z.
D1(config)#spanning-tree mst root primary

% Invalid input detected at '^' marker.

D1(config)#spanning-tree mst 1 root primary
D1(config)#
D1(config)#
D1(config)#
D1(config)#
D1(config)#
```

After you have configured both D1 and D2, go to A1 and issue the command show spanning-tree root.

In this output, you will see the root bridges differentiated.

```
Al#show spanning-tree root

Root Hello Max Fwd

MST Instance Root ID Cost Time Age Dly Root Port

MST0 32768 0c28.f7bd.0000 0 2 20 15

MST1 24577 0c8f.fc0c.0000 20000 2 20 15 Gi0/0

MST2 28674 0c8f.fc0c.0000 20000 2 20 15 Gi0/0

Al#show spanning-tree mst 1
```

On A1, issue the commands show spanning-tree vlan 1 and show spanning-tree blockedports.

```
MST2 28674 0c8t.
Al#show spanning-tree mst 1
##### MST1 vlans mapped: 2-3
Bridge address 0c28.f7bd.0000 priority 32769 (32768 sysid 1)
Root address 0c8f.fc0c.0000 priority 24577 (24576 sysid 1)
Root address 0c8f.fc0c.0000 cost 20000 rem hops 19
Interface
                      Role Sts Cost
                                                 Prio.Nbr Type
           Root FWD 20000 128.1 Shr
Altn BLK 20000 128.2 Shr
Gi0/0
                                                             Shr
Gi0/1
                     Desg FWD 20000
Desg FWD 20000
Gi0/2
Gi0/3
                                                 128.3
                                                             Shr
                                                          Shr
                                                 128.4
Al#show spanking-tree blockedports
% Invalid input detected at '^' marker.
Al#show spanning-tree blockedports
Name
                            Blocked Interfaces List
MST1
                            Gi0/1
MST2
Number of blocked ports (segments) in the system : 2
```

On A1, shutdown interfaces F0/1 and F0/2, assign a new port cost of 1000 to F0/2 using the spanning- tree mst 1 cost value command, and then issue the no shutdown command on the ports.

```
Enter configuration commands, one per line. End with CNTL/Z. Al(config)#int range gi0/0-1
Al(config-if-range)#shut
 A1(config-if-range)#exit
 A1(config)#int
  Oct 31 13:35:26.551: %LINK-5-CHANGED: Interface GigabitEthernet0/0, changed state to administratively down"
e *Oct 31 13:35:26.580: %LINK-5-CHANGED: Interface GigabitEthernet0/1, changed state to administratively down
  *Oct 31 13:35:27.551: %LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/0, changed state to down
 A1(config)#int
  Oct 31 13:35:27.580: %LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/1, changed state to down
 Al(config)#int gi0/1
 Al(config-if)#spanning-tree mst 1 cost 100
 A1(config-if)#ex
 Al(config)#int range gi0/0-1
 Al(config-if-range)#no shut
Al(config-if-range)#ex
 A1(config)#
*Oct 31 13:35:42.951: %LINK-3-UPDOWN: Interface GigabitEthernet0/0, changed state to up
 *Oct 31 13:35:42.979: %LINK-3-UPDOWN: Interface GigabitEthernet0/1, changed state to up
  *Oct 31 13:35:43.951: %LINEPROTO-5-UPDOwN: Line protocol on Interface GigabitEthernet0/0, changed state to up
  *Oct 31 13:35:43.979: %LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/1, changed state to up
```

Now verify that this impacts root port selection on A1 using the show spanning-tree vlan 1 and show spanning-tree blockedports commands.

The port priority can be any value between 0 and 240, in increments of 16 (older switches may allow setting the priority in different increments). On A1, issue the command show spanning-tree mst 2 and take note of the port ID values listed.

```
Al#show spanning-tree mst 2
##### MST2 vlans mapped: 4-5
Bridge address 0c28.f7bd.0000 priority
                                                32770 (32768 sysid 2)
            address 0c8f.fc0c.0000 priority 28674 (28672 sysid 2)
Root
             port Gi0/0
                                                  20000
                                                         rem hops 19
                                    cost
                                Prio.Nbr Type
Interface
               Role Sts Cost
       Root FWD 20000 128.1 Shr
Altn BLK 20000 128.2 Shr
Desg FWD 20000 128.3 Shr
Gi0/0
Gi0/1
G10/2
               Desg FWD 20000
Gi0/3
                                  128.4
                                           Shr
```

Modify the port priority of D2 interface G1/0/6 so that it becomes the preferred port by issuing the spanning-tree mst 2 port-priority value interface configuration command. Use a value of 64.

```
D2#conf t
Enter configuration commands, one per line. End with CNTL/Z.

D2(config)#int range gi0/0-1

D2(config-if-range)#shut

D2(config-if-range)#ex

D2(config)#int gi0/1

*Oct 31 13:37:23.478: %LINK-5-CHANGED: Interface GigabitEthernet0/0, changed state to administratively down

*Oct 31 13:37:23.511: %LINK-5-CHANGED: Interface GigabitEthernet0/1, changed state to administratively down

*Oct 31 13:37:24.478: %LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/0, changed state to down

D2(config)#int gi0/1

*Oct 31 13:37:24.511: %LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/1, changed state to down

D2(config)#int gi0/1

*Oct 31 13:37:24.511: %LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/1, changed state to down

D2(config)#int gi0/1

D2(config-if)#spanning-tree mst 2 port-priority 64

D2(config-if)#ex

D2(config-if-range)#no shut

D2(config-if-range)#ex
```

On A1, issue the show spanning-tree mst 2 command and you will see that Fa0/4 is now the selected root port.

```
A1#show spanning-tree mst 2
##### MST2 vlans mapped: 4-5
           address 0c28.f7bd.0000 priority
address 0c8f.fc0c.0000 priority
Bridge
                                                     32770 (32768 sysid 2)
                                                     28674 (28672 sysid 2)
Root
                                                     20000
            port
                    Gi0/0
                                     cost
                                                             rem hops 19
                                    Prio.Nbr Type
Interface
                Role Sts Cost
Gi0/0
          Root FWD 20000 128.1
                                              Shr
Gi0/1
Gi0/1
                Altn BLK 20000
                                    128.2
                                              Shr
                Desg FWD 20000
Desg FWD 20000
                                   128.3
                                    128.4
                                             Shr
Gi0/3
```