
Probability

Release 10.8

The Sage Development Team

Dec 23, 2025

CONTENTS

1	Probability Distributions	1
2	Random variables and probability spaces	21
3	Indices and Tables	25
	Python Module Index	27
	Index	29

PROBABILITY DISTRIBUTIONS

This module provides three types of probability distributions:

- *RealDistribution*: various real-valued probability distributions.
- *SphericalDistribution*: uniformly distributed points on the surface of an $n - 1$ sphere in n dimensional euclidean space.
- *GeneralDiscreteDistribution*: user-defined discrete distributions.

AUTHORS:

- Josh Kantor (2007-02): first version
- William Stein (2007-02): rewrite of docs, conventions, etc.
- Carlo Hamalainen (2008-08): full doctest coverage, more documentation, GeneralDiscreteDistribution, misc fixes.
- Kwankyu Lee (2010-05-29): F-distribution support.

REFERENCES:

GNU gsl library, General discrete distributions http://www.gnu.org/software/gsl/manual/html_node/General-Discrete-Distributions.html

GNU gsl library, Random number distributions http://www.gnu.org/software/gsl/manual/html_node/Random-Number-Distributions.html

class sage.probability.probability_distribution.**GeneralDiscreteDistribution**

Bases: *ProbabilityDistribution*

Create a discrete probability distribution.

INPUT:

- P – list of probabilities; the list will automatically be normalised if $\text{sum}(P)$ is not equal to 1
- rng – (optional) random number generator to use; may be one of 'default', 'luxury', or 'taus'
- seed – (optional) seed to use with the random number generator

OUTPUT: a probability distribution where the probability of selecting x is $P[x]$.

EXAMPLES:

Construct a GeneralDiscreteDistribution with the probability distribution P where $P(0) = 0.3$, $P(1) = 0.4$, $P(2) = 0.3$:

```
sage: P = [0.3, 0.4, 0.3]
sage: X = GeneralDiscreteDistribution(P)
sage: X.get_random_element() in (0, 1, 2)
True
```

```
>>> from sage.all import *
>>> P = [RealNumber('0.3'), RealNumber('0.4'), RealNumber('0.3')]
>>> X = GeneralDiscreteDistribution(P)
>>> X.get_random_element() in (Integer(0), Integer(1), Integer(2))
True
```

Checking the distribution of samples:

```
sage: P = [0.3, 0.4, 0.3]
sage: counts = [0] * len(P)
sage: X = GeneralDiscreteDistribution(P)
sage: nr_samples = 10000
sage: for _ in range(nr_samples):
....:     counts[X.get_random_element()] += 1
sage: [1.0*x/nr_samples for x in counts] # abs tol 3e-2
[0.3, 0.4, 0.3]
```

```
>>> from sage.all import *
>>> P = [RealNumber('0.3'), RealNumber('0.4'), RealNumber('0.3')]
>>> counts = [Integer(0)] * len(P)
>>> X = GeneralDiscreteDistribution(P)
>>> nr_samples = Integer(10000)
>>> for _ in range(nr_samples):
...     counts[X.get_random_element()] += Integer(1)
>>> [RealNumber('1.0')*x/nr_samples for x in counts] # abs tol 3e-2
[0.3, 0.4, 0.3]
```

The distribution probabilities will automatically be normalised:

```
sage: P = [0.1, 0.3]
sage: X = GeneralDiscreteDistribution(P, seed=0)
sage: counts = [0, 0]
sage: for _ in range(10000):
....:     counts[X.get_random_element()] += 1
sage: float(counts[1]/counts[0])
3.042037186742118
```

```
>>> from sage.all import *
>>> P = [RealNumber('0.1'), RealNumber('0.3')]
>>> X = GeneralDiscreteDistribution(P, seed=Integer(0))
>>> counts = [Integer(0), Integer(0)]
>>> for _ in range(Integer(10000)):
...     counts[X.get_random_element()] += Integer(1)
>>> float(counts[Integer(1)]/counts[Integer(0)])
3.042037186742118
```

`get_random_element()`

Get a random sample from the probability distribution.

EXAMPLES:

```
sage: P = [0.3, 0.4, 0.3]
sage: X = GeneralDiscreteDistribution(P)
```

(continues on next page)

(continued from previous page)

```
sage: all(X.get_random_element() in (0,1,2) for _ in range(10))
True
sage: isinstance(X.get_random_element(), sage.rings.integer.Integer)
True
```

```
>>> from sage.all import *
>>> P = [RealNumber('0.3'), RealNumber('0.4'), RealNumber('0.3')]
>>> X = GeneralDiscreteDistribution(P)
>>> all(X.get_random_element() in (Integer(0), Integer(1), Integer(2)) for _ in
↳ range(Integer(10)))
True
>>> isinstance(X.get_random_element(), sage.rings.integer.Integer)
True
```

reset_distribution()

This method resets the distribution.

EXAMPLES:

```
sage: T = GeneralDiscreteDistribution([0.1, 0.3, 0.6])
sage: T.set_seed(0)
sage: [T.get_random_element() for _ in range(10)]
[2, 2, 2, 2, 2, 1, 2, 2, 1, 2]
sage: T.reset_distribution()
sage: [T.get_random_element() for _ in range(10)]
[2, 2, 2, 2, 2, 1, 2, 2, 1, 2]
```

```
>>> from sage.all import *
>>> T = GeneralDiscreteDistribution([RealNumber('0.1'), RealNumber('0.3'),
↳ RealNumber('0.6')])
>>> T.set_seed(Integer(0))
>>> [T.get_random_element() for _ in range(Integer(10))]
[2, 2, 2, 2, 2, 1, 2, 2, 1, 2]
>>> T.reset_distribution()
>>> [T.get_random_element() for _ in range(Integer(10))]
[2, 2, 2, 2, 2, 1, 2, 2, 1, 2]
```

set_random_number_generator(rng='default')

Set the random number generator to be used by gsl.

EXAMPLES:

```
sage: X = GeneralDiscreteDistribution([0.3, 0.4, 0.3])
sage: X.set_random_number_generator('taus')
```

```
>>> from sage.all import *
>>> X = GeneralDiscreteDistribution([RealNumber('0.3'), RealNumber('0.4'),
↳ RealNumber('0.3')])
>>> X.set_random_number_generator('taus')
```

set_seed(seed)

Set the seed to be used by the random number generator.

EXAMPLES:

```
sage: X = GeneralDiscreteDistribution([0.3, 0.4, 0.3])
sage: X.set_seed(1)
sage: X.get_random_element()
1
```

```
>>> from sage.all import *
>>> X = GeneralDiscreteDistribution([RealNumber('0.3'), RealNumber('0.4'),
↳ RealNumber('0.3')])
>>> X.set_seed(Integer(1))
>>> X.get_random_element()
1
```

class sage.probability.probability_distribution.**ProbabilityDistribution**

Bases: object

Concrete probability distributions should be derived from this abstract class.

generate_histogram_data (*num_samples=1000*, *bins=50*)

Compute a histogram of the probability distribution.

INPUT:

- *num_samples* – (optional) number of times to sample from the probability distribution
- *bins* – (optional) number of bins to divide the samples into

OUTPUT:

- a tuple. The first element of the tuple is a list of length *bins*, consisting of the normalised histogram of the random samples. The second list is the bins.

EXAMPLES:

```
sage: set_random_seed(0)
sage: from sage.probability.probability_distribution import _
↳ GeneralDiscreteDistribution
sage: P = [0.3, 0.4, 0.3]
sage: X = GeneralDiscreteDistribution(P)
sage: h, b = X.generate_histogram_data(bins=10) #_
↳ needs sage.plot
sage: h # rel tol 1e-08 #_
↳ needs sage.plot
[1.6299999999999999,
 0.0,
 0.0,
 0.0,
 0.0,
 1.9049999999999985,
 0.0,
 0.0,
 0.0,
 1.4650000000000003]
sage: b #_
↳ needs sage.plot
[0.0,
```

(continues on next page)

(continued from previous page)

```

0.2,
0.4,
0.6000000000000001,
0.8,
1.0,
1.2000000000000002,
1.4000000000000001,
1.6,
1.8,
2.0]

```

```

>>> from sage.all import *
>>> set_random_seed(Integer(0))
>>> from sage.probability.probability_distribution import _
↳GeneralDiscreteDistribution
>>> P = [RealNumber('0.3'), RealNumber('0.4'), RealNumber('0.3')]
>>> X = GeneralDiscreteDistribution(P)
>>> h, b = X.generate_histogram_data(bins=Integer(10))
↳ # needs sage.plot
>>> h # rel tol 1e-08 #
↳needs sage.plot
[1.6299999999999999,
 0.0,
 0.0,
 0.0,
 0.0,
 1.9049999999999985,
 0.0,
 0.0,
 0.0,
 1.4650000000000003]
>>> b #
↳needs sage.plot
[0.0,
 0.2,
 0.4,
 0.6000000000000001,
 0.8,
 1.0,
 1.2000000000000002,
 1.4000000000000001,
 1.6,
 1.8,
 2.0]

```

generate_histogram_plot (*name*, *num_samples*=1000, *bins*=50)

Save the histogram from `generate_histogram_data()` to a file.

INPUT:

- *name* – file to save the histogram plot (as a PNG)
- *num_samples* – (optional) number of times to sample from the probability distribution

- `bins` – (optional) number of bins to divide the samples into

EXAMPLES:

This saves the histogram plot to a temporary file:

```
sage: from sage.probability.probability_distribution import_
↪ GeneralDiscreteDistribution
sage: import tempfile
sage: P = [0.3, 0.4, 0.3]
sage: X = GeneralDiscreteDistribution(P)
sage: with tempfile.NamedTemporaryFile() as f:
↪ needs sage.plot
.....:     X.generate_histogram_plot(f.name) #_
```

```
>>> from sage.all import *
>>> from sage.probability.probability_distribution import_
↪ GeneralDiscreteDistribution
>>> import tempfile
>>> P = [RealNumber('0.3'), RealNumber('0.4'), RealNumber('0.3')]
>>> X = GeneralDiscreteDistribution(P)
>>> with tempfile.NamedTemporaryFile() as f:
↪ needs sage.plot
...:     X.generate_histogram_plot(f.name) #_
```

`get_random_element()`

To be implemented by a derived class:

```
sage: P = sage.probability.probability_distribution.ProbabilityDistribution()
sage: P.get_random_element()
Traceback (most recent call last):
...
NotImplementedError: implement in derived class
```

```
>>> from sage.all import *
>>> P = sage.probability.probability_distribution.ProbabilityDistribution()
>>> P.get_random_element()
Traceback (most recent call last):
...
NotImplementedError: implement in derived class
```

class `sage.probability.probability_distribution.RealDistribution`

Bases: *ProbabilityDistribution*

The *RealDistribution* class provides a number of routines for sampling from and analyzing and visualizing probability distributions. For precise definitions of the distributions and their parameters see the gsl reference manuals chapter on random number generators and probability distributions.

EXAMPLES:

Uniform distribution on the interval $[a, b]$:

```
sage: a = 0
sage: b = 2
sage: T = RealDistribution('uniform', [a, b])
```

(continues on next page)

(continued from previous page)

```

sage: a <= T.get_random_element() <= b
True
sage: T.distribution_function(0)
0.5
sage: T.cum_distribution_function(1)
0.5
sage: T.cum_distribution_function_inv(.5)
1.0

```

```

>>> from sage.all import *
>>> a = Integer(0)
>>> b = Integer(2)
>>> T = RealDistribution('uniform', [a, b])
>>> a <= T.get_random_element() <= b
True
>>> T.distribution_function(Integer(0))
0.5
>>> T.cum_distribution_function(Integer(1))
0.5
>>> T.cum_distribution_function_inv(RealNumber('.5'))
1.0

```

The gaussian distribution takes 1 parameter `sigma`. The standard gaussian distribution has `sigma = 1`:

```

sage: sigma = 1
sage: T = RealDistribution('gaussian', sigma)
sage: s = T.get_random_element()
sage: s.parent()
Real Double Field
sage: T.distribution_function(0)
0.3989422804014327
sage: T.cum_distribution_function(1)
0.8413447460685429
sage: T.cum_distribution_function_inv(.5)
0.0

```

```

>>> from sage.all import *
>>> sigma = Integer(1)
>>> T = RealDistribution('gaussian', sigma)
>>> s = T.get_random_element()
>>> s.parent()
Real Double Field
>>> T.distribution_function(Integer(0))
0.3989422804014327
>>> T.cum_distribution_function(Integer(1))
0.8413447460685429
>>> T.cum_distribution_function_inv(RealNumber('.5'))
0.0

```

The rayleigh distribution has 1 parameter `sigma`:

```

sage: sigma = 3
sage: T = RealDistribution('rayleigh', sigma)
sage: s = T.get_random_element()
sage: s >= 0
True
sage: s.parent()
Real Double Field
sage: T.distribution_function(0)
0.0
sage: T.cum_distribution_function(1)
0.054040531093234534
sage: T.cum_distribution_function_inv(.5)
3.532230067546424...

```

```

>>> from sage.all import *
>>> sigma = Integer(3)
>>> T = RealDistribution('rayleigh', sigma)
>>> s = T.get_random_element()
>>> s >= Integer(0)
True
>>> s.parent()
Real Double Field
>>> T.distribution_function(Integer(0))
0.0
>>> T.cum_distribution_function(Integer(1))
0.054040531093234534
>>> T.cum_distribution_function_inv(RealNumber('.5'))
3.532230067546424...

```

The lognormal distribution has two parameters σ and ζ :

```

sage: zeta = 0
sage: sigma = 1
sage: T = RealDistribution('lognormal', [zeta, sigma])
sage: s = T.get_random_element()
sage: s >= 0
True
sage: s.parent()
Real Double Field
sage: T.distribution_function(0)
0.0
sage: T.cum_distribution_function(1)
0.5
sage: T.cum_distribution_function_inv(.5)
1.0

```

```

>>> from sage.all import *
>>> zeta = Integer(0)
>>> sigma = Integer(1)
>>> T = RealDistribution('lognormal', [zeta, sigma])
>>> s = T.get_random_element()
>>> s >= Integer(0)

```

(continues on next page)

(continued from previous page)

```

True
>>> s.parent()
Real Double Field
>>> T.distribution_function(Integer(0))
0.0
>>> T.cum_distribution_function(Integer(1))
0.5
>>> T.cum_distribution_function_inv(RealNumber('.5'))
1.0

```

The pareto distribution has two parameters a, and b:

```

sage: a = 1
sage: b = 1
sage: T = RealDistribution('pareto', [a, b])
sage: s = T.get_random_element()
sage: s >= b
True
sage: s.parent()
Real Double Field
sage: T.distribution_function(0)
0.0
sage: T.cum_distribution_function(1)
0.0
sage: T.cum_distribution_function_inv(.5)
2.0

```

```

>>> from sage.all import *
>>> a = Integer(1)
>>> b = Integer(1)
>>> T = RealDistribution('pareto', [a, b])
>>> s = T.get_random_element()
>>> s >= b
True
>>> s.parent()
Real Double Field
>>> T.distribution_function(Integer(0))
0.0
>>> T.cum_distribution_function(Integer(1))
0.0
>>> T.cum_distribution_function_inv(RealNumber('.5'))
2.0

```

The t-distribution has one parameter nu:

```

sage: nu = 1
sage: T = RealDistribution('t', nu)
sage: s = T.get_random_element()
sage: s.parent()
Real Double Field
sage: T.distribution_function(0)      # rel tol 1e-15
0.3183098861837906

```

(continues on next page)

(continued from previous page)

```
sage: T.cum_distribution_function(1) # rel tol 1e-15
0.75
sage: T.cum_distribution_function_inv(.5)
0.0
```

```
>>> from sage.all import *
>>> nu = Integer(1)
>>> T = RealDistribution('t', nu)
>>> s = T.get_random_element()
>>> s.parent()
Real Double Field
>>> T.distribution_function(Integer(0)) # rel tol 1e-15
0.3183098861837906
>>> T.cum_distribution_function(Integer(1)) # rel tol 1e-15
0.75
>>> T.cum_distribution_function_inv(RealNumber('.5'))
0.0
```

The F-distribution has two parameters `nu1` and `nu2`:

```
sage: nu1 = 9; nu2 = 17
sage: F = RealDistribution('F', [nu1,nu2])
sage: s = F.get_random_element()
sage: s >= 0
True
sage: s.parent()
Real Double Field
sage: F.distribution_function(1) # rel tol 1e-14
0.6695025505192798
sage: F.cum_distribution_function(3.68) # rel tol 1e-14
0.9899717772300652
sage: F.cum_distribution_function_inv(0.99) # rel tol 1e-14
3.682241524045864
```

```
>>> from sage.all import *
>>> nu1 = Integer(9); nu2 = Integer(17)
>>> F = RealDistribution('F', [nu1,nu2])
>>> s = F.get_random_element()
>>> s >= Integer(0)
True
>>> s.parent()
Real Double Field
>>> F.distribution_function(Integer(1)) # rel tol 1e-14
0.6695025505192798
>>> F.cum_distribution_function(RealNumber('3.68')) # rel tol 1e-14
0.9899717772300652
>>> F.cum_distribution_function_inv(RealNumber('0.99')) # rel tol 1e-14
3.682241524045864
```

The chi-squared distribution has one parameter `nu`:

```

sage: nu = 1
sage: T = RealDistribution('chisquared', nu)
sage: s = T.get_random_element()
sage: s >= 0
True
sage: s.parent()
Real Double Field
sage: T.distribution_function(0)
+infinity
sage: T.cum_distribution_function(1) # rel tol 1e-14
0.6826894921370856
sage: T.cum_distribution_function_inv(.5) # rel tol 1e-14
0.45493642311957305

```

```

>>> from sage.all import *
>>> nu = Integer(1)
>>> T = RealDistribution('chisquared', nu)
>>> s = T.get_random_element()
>>> s >= Integer(0)
True
>>> s.parent()
Real Double Field
>>> T.distribution_function(Integer(0))
+infinity
>>> T.cum_distribution_function(Integer(1)) # rel tol 1e-14
0.6826894921370856
>>> T.cum_distribution_function_inv(RealNumber('.5')) # rel tol 1e-14
0.45493642311957305

```

The exponential power distribution has two parameters a and b:

```

sage: a = 1
sage: b = 2.5
sage: T = RealDistribution('exppow', [a, b])
sage: s = T.get_random_element()
sage: s.parent()
Real Double Field
sage: T.distribution_function(0) # rel tol 1e-14
0.5635302489930136
sage: T.cum_distribution_function(1) # rel tol 1e-14
0.940263052542855

```

```

>>> from sage.all import *
>>> a = Integer(1)
>>> b = RealNumber('2.5')
>>> T = RealDistribution('exppow', [a, b])
>>> s = T.get_random_element()
>>> s.parent()
Real Double Field
>>> T.distribution_function(Integer(0)) # rel tol 1e-14
0.5635302489930136
>>> T.cum_distribution_function(Integer(1)) # rel tol 1e-14
0.940263052542855

```

The beta distribution has two parameters a and b :

```
sage: a = 2
sage: b = 2
sage: T = RealDistribution('beta', [a, b])
sage: s = T.get_random_element()
sage: 0 <= s <= 1
True
sage: s.parent()
Real Double Field
sage: T.distribution_function(0)
0.0
sage: T.cum_distribution_function(1)
1.0
```

```
>>> from sage.all import *
>>> a = Integer(2)
>>> b = Integer(2)
>>> T = RealDistribution('beta', [a, b])
>>> s = T.get_random_element()
>>> Integer(0) <= s <= Integer(1)
True
>>> s.parent()
Real Double Field
>>> T.distribution_function(Integer(0))
0.0
>>> T.cum_distribution_function(Integer(1))
1.0
```

The exponential distribution has one parameter μ :

```
sage: mu = 2
sage: T = RealDistribution('exponential', mu)
sage: s = T.get_random_element()
sage: 0 <= s
True
sage: s.parent()
Real Double Field
sage: T.distribution_function(0)
0.5
```

```
>>> from sage.all import *
>>> mu = Integer(2)
>>> T = RealDistribution('exponential', mu)
>>> s = T.get_random_element()
>>> Integer(0) <= s
True
>>> s.parent()
Real Double Field
>>> T.distribution_function(Integer(0))
0.5
```

The gamma distribution has two parameters a and b :

```

sage: a = 2
sage: b = 2
sage: T = RealDistribution('gamma', [a, b])
sage: s = T.get_random_element()
sage: 0 <= s
True
sage: s.parent()
Real Double Field
sage: T.distribution_function(0)
0.0

```

```

>>> from sage.all import *
>>> a = Integer(2)
>>> b = Integer(2)
>>> T = RealDistribution('gamma', [a, b])
>>> s = T.get_random_element()
>>> Integer(0) <= s
True
>>> s.parent()
Real Double Field
>>> T.distribution_function(Integer(0))
0.0

```

The weibull distribution has two parameters a and b:

```

sage: a = 1
sage: b = 1
sage: T = RealDistribution('weibull', [a, b])
sage: s = T.get_random_element()
sage: s >= 0
True
sage: s.parent()
Real Double Field
sage: T.distribution_function(0)
1.0
sage: T.cum_distribution_function(1)
0.6321205588285577
sage: T.cum_distribution_function_inv(.5)
0.6931471805599453

```

```

>>> from sage.all import *
>>> a = Integer(1)
>>> b = Integer(1)
>>> T = RealDistribution('weibull', [a, b])
>>> s = T.get_random_element()
>>> s >= Integer(0)
True
>>> s.parent()
Real Double Field
>>> T.distribution_function(Integer(0))
1.0
>>> T.cum_distribution_function(Integer(1))

```

(continues on next page)

(continued from previous page)

```
0.6321205588285577
>>> T.cum_distribution_function_inv(RealNumber('.5'))
0.6931471805599453
```

It is possible to select which random number generator drives the sampling as well as the seed. The default is the Mersenne twister. Also available are the RANDLXS algorithm and the Tausworthe generator (see the gsl reference manual for more details). These are all supposed to be simulation quality generators. For RANDLXS use `rng='luxury'` and for tausworthe use `rng='taus'`:

```
sage: T = RealDistribution('gaussian', 1, rng='luxury', seed=10)
```

```
>>> from sage.all import *
>>> T = RealDistribution('gaussian', Integer(1), rng='luxury', seed=Integer(10))
```

To change the seed at a later time use `set_seed`:

```
sage: T.set_seed(100)
```

```
>>> from sage.all import *
>>> T.set_seed(Integer(100))
```

`cum_distribution_function(x)`

Evaluate the cumulative distribution function of the probability distribution at x .

EXAMPLES:

```
sage: T = RealDistribution('uniform', [0, 2])
sage: T.cum_distribution_function(1)
0.5
```

```
>>> from sage.all import *
>>> T = RealDistribution('uniform', [Integer(0), Integer(2)])
>>> T.cum_distribution_function(Integer(1))
0.5
```

`cum_distribution_function_inv(x)`

Evaluate the inverse of the cumulative distribution function of the probability distribution at x .

EXAMPLES:

```
sage: T = RealDistribution('uniform', [0, 2])
sage: T.cum_distribution_function_inv(.5)
1.0
```

```
>>> from sage.all import *
>>> T = RealDistribution('uniform', [Integer(0), Integer(2)])
>>> T.cum_distribution_function_inv(RealNumber('.5'))
1.0
```

`distribution_function(x)`

Evaluate the distribution function of the probability distribution at x .

EXAMPLES:

```
sage: T = RealDistribution('uniform', [0, 2])
sage: T.distribution_function(0)
0.5
sage: T.distribution_function(1)
0.5
sage: T.distribution_function(1.5)
0.5
sage: T.distribution_function(2)
0.0
```

```
>>> from sage.all import *
>>> T = RealDistribution('uniform', [Integer(0), Integer(2)])
>>> T.distribution_function(Integer(0))
0.5
>>> T.distribution_function(Integer(1))
0.5
>>> T.distribution_function(RealNumber('1.5'))
0.5
>>> T.distribution_function(Integer(2))
0.0
```

get_random_element()

Get a random sample from the probability distribution.

EXAMPLES:

```
sage: T = RealDistribution('gaussian', 1, seed=0)
sage: T.get_random_element() # rel tol 4e-16
0.13391860811867587
```

```
>>> from sage.all import *
>>> T = RealDistribution('gaussian', Integer(1), seed=Integer(0))
>>> T.get_random_element() # rel tol 4e-16
0.13391860811867587
```

plot(*args, **kws)

Plot the distribution function for the probability distribution. Parameters to `sage.plot.plot.plot()` can be passed through `*args` and `**kws`.

EXAMPLES:

```
sage: T = RealDistribution('uniform', [0, 2])
sage: P = T.plot() #_
↪needs sage.plot
```

```
>>> from sage.all import *
>>> T = RealDistribution('uniform', [Integer(0), Integer(2)])
>>> P = T.plot() #_
↪needs sage.plot
```

reset_distribution()

Reset the distribution.

EXAMPLES:

```

sage: T = RealDistribution('gaussian', 1, seed=10)
sage: [T.get_random_element() for _ in range(10)] # rel tol 4e-16
[-0.7460999595745819, -0.004644606626413462, -0.8720538317207641, 0.
↪ 6916259921666037, 2.67668674666043, 0.6325002813661014, -0.7974263521959355,
↪ -0.5284976893366636, 1.1353119849528792, 0.9912505673230749]
sage: T.reset_distribution()
sage: [T.get_random_element() for _ in range(10)] # rel tol 4e-16
[-0.7460999595745819, -0.004644606626413462, -0.8720538317207641, 0.
↪ 6916259921666037, 2.67668674666043, 0.6325002813661014, -0.7974263521959355,
↪ -0.5284976893366636, 1.1353119849528792, 0.9912505673230749]

```

```

>>> from sage.all import *
>>> T = RealDistribution('gaussian', Integer(1), seed=Integer(10))
>>> [T.get_random_element() for _ in range(Integer(10))] # rel tol 4e-16
[-0.7460999595745819, -0.004644606626413462, -0.8720538317207641, 0.
↪ 6916259921666037, 2.67668674666043, 0.6325002813661014, -0.7974263521959355,
↪ -0.5284976893366636, 1.1353119849528792, 0.9912505673230749]
>>> T.reset_distribution()
>>> [T.get_random_element() for _ in range(Integer(10))] # rel tol 4e-16
[-0.7460999595745819, -0.004644606626413462, -0.8720538317207641, 0.
↪ 6916259921666037, 2.67668674666043, 0.6325002813661014, -0.7974263521959355,
↪ -0.5284976893366636, 1.1353119849528792, 0.9912505673230749]

```

set_distribution (name='uniform', parameters=None)

This method can be called to change the current probability distribution.

EXAMPLES:

```

sage: T = RealDistribution('gaussian', 1)
sage: T.set_distribution('gaussian', 1)
sage: T.set_distribution('pareto', [0, 1])

```

```

>>> from sage.all import *
>>> T = RealDistribution('gaussian', Integer(1))
>>> T.set_distribution('gaussian', Integer(1))
>>> T.set_distribution('pareto', [Integer(0), Integer(1)])

```

set_random_number_generator (rng='default')

Set the gsl random number generator to be one of 'default', 'luxury', or 'taus'.

EXAMPLES:

```

sage: T = SphericalDistribution()
sage: T.set_random_number_generator('default')
sage: T.set_seed(0)
sage: T.get_random_element() # rel tol 4e-16
(0.07961564104639995, -0.05237671627581255, 0.9954486572862178)
sage: T.set_random_number_generator('luxury')
sage: T.set_seed(0)
sage: T.get_random_element() # rel tol 4e-16
(0.07961564104639995, -0.05237671627581255, 0.9954486572862178)

```

```

>>> from sage.all import *
>>> T = SphericalDistribution()
>>> T.set_random_number_generator('default')
>>> T.set_seed(Integer(0))
>>> T.get_random_element() # rel tol 4e-16
(0.07961564104639995, -0.05237671627581255, 0.9954486572862178)
>>> T.set_random_number_generator('luxury')
>>> T.set_seed(Integer(0))
>>> T.get_random_element() # rel tol 4e-16
(0.07961564104639995, -0.05237671627581255, 0.9954486572862178)

```

set_seed(seed)

Set the seed for the underlying random number generator.

EXAMPLES:

```

sage: T = RealDistribution('gaussian', 1, rng='luxury', seed=10)
sage: T.set_seed(100)

```

```

>>> from sage.all import *
>>> T = RealDistribution('gaussian', Integer(1), rng='luxury',
↪seed=Integer(10))
>>> T.set_seed(Integer(100))

```

class sage.probability.probability_distribution.SphericalDistribution

Bases: *ProbabilityDistribution*

This class is capable of producing random points uniformly distributed on the surface of an $(n - 1)$ -sphere in n -dimensional euclidean space. The dimension n is selected via the keyword `dimension`. The random number generator which drives it can be selected using the keyword `rng`. Valid choices are 'default' which uses the Mersenne-Twister, 'luxury' which uses RANDLXS, and 'taus' which uses the tausworth generator. The default dimension is 3.

EXAMPLES:

```

sage: T = SphericalDistribution()
sage: s = T.get_random_element()
sage: s.norm() # rel tol 1e-14
1.0
sage: len(s)
3
sage: T = SphericalDistribution(dimension=4, rng='luxury')
sage: s = T.get_random_element()
sage: s.norm() # rel tol 1e-14
1.0
sage: len(s)
4

```

```

>>> from sage.all import *
>>> T = SphericalDistribution()
>>> s = T.get_random_element()
>>> s.norm() # rel tol 1e-14
1.0
>>> len(s)

```

(continues on next page)

(continued from previous page)

```

3
>>> T = SphericalDistribution(dimension=Integer(4), rng='luxury')
>>> s = T.get_random_element()
>>> s.norm() # rel tol 1e-14
1.0
>>> len(s)
4

```

get_random_element()

Get a random sample from the probability distribution.

EXAMPLES:

```

sage: T = SphericalDistribution(seed=0)
sage: T.get_random_element() # rel tol 4e-16
(0.07961564104639995, -0.05237671627581255, 0.9954486572862178)

```

```

>>> from sage.all import *
>>> T = SphericalDistribution(seed=Integer(0))
>>> T.get_random_element() # rel tol 4e-16
(0.07961564104639995, -0.05237671627581255, 0.9954486572862178)

```

reset_distribution()

This method resets the distribution.

EXAMPLES:

```

sage: T = SphericalDistribution(seed=0)
sage: [T.get_random_element() for _ in range(4)] # rel tol 4e-16
[(0.07961564104639995, -0.05237671627581255, 0.9954486572862178),
 (0.4123599490593727, 0.5606817859360097, -0.7180495855658982),
 (-0.9619860891623148, -0.2726473494040498, -0.015690351211529927),
 (0.5674297579435619, -0.011206783800420301, -0.8233455397322326)]
sage: T.reset_distribution()
sage: [T.get_random_element() for _ in range(4)] # rel tol 4e-16
[(0.07961564104639995, -0.05237671627581255, 0.9954486572862178),
 (0.4123599490593727, 0.5606817859360097, -0.7180495855658982),
 (-0.9619860891623148, -0.2726473494040498, -0.015690351211529927),
 (0.5674297579435619, -0.011206783800420301, -0.8233455397322326)]

```

```

>>> from sage.all import *
>>> T = SphericalDistribution(seed=Integer(0))
>>> [T.get_random_element() for _ in range(Integer(4))] # rel tol 4e-16
[(0.07961564104639995, -0.05237671627581255, 0.9954486572862178),
 (0.4123599490593727, 0.5606817859360097, -0.7180495855658982),
 (-0.9619860891623148, -0.2726473494040498, -0.015690351211529927),
 (0.5674297579435619, -0.011206783800420301, -0.8233455397322326)]
>>> T.reset_distribution()
>>> [T.get_random_element() for _ in range(Integer(4))] # rel tol 4e-16
[(0.07961564104639995, -0.05237671627581255, 0.9954486572862178),
 (0.4123599490593727, 0.5606817859360097, -0.7180495855658982),
 (-0.9619860891623148, -0.2726473494040498, -0.015690351211529927),
 (0.5674297579435619, -0.011206783800420301, -0.8233455397322326)]

```

set_random_number_generator (*rng='default'*)

Set the gsl random number generator to be one of default, luxury, or taus.

EXAMPLES:

```
sage: T = SphericalDistribution()
sage: T.set_random_number_generator('default')
sage: T.set_seed(0)
sage: T.get_random_element() # rel tol 4e-16
(0.07961564104639995, -0.05237671627581255, 0.9954486572862178)
sage: T.set_random_number_generator('luxury')
sage: T.set_seed(0)
sage: T.get_random_element() # rel tol 4e-16
(0.07961564104639995, -0.05237671627581255, 0.9954486572862178)
```

```
>>> from sage.all import *
>>> T = SphericalDistribution()
>>> T.set_random_number_generator('default')
>>> T.set_seed(Integer(0))
>>> T.get_random_element() # rel tol 4e-16
(0.07961564104639995, -0.05237671627581255, 0.9954486572862178)
>>> T.set_random_number_generator('luxury')
>>> T.set_seed(Integer(0))
>>> T.get_random_element() # rel tol 4e-16
(0.07961564104639995, -0.05237671627581255, 0.9954486572862178)
```

set_seed (*seed*)

Set the seed for the underlying random number generator.

EXAMPLES:

```
sage: T = SphericalDistribution(seed=0)
sage: T.set_seed(100)
```

```
>>> from sage.all import *
>>> T = SphericalDistribution(seed=Integer(0))
>>> T.set_seed(Integer(100))
```


RANDOM VARIABLES AND PROBABILITY SPACES

This introduces a class of random variables, with the focus on discrete random variables (i.e. on a discrete probability space). This avoids the problem of defining a measure space and measurable functions.

```
class sage.probability.random_variable.DiscreteProbabilitySpace (X, P, codomain=None,  
                                                                check=False)
```

Bases: *ProbabilitySpace_generic, DiscreteRandomVariable*

The discrete probability space

entropy ()

The entropy of the probability space.

set ()

The set of values of the probability space taking possibly nonzero probability (a subset of the domain).

```
class sage.probability.random_variable.DiscreteRandomVariable (X, f, codomain=None,  
                                                                check=False)
```

Bases: *RandomVariable_generic*

A random variable on a discrete probability space.

correlation (*other*)

The correlation of the probability space $X = \text{self}$ with $Y = \text{other}$.

covariance (*other*)

The covariance of the discrete random variable $X = \text{self}$ with $Y = \text{other}$.

Let S be the probability space of $X = \text{self}$, with probability function p , and $E(X)$ be the expectation of X . Then the variance of X is:

$$\text{cov}(X, Y) = E((X - E(X)) \cdot (Y - E(Y))) = \sum_{x \in S} p(x)(X(x) - E(X))(Y(x) - E(Y))$$

expectation ()

The expectation of the discrete random variable, namely $\sum_{x \in S} p(x)X[x]$, where $X = \text{self}$ and S is the probability space of X .

function ()

The function defining the random variable.

standard_deviation ()

The standard deviation of the discrete random variable.

Let S be the probability space of $X = \text{self}$, with probability function p , and $E(X)$ be the expectation of X . Then the standard deviation of X is defined to be

$$\sigma(X) = \sqrt{\sum_{x \in S} p(x)(X(x) - E(x))^2}$$

translation_correlation (*other*, *map*)

The correlation of the probability space $X = \text{self}$ with image of $Y = \text{other}$ under *map*.

translation_covariance (*other*, *map*)

The covariance of the probability space $X = \text{self}$ with image of $Y = \text{other}$ under the given map of the probability space.

Let S be the probability space of $X = \text{self}$, with probability function p , and $E(X)$ be the expectation of X . Then the variance of X is:

$$\text{cov}(X, Y) = E((X - E(X)) \cdot (Y - E(Y))) = \sum_{x \in S} p(x)(X(x) - E(X))(Y(x) - E(Y))$$

translation_expectation (*map*)

The expectation of the discrete random variable, namely $\sum_{x \in S} p(x)X[e(x)]$, where $X = \text{self}$, S is the probability space of X , and $e = \text{map}$.

translation_standard_deviation (*map*)

The standard deviation of the translated discrete random variable $X \circ e$, where $X = \text{self}$ and $e = \text{map}$.

Let S be the probability space of $X = \text{self}$, with probability function p , and $E(X)$ be the expectation of X . Then the standard deviation of X is defined to be

$$\sigma(X) = \sqrt{\sum_{x \in S} p(x)(X(x) - E(x))^2}$$

translation_variance (*map*)

The variance of the discrete random variable $X \circ e$, where $X = \text{self}$, and $e = \text{map}$.

Let S be the probability space of $X = \text{self}$, with probability function p , and $E(X)$ be the expectation of X . Then the variance of X is:

$$\text{var}(X) = E((X - E(x))^2) = \sum_{x \in S} p(x)(X(x) - E(x))^2$$

variance ()

The variance of the discrete random variable.

Let S be the probability space of $X = \text{self}$, with probability function p , and $E(X)$ be the expectation of X . Then the variance of X is:

$$\text{var}(X) = E((X - E(x))^2) = \sum_{x \in S} p(x)(X(x) - E(x))^2$$

class sage.probability.random_variable.**ProbabilitySpace_generic** (*domain*, *RR*)

Bases: *RandomVariable_generic*

A probability space.

```
    domain()

class sage.probability.random_variable.RandomVariable_generic( $X$ ,  $RR$ )
    Bases: Parent
    A random variable.
    codomain()
    domain()
    field()
    probability_space()

sage.probability.random_variable.is_DiscreteProbabilitySpace( $S$ )
sage.probability.random_variable.is_DiscreteRandomVariable( $X$ )
sage.probability.random_variable.is_ProbabilitySpace( $S$ )
sage.probability.random_variable.is_RandomVariable( $X$ )
```


INDICES AND TABLES

- [Index](#)
- [Module Index](#)
- [Search Page](#)

PYTHON MODULE INDEX

p

`sage.probability.probability_distribution,`
 [1](#)
`sage.probability.random_variable,` [21](#)

C

`codomain()` (*sage.probability.random_variable.RandomVariable_generic method*), 23
`correlation()` (*sage.probability.random_variable.DiscreteRandomVariable method*), 21
`covariance()` (*sage.probability.random_variable.DiscreteRandomVariable method*), 21
`cum_distribution_function()` (*sage.probability.probability_distribution.RealDistribution method*), 14
`cum_distribution_function_inv()` (*sage.probability.probability_distribution.RealDistribution method*), 14

D

`DiscreteProbabilitySpace` (*class in sage.probability.random_variable*), 21
`DiscreteRandomVariable` (*class in sage.probability.random_variable*), 21
`distribution_function()` (*sage.probability.probability_distribution.RealDistribution method*), 14
`domain()` (*sage.probability.random_variable.ProbabilitySpace_generic method*), 22
`domain()` (*sage.probability.random_variable.RandomVariable_generic method*), 23

E

`entropy()` (*sage.probability.random_variable.DiscreteProbabilitySpace method*), 21
`expectation()` (*sage.probability.random_variable.DiscreteRandomVariable method*), 21

F

`field()` (*sage.probability.random_variable.RandomVariable_generic method*), 23
`function()` (*sage.probability.random_variable.DiscreteRandomVariable method*), 21

G

`GeneralDiscreteDistribution` (*class in sage.probability.probability_distribution*), 1

`generate_histogram_data()` (*sage.probability.probability_distribution.ProbabilityDistribution method*), 4
`generate_histogram_plot()` (*sage.probability.probability_distribution.ProbabilityDistribution method*), 5
`get_random_element()` (*sage.probability.probability_distribution.GeneralDiscreteDistribution method*), 2
`get_random_element()` (*sage.probability.probability_distribution.ProbabilityDistribution method*), 6
`get_random_element()` (*sage.probability.probability_distribution.RealDistribution method*), 15
`get_random_element()` (*sage.probability.probability_distribution.SphericalDistribution method*), 18

I

`is_DiscreteProbabilitySpace()` (*in module sage.probability.random_variable*), 23
`is_DiscreteRandomVariable()` (*in module sage.probability.random_variable*), 23
`is_ProbabilitySpace()` (*in module sage.probability.random_variable*), 23
`is_RandomVariable()` (*in module sage.probability.random_variable*), 23

M

`module`
`sage.probability.probability_distribution`, 1
`sage.probability.random_variable`, 21

P

`plot()` (*sage.probability.probability_distribution.RealDistribution method*), 15
`probability_space()` (*sage.probability.random_variable.RandomVariable_generic method*), 23
`ProbabilityDistribution` (*class in sage.probability.probability_distribution*), 4

ProbabilitySpace_generic (class in *sage.probability.random_variable*), 22

R

RandomVariable_generic (class in *sage.probability.random_variable*), 23

RealDistribution (class in *sage.probability.probability_distribution*), 6

reset_distribution() (*sage.probability.probability_distribution.GeneralDiscreteDistribution* method), 3

reset_distribution() (*sage.probability.probability_distribution.RealDistribution* method), 15

reset_distribution() (*sage.probability.probability_distribution.SphericalDistribution* method), 18

S

sage.probability.probability_distribution module, 1

sage.probability.random_variable module, 21

set() (*sage.probability.random_variable.DiscreteProbabilitySpace* method), 21

set_distribution() (*sage.probability.probability_distribution.RealDistribution* method), 16

set_random_number_generator() (*sage.probability.probability_distribution.GeneralDiscreteDistribution* method), 3

set_random_number_generator() (*sage.probability.probability_distribution.RealDistribution* method), 16

set_random_number_generator() (*sage.probability.probability_distribution.SphericalDistribution* method), 18

set_seed() (*sage.probability.probability_distribution.GeneralDiscreteDistribution* method), 3

set_seed() (*sage.probability.probability_distribution.RealDistribution* method), 17

set_seed() (*sage.probability.probability_distribution.SphericalDistribution* method), 19

SphericalDistribution (class in *sage.probability.probability_distribution*), 17

standard_deviation() (*sage.probability.random_variable.DiscreteRandomVariable* method), 21

T

translation_correlation() (*sage.probability.random_variable.DiscreteRandomVariable* method), 22

translation_covariance() (*sage.probability.random_variable.DiscreteRandomVariable* method), 22

translation_expectation() (*sage.probability.random_variable.DiscreteRandomVariable* method), 22

translation_standard_deviation() (*sage.probability.random_variable.DiscreteRandomVariable* method), 22

translation_variance() (*sage.probability.random_variable.DiscreteRandomVariable* method), 22

V

variance() (*sage.probability.random_variable.DiscreteRandomVariable* method), 22