
## Chapter 2 Assemblers



## **Outline**

- 2.1 Basic Assembler Functions
  - A simple SIC assembler
  - Assembler tables and logic
- 2.2 Machine-Dependent Assembler Features
  - Instruction formats and addressing modes
  - Program relocation
- 2.3 Machine-Independent Assembler Features
- 2.4 Assembler Design Options
  - Two-pass
  - One-pass
  - Multi-pass

## Why an Assembly Language is needed?

- Programming in machine code, by supplying the computer with the numbers of the operations it must perform, can be quite a burden, because for every operation the corresponding number must be looked up or remembered.
- Looking up all numbers takes a lot of time, and mis-remembering a number may introduce computer bugs.
- So Assembly Languages are evolved which contains mnemonic instructions corresponding to the Machine codes using which the program can be written easily.
- Therefore a set of mnemonics was devised. Each number was represented by an alphabetic code. So instead of entering the number corresponding to addition to add two numbers one can enter "add".
- Although mnemonics differ between different CPU designs some are common, for instance: "sub" (subtract), "div" (divide), "add" (add) and "mul" (multiply).

## What is an Assembler?

 An assembler is system software which is used to convert an assembly language program to its equivalent object code. The input to an assembler is a source code written in assembly language (using mnemonics) and the output is the object code.

#### Format of Assembly language program

#### 1.Label field.

The label is a symbolic name that represents the memory address of an executable statement or a variable.

#### 2.Opcode/directive fields.

The opcode (e.g. operation code) specifies the symbolic name for a machine instruction.

The directive specifies commands to the assembler about the way to assemble the program.

#### 3. Operand field.

The operand specifies the data that is needed by a statement.

#### 4.Comment field.

The comment provides clear explanation for a statement.

## **Basic Assembler Functions**

The basic assembler functions are

- ☐ Translating mnemonic language code to its equivalent object code.
- ☐ Assigning machine addresses to symbolic labels.



Convert mnemonic operation codes to their machine language equivalents

Convert symbolic operands to their equivalent machine addresses

- Build the machine instructions in the proper format
- Convert the data constants to internal machine representations

Write the object program and the assembly listing

## **Assembler Directives**

Assembler directives are Pseudo-instructions that are not translated into machine instructions and they provide instructions to the assembler itself.


- **➤** The SIC assembler directives.
  - START
    - Specification of the name and start address of the program.
  - o END
    - Indication of the end of the program and optionally the address of the first executable instruction.
  - o BYTE
    - Generate character or hexadecimal constant occupying as many as needed to represent the constant.
  - o WORD
    - Generate one word constant.
  - o RESB
    - Reserve the indicated number of bytes for a data area.
  - RESW
    - Reserve the indicated number of words for a data area.

### Functions of Two pass Assembler

#### Functions of Two Pass Assembler

- Pass 1 Define symbols (assign addresses)
  - Assign addresses to all statements in the program
  - o Save the values assigned to all labels for use in Pass 2
  - o Process some assembler directives
- ➤ Pass 2 Assemble instructions and generate object program
  Assemble instructions
  - Generate data values defined by BYTE, WORD, etc.
  - Process the assembler directives not done in Pass 1
  - Write the object program and the assembly listing

#### **Functions of Two Pass Assembler**



# Object Code Generation for SIC Assembler Language Program

#### Note:

- Add 3 to LOCCTR (Instruction 3 Format)
- Add 4 to LOCCTR(Instruction 4 Format)(Instructions prefixed with + sign)

- OPCODE =WORD→Add 3 to LOCCTR
- OPCODE =RESW-→Add 3 \* Value of Operand to LOCCTR
- OPCODE =BYTE-→Add length of constant in bytes to LOCCTR
- OPCODE =RESB-→Add Value of operand to LOCCTR

## **Example 1: SIC program Given Opcode values and Hex Codes**

Mnemonic	Opcode
STL	14
JSUB	48
СОМР	28
JEQ	30
J	3C
LDA	00
STA	0C

ASCII CODE	HEX Code
Е	45
0	4F
F	46

LOCCTR	Labels	Opcode	operand	<b>Object Code</b>
	COPY	START	1000	
1000	FIRST	STL	RETADR	141024
1003	CLOOP	JSUB	RDREC	482039
1006		LDA	LENGTH	001021
1009		COMP	ZERO	28101E
100C		JEQ	ENDFIL	301015
100F		JSUB	WRREC	482061
1012		J	CLOOP	3C1003
1015	ENDFIL	LDA	EOF	00101B
1018		STA	LENGTH	OC1021
101B	EOF	BYTE	C'EOF'	454F46
101E	ZERO	WORD	0	000000
1021	LENGTH	RESW	1	
1024	RETADR	RESW	1	
1027				
2039	RDREC	LDX	ZERO	
2061	WRREC	LDX	ZERO	

## **Example 2: SIC Program Given Opcode values and Hex Codes**

Mnemonic	Opcode
LDX	04
LDA	00
TD	E0
JEQ	30
RD	D8
COMP	28
STCH	54
TIX	2C
JLT	38
STX	10
RSUB	4C

ASCII CODE	HEX Code
T	54
Е	45
S	53

LOCCTR	Labels	Opcode	operand	Object Code
	COPY	START	2039	
2039	RDREC	LDX	CLOOP	04204E
203C		LDA	CLOOP	00204E
203F	RLOOP	TD	INPUT	E0205D
2042		JEQ	RLOOP	30203F
2045		RD	INPUT	D8205D
2048		COMP	EXIT	282057
204B		JEQ	RDREC	302039
<b>204</b> E	CLOOP	STCH	EXIT	542057
2051		TIX	MAXLEN	2C205E
2054		JLT	RLOOP	38203F
2057	EXIT	STX	EOF	103061
205A		RSUB		4C0000
205D	INPUT	BYTE	X 'F1'	F1
205E	MAXLEN	WORD	0	000000
2061	BUFFER	RESB	4096	
3061	EOF	BYTE	C 'TEST'	54455354
3065		END	COPY	

## **Object Program**

#### Three types of records

- Header: program name, starting address, length.
- Text: starting address, length, object code.
- End: address of first executable instruction

#### Header record:

Col. 1	H
Col. 2-7	Program name
Col. 8–13	Starting address of object program (hexadecimal)
Col. 14-19	Length of object program in bytes (hexadecimal)

## **Object Program**

#### Text record:

Col. 1 T

Col. 2–7 Starting address for object code in this record(hexadecimal)

Col. 8–9 Length of object code in this record in bytes (hexadecimal)

Col. 10–69 Object code, represented in hexadecimal (2 columns per byte of object code)

#### End record:

Col. 1 E

Col. 2–7 Address of first executable instruction in object program (hexadecimal)

## **Assembler Data Structures**

- Our simple assembler uses two internal tables: The OPTAB and SYMTAB.
  - OPTAB is used to look up <u>mnemonic operation codes</u> and translate them to their machine language equivalents.
    - LDA $\rightarrow$ 00, STL $\rightarrow$ 14, ...
  - SYMTAB is used to store values (addresses) assigned to <u>labels</u>.
    - FIRST→1000, COPY→1000, ...
- Location Counter LOCCTR
  - LOCCTR is a variable for assignment addresses.
  - LOCCTR is initialized to address specified in START.
  - When reach a label, the current value of LOCCTR gives the address to be associated with that label.

## The Operation Code Table (OPTAB)

- Contain the mnemonic operation & its machine language equivalents (at least).
- Contain instruction format & length.
- Pass 1, OPTAB is used to look up and validate operation codes.
- Pass 2, OPTAB is used to translate the operation codes to machine language.
- In SIC/XE, assembler search OPTAB in Pass 1 to find the instruction length for incrementing LOCCTR.
- Organize as a hash table (static table).

mnemonic	Opcode	format	
STL	14	3	
LDB	68	3	
JSUB	48	4	
LDA	00	3	

### The Symbol Table (SYMTAB)

- Include the name and value (address) for each label.
- Include flags to indicate error conditions
- Contain type, length.
- Pass 1, labels are entered into SYMTAB, along with assigned addresses (from LOCCTR).
- Pass 2, symbols used as operands are look up in SYMTAB to obtain the addresses.
- Organize as a hash table (static table).
- The entries are rarely deleted from table.

COPY	1000
FIRST	1000
CLOOP	1003
ENDFIL	1015
EOF	1024
THREE	102D
ZERO	1030
RETADR	1033
LENGTH	1036
BUFFER	1039
RDREC	2039

#### PASS 1 of Two Pass Assembler

```
Pass 1:
begin
   read first input line
   if OPCODE = 'START' then
      begin
          save #[OPERAND] as starting address
          initialize LOCCTR to starting address
         write line to intermediate file
         read next input line
      end {if START}
  else
      initialize LOCCTR to 0
```

#### PASS 1 of Two Pass Assembler

```
while OPCODE ≠ 'END' do
   begin
      if this is not a comment line then
          begin
             if there is a symbol in the LABEL field then
                 begin
                    search SYMTAB for LABEL
                    if found then
                        set error flag (duplicate symbol)
                    else
                        insert (LABEL, LOCCTR) into SYMTAB
                 end {if symbol}
             search OPTAB for OPCODE
             if found then
                 add 3 (instruction length) to LOCCTR
             else if OPCODE = 'WORD' then
                 add 3 to LOCCTR
             else if OPCODE = 'RESW' then
                 add 3 * #[OPERAND] to LOCCTR
             else if OPCODE = 'RESB' then
                 add #[OPERAND] to LOCCTR
             else if OPCODE = 'BYTE' then
                begin
                    find length of constant in bytes
                    add length to LOCCTR
                 end {if BYTE}
             else
                 set error flag (invalid operation code)
          end {if not a comment}
      write line to intermediate file
      read next input line
   end {while not END}
```

#### PASS 2 of Two Pass Assembler

```
begin
  read first input line {from intermediate file}
  if OPCODE = 'START' then
     begin
         write listing line
         read next input line
     end {if START}
  write Header record to object program
  initialize first Text record
```

#### **PASS 2 of Two Pass Assembler**

end {while not END}

```
while OPCODE ≠ 'END' do
   begin
       if this is not a comment line then
          begin
              search OPTAB for OPCODE
              if found then
                 begin
                     if there is a symbol in OPERAND field then
                        begin
                            search SYMTAB for OPERAND
                           if found then
                               store symbol value as operand address
                            else
                               begin
                                  store 0 as operand address
                                  set error flag (undefined symbol)
                               end
                        end {if symbol}
                    else
                        store 0 as operand address
                    assemble the object code instruction
                 end {if opcode found}
             else if OPCODE = 'BYTE' or 'WORD' then
                 convert constant to object code
             if object code will not fit into the current Text record then
                 begin
                    write Text record to object program
                    initialize new Text record
                 end
             add object code to Text record
          end {if not comment}
      write listing line
      read next input line
```

- Add 3 to LOCCTR (Instruction 3 Format)
- Add 4 to LOCCTR(Instruction 4 Format)(Instructions prefixed with + sign)
- OPCODE =WORD→Add 3 to LOCCTR
- OPCODE =RESW → Add 3 \* Value of Operand to LOCCTR
- OPCODE =BYTE-→Add length of constant in bytes to LOCCTR
- OPCODE =RESB-→Add Value of operand to LOCCTR
- Set n= 1 for opcode @m (indirect)
- Set i=1 for opcode #c (immediate)
- Set n=i=1 for simple addressing mode
- Set x=1 for opcode m,x (indexed)
- Set e=1 for instruction format 4

-			-	
LOCCTR	Label	Opcode	Operand	Object Code
	COPY	START	0	
	FIRST	STL	RETADR	
		LDB	#LENGTH	
	CLOOP	+JSUB	RDREC	
		LDA	LENGTH	
		COMP	#0	
		JEQ	ENDFIL	
		J	CLOOP	
	ENDFIL	LDA	EOF	
	RDREC	+LDT	#4096	
	EOF	ВҮТЕ	C 'EOF'	
	RETADR	RESW	1	
	LENGTH	RESW	1	
		END	CODV	

## Example 1: Given Opcode values and Hex Codes

Mnemonic	Opcode
STL	14
LDB	68
JSUB	48
LDA	00
СОМР	28
JEQ	30
J	3C
LDT	74

ASCII CODE	HEX Code
Е	45
0	4F
F	46

LOCCTR	Label	Opcode	Operand	Object Code
	СОРУ	START	0	
0000	FIRST	STL	RETADR	
0003		LDB	#LENGTH	
0006	CLOOP	+JSUB	RDREC	
000A		LDA	LENGTH	
000D		COMP	#0	
0010		JEQ	ENDFIL	
0013		J	CLOOP	
0016	ENDFIL	LDA	EOF	
0019	RDREC	+LDT	#4096	
001D	EOF	ВҮТЕ	C 'EOF'	
0020	RETADR	RESW	1	
0023	LENGTH	RESW	1	
0026		END	COPY	

• FIRST STL RETADR

Op(6) n	n(1)	i(1)	x(1)	b(1)	p(1)	e(1)	disp(12)
1		1	0	0	1	0	017
000000							
1			4				

• STL $\rightarrow$ opcode $\rightarrow$ 14 Add (STL value )+ (op,n,i) $\rightarrow$ 14+3 $\rightarrow$ 17

- $x,b,p,e \rightarrow 0010 \rightarrow 2$
- Disp=TA-(PC)
  - =(RETADR Address)-(PC)
  - =0020-003
  - =017

LDB #LENGTH

Op(6)	n(1)	i(1)	x(1)	b(1)	p(1)	e(1)	disp(12)
	0	1	0	0	1	0	01D
000000							
4			4				

LDB→ opcode→68
 Add LDB Value+ (op,n,i)= 68+ 1 →69

- $x,b,p,e \rightarrow 0010 \rightarrow 2$
- Disp= TA-(PC)
   =(LENGTH Address) (0006)
   =(0023)-(0006)
   =001D

CLOOP +JSUB

**RDREC** 

Op(6)	n(1)	i(1)	x(1)	b(1)	p(1)	e(1)	Address(20 bits)
000000	1	1	0	0	0	1	00019

• JSUB $\rightarrow$ opcode $\rightarrow$ 48 Add (JSUB value)+ (op,n,i) $\rightarrow$ 48+3 $\rightarrow$ 4B

Instruction 4 format -> Set e=1

- x,b,p,e $\rightarrow$  0001 $\rightarrow$ 1
- Address= 0019

LDA LENGTH

Op(6)	n(1)	i(1)	x(1)	b(1)	p(1)	e(1)	Disp(12bits)
000000	1	1	0	0	1	0	016

- LDA $\rightarrow$ opcode $\rightarrow$ 00 Add (LDA value)+ (op,n,i) $\rightarrow$ 00+3 $\rightarrow$ 03
- $x,b,p,e \rightarrow 0010 \rightarrow 2$
- Disp=(TA)-(PC)
  - =(LENGTH address)-(000D)
  - =0023-000D
  - =0016

• COMP #0

Op(6)	n(1)	i(1)	x(1)	b(1)	p(1)	e(1)	Disp(12bits)
000000	0	1	0	0	0	0	000

- COMP $\rightarrow$ opcode $\rightarrow$ 28 Add (COMP value)+ (op,n,i) $\rightarrow$ 28+1 $\rightarrow$ 29
- $x,b,p,e \rightarrow 0000 \rightarrow 0$
- Disp=000

JEQ ENDFIL

Op(6)	n(1)	i(1)	x(1)	b(1)	p(1)	e(1)	Disp(12bits)
000000	1	1	0	0	1	0	003
			4				

- JEQ $\rightarrow$ opcode $\rightarrow$ 30 Add (JEQ value)+ (op,n,i) $\rightarrow$ 30+3 $\rightarrow$ 33
- x,b,p,e- $\rightarrow$  0010 $\rightarrow$ 2
- Disp=(TA)-(PC)
  - =(ENDFIL address)-(0013)
  - =0016-0013
  - =0003

#### J CLOOP

Op(6)	n(1)	i(1)	x(1)	b(1)	p(1)	e(1)	Disp(12bits)
	1	1	0	0	1	0	FF0
000000							
4							

- J $\rightarrow$ opcode $\rightarrow$ 3C Add (J value)+ (op,n,i) $\rightarrow$ 3C+3- $\rightarrow$ 3F
- x,b,p,e→ 0010→2
- Disp=(TA)-(PC)
- =(CLOOP address)-(0016)
- **=(=0006-0016**
- == -10

#### Convert the 2s complement of -10

10 into binary → 0001 0000

Convert 0's to 1's and 1's to 0's → 1110 1111

Add 1 → 0000 0001

1111 0000

Value is F0. To fit into 12 bit displacement field Value is FF0

**Therefore Object code is 3F2FF0** 

#### **Object Code Generation-SIC/XE**

ENDFIL LDA EOF

Op(6)	n(1)	i(1)	x(1)	b(1)	p(1)	e(1)	Disp(12bits)
	1	1	0	0	1	0	004
000000							
			<del></del>				

• LDA- $\rightarrow$ opcode- $\rightarrow$ 00 Add (LDA value)+ (op,n,i) $\rightarrow$ 00 + 3  $\rightarrow$ 03

- x,b,p,e $\rightarrow$  0010 $\rightarrow$ 2
- Disp=(TA)-(PC)
- =(EOF address)-(0019)
- =(=001D-0019)
- =004

Object Code = 032004

#### **Object Code Generation-SIC/XE**

RDREC +LDT #4096

Op(6)	n(1)	i(1)	x(1)	b(1)	p(1)	e(1)	Addr(20bits
000000	0	1	0	0	0	1	01000
			$\overline{}$				

• LDT→opcode→74

Add (LDT value)+ (op,n,i) $\rightarrow$ 74 + 1  $\rightarrow$ 75

• x,b,p,e $\rightarrow$ 0001 $\rightarrow$ 1

Address= Immediate value = 4096 Convert 4096 to hex equivalent = 1000h

#### **Problem 2: Object Code Generation-SIC/XE**

LOCCTR	Label	Opcode	Operand	Object Code
	SUM	START	0	
	FIRST	CLEAR	Χ	
		LDA	#0	
		+LDB	#TOTAL	
		BASE	TOTAL	
	LOOP	ADD	TABLE,X	
		TIX	COUNT	
		JLT	LOOP	
		+STA	TOTAL	
	COUNT	RESW	1	
	TABLE	RESW	2000	
	TOTAL	RESW	1	
		END	FIRST	

#### **Object Code Generation-SIC/XE**

LOCCTR	Label	Opcode	Operand	Object Code
	SUM	START	0	
0000	FIRST	CLEAR	Χ	B410
0002		LDA	#0	010000
0005		+LDB	#TOTAL	69101789
		BASE	TOTAL	
0009	LOOP	ADD	TABLE,X	1BA00D
000C		TIX	COUNT	2F2007
000F		JLT	LOOP	382FF7
0012		+STA	TOTAL	0F101789
0016	COUNT	RESW	1	
0019	TABLE	RESW	2000	
1789	TOTAL	RESW	1	
178C		END	FIRST	

# Machine dependant features of a SIC/XE Assembler

- 1.Instruction formats
- 2. Addressing modes
- 3. Program relocation

### **Instruction Formats**

- The instruction formats depend on the memory organization and the size of the memory.
- In **SIC machine** the memory is byte addressable. Word size is 3 bytes. The size of the memory is 32768(2^15) bytes
- Accordingly it supports only one instruction format. It has only two registers: register A and Index register. Therefore the addressing modes supported by this architecture are direct, indirect, and indexed.
- Whereas the memory of a **SIC/XE** machine is 1MegaByte(2^20) bytes.
- This supports four different types of instruction types, they are
- a. 1 byte instruction
- b.2 bytes instruction
- c. 3 bytes instruction
- d. 4 bytes instruction

## Instruction formats

Format 1 (1 byte)		
op(8)		
Format 2 (2 bytes)		
op(8)	r1(4)	r2(4)

#### Format 3(3 bytes)

op(6)	n	i	X	b	p	e	disp(12)
	1	1	1	1	1	1	

#### Format 4(4 bytes)

op(6)	n	i	x	b	p	e	address (20)
	1	1	1	1	1	1	

## Addressing Modes

#### Addressing Modes are:

- Index Addressing(SIC): Opcode m, x
- Indirect Addressing: Opcode @m
- PC-relative: Opcode m
- Base relative: Opcode m
- Immediate addressing: Opcode #c

- Principles.
- o The load address of an object program is unknown at assembly time if the system implements the multiprogramming feature.
- o The assembler generates addresses relative to zero in the object program.
- o At load time, relocation is performed by adding the load address to the relative addresses.
- o Operands of instructions that use direct addressing must be relocated, and the assembler provides the relocation information in the object program.
- o Operands of instructions that use relative addressing do not need to be relocated.
- o Relocation can be processed by the loader or by the CPU using relocation registers

Absolute Program


In this the address is mentioned during assembling itself. This is called Absolute Assembly.

Consider the instruction:

#### 55 101B LDA THREE 00102D

• This statement says that the register A is loaded with the value stored at location 102D. Suppose it is decided to load and execute the program at location 2000 instead of location 1000. Then at address 102D the required value which needs to be loaded in the register A is no more available. The address also gets changed relative to the displacement of the program. Hence we need to make some changes in the address portion of the instruction so that we can load and execute the program at location 2000.

- Apart from the instruction which will undergo a change in their operand address value as the program load address changes.
- There exist some parts in the program which will remain same regardless of where the program is being loaded.
- Since assembler will not know actual location where the program will get loaded, it cannot make the necessary changes in the addresses used in the program.
- However, the assembler identifies for the loader those parts of the program which need modification. An object program that has the information necessary to perform this kind of modification is called the relocatable program.



- ➤ The above diagram shows the concept of relocation. Initially the program is loaded at location 0000. The instruction JSUB is loaded at location 0006.
- ➤ The address field of this instruction contains 01036, which is the address of the instruction labeled RDREC
- The second figure shows that if the program is to be loaded at new location 5000. The address of the instruction JSUB gets modified to new location 6036.
- ➤ Likewise the third figure shows that if the program is relocated at location 7420, the JSUB instruction would need to be changed to 4B108456 that correspond to the new address of RDREC.
- ➤ When assembler generates the object code for the JSUB instruction we are considering, it will insert the address of RDREC relative to the start of the program.
- ➤ The assembler will produce a command for the loader instructing it to add the beginning address of the program to the address field in the JSUB instruction at load time.
- > From the object program, it is not possible to distinguish the address and constant The assembler must keep some information to tell the loader. The object program that contains the modification record is called a relocatable program.

### **Advantages of Program Relocation**

- 1.The larger main memory of SIC/XE
- Several programs can be loaded and run at the same time.
- This kind of sharing of the machine between programs is called multiprogramming
  - 2. To take full advantage
- Load programs into memory wherever there is space.
- Not specifying a fixed address at assembly time.

### **Modification Record**

- Col 1: M
- Col 2-7 Starting location of the address field to be modified relative to the beginning of the program(hexadecimal)
- Col 8-9 length of the address field to be modified, in half bytes(hexadecimal).

# Machine Independent Assembler Features

- 1.Literals
- 2. Symbol Defining Statements
- 3.Expressions
- **4.Program Blocks**
- 5. Control Sections and program linking

- Let programmers to be able to write the value of a constant operand as a part of the instruction that uses it.
- This avoids having to define the constant elsewhere in the program and make up a label for it.
- Such an operand is called a literal because the value is literally stated in the instruction. Note that a literal is identified with the prefix = which followed by a specification of the literal value.
- The literal is a special type of relocatable term. It behaves like a symbol in that it represents data. However, it is a special kind of term because it also is used to define the constant specified by the literal.

- This is convenient because:
- a. The data you enter as numbers for computation, addresses, or messages to be printed is visible in the instruction in which the literal appears.
- b. You avoid the added effort of defining constants elsewhere in your source module and then using their symbolic names in machine instruction operands.

#### Examples:

Ex 1:

45 001A ENDFIL

BYTE =C "EOF"

454F46

Specifies a 3 byte operand with value "EOF"

Ex 2:

69101A CLOOP

STA = X '05'

E32011

Specifies a 1 byte literal with hexadecimal value 05

### Literals vs Immediate Operands

> Immediate Operands

The operand value is assembled as part of the machine instruction

e.g. 55 0020 LDA #3 010003

**▶** *Literals* 

The assembler generates the specified value as a constant at some other memory location

e.g. 45 001A ENDFIL LDA = C'EOF' 032010

## Literal pools

- All of the literal operands used in a program are gathered together into one or more literal pools.
- Normally literals are placed into a pool at the end of the program.
- In some cases, it is desirable to place literals into a pool at some other location in the object program .
- For this purpose assembler directive LTORG is used.

Reason: Keep the literal operand close to the instruction.

- 1. When the assembler encounters a LTORG statement, it creates a literal pool that contains all of the literal operands used since the previous LTORG.
- 2. This literal pool is placed in the object program at the location where the LTORG directive was encountered.
- 3. Literal placed in a pool by LTORG will not be repeated in the pool at the end of the program

## Duplicate literals:

e.g. 215 1062 WLOOP TD =X"05" e.g. 230 106B WD =X"05"

- The assemblers should recognize duplicate literals and store only one copy of the specified data value .
- Only one data area with this value is generated. Both the instruction refer to the same address in the literal pool for their operand.
- The easiest method to recognize duplicate literals is by:
  - 1. Comparison of the defining expression

Same literal name with different value, e.g. LOCCTR=\*

2. Comparison of the generated data value

The benefits of using generate data value are usually not great enough to justify the additional complexity in the assembler.

### LITTAB:

• The basic data structure that assembler handles literal operands is literal table. For each literal used, this table contains the literal name, the operand value, the length and the address assigned to the operand when its placed in the literal pool.

#### Pass 1

- a. Build LITTAB with literal name, operand value and length, leaving the address unassigned.
- b. When LTORG statement is encountered, assign an address to each literal not yet assigned an address

#### Pass 2

- a. Search LITTAB for each literal operand encountered .
- b. Generate the data values using BYTE or WORD statement.
- c. Generate modification record for literals that represent an address in the program

Line	So	ource state	ment	
5	COPY	START	0	COPY FILE FROM INPUT TO OUTPUT
10	FIRST	STL	RETADR	SAVE RETURN ADDRESS
13		LDB	#LENGTH	ESTABLISH BASE REGISTER
14		BASE	LENGTH	
15	CLOOP	+JSUB	RDREC	READ INPUT RECORD
20		LDA	LENGTH	TEST FOR EOF (LENGTH = $0$ )
25		COMP	#0	
30		JEQ	ENDFIL	EXIT IF EOF FOUND
35		+JSUB	WRREC	WRITE OUTPUT RECORD
40		J	CLOOP	LOOP
45	ENDFIL	LDA	=C'EOF'	INSERT END OF FILE MARKER
50		STA	BUFFER	
55		LDA	#3	SET LENGTH = 3
60		STA	LENGTH	
65		+JSUB	WRREC	WRITE EOF
70		J	@RETADR	RETURN TO CALLER
93		L/TORG		
95	RETADR	RESW	1	
100	LENGTH	RESW	1	LENGTH OF RECORD
105	BUFFER	RESB	4096	4096-BYTE BUFFER AREA
106	BUFEND	EQU	*	
107	MAXLEN	EQU	BUFEND-BUFFER	MAXIMUM RECORD LENGTH

Line	Loc	So	urce state	ment	Object code
5	0000	COPY	START	0	
10	0000	FIRST	$\mathtt{STL}$	RETADR	17202D
13	0003		LDB	#LENGTH	69202D
14			BASE	LENGTH	
15	0006	CLOOP	+JSUB	RDREC	4B101036
20	A000		LDA	LENGTH	032026
25	000D		COMP	#0	290000
30	0010		JEQ	ENDFIL	332007
35	0013		+JSUB	WRREC	4B10105D
40	0017		J	CLOOP	3F2FEC
<b>4</b> 5	001A	ENDFIL	LDA	=C'EOF'	032010
50	001D		STA	BUFFER	0F2016
55	0020		LDA	#3	010003
60	0023		STA	LENGTH	0F200D
65	0 <b>026</b>		+JSUB	WRREC	4B10105D
70	0 <b>02A</b>		J	@RETADR	3E2003
93			LTORG		
	002D	*	=C'EOF'		<b>4</b> 54 <b>F4</b> 6
95	0030	RETADR	RESW	1	
100	0033	LENGTH	RESW	1	
105	0036	BUFFER	RESB	4096	
106	1036	BUFEND	EQU	*	
107	1000	MAXLEN	EQU	BUFEND-BUFFER	

			****	AL L'I	Γ⊥
195		•			
200		•	SUBROU	TINE TO WRITE	RECORD FROM BUFFER
205			502400	TIME TO WELL	RECORD FROM BUFFER
		•			
210	105D	WRREC	CLEAR	X	B410
212	105F		$\mathrm{L}\mathrm{D}\mathrm{T}$	LENGTH	774000
215	1062	WLOOP	TD	=X'05'	E32011
220	1005	.,_001			FOZOTI
220	1065		JEQ	WLOOP	332FFA
225	1068		LDCH	BUFFER, X	53C003
230	106B		WD	=X'05'	DF2008
235	106E		TIXR	T	B850
240	1070			_	
			JLT	WLOOP	3B2FEF
2 <b>4</b> 5	1073		RSUB		4F0000
255			END	FIRST	
	1076	*	=X'05'	- <del></del>	05
			-21 00		US

Figure 2.10 Program from Fig. 2.9 with object code.

## LITTAB

Literal Name	Operand Value	Length	Address
C='EOF'	454F46	3	002D
X='05'	05	1	1076

## Symbol defining statements

#### 1. EQU Directive

#### **2.ORG Directive**

**1.EQU:** The user defined symbols in the assembler language program appears as labels on instructions or data areas. The value of such a label is the address assigned to the statement on which it appears. Most assemblers provide an assembler directive that allows the user to define the symbol and specify their values. **EQU is the assembler directive used.** 

The general form of such a statement is

#### Symbol EQU Value

It defines the given symbol and assigns the specified value.

The value may be a

- a. Constant
- b. Any expression involving constant.
- c. Previously defined symbol

## **EQU** Directive

- EQU is used to establish symbolic names that can be used for improved readability in place of numeric values.
- 1. In the last program, the statement used as
  - **+LDT** #4096 // to load the value 4096 into register T.
- 2. If we include the statement

MAXLEN EQU 4096

In the program then we can write it as

+LDT #MAXLEN

3. When the assembler encounters the EQU statement, it enters MAXLEN into SYMTAB with the value 4096.

## **EQU** Directive

4. Another common use of the EQU is defining mnemonic names for registers.

For ex

- A EQU 0
- X EQU 1
- L EQU 2

These statement cause the symbols A,X,L... to be entered into SYMBOL with their corresponding values 0.1,2...

### **ORG DIRECTIVE:**

- 1. Indirectly assigns values to symbols. This is called Origin directive.
- 2. Resets the location counter value to the specified value.
- 3. Since the values of the symbols are taken from the LOCCTR, the ORG statement will affect the values of all the labels defined until the next ORG.

#### EX:

- To define a symbol table with the following structure:
  - a. SYMBOL field: 6 bytes
  - b. VALUE field: one word.
  - c. FLAGS field: 2 byte

STAB (100 entries)

Symbol field contains user defined symbol: Value field represents the value assigned to the symbol and the Flags field specifies symbol type and other information.

To reserve the space we write

STAB RESB 1100

We also define the labels as SYMBOL, VALUE, FLAGSS using with EQU statements:

SYMBOL EQU STAB VALUE EQU STAB+6 FLAGS EQU STAB+9

- To fetch the value field LDA VALUE,X
- We can accomplish the same symbol definition using ORG in the following way

STAB	RESB	1100
ORG	STAB	
SYMBOL	RESB	6
VALUE	RESW	1
FLAGS	RESB	2
	ORG	STAB+1100

- a. The first ORG resets the LOCCTR to the value of STAB.
- b. RESB statement defines the SYMBOL to have the current value in LOCCTR.
- c. LOCCTR is then advanced so that the label on the RESW statement assigns to VALUE the address(STAB+6) and so on..
- d. So that each entry in STAB consists of 6 byte SYMBOL, followed by one word VALUE, followed by a 2 byte FLAGS.
- e. The last ORG statement set LOCCTR back to its previous value.

Notice that the two pass assembler design requires that all symbols be defined during Pass 1.

For ex:

The sequence

ALPHA RESW

BETA EQU ALPHA

would be allowed, whereas the sequence

BETA EQU ALPHA

ALPHA RESW

would not be allowed.

Reason for this is symbol definition process.

ORG has the same type of restriction.

Consider the following example

ORG ALPHA
BYTE1 RESB 1
BYTE2 RESB 1
BYTE3 RESB 1
ORG
ALPHA RESB 1

The above sequence cannot be processed because assembler directive would not know the value assigned to the location counter in response to the first ORG statement.

The symbols BYTE1, BYTE2, BYTE3 cant be assigned addresses during PASS1.

## Expressions

- Most assemblers allow the use of the expressions whenever a single operand is permitted.
- Each such expression has to be evaluated by the assembler to produce a single operand address or value.
- Expressions can be classified as
- **1.ABSOLUTE EXPRESSIONS**
- 2. RELATIVE EXPRESSIONS

## Expressions

#### RELATIVE EXPRESSIONS:

 Relative means relative to the beginning of the program. labels on the instructions and data areas and references to the location counter values are relative terms. No relative term into multiplication or division operation.

#### ABSOLUTE EXPRESSIONS:

- Absolute means independent of program location. A constant is an absolute term. Absolute expressions may also contain relative terms provided they occur in pair and the terms in each pair have opposite sign.
- A relative term or expression represents some value that may be written as (S+r) where
- S= Starting address of the program
- R= value of the term or expression relative to the starting address

# Expressions

Example: 107 MAXLEN EQU BUFFEND-BUFFER

Both BUFFEND and BUFFER are relative terms, each representing an address within the program.

However the expression BUFFEND-BUFFER represents the absolute term.

To determine the type of an expression we must keep track of the type of the symbols defined in the program.

Following table shows the symbol table entries.

Symbol	Type	Value
RETADR	R	0000
BUFFER	R	0036
BUFFEND	R	1036
MAXLEN	A	1000

SIC program

Sic pro	grain			
LOCCTR	Labels	Opcode	operand	<b>Object Code</b>
	COPY	START	1000	
1000	FIRST	STL	RETADR	141021
1003	CLOOP	JSUB	RDREC	482039
1006		LDA	LENGTH	00101E
1009		COMP	RETADR	281021
100C		JEQ	ENDFIL	301015
100F		JSUB	WRREC	482061
1012		J	CLOOP	3C1003
1015	ENDFIL	LDA	EOF	00101B
1018		STA	LENGTH	OC101E
101B	EOF	BYTE	C'EOF'	454F46
101E	LENGTH	RESW	1	
1021	RETADR	RESW	1	
1024		END	COPY	
				•
2039	RDREC			
2061	WRREC			

/4

# Object Program

Header record:

Col. 1 H

Col. 2–7 Program name

Col. 8–13 Starting address of object program (hexadecimal)

Col. 14–19 Length of object program in bytes (hexadecimal)

1	2	3	4	5	6	7	8	9	10
Н	С	0	Р	Υ			0	0	1

11	12	13	14	15	16	17	18	19
0	0	0	0	0	0	0	2	4

## Object Program

Text record:

Col. 1 T

Col. 2–7 Starting address for object code in this record(hexadecimal)

Col. 8–9 Length of object code in this record in bytes (hexadecimal)

Col. 10-69 Object code, represented in hexadecimal (2 columns per

byte of object code)

1	2	3	4	5	6	7	8	9	10
Т	0	0	1	0	0	0	1	Е	1

11	12	13	14	15	16	17	18	19	20
4	1	0	2	1	4	8	2	0	3

21	22	23	24	25	26	27	28	29	30
9	0	0	1	0	1	Е	2	8	1

## Text Record

31	32	33	34	35	36	37	38	39	40
0	2	1	3	0	1	0	1	5	4

41	42	43	44	45	46	47	48	49	50
8	2	0	6	1	3	С	1	0	0

51	52	53	54	55	56	57	58	59	60
3	0	0	1	0	1	В	0	С	1

61	62	63	64	65	66	67	68	69
0	1	E	4	5	4	F	4	6

## **End Record**

End record:

Col. 1 E

Col. 2-7 Address of first executable instruction in object program

(hexadecimal)

1	2	3	4	5	6	7
Е	0	0	1	0	0	0

## Program Blocks and Control Sections

- Although the source program logically contains subroutines, data area, etc, they were assembled into a single block of object code in which the machine instructions and data appeared in the same order as they were in the source program.
- To provide flexibility:
  - Program blocks
    - Segments of code that are rearranged within a single object program unit
  - Control sections
    - Segments of code that are translated into independent object program units

# Program Blocks

- As an example, three blocks are used:
  - default: executable instructions
  - CDATA: all data areas that are less in length
  - CBLKS: all data areas that consists of larger blocks of memory
- The assembler directive USE indicates which portions of the source program belong to the various blocks.

## Program with Multiple Program Blocks


#### At the beginning, the default block is assumed.

			5,	
5 10 15 20 25	COPY FIRST CLOOP		0 RETADR RDREC LENGTH #0	COPY FILE FROM INPUT TO OUTPUT SAVE RETURN ADDRESS READ INPUT RECORD TEST FOR EOF (LENGTH = 0)
30 35		JEQ JSUB	ENDFIL WRREC	EXIT IF EOF FOUND WRITE OUTPUT RECORD
40 45	ENDFIL	J LDA	CLOOP =C'EOF'	LOOP INSERT END OF FILE MARKER
50	EMPLIP	STA	BUFFER	INDERT END OF FIDE PARKET
55		LDA	#3	SET LENGTH = 3
60		STA	LENGTH	
65		JSUB	WRREC	WRITE EOF
70		J	GRETADR	RETURN TO CALLER
92		CUSE	CDATA	
95	RETADR	RESW	1	
100	LENGTH	RESW	1	LENGTH OF RECORD
103		USE	CBLKS	
105	BUFFER	RESB	4096	4096-BYTE BUFFER AREA
106	BUFEND	EQU	*	FIRST LOCATION AFTER BUFFER
107	MAXLEN	EQU	BUFEND-BUFFER	MAXIMUM RECORD LENGTH
110				

## Program with Multiple Program Blocks

				Resume the default block
115		SITEROIT	INE TO READ REC	ORD INTO BUFFER
120		5054001	IND TO RUBBIA	DULLER THE DULLER
123		USE		
125	RDREC	CLEAR	X	CLEAR LOOP COUNTER
130		CLEAR	A	CLEAR A TO ZERO
132		CLEAR	S	CLEAR S TO ZERO
133		+LDT	#MAXLEN	
135	RLOOP	TD	INPUT	TEST INPUT DEVICE
140		JEQ	RLOOP	LOOP UNTIL READY
145		RD	INPUT	READ CHARACTER INTO REGISTER A
150		COMPR	A,S	TEST FOR END OF RECORD (X'00')
155		JEO	EXIT	EXIT LOOP IF EOR
160		STCH	BUFFER, X	STORE CHARACTER IN BUFFER
165		TIXR	T	LOOP UNLESS MAX LENGTH
170		JLT	RLOOP	HAS BEEN REACHED
175	EXIT	STX	LENGTH	SAVE RECORD LENGTH
180		RSUB		RETURN TO CALLER
183	(	USE	CDATA	
185	INPUT	BYTE	X'F1'	CODE FOR INPUT DEVICE
				Resume the CDATA block

## Program with Multiple Program Blocks



## Program Blocks

- Each program block may actually contain several separate segments of the source program.
- The assembler will logically rearrange these segments to gather together the pieces of each block.
- The result is the same as if the programmer had physically rearranged the source statements to group together all the source lines belonging to each block.

# Why Program Blocks

- To satisfy the contradictive goals:
  - Separate the program into blocks in a particular order
    - Large buffer area is moved to the end of the object program
    - Using the extended format instructions or base relative mode may be reduced. (lines 15, 35, and 65)
    - Placement of literal pool is easier: simply put them before the large data area, CDATA block. (line 253)
  - Data areas are scattered
    - Program readability is better if data areas are placed in the source program close to the statements that reference them.

# How to Rearrange Codes into Program Blocks

#### Pass 1

- Maintain a separate LOCCTR for each program block
  - initialized to 0 when the block is first begun
  - saved when switching to another block
  - restored when resuming a previous block
- Assign to each label an address relative to the start of the block that contains it
- Store the block name or number in the SYMTAB along with the assigned relative address of the label
- Indicate the block length as the latest value of LOCCTR for each block at the end of Pass1
- Assign to each block a starting address in the object program by concatenating the program blocks in a particular order

# How to Rearrange Codes into Program Blocks

- Pass 2
  - Calculate the address for each symbol relative to the start of the object program by adding
    - the location of the symbol relative to the start of its block
    - the assigned starting address of this block

## Object Program with Multiple Program Blocks

	Loc/I	3lo	ck			
5	0000	0	COPY	START	0	
10	0000	0	FIRST	STL	RETADR	172063
15	0003	0	CLOOP	JSUB	RDREC	4B2021
20	0006	0		LDA	LENGTH	032060
25	0009	0		COMP	#0	290000
30	000C	0		JEO	ENDFIL	332006
35	000F	0		JSUB	WRREC	4B203B
40	0012	0		J	CLOOP	3F2FEE
45	0015	0	ENDFIL	LDA	=C'EOF'	032055
50	0018	0		STA	BUFFER	0F2056
55	001B	0	0: default	LDA	#3	010003
60	001E	0	1: CDATA	STA	LENGTH	0F2048
65	0021	0	2: CBLKS	JSUB	WRREC	4B2029
70	0024	0	Z. CBLNS	J	GRETADR	3E203F
92	0000	1	STROUGH SHEET	USE	CDATA	distribution of the
95	0000	1	RETADR	RESW	1	
100	0003	1	LENGTH	RESW	1	- 47
103	0000	2		USE	CBLKS	I turn galacer active
105	0000	2	BUFFER	RESB	4096	
106	1000	2	BUFEND	EQU	*	
107	1000	1	MAXLEN	EQU	BUFEND-BUFF	ER
110		_	No block nun	nber becaus	se MAXLEN is ar	n absolute symbol

# Object Program with Multiple Program Blocks

AAV						
115				SUBROUT	INE TO READ R	ECORD INTO BUFFER
120						
123	0027	0		USE		
125	0027	0	RDREC	CLEAR	X	B410
130 -	0029	0		CLEAR	A	B400
132	002B	0		CLEAR	S	B440
133	002D	0		+LDT	#MAXLEN	75101000
135	0031	0	RLOOP	TD	INPUT	E32038
140	0034	0		JEO	RLOOP	332FFA
145	0037	0		RD	INPUT	DB2032
150	003A	0		COMPR	A,S	A004
155	003C	0		JEQ	EXIT	332008
160	003F	0		STCH	BUFFER, X	57A02F
165	0042	0		TIXR	T	B850
170	0044	0		JLT	RLOOP	△ 3B2FEA
175	0047	0	EXIT	STX	LENGTH	13201F
180	004A	0		RSUB		4F0000
183	0006	1		USE	CDATA	
185	0006	1	INPUT	BYTE	X'F1'	F1

# Object Program with Multiple Program Blocks

195				CURROUM	TARE MY WEITHER	ECORD FROM BUFF
200				SUBRUUT	INE TO WRITE P	CECORD FROM BOFF
205						
208	004D	0		USE		
210	004D	0	WRREC	CLEAR	X	B410
212	004F	0		LDT	LENGTH	772017
215	0052	0	WLOOP	TD	=X'05'	E3201B
220	0055	0		JEQ	WLOOP	332FFA
225	0058	0		LDCH	BUFFER, X	53A016
230	005B	0		WD	=X'05'	DF2012
235	005E	0		TIXR	T	B850
240	0060	0		JLT	WLOOP	3B2FEF
245	0063	0		RSUB	100000000000000000000000000000000000000	4F0000
252	0007	1		USE	CDATA	
253				LTORG		
TRO -	0007	1	*	=C'EOF		454F46
	000A	1	*	=X'05'		05
255				END	FIRST	

# Table for Program Blocks


At the end of Pass 1:

Block name	Block number	Address	Length
(default)	0	0000	0066
CDATA	1	0066	000B
CBLKS	2	0071	1000

## Object Program

- It is not necessary to physically rearrange the generated code in the object program to place the pieces of each program block together.
- The assembler just simply insert the proper load address in each Text record.

## Program Blocks Loaded in Memory



### Control Sections

- A control section
  - is a part of the program that maintains its identity after assembly
  - is often used for subroutine or other logical subdivision of a program
  - can be assembled, loaded, and relocated independently
  - is more flexible

# Program Linking

- Program linking is used to link together logically related control sections
- Problem:
  - The assembler does not know where any other control section will be located at execution time.
  - When an instruction needs to refer to instructions or data located in another control section, the assembler is unable to process this reference.
  - The assembler has to generate information for such kind of references, called external references, that will allow the loader to perform the required linking.


## Program with Multiple Control Sections

	/	Implic	itly defined as an ex	ternal symbol
		Fir	st control section: C	OPY
5	COPY	START	0	COPY FILE FROM INPUT TO OUTPUT
6		EXTDEF EXTREF	BUFFER, BUFEND, I RDREC, WRREC	Define external symbols
0	FIRST	STL	RETADR	SAVE RETURN ADDRESS
5	CLOOP	+JSUB	RDREC	READ INPUT RECORD
0		LOA	LENGTH	TEST FOR EOF (LENGTH = 0)
5	External	COMP	#0	
0	reference	JEQ	ENDFIL	EXIT IF EOF FOUND
5		+JSUB	WRREC	WRITE OUTPUT RECORD
0		J	CLOOP	LOOP
5	ENDFIL	LDA	=C'EOF'	INSERT END OF FILE MARKER
0		STA	BUFFER	
5		LDA	#3	SET LENGTH = 3
0		STA	LENGTH	
5		+JSUB	WRREC	WRITE EOF
0		J	@RETADR	RETURN TO CALLER
5	RETADR	RESW	1	
0	LENGTH	RESW	1 1 2 2 2 2 2 2 2 2 2 2 2 2 2 2 2 2 2 2	LENGTH OF RECORD
3		LTORG		
5	BUFFER	RESB	4096	4096-BYTE BUFFER AREA
)6	BUFEND	EQU	*	
)7	MAXLEN	EQU	BUFEND-BUFFER	

## Program with Multiple Control Sections

			Implic	itly defined as an external symbol
109	RDREC	CSECT		econd control section: RDREC
110	TO ADDING T		3	econd control section. NDNEC
115	Femilials a	SUBROUTI	NE TO READ R	ECORD INTO BUFFER
120				External reference
122		EXTREF	BUFFER, LEN	GTH, BUFEND
125		CLEAR	X	CLEAR LOOP COUNTER
130		CLEAR	A	CLEAR A TO ZERO
132		CLEAR	S	CLEAR S TO ZERO
133		LDT	MAXLEN	
135	RLOOP	TD	INPUT	TEST INPUT DEVICE
140		JEQ	RLOOP	LOOP UNTIL READY
145		RD	INPUT	READ CHARACTER INTO REGISTER A
150		COMPR	A,S	TEST FOR END OF RECORD (X'00')
155		JEQ	EXIT	EXIT LOOP IF EOR
160		+STCH	BUFFER, X	STORE CHARACTER IN BUFFER
165		TIXR	ф	LOOP UNLESS MAX LENGTH
170		JLT	RLOOP	HAS BEEN REACHED
175	EXIT	+STX	LENGTH	SAVE RECORD LENGTH
180	DUTI	RSUB	DLEVOIT	RETURN TO CALLER
185	INPUT	BYTE	X'F1'	CODE FOR INPUT DEVICE
190	MAXLEN	WORD	BUFEND-BUI	

## Program with Multiple Control Sections



#### Assembler Directives for Control Section

#### START:

- start the first control section
- set program name as the control section name
- define the control section name as an external symbol

#### CSECT:

- start a new control section
- specify the control section name
- define the control section name as an external symbol

#### EXTDEF:

- define external symbols
- EXTREF:
  - name symbols defined in other control sections

#### How to Handle External References

- 15 0003 CLOOP +JSUB RDREC 4B100000
- The operand RDREC is an external reference.
- The assembler
  - has no idea where RDREC is
  - inserts an address of zero
  - can only use extended format to provide enough room (that is, relative addressing for external reference is invalid)
  - passes information to the loader

#### How to Handle External References

190 0028 MAXLEN WORD BUFEND-BUFFER 000000

- There are two external references in the expression, BUFEND and BUFFER.
- The assembler
  - inserts a value of zero
  - passes information to the loader
    - Add to this data area the address of BUFEND
    - Subtract from this data area the address of BUFFER
- On line 107, BUFEND and BUFFER are defined in the same control section and the expression can be calculated immediately.

107 1000 MAXLEN EQU BUFEND-BUFFER

### Object Code with Multiple Control Sections

5 6 7	0000	COPY	START EXTDEF EXTREF	0 BUFFER, BUFEND, I RDREC, WRREC	LENGTH
10	0000	FIRST	STL	RETADR	172027
15	0003	CLOOP	+JSUB	RDREC	4B100000
20	0007		LDA	LENGTH	032023
25	A000		COMP	#0	290000
30	000D		JEQ	ENDFIL	332007
35	0010		+JSUB	WRREC	4B100000
40	0014		J	CLOOP	3F2FEC
45	0017	ENDFIL	LDA	=C'EOF'	032016
50	001A		STA	BUFFER	0F2016
55	001D		LDA	#3	010003
60	0020		STA	LENGTH	0F200A
65	0023		+JSUB	WRREC	4B100000
70	0027		J	@RETADR	3E2000
95	002A	RETADR	RESW	1	
100	002D	LENGTH	RESW	1	
103			LTORG		
	0030	*	=C'EOF'		454F46
105	0033	BUFFER	RESB	4096	
106	1033	BUFEND	EQU	*	
107	1000	MAXLEN	EQU	BUFEND-BUFFER	

### Object Code with Multiple Control Sections

109	0000	RDREC	CSECT		
110					
115			SUBROUT:	INE TO READ RECORD	D INTO BUFFER
120					
122			EXTREF	BUFFER, LENGTH, BU	JFEND
125	0000		CLEAR	X	B410
130	0002		CLEAR	A	B400
132	0004		CLEAR	S	B440
133	0006		LDT	MAXLEN	77201F
135	0009	RLOOP	TD	INPUT	E3201B
140	000C		JEQ	RLOOP	332FFA
145	000F		RD	INPUT	DB2015
150	0012		COMPR	A,S	A004
155	0014		JEQ	EXIT	332009
160	0017		+STCH	BUFFER, X	57900000
165	001B		TIXR	T	B850
170	001D		JLT	RLOOP	3B2FE9
175	0020	EXIT	+STX	LENGTH	13100000
180	0024		RSUB		4F0000
185	0027	INPUT	BYTE	X'F1'	F1
190	0028	MAXLEN	WORD	BUFEND-BUFFER	000000

### Object Code with Multiple Control Sections

193	0000	WRREC	CSECT		
195					
200			SUBROUT	INE TO WRITE	RECORD FROM BUFFER
205					
207			EXTREF	LENGTH, BUFF	ER
210	0000		CLEAR	X	B410
212	0002		+LDT	LENGTH	77100000
215	0006	WLOOP	TD	=X'05'	E32012
220	0009		JEQ	WLOOP	332FFA
225	000C		+LDCH	BUFFER, X	53900000
230	0010		WD	=X'05'	DF2008
235	0013		TIXR	T	B850
240	0015		JLT	WLOOP	3B2FEE
245	0018		RSUB		4F0000
255			END	FIRST	
	001B	*	=X'05'		05

## How to Handle Control Sections

#### The assembler

- processes each control section independently
- establishes a separate LOCCTR (initialized to 0) for each control section
- stores in SYMTAB the control section in which a symbol is defined
- allow the same symbol to be used in different control sections
- reports an error when attempting to refer to a symbol in another control section, unless the symbol is defined as an external reference
- generates information in the object program for external references

#### New Records for External References

Define record: gives information about external symbols named by EXTDEF

Col. 2–7 Name of external symbol defined in this control section
Col. 8–13 Relative address of symbol within this control section (hexadecimal)
Col. 14–73 Repeat information in Col. 2–13 for other external symbols

Refer record: lists symbols used as external references, i.e., symbols named by EXTREF

Col. 1 R

Col. 2–7 Name of external symbol referred to in this control

section

Col. 8–73 Names of other external reference symbols

## Revised Modification Record

Modification	record	(revised):
--------------	--------	------------

0-1	1	. 11
Col		M
CO)		TAT

Col. 2–7 Starting address of the field to be modified, relative to

the beginning of the control section (hexadecimal)

Col. 8-9 Length of the field to be modified, in half-bytes (hexa-

decimal)

Col. 10 Modification flag (+ or –)

Col. 11-16 External symbol whose value is to be added to or sub-

tracted from the indicated field

```
000000001033
                                                     Object Program
         DBUFFEROOOO33BUFENDOO1033LENGTHOOO02D
        RRDREC WRREC
         T,000000,1D,172027,4B100000,032023,290000,332007,4B100000,3F2FEC,032016,0F2016
         T,00001D,0D,010003,0F200A,4B100000,3E2000
COPY
         T,000030,03,454F46
         M00000405+RDREC
         M00001105+WRREC
         M00002405+WRREC
         E000000
```

```
RDREC | HRDREC | 00000000002B | RBUFFER | H000001 DB410B400B44077201FE3201B332FFADB2015A00433200957900000B850 | T00001D0E3B2FE9131000004F0000F1000000 | M00001805+BUFFER | M00002105+LENGTH | M00002806+BUFEND | M00002806-BUFFER | E
```

####