Compiler

- The **compiler** is software that converts a program written in a high-level language (Source Language) to low-level language (Object/Target/Machine Language)..
- Some compilers
 - generate machine language
 - generate assembly language
 - more portable code such as C code,
- Some create abstract machine code.
- Some just generate data structures that are used by other parts of a program.
- That is the type of compiler that you will develop.

Why study compilers?

- It is useful for a computer scientist to study compiler design for several reasons.
- 1. Anyone who does any software development needs to use a compiler. It is a good idea to understand what is going on inside the tools that you use.
- 2. Studying compilers enables you to design and implement your own domain-specific language.
- 3. Compilers provide an essential interface between applications and architectures.
- 4. Compilers embody a wide range of theoretical techniques.
- 5. Compiler construction teaches programming and software engineering skills.

Why study compilers?

- It teaches you how real world applications are designed.
- It brings you closer to the language to exploit it. Compiler (a sophisticated program) bridges a gap between the language chosen & a computer architecture.
- Compiler improves software productivity by hiding low level details while delivering performance.
- Compiler provides techniques for developing other programming tools, like error detection tools.
- Program translation can be used to solve other problems, like Binary translation

Machines have continued to change since they have been invented.

- Changes in Architecture

 Changes in Compilers
- New features present new problems
- Changing costs lead to different concerns
- Must re-engineer well known solution

Qualities in compiler


- 1. Correct code
- 2. Output runs fast
- 3. Compiler runs fast
- 4. Compile time proportional to program size
- 5. Support for separate compilation
- 6. Good diagnostics for syntax errors
- 7. Works well with the debugger
- 8. Good diagnostics for flow anomalies
- 9. Cross language calls
- 10. Consistent, predictable optimization

Compiler construction shows us a microcosmic view of computer science.

artificial	greedy algorithms	
intelligence	learning algorithms	
	graph algorithms	
algorithms	union-find	
	network flows	
	network flows dynamic programming	
	dfa's for scanning	
theory	dfa's for scanning parser generators	
	lattice theory for analysis	
	allocation and naming	
systems	locality	
	synchronization	
	pipeline management	
architecture	memory hierarchy management	
	instruction set use	


Program Execution

- Execution of a program written in HLL is basically a 2-step process
- 1. The source program is compiled first i.e. translated into the object program.
- 2. The resulting object program is loaded into memory and executed



System Software:

An Introduction to Systems Programming



Outline

- Introduction
- System Software and Machine Architecture
- The Simplified Instructional Computer (SIC)
 - SIC Machine Architecture
 - SIC/XE Machine Architecture
 - SIC Programming Examples

1.1 Introduction

- System Software consists of a variety of programs that support the operation of a computer.
- The programs implemented in either software and (or) firmware that makes the computer hardware usable.
- The software makes it possible for the users to focus on an application or other problem to be solved, without needing to know the details of how the machine works internally.
- BIOS (Basic Input Output System).

1.2 System Software and Machine Architecture

- System Software vs Application Software
 - One characteristic in which most system software differs from application software is machine dependency.
 - System programs are intended to support the operation and use of the computer itself, rather than any particular application.
- Examples of system software
 - Text editor, assembler, compiler, loader or linker, debugger, macro processors, operating system.

1.2 System Software and Machine Architecture

Text editor

To create and modify the program

Compiler and assembler

You translated these programs into machine language

Loader or linker

 The resulting machine program was loaded into memory and prepared for execution

Debugger

• To help detect errors in the program.

Macro processor

translate macros instructions into its definition

Application Software Examples.

APPLICATION SOFTWARE	EXAMPLES
Office suites	Microsoft Office, Libre Office, Google G-Suite
Internet browser	Chrome, Firefox, Internet Explorer, Edge
Movie player	VLC, Windows Media Player
Presentations	PowerPoint
Word processor	Microsoft Word
Portable Document Format (PDF)	Adobe Acrobat Reader, Foxit Reader
Operating system	Microsoft Windows, Linux, Android, iOS
Antivirus	Norton, AVG, McAfee, Symantec, Windows Defender
Spreadsheets	Microsoft Excel
Accounting	Pastel, QuickBooks
Gaming	Minesweeper, Solitaire, Counter Strike
Designing and graphics	Adobe Photoshop, AutoCAD

System Software vs Application Software

S.No.	System Software	Application Software
1.	System software is used for	Application software is used by user
	operating computer hardware.	to perform specific task.
2.	System softwares are installed on	Application softwares are installed
	the computer when operating	according to user's requirements.
	system is installed.	
3.	In general, the user does not	In general, the user interacts with
	interact with system software	application sofwares.
	because it works in the	
	background.	
4.	System software can run	Application software can't run
	independently. It provides platform	independently. They can't run without
	for running application softwares.	the presence of system software.
5.	Some examples of system	Some examples of application
	softwares are compiler, assembler,	softwares are word processor, web
	debugger, driver, etc.	browser, media player, etc.

System Software Concept

Users

Application Program

Debugger

Macro Processor

Text Editor

Utility Program (Library)

Complier

Assembler

Load and Linker

Memory Management Process Management Device Management Information Management

OS

Bare Machine (Computer)


System Software and Machine Architecture

Machine dependent

Instruction Set, Instruction Format, Addressing Mode, Assembly language ...

Machine independent

General design logic/strategy, literals, symbol-defining statements, program blocks, control sections and program linking...



1.3 The Simplified Instructional Computer

- SIC refers to Simplified Instruction Computer which is a hypothetical computer that has been designed to include the hardware features most often found on real machines, while avoiding unusual and irrelevant complexities.
- This allows to clearly separate the central concepts of a system software from the implementation details associated with a particular machine.
- Like many other products, SIC comes in two versions
 - The standard model
 - An XE version "extra equipment's"
 - The two versions has been designed to be upward compatible

1.SIC (Simplified Instructional Computer)

2.SIC/XE (Extra Equipment)

1.Memory

- All addresses are byte addresses with words associated by the location of their Lowest numbered byte.
- Consist of 8-bit bytes.
- 3 consecutive bytes form a word (24 bits)
- Total size of the memory is $32768(2^{15})$ bytes

2.Registers

There are 5 special purpose registers each of which are 24 bits in

Mnemonic	Number	Special use
A	0	Accumulator; used for arithmetic operations
X	1	Index register; used for addressing
L	2	Linkage register; JSUB
PC	8	Program counter
SW	9	Status word, including CC

3.Data Formats

- Integers are stored as 24-bit binary number
- 2's complement representation for negative values
- Characters are stored using 8-bit ASCII codes
- No floating-point hardware on the standard version of SIC.

4. Instruction format

- 24-bit format
- The flag bit x is used to indicate indexed-addressing mode

8	1	15
opcode	X	address

5.Addressing Modes

- There are two addressing modes available
 - Indicated by x bit in the instruction
 - (X) represents the contents of reg. X

Mode	Indication	Target address calculation
Direct	x = 0	TA = address
Indexed	x = 1	TA = address + (X)

6. Instruction set

a. Integer arithmetic operations: ADD, SUB, MUL, DIV, etc.

All arithmetic operations involve register A and a word in memory, with the result being left in the register

b. comparison: COMP

COMP compares the value in register A with a word in memory, this instruction sets a condition code CC to indicate the result

c. conditional jump instructions: JLT, JEQ, JGT

These instructions test the setting of CC and jump accordingly.

d. subroutine linkage: JSUB, RSUB

- **JSUB** jumps to the subroutine, placing the return address in register L
- **RSUB** returns by jumping to the address contained in register L.

e. Load and store registers

Instructions to store and load registers are LDA, LDX, STA, STX.

7. I/O operations

- I/O are performed by transferring 1 byte at a time to or from the rightmost 8 bits of register A.
- Each device is assigned a unique 8-bit code as an operand.
- There are 3 I/O instructions
- 1.The **Test Device (TD)** instruction tests whether the addressed device is ready to send or receive a byte of data.(CC is set to <,if it is ready and set to =, if its not ready).
- 2. **Read Data (RD),** reads the data from an input device, if it is ready to send the data.
- 3. Write Data (WD) writes the data onto an output device, if its ready to receive the data

1.Memory:

Structure is same as that of the SIC standard version.

The maximum memory available is 1MegaByte(2^20) bytes.

2. Registers In addition to the registers of SIC standard version, the following registers are provided in SIC/XE.

Mnemonic	Number	Special use
A	0	Accumulator; used for arithmetic operations
X	1	Index register; used for addressing
L	2	Linkage register; JSUB
PC	8	Program counter
SW	9	Status word, including CC

M ne monic	Number	Special use
В	3	Base register; used for addressing
S	4	General working register
T	5	General working register
F	6	Floating-point acumulator (48bits)

7. Input/Output:

- In addition to the I/O instructions provided in SIC Standard version, SIC/XE provides I/O channels used to perform input and output while CPU is executing other instructions.
- •SIO, TIO, HIO: start, test, halt the operation of I/O channels respectively

3.Data format

- 24-bit binary number for integer, 2's complement for negative values
- 48-bit floating-point data type
- The exponent is between 0 and 2047
- The absolute value of the number is represented by $f^*2^{(e-1024)}$
- The sign of floating number is represented by
- 0: for +ve
- 1 for –ve

1	11	36

S exponent fraction	
---------------------	--

4.Instruction formats

- Relative addressing format 3 (e=0)
- Extend the address to 20 bits format 4 (e=1)
- Don't refer memory at all formats 1 and 2


Format 1 (1 byte):

Format 2 (2 bytes):


8 op

8	. 4	4
ор	r1	r2

Format 3 (3 bytes):



Format 4 (4 bytes):



5.Addressing modes

n i x b p e	
1. (n, i) Simple	n=0, i=0 or n=1, i=1
2. (i) Immediate	n=0, i=1 TA=Value
3. (n) Indirect	n=1, i=0 TA=(Operand)
4. Base relative	b=1, p=0 TA=(B)+disp
	$0 \le disp \le 4095$
5.PC relative b=0, p=1	TA=(PC)+disp
	$-2048 \le disp \le 2047$

Mode	Indication	Target address ca	rget address calculation				
Base relative	b = 1, p = 0	TA = (B) + disp	$(0 \le \text{disp} \le 4095)$				
Program-counter relative	b = 0, p = 1	TA = (PC) + disp	$(-2048 \le \text{disp} \le 2047)$				

6.Instruction Set

In addition to the instruction set, provided in SIC Standard version, SIC/XE provides following instructions.

- •new registers: LDB, STB, etc.
- floating-point arithmetic: ADDF, SUBF, MULF, DIVF
- register move: RMO
- register-register arithmetic: ADDR, SUBR, MULR, DIVR
- •supervisor call: SVC generates an interrupt for OS.

1.Base relative addressing:

bit b=1and p=0 and disp field is interpreted as a 12 bit unsigned integer in format 3.

2.Program counter relative addressing:

bit b=0and p=1 and disp field is interpreted as a 12 bit signed integer, with negative values represented in 2's complement notation.

3.Direct addressing : The displacement and address fields will be taken as the target address respectively in format 3 and format 4, if the bits b and p are both set to 0.

4.Indexed addressing:

If the bit x is set to 1, the content of register X is also added in the target address calculation.

5.Immediate addressing:

if the bits i=1 and n=0, the target address itself is the operand value and no memory is referenced.

6.Indirect addressing:

if the bits i=0, and n=1, the word at the location given by the target address contains the address of the operand value.

7. Simple addressing: if the bits i = n=0 or i=n=1, the target address is taken as the location of the operand.

Calculate the target address generated for the following machine instruction:

- I. 032600 h
- II. 03C300 h
- III. 022030 h
- IV. 010030 h
- V. 003600 h
- VI. 0310C303 h

Given

• (B)= 006000, (PC)=003000, (X)=000090

Number	0	1	2	3	4	5	6	7
Binary	0000	0001	0010	0011	0100	0101	0110	0111
Hexadecimal	0	1	2	3	4	5	6	7
				955 955	13.7	57 July 30		
Number	8	9	10	11	12	13	14	15
Number Binary	8 1000	9	10 1010	11 1011	12 1100	13 1101	555500-5	15 1111

1. **032600 h**

0-0000

3-0011

2-0010

6-0110

0-0000

0-0000

op(6 bits)	n(1)	i(1)	x(1)	b (1)	p (1)	e (1)	disp(12 bits)
0000 00	1	1	0	0	1	0	0110 0000 0000

Since p=1 it is program counter relative addressing add content of (PC) to disp value.

=600+003000

= 3600.

2.

03C300 h

0-0000

3-0011

C-1100

3-0011

0-0000

0-0000

op((6 bits)	n(1)	i(1)	x(1)	b (1)	p(1)	e (1)	disp(12 bits)
000	00 00	1	1	1	1	0	0	0011 0000 0000

Add content of both (X) and (B) contents to disp

3.

022030 h

op(6 bits)	n(1)	i(1)	x(1)	b (1)	p(1)	e (1)	disp(12 bits)
0000 00	1	0	0	0	1	0	0000 0011 0000

p is set to 1.

• 4.

010030 h

op(6 bits)	n(1)	i(1)	x(1)	b (1)	p(1)	e (1)	disp(12 bits)
0000 00	0	1	0	0	0	0	0000 0011 0000

b=p=0; the disp field is taken as TA for format 3(direct addressing)

TA=030.

6.


0310C303

op(6 bits)	n(1)	i(1)	x(1)	b (1)	p(1)	e (1)	address(20 bits)
0000 00	1	1	0	0	0	1	0000 1100 0011
							0000 0011

b=p=0; the address field is taken as TA for format 4(direct addressing)

$$TA = C303$$
.

Calculate the value Loaded into Register A



1. 032600 h

op(6 bits)	n(1)	i(1)	x(1)	b (1)	p(1)	e (1)	disp(12 bits)
0000 00	1	1	0	0	1	0	0110 0000 0000

n=i=1: Simple addressing; TA is taken as the location of the operand

$$TA = 3600$$

Value loaded= 103000

// value stored in the mem location 3600

2. 03C300 h

op(6 bits)	n(1)	i(1)	x(1)	b (1)	p(1)	e (1)	disp(12 bits)
0000 00	1	1	1	1	0	0	0011 0000 0000

n=i=1: Simple addressing; TA is taken as the location of the operand

$$TA = 6390$$

Value loaded= 00C303

// value stored in the mem location 6390

3. 022030 h

op(6 bits)	n(1)	i(1)	x(1)	b (1)	p(1)	e (1)	disp(12 bits)
0000 00	1	0	0	0	1	0	0000 0011 0000

n=1 and i=0; indirect addressing;

The word at the location given by the target address contains the address of the operand value.

TA = 3030

Value stored in 3030 mem loc = 003600

003600 is the address of the operand value

Value stored in 3600 = 103000

So value loaded = 103000.

4. 010030 h

op(6 bits)	n(1)	i(1)	x(1)	b (1)	p(1)	e (1)	disp(12 bits)
0000 00	0	1	0	0	0	0	0000 0011 0000

i=1 and n=0; immediate addressing; TA is taken as operand value. No memory reference is done.

6. 0310C303

op(6 bits)	n(1)	i(1)	x(1)	b (1)	p(1)	e (1)	address(20 bits)
000000	1	1	0	0	0	1	0000 1100 0011
							0000 0011

i=n=1; simple addressing; TA is taken as the location of the operand

TA = C303

Value loaded= 00303.