# **■** NetApp

### **Protect data**

**ONTAP System Manager** 

NetApp December 17, 2020

This PDF was generated from https://docs.netapp.com/us-en/ontap/concept\_dp\_overview.html on December 17, 2020. Always check docs.netapp.com for the latest.

## **Table of Contents**

Protect data	1
Data protection overview	1
Configure Snapshot copies	1
Recover from Snapshot copies	1
Prepare for mirroring and vaulting	1
Configure mirrors and vaults	2
Serve data from a SnapMirror destination	3
Resynchronize a protection relationship	3
Restore a volume from an earlier Snapshot copy	4
Restore to a new volume	4
Reverse Resynchronizing a Protection Relationship	4
Reactivate a source storage VM	5
Resynchronize a destination storage VM	5

### **Protect data**

### Data protection overview

Protect your data by creating and managing Snapshot copies, mirrors, vaults, and mirrorand-vault relationships.

SnapMirror is disaster recovery technology, designed for failover from primary storage to secondary storage at a geographically remote site. As its name implies, SnapMirror creates a replica, or mirror, of your working data in secondary storage from which you can continue to serve data in the event of a catastrophe at the primary site.

A *vault* is designed for disk-to-disk Snapshot copy replication for standards compliance and other governance-related purposes. In contrast to a SnapMirror relationship, in which the destination usually contains only the Snapshot copies currently in the source volume, a vault destination typically retains point-in-time Snapshot copies created over a much longer period.

### **Configure Snapshot copies**

You can create Snapshot copy policies to specify the maximum number of Snapshot copies that are automatically created and how frequently they are created. The policy specifies when to create Snapshot copies, how many copies to retain, and how to name them.

This procedure creates a Snapshot copy policy on the local cluster only.

#### Steps

- 1. Click Protection > Overview > Local Policy Settings.
- 2. Under **Snapshot Policies**, click  $\rightarrow$ , and then click + Add.
- Type the policy name, select the policy scope, and under Schedules, click + Add to enter the schedule details.

### **Recover from Snapshot copies**

You can recover a volume to an earlier point in time by restoring from a Snapshot copy.

This procedure restores a volume from a Snapshot copy.


#### **Steps**

- 1. Click **Storage** and select a volume.
- 2. Under **Snapshot Copies**, click inext to the Snapshot copy you want to restore, and select **Restore**.

### Prepare for mirroring and vaulting

You can protect your data by replicating it to a remote cluster for data backup and disaster recovery purposes.

Several default protection policies are available. You must have created your protection policies if you want to use custom policies.



#### **Steps**

- 1. In the local cluster, click **Protection > Overview**.
- Expand Intercluster Settings. Click Add Network Interfaces and add intercluster network interfaces for the cluster.

Repeat this step on the remote cluster.

- 3. In the remote cluster, click **Protection > Overview**. Click in the Cluster Peers section and click **Generate Passphrase**.
- 4. Copy the generated passphrase and paste it in the local cluster.
- 5. In the local cluster, under Cluster Peers, click **Peer Clusters** and peer the local and remote clusters.
- 6. Optionally, under Storage VM Peers, click and then Peer Storage VMs to peer the storage VMs.
- 7. Click **Protect Volumes** to protect your volumes. To protect your LUNs, click **Storage > LUNs**, select a LUN to protect, and then click **Protect**.

Select the protection policy based on the type of data protection you need.

8. To verify the volumes and LUNs are successfully protected from the local cluster, click **Storage > Volumes** or **Storage > LUNs** and, expand the volume/LUN view.

### **Configure mirrors and vaults**

Create a mirror and vault of a volume to protect data in case of a disaster and to have multiple archived versions of data to which you can roll back. Only the combined mirror-and-vault policy is supported. You cannot specify separate mirror and vault policies.

This procedure creates a mirror-and-vault policy on a remote cluster. The source cluster and destination cluster use intercluster network interfaces for exchanging data. The procedure assumes the intercluster network interfaces are created and the clusters containing the volumes are peered (paired). You can also peer storage VMs for data protection; however, if storage VMs are not peered, but permissions are enabled, storage VMs are automatically peered when the protection relationship is created.



#### Steps


1. Select the volume or LUN to protect: click Storage > Volumes or Storage > LUNs, and then click the

desired volume or LUN name.

- 2. Click Protect
- 3. Select the destination cluster and storage VM.
- 4. The asynchronous policy is selected by default. To select a synchronous policy, click More Options.
- 5. Click Protect.
- 6. Click the **SnapMirror** (**Local or Remote**) tab for the selected volume or LUN to verify that protection is set up correctly.

### Serve data from a SnapMirror destination

To serve data from a mirror destination when a source becomes unavailable, stop scheduled transfers to the destination, and then break the SnapMirror relationship to make the destination writable.



#### **Steps**

- 1. Select the desired protection relationship: click **Protection > Relationships**, and then click the desired volume name.
- 2. Click .
- 3. Stop scheduled transfers : click Pause.
- 4. Make the destination writable: click Break.
- 5. Go to the main **Relationships** page to verify that the relationship state displays as "broken off".

### **Next steps:**

When the disabled source volume is available again, you should resynchronize the relationship to copy the current data to the original source volume. This process replaces the data on the original source volume.

### Resynchronize a protection relationship

When your original source volume is available again after a disaster, you can resynchronize data from the destination volume and reestablish the protection relationship.

This procedure replaces the data in the original source volume in an asynchronous relationship so that you can start serving data from the original source volume again and resume the original protection relationship.

#### **Steps**

- 1. Click **Protection > Relationships** and then click the broken off relationship you want to resynchronize.
- Click and then select Resync.

3. Under **Relationships**, monitor the resynchronization progress by checking the relationship state. The state changes to "Mirrored" when resynchronization is complete.

### Restore a volume from an earlier Snapshot copy

When data in a volume is lost or corrupted, you can roll back your data by restoring from an earlier Snapshot copy.

This procedure replaces the current data on the source volume with data from an earlier Snapshot copy version. You should perform this task on the destination cluster.

### **Steps**

- 1. Click **Protection > Relationships**, and then click the source volume name.
- 2. Click and then select **Restore**.
- Under Source, the source volume is selected by default. Click Other Volume if you want to choose a different volume.
- 4. Under **Destination**, choose the Snapshot copy you want to restore.
- If your source and destination are located on different clusters, on the remote cluster, click Protection > Relationships to monitor the restore progress.

### Restore to a new volume

Starting in System Manager 9.8, you can restore backed up data on the destination volume to a volume other than the original source.

When you restore to a different volume, you can select an existing volume, or you can create a new volume.

#### **Steps**

- 1. Select the desired protection relationship: click **Protection > Relationships**.
- 2. Click and click Restore.
- 3. Under **Relationships**, monitor the restore progress by viewing **Transfer Status** for the relationship.

### Reverse Resynchronizing a Protection Relationship

Starting in System Manager 9.8, you can perform a reverse resynchronization operation to delete an existing protection relationship and reverse the functions of the source and destination volumes. Then you use the destination volume to serve data while you repair or replace the source, update the source, and reestablish the original configuration of the systems.

When you perform a reverse resynch operation, any data on the source volume that is newer than the data in the common Snapshot copy is deleted.

#### **Steps**

- 1. Select the desired protection relationship: click **Protection > Relationships**.
- Click and click Reverse Resync.

3. Under **Relationships**, monitor the reverse resynchronization progress by viewing **Transfer Status** for the relationship.

### Reactivate a source storage VM

Starting in System Manager 9.8, you can reactivate a source storage VM after a disaster. Reactivating the source storage VM stops the destination storage VM, and it reenables replication from the source to the destination.

### Steps

- 1. Select the desired protection relationship: click **Protection > Relationships**.
- 2. Click and click Reactivate Source Storage VM.
- 3. Under **Relationships**, monitor the source reactivation progress by viewing **Transfer Status** for the protection relationship.

### Resynchronize a destination storage VM

You can resynchronize the data and configuration details from the source SVM to the destination SVM in a broken protection relationship and reestablish the relationship.

You perform the resync operation only from the destination of the original relationship. The resync deletes any data in the destination storage VM that is newer than the data in the source storage VM.

#### **Steps**

- 1. Select the desired protection relationship: click **Protection > Relationships**.
- 2. Click and click **Resync**.
- 3. Under **Relationships**, monitor the resynchronization progress by viewing **Transfer Status** for the relationship.

#### **Copyright Information**

Copyright © 2020 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system-without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

#### **Trademark Information**

NETAPP, the NETAPP logo, and the marks listed at <a href="http://www.netapp.com/TM">http://www.netapp.com/TM</a> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.