Chapter 3: roadmap

- Transport-layer services
- Multiplexing and demultiplexing
- Connectionless transport: UDP
- Principles of reliable data transfer
- Connection-oriented transport: TCP
- Principles of congestion control
- TCP congestion control
- Evolution of transport-layer functionality



한글판 버전:

컴퓨터 네트워킹 하향식 접근[8판] James F. Kurose, Keith W. Ross 저/최종원, 강현국, 김기태

Principles of congestion control

Congestion:

• informally: "too many sources sending too much data too fast for network to handle"

- manifestations:
 - long delays (queueing in router buffers)
 - packet loss (buffer overflow at routers)
- different from flow control!
- a top-10 problem!




congestion control: too many senders,

sending too fast


flow control: one sender too fast for one receiver

Simplest scenario:


- one router, infinite buffers
- input, output link capacity: R
- two flows
- no retransmissions needed



Q: What happens as arrival rate λ_{in} approaches R/2?




maximum per-connection throughput: R/2




large delays as arrival rate $\lambda\iota\nu\epsilon$ approaches capacity


- one router, finite buffers
- sender retransmits lost, timed-out packet
 - application-layer input = application-layer output: $\lambda_{in} = \lambda_{out}$
 - transport-layer input includes retransmissions : $\lambda'_{in} \ge \lambda_{in}$



Idealization: perfect knowledge


sender sends only when router buffers available






Idealization: some perfect knowledge


- packets can be lost (dropped at router) due to full buffers
- sender knows when packet has been dropped: only resends if packet known to be lost



Idealization: some perfect knowledge

- packets can be lost (dropped at router) due to full buffers
- sender knows when packet has been dropped: only resends if packet known to be lost







R/2

Realistic scenario: un-needed duplicates


- packets can be lost, dropped at router due to full buffers – requiring retransmissions
- but sender times can time out prematurely, sending two copies, both of which are delivered





Realistic scenario: *un-needed duplicates*

- packets can be lost, dropped at router due to full buffers – requiring retransmissions
- but sender times can time out prematurely, sending two copies, both of which are delivered





"costs" of congestion:

- more work (retransmission) for given receiver throughput
- unneeded retransmissions: link carries multiple copies of a packet
 - decreasing maximum achievable throughput

- four senders
- multi-hop paths
- timeout/retransmit

- \underline{Q} : what happens as λ_{in} and λ_{in} increase?
- A: as red λ_{in} increases, all arriving blue pkts at upper queue are dropped, blue throughput \rightarrow 0







another "cost" of congestion:


when packet dropped, any upstream transmission capacity and buffering used for that packet was wasted!


Causes/costs of congestion: insights


- throughput can never exceed capacity
- delay increases as capacity approached
- loss/retransmission decreases effective throughput
- un-needed duplicates further decreases effective throughput
- upstream transmission capacity / buffering wasted for packets lost downstream












Approaches towards congestion control

End-end congestion control:


- no explicit feedback from network
- congestion inferred from observed loss, delay
- approach taken by TCP



Approaches towards congestion control

Network-assisted congestion control:

- routers provide direct feedback to sending/receiving hosts with flows passing through congested router
- may indicate congestion level or explicitly set sending rate
- TCP ECN, ATM, DECbit protocols



Chapter 3: roadmap

- Transport-layer services
- Multiplexing and demultiplexing
- Connectionless transport: UDP
- Principles of reliable data transfer
- Connection-oriented transport: TCP
- Principles of congestion control
- TCP congestion control
- Evolution of transport-layer functionality



TCP congestion control: AIMD

 approach: senders can increase sending rate until packet loss (congestion) occurs, then decrease sending rate on loss event

Additive Increase <u>Multiplicative Decrease</u> increase sending rate by 1 cut sending rate in half at maximum segment size every each loss event RTT until loss detected Sending rate **AIMD** sawtooth behavior: probing TCP sender for bandwidth

time

TCP AIMD: more


Multiplicative decrease detail: sending rate is

- Cut in half on loss detected by triple duplicate ACK (TCP Reno)
- Cut to 1 MSS (maximum segment size) when loss detected by timeout (TCP Tahoe)

Why AIMD?

- AIMD a distributed, asynchronous algorithm has been shown to:
 - optimize congested flow rates network wide!
 - have desirable stability properties

TCP congestion control: details



TCP sending behavior:


 roughly: send cwnd bytes, wait RTT for ACKS, then send more bytes

TCP rate
$$\approx \frac{\text{cwnd}}{\text{RTT}}$$
 bytes/sec

- TCP sender limits transmission: LastByteSent- LastByteAcked < cwnd
- cwnd is dynamically adjusted in response to observed network congestion (implementing TCP congestion control)

TCP slow start

- when connection begins, increase rate exponentially until first loss event:
 - initially cwnd = 1 MSS
 - double cwnd every RTT
 - done by incrementing cwnd for every ACK received
- summary: initial rate is slow, but ramps up exponentially fast




TCP: from slow start to congestion avoidance

Q: when should the exponential increase switch to linear?


A: when **cwnd** gets to 1/2 of its value before timeout.

Implementation:

- variable ssthresh
- on loss event, ssthresh is set to
 1/2 of cwnd just before loss event




Summary: TCP congestion control




TCP CUBIC

- Is there a better way than AIMD to "probe" for usable bandwidth?
- Insight/intuition:
 - W_{max}: sending rate at which congestion loss was detected
 - congestion state of bottleneck link probably (?) hasn't changed much
 - after cutting rate/window in half on loss, initially ramp to to W_{max} faster, but then approach W_{max} more slowly




TCP CUBIC

- K: point in time when TCP window size will reach W_{max}
 - K itself is tunable
- increase W as a function of the cube of the distance between current time and K
 - larger increases when further away from K
 - smaller increases (cautious) when nearer K
- TCP CUBIC default in Linux, most popular TCP for popular Web servers




TCP and the congested "bottleneck link"

 TCP (classic, CUBIC) increase TCP's sending rate until packet loss occurs at some router's output: the bottleneck link




TCP and the congested "bottleneck link"

- TCP (classic, CUBIC) increase TCP's sending rate until packet loss occurs at some router's output: the bottleneck link
- understanding congestion: useful to focus on congested bottleneck link



Delay-based TCP congestion control

Keeping sender-to-receiver pipe "just full enough, but no fuller": keep bottleneck link busy transmitting, but avoid high delays/buffering



Delay-based approach:

- RTT_{min} minimum observed RTT (uncongested path)
- uncongested throughput with congestion window cwnd is cwnd/RTT_{min}

```
if measured throughput "very close" to uncongested throughput increase cwnd linearly /* since path not congested */ else if measured throughput "far below" uncongested throughout decrease cwnd linearly /* since path is congested */
```


Delay-based TCP congestion control

- congestion control without inducing/forcing loss
- maximizing throughout ("keeping the just pipe full...") while keeping delay low ("...but not fuller")
- a number of deployed TCPs take a delay-based approach
 - BBR (Bottleneck Bandwidth and RTT) deployed on Google's (internal) backbone network

Explicit congestion notification (ECN)


TCP deployments often implement *network-assisted* congestion control:

- two bits in IP header (ToS field) marked by network router to indicate congestion
 - policy to determine marking chosen by network operator
- congestion indication carried to destination
- destination sets ECE bit on ACK segment to notify sender of congestion
- involves both IP (IP header ECN bit marking) and TCP (TCP header C,E bit marking)



TCP fairness


Fairness goal: if K TCP sessions share same bottleneck link of bandwidth R, each should have average rate of R/K



Q: is TCP Fair?

Example: two competing TCP sessions:

- additive increase gives slope of 1, as throughout increases
- multiplicative decrease decreases throughput proportionally



Is TCP fair?

A: Yes, under idealized assumptions:

- same RTT
- fixed number of sessions only in congestion avoidance

Fairness: must all network apps be "fair"?

Fairness and UDP

- multimedia apps often do not use TCP
 - do not want rate throttled by congestion control
- instead use UDP:
 - send audio/video at constant rate, tolerate packet loss
- there is no "Internet police" policing use of congestion control

Fairness, parallel TCP connections

- application can open multiple parallel connections between two hosts
- web browsers do this, e.g., link of rate R with 9 existing connections:
 - new app asks for 1 TCP, gets rate R/10
 - new app asks for 11 TCPs, gets R/2

Transport layer: roadmap

- Transport-layer services
- Multiplexing and demultiplexing
- Connectionless transport: UDP
- Principles of reliable data transfer
- Connection-oriented transport: TCP
- Principles of congestion control
- TCP congestion control
- Evolution of transport-layer functionality



Evolving transport-layer functionality


- TCP, UDP: principal transport protocols for 40 years
- different "flavors" of TCP developed, for specific scenarios:

Scenario	Challenges
Long, fat pipes (large data	Many packets "in flight"; loss shuts down
transfers)	pipeline
Wireless networks	Loss due to noisy wireless links, mobility;
	TCP treat this as congestion loss
Long-delay links	Extremely long RTTs
Data center networks	Latency sensitive
Background traffic flows	Low priority, "background" TCP flows

- moving transport—layer functions to application layer, on top of UDP
 - HTTP/3: QUIC

QUIC: Quick UDP Internet Connections

- application-layer protocol, on top of UDP
 - increase performance of HTTP
 - deployed on many Google servers, apps (Chrome, mobile YouTube app)




QUIC: Quick UDP Internet Connections

adopts approaches we've studied in this chapter for connection establishment, error control, congestion control


- error and congestion control: "Readers familiar with TCP's loss detection and congestion control will find algorithms here that parallel well-known TCP ones." [from QUIC specification]
- connection establishment: reliability, congestion control, authentication, encryption, state established in one RTT
- multiple application-level "streams" multiplexed over single QUIC connection
 - separate reliable data transfer, security
 - common congestion control

QUIC: Connection establishment



TCP (reliability, congestion control state) + TLS (authentication, crypto state)


2 serial handshakes



QUIC: reliability, congestion control, authentication, crypto state

1 handshake

QUIC: streams: parallelism, no HOL blocking



(a) HTTP 1.1

Chapter 3: summary

- principles behind transport layer services:
 - multiplexing, demultiplexing
 - reliable data transfer
 - flow control
 - congestion control
- instantiation, implementation in the Internet
 - UDP
 - TCP



Up next:


- leaving the network "edge" (application, transport layers)
- into the network "core"
- two network-layer chapters:
 - data plane
 - control plane

Additional Chapter 3 slides

Go-Back-N: sender extended FSM

```
rdt_send(data)
                       if (nextseqnum < base+N) {
                          sndpkt[nextseqnum] = make_pkt(nextseqnum,data,chksum)
                          udt_send(sndpkt[nextseqnum])
                          if (base == nextseqnum)
                           start_timer
                          nextseqnum++
                       else
                        refuse_data(data)
  base=1
  nextsegnum=1
                                          timeout
                                          start_timer
                             Wait
                                          udt_send(sndpkt[base])
                                          udt_send(sndpkt[base+1])
rdt rcv(rcvpkt)
 && corrupt(rcvpkt)
                                          udt_send(sndpkt[nextseqnum-1])
                         rdt_rcv(rcvpkt) &&
                           notcorrupt(rcvpkt)
                         base = getacknum(rcvpkt)+1
                         If (base == nextseqnum)
                           stop_timer
                          else
                           start_timer
```


Go-Back-N: receiver extended FSM




ACK-only: always send ACK for correctly-received packet with highest in-order seq

- may generate duplicate ACKs
- need only remember expectedseqnum
- out-of-order packet:
 - discard (don't buffer): no receiver buffering!
 - re-ACK pkt with highest in-order seq #


TCP sender (simplified)



TCP 3-way handshake FSM



Closing a TCP connection



TCP throughput

- avg. TCP thruput as function of window size, RTT?
 - ignore slow start, assume there is always data to send
- W: window size (measured in bytes) where loss occurs
 - avg. window size (# in-flight bytes) is ¾ W
 - avg. thruput is 3/4W per RTT

avg TCP thruput =
$$\frac{3}{4} \frac{W}{RTT}$$
 bytes/sec

TCP over "long, fat pipes"

- example: 1500 byte segments, 100ms RTT, want 10 Gbps throughput
- requires W = 83,333 in-flight segments
- throughput in terms of segment loss probability, L [Mathis 1997]:

TCP throughput =
$$\frac{1.22 \cdot MSS}{RTT \sqrt{L}}$$

- → to achieve 10 Gbps throughput, need a loss rate of L = $2\cdot10^{-10} a$ very small loss rate!
- versions of TCP for long, high-speed scenarios