
# **Topology Diagram**



# **Addressing Table**

Device	Interface	IP Address	Subnet Mask	Default Gateway
	Fa0/0	172.30.1.1	255.255.255.0	N/A
R1	Fa0/1	172.30.2.1	255.255.255.0	N/A
	S0/0/0	209.165.200.230	255.255.255.252	N/A
	Fa0/0	10.1.0.1	255.255.0.0	N/A
R2	S0/0/0	209.165.200.229	255.255.255.252	N/A
	S0/0/1	209.165.200.233	255.255.255.252	N/A
	Fa0/0	172.30.100.1	255.255.255.0	N/A
	S0/0/1	209.165.200.234	255.255.255.252	N/A
R3	Lo0	172.30.110.1	255.255.255.0	N/A
	Lo1	172.30.200.17	255.255.255.240	N/A
	Lo2	172.30.200.33	255.255.255.240	N/A
PC1	NIC	172.30.2.10	255.255.255.0	172.30.2.1
PC2	NIC	172.30.1.10	255.255.255.0	172.30.1.1
PC3	NIC	10.1.0.10	255.255.0.0	10.1.0.1
PC4	NIC	172.30.100.10	255.255.255.0	172.30.100.1

## **Learning Objectives**

Upon completion of this lab, you will be able to:

- Cable a network according to the Topology Diagram.
- Load provided scripts onto the routers.
- Examine the current status of the network.
- Configure RIPv2 on all routers.
- Examine the automatic summarization of routes.
- Examine routing updates with debug ip rip.
- Disable automatic summarization.
- Examine the routing tables.
- Verify network connectivity.
- Document the RIPv2 configuration.

## Scenario


The network shown in the Topology Diagram contains a discontiguous network, 172.30.0.0. This network has been subnetted using VLSM. The 172.30.0.0 subnets are physically and logically divided by at least one other classful or major network, in this case the two serial networks 209.165.200.228/30 and 209.165.200.232/30. This can be an issue when the routing protocol used does not include enough information to distinguish the individual subnets. RIPv2 is a classless routing protocol that can be used to provide subnet mask information in the routing updates. This will allow VLSM subnet information to be propagated throughout the network.

## Task 1: Cable, Erase, and Reload the Routers.


## Step 1: Cable a network.

Cable a network that is similar to the one in the Topology Diagram.


## PC1 config




## PC2 config




## PC3 config



## **PC4 Config**





Step 2: Clear the configuration on each router.

Clear the configuration on each of routers using the erase startup-config command and then reload the routers. Answer **no** if asked to save changes.

#### R1 -

```
₽ R1
     Physical Config CLI Attributes
                                                                                                                                                                                                                                                             105
      Router#erase startup-config
Erasing the nvram filesystem will remove all configuration files! Continue? [confirm]
       %SYS-7-NV_BLOCK_INIT: Initialized the geometry of nvram Router#reload
       Routerfreload

Proceed with reload? [confirm]

System Bootstrap, Version 12.3(8r)T8, RELEASE SOFTWARE (fcl)

Initializing memory for ECC
       ..
C1841 processor with 524288 Kbytes of main memory
Main memory is configured to 64 bit mode with ECC enabled
        Readonly ROMMON initialized
       Self decompressing the image:
                                      Restricted Rights Legend
      Use, duplication, or disclosure by the Government is subject to restrictions as set forth in subparagraph (c) of the Commercial Computer Software - Restricted Rights clause at FAR sec. 52.227-19 and subparagraph (c) (1) (i) of the Rights in Technical Data and Computer Software clause at DFARS sec. 252.227-7013.
                               cisco Systems, Inc.
170 West Tasman Drive
San Jose, California 95134-1706
      Cisco IOS Software, 1841 Software (C1841-ADVIPSERVICESK9-M), Version 12.4(15)T1, RELEASE SOFTWARE (fc2) Technical Support: http://www.cisco.com/techsupport
Copyright (c) 1986-2007 by Cisco Systems, Inc.
Compiled Wed 18-5ul-07 04:52 by pt_team
Image text-base: 0x60080608, data-base: 0x6270CD50
      This product contains cryptographic features and is subject to United States and local country laws governing import, export, transfer and use. Delivery of Cisco cryptographic products does not imply third-party authority to import, export, distribute or use encryption. Importers, exporters, distributors and users are responsible for compliance with U.S. and local country laws. By using this product you agree to comply with applicable laws and regulations. If you are unable to comply with U.S. and local laws, return this product immediately.
       A summary of U.S. laws governing Cisco cryptographic products may be found at: http://www.cisco.com/wwl/export/crypto/tool/stqrg.html
      If you require further assistance please contact us by sending email to
    Ctrl+F6 to exit CLI focus
```



Physical Config CLI Attributes Ю Router>enable Routerferase startup-config Erasing the nvram filesystem will remove all configuration files! Continue? [confirm] [OK]
Erase of nvram: complete
%SYS-7-NV\_BLOCK\_INIT: Initialized the geometry of nvram Router# Router#reload NOUTE::FELDOM
System configuration has been modified. Save? [yes/no]:no
Proceed with reload? [confirm]
System Bootstrap, Version 12.3(8r)T8, RELEASE SOFTWARE (fcl)
Initializing memory for ECC ... C1841 processor with 524288 Kbytes of main memory Main memory is configured to 64 bit mode with ECC enabled Readonly ROMMON initialized Self decompressing the image : Restricted Rights Legend Use, duplication, or disclosure by the Government is subject to restrictions as set forth in subparagraph (c) of the Commercial Computer Software - Restricted Rights clause at FAR sec. 52.227-19 and subparagraph (c) (1) (i) of the Rights in Technical Data and Computer Software clause at DFARS sec. 252.227-7013. cisco Systems, Inc. 170 West Tasman Drive San Jose, California 95134-1706 Cisco IOS Software, 1841 Software (C1841-ADVIPSERVICESK9-M), Version 12.4(15)T1, RELEASE SOFTWARE (fc2) Technical Support: http://www.cisco.com/techsupport Copyright (c) 1986-2007 by Cisco Systems, Inc. Compiled Wed 18-Jul-07 04:52 by pt\_team Image text-base: 0x60080608, data-base: 0x6270CD50 This product contains cryptographic features and is subject to United States and local country laws governing import, export, transfer and use. Delivery of Cisco cryptographic products does not imply third-party authority to import, export, distribute or use encryption. Importers, exporters, distributors and users are responsible for compliance with U.S. and local country laws. By using this product you agree to comply with applicable laws and regulations. If you are unable to comply with U.S. and local laws, return this product immediately.

Ctrl+F6 to exit CLI focus

#### R3 -




Ctrl+F6 to exit CLI focus

## Task 2: Load Routers with the Supplied Scripts.

## Step 1: Load the following script onto R1.

```
hostname R1
interface FastEthernet0/0
ip address 172.30.1.1 255.255.255.0
duplex auto
speed auto
no shutdown
interface FastEthernet0/1
ip address 172.30.2.1 255.255.255.0
duplex auto
speed auto
no shutdown
!
interface Serial0/0/0
 ip address 209.165.200.230 255.255.255.252
clock rate 64000
no shutdown
router rip
passive-interface FastEthernet0/0
passive-interface FastEthernet0/1
network 172.30.0.0
network 209.165.200.0
line con 0
line vty 0 4
login
!
end
```




Step 2: Load the following script onto R2.

R1 (config-line) #end

```
hostname R2
!
!
!
interface FastEthernet0/0
ip address 10.1.0.1 255.255.0.0
duplex auto
speed auto
no shutdown
!
interface Serial0/0/0
ip address 209.165.200.229 255.255.252
no shutdown
```

```
1
interface Serial0/0/1
    ip address 209.165.200.233 255.255.255.252
   clock rate 64000
   no shutdown
router rip
   passive-interface FastEthernet0/0
   network 10.0.0.0
  network 209.165.200.0
line con 0
line vty 0 4
   login
!
end
№ R2
      Physical Config CLI Attributes
        Router>
        Router>enable
        Router#config t
        Enter configuration commands, one per line. End with CNTL/Z.
        Router(config) #hostname R2
        R2 (config) #
       R2(config) #interface FastEthernet0/0
R2(config-if) #ip address 10.1.0.1 255.255.0.0
        R2(config-if)#duplex auto
        R2(config-if) #speed auto
        R2(config-if) #no shutdown
        R2(config-if)#
        %LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up
        %LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
        R2(config-if)#interface Serial0/0/0
       R2(config-if) #ip address 209.165.200.229 255.255.255.252 R2(config-if) #no shutdown
        R2(config-if) # %LINK-5-CHANGED: Interface Serial0/0/0, changed state to up
        %LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0/0, changed state to up
        R2(config-if)#interface Serial0/0/1
       R2(config-if)*ip address 209.165.200.233 255.255.255 R2(config-if)*clock rate 64000
        R2(config-if) #no shutdown
        %LINK-5-CHANGED: Interface Serial0/0/1, changed state to down
       R2(config-if)#
R2(config-if)#router rip
       R2(config-router) #passive-interface FastEthernet0/0
R2(config-router) #network 10.0.0.0
       R2(config-router)#network 209.165.200.0
R2(config-router)#
R2(config-router)#line con 0
        R2(config-line) #line vty 0 4
        R2(config-line) #login
      R2(config-line) #login 
% Login disabled on line 194, until 'password' is set 
% Login disabled on line 195, until 'password' is set 
% Login disabled on line 196, until 'password' is set 
% Login disabled on line 197, until 'password' is set 
% Login disabled on line 198, until 'password' is set 
R2(config-line) # 
R2(config-line) #
```


Ctrl+F6 to exit CLI focus



Step 3: Load the following script onto R3.

```
hostname R3
!
!
interface FastEthernet0/0
 ip address 172.30.100.1 255.255.255.0
 duplex auto
 speed auto
no shutdown
interface Serial0/0/1
 ip address 209.165.200.234 255.255.255.252
no shutdown
interface Loopback0
 ip address 172.30.110.1 255.255.255.0
interface Loopback1
 ip address 172.30.200.17 255.255.255.240
interface Loopback2
 ip address 172.30.200.33 255.255.255.240
router rip
passive-interface FastEthernet0/0
network 172.30.0.0
network 209.165.200.0
line con 0
line vty 0 4
login
!
End
```






#### Task 3: Examine the Current Status of the Network.

## Step 1: Verify that both serial links are up.

The two serial links can quickly be verified using the show ip interface brief command on R2.


R2#show ip interface brief



Step 2: Check the connectivity from R2 to the hosts on the R1 and R3 LANs.


Note: For the 1841 router, you will need to disable IP CEF to obtain the correct output from the ping command. Although a discussion of IP CEF is beyond the scope of this course, you may disable IP CEF by using the following command in global configuration mode:

R2(config) #no ip cef




From the R2 router, how many ICMP messages are successful when pinging PC1?

\_2



From the R2 router, how many ICMP messages are successful when pinging PC4?


3\_\_\_\_\_



## Step 3: Check the connectivity between the PCs.


From the PC1, is it possible to ping PC2? \_\_\_\_yes\_\_\_\_

What is the success rate? \_\_\_\_100%\_\_\_\_




From the PC1, is it possible to ping PC3? \_\_\_yes\_\_\_\_

What is the success rate? \_\_\_\_50%\_\_\_




From the PC1, is it possible to ping PC4? \_\_\_\_no\_\_\_

What is the success rate? \_\_\_\_0%\_\_\_\_




From the PC4, is it possible to ping PC2? \_\_\_no\_\_\_\_ What is the success rate? \_\_\_0%\_\_\_



From the PC4, is it possible to ping PC3? \_\_\_yes\_\_\_\_

What is the success rate? \_\_\_\_50%\_\_\_\_



## Step 4: View the routing table on R2.

Both the R1 and R3 are advertising routes to the 172.30.0.0/16 network; therefore, there are two entries for this network in the R2 routing table. The R2 routing table only shows the major classful network address of 172.30.0.0—it does not show any of the subnets for this network that are used on the LANs attached to R1 and R3. Because the routing metric is the same for both entries, the router alternates the routes that are used when forwarding packets that are destined for the 172.30.0.0/16 network.

#### R2#show ip route

```
R2#
R2#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
1 - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
* - candidate default, U - per-user static route, O - ODR
P - periodic downloaded static route

Gateway of last resort is not set

10.0.0.0/16 is subnetted, 1 subnets
C 10.1.0.0 is directly connected, FastEthernet0/0
R 172.30.0.0/16 [120/1] via 209.165.200.230, 00:00:24, Serial0/0/0
[120/1] via 209.165.200.234, 00:00:01, Serial0/0/1
209.165.200.0/30 is subnetted, 2 subnets
C 209.165.200.228 is directly connected, Serial0/0/0
R2#

Ctrl+F6 to exit CLI focus
```

#### Step 5: Examine the routing table on the R1 router.

Both R1 and R3 are configured with interfaces on a discontiguous network, 172.30.0.0. The 172.30.0.0 subnets are physically and logically divided by at least one other classful or major network—in this case,

the two serial networks 209.165.200.228/30 and 209.165.200.232/30. Classful routing protocols like RIPv1 summarize networks at major network boundaries. Both R1 and R3 will be summarizing 172.30.0.0/24 subnets to 172.30.0.0/16. Because the route to 172.30.0.0/16 is directly connected, and because R1 does not have any specific routes for the 172.30.0.0 subnets on R3, packets destined for the R3 LANs will not be forwarded properly.

#### R1#show ip route

```
R1>
R1>enable
Rl#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route
Gateway of last resort is not set
     10.0.0.0/8 [120/1] via 209.165.200.229, 00:00:23, Serial0/0/0
     172.30.0.0/24 is subnetted. 2 subnets
        172.30.1.0 is directly connected, FastEthernet0/0
C
        172.30.2.0 is directly connected, FastEthernet0/1
     209.165.200.0/30 is subnetted, 2 subnets
C
        209.165.200.228 is directly connected, Serial0/0/0
R
        209.165.200.232 [120/1] via 209.165.200.229, 00:00:23, Serial0/0/0
R1#
Ctrl+F6 to exit CLI focus
```

## Step 6: Examine the routing table on the R3 router.

R3 only shows its own subnets for 172.30.0.0 network: 172.30.100/24, 172.30.110/24, 172.30.200.16/28, and 172.30.200.32/28. R3 does not have any routes for the 172.30.0.0 subnets on R1.

#### R3#show ip route

```
R3>
R3>enable
R3#
R3#
R3#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       {\tt N1} - OSPF NSSA external type 1, {\tt N2} - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route
Gateway of last resort is not set
    10.0.0.0/8 [120/1] via 209.165.200.233, 00:00:19, Serial0/0/1
    172.30.0.0/16 is variably subnetted, 4 subnets, 2 masks
        172.30.100.0/24 is directly connected, FastEthernet0/0
        172.30.110.0/24 is directly connected, Loopback0
        172.30.200.16/28 is directly connected, Loopbackl
        172.30.200.32/28 is directly connected, Loopback2
     209.165.200.0/30 is subnetted, 2 subnets
R
        209.165.200.228 [120/1] via 209.165.200.233, 00:00:19, Serial0/0/1
        209.165.200.232 is directly connected, Serial0/0/1
R3#
```

Ctrl+F6 to exit CLI focus

#### Step 7: Examine the RIPv1 packets that are being received by R2.

Use the debug ip rip command to display RIP routing updates.

R2 is receiving the route 172.30.0.0, with 1 hop, from both R1 and R3. Because these are equal cost metrics, both routes are added to the R2 routing table. Because RIPv1 is a classful routing protocol, no subnet mask information is sent in the update.

#### R2#debug ip rip

R2 is sending only the routes for the 10.0.0.0 LAN and the two serial connections to R1 and R3. R1 and R3 are not receiving any information about the 172.30.0.0 subnet routes.

When you are finished, turn off the debugging.

```
₹ R2
  Physical Config CLI Attributes
  R2#
  R2#
  R2#
  R2#debug ip rip
   RIP protocol debugging is on
  R2#RIP: received v1 update from 209.165.200.234 on Serial0/0/1
        172.30.0.0 in 1 hops
   RIP: received vl update from 209.165.200.230 on Serial0/0/0
        172.30.0.0 in 1 hops
  RIP: sending vl update to 255.255.255.255 via Serial0/0/0 (209.165.200.229)
  RIP: build update entries
         network 10.0.0.0 metric 1
         network 209.165.200.232 metric 1
   RIP: sending v1 update to 255.255.255.255 via Serial0/0/1 (209.165.200.233)
  RIP: build update entries
        network 10.0.0.0 metric 1
         network 209.165.200.228 metric 1
  RIP: received v1 update from 209.165.200.234 on Serial0/0/1
         172.30.0.0 in 1 hops
   RIP: received vl update from 209.165.200.230 on Serial0/0/0
         172.30.0.0 in 1 hops
   RIP: sending v1 update to 255.255.255.255 via Serial0/0/0 (209.165.200.229)
  RIP: build update entries
        network 10.0.0.0 metric 1
        network 209.165.200.232 metric 1
  RIP: sending v1 update to 255.255.255.255 via Serial0/0/1 (209.165.200.233)
  RIP: build update entries
        network 10.0.0.0 metric 1
         network 209.165.200.228 metric 1
   RIP: received v1 update from 209.165.200.234 on Serial0/0/1
        172.30.0.0 in 1 hops
   RIP: received v1 update from 209.165.200.230 on Serial0/0/0
         172.30.0.0 in 1 hops
   RIP: sending v1 update to 255.255.255.255 via Serial0/0/0 (209.165.200.229)
  RIP: build update entries
        network 10.0.0.0 metric 1
         network 209.165.200.232 metric 1
   RIP: sending v1 update to 255.255.255.255 via Serial0/0/1 (209.165.200.233)
  RIP: build update entries
         network 10.0.0.0 metric 1
         network 209.165.200.228 metric 1
  RIP: received v1 update from 209.165.200.234 on Serial0/0/1
         172.30.0.0 in 1 hops
   RIP: received vl update from 209.165.200.230 on Serial0/0/0
         172.30.0.0 in 1 hops
  RIP: sending v1 update to 255.255.255.255 via Serial0/0/0 (209.165.200.229) RIP: build update entries
        network 10.0.0.0 metric 1
         network 209.165.200.232 metric 1
  RIP: sending v1 update to 255.255.255.255 via Serial0/0/1 (209.165.200.233)
  RIP: build update entries
  Ctrl+E6 to exit CLI focus
```

#### R2#undebug all

```
R2#undebug all
All possible debugging has been turned off
R2#
```

## Task 4: Configure RIP Version 2.

Step 1: Use the version 2 command to enable RIP version 2 on each of the routers.


```
R2(config) #router rip
R2(config-router) #version 2
   R2(config)#
   R2 (config) #router rip
   R2(config-router) #version 2
   R2(config-router)#
   Ctrl+F6 to exit CLI focus
R1(config) #router rip
R1 (config-router) #version 2
   R1#config t
   Enter configuration commands, one per line. End with CNTL/Z.
   R1(config) #router rip
   R1(config-router) #version 2
   R1(config-router)#
  Ctrl+F6 to exit CLI focus
R3(config) #router rip
R3(config-router) #version 2
   R3#config t
   Enter configuration commands, one per line. End with CNTL/Z.
   R3(config) #router rip
   R3(config-router) #version 2
   R3(config-router)#
   Ctrl+F6 to exit CLI focus
```


RIPv2 messages include the subnet mask in a field in the routing updates. This allows subnets and their masks to be included in the routing updates. However, by default RIPv2 summarizes networks at major network boundaries, just like RIPv1, except that the subnet mask is included in the update.

#### Step 2: Verify that RIPv2 is running on the routers.

The debug ip rip, show ip protocols, and show run commands can all be used to confirm that RIPv2 is running. The output of the show ip protocols command for R1 is shown below.

```
R1# show ip protocols
```





#### Task 5: Examine the Automatic Summarization of Routes.

The LANs connected to R1 and R3 are still composed of discontiguous networks. R2 still shows two equal cost paths to the 172.30.0.0/16 network in the routing table. R2 still shows only the major classful network address of 172.30.0.0 and does not show any of the subnets for this network.

```
R2#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       {\tt E1} - OSPF external type 1, {\tt E2} - OSPF external type 2, {\tt E} - {\tt EGP}
      i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route
Gateway of last resort is not set
    10.0.0.0/16 is subnetted, 1 subnets
С
       10.1.0.0 is directly connected, FastEthernet0/0
    172.30.0.0/16 [120/1] via 209.165.200.230, 00:00:01, Serial0/0/0
R
                   [120/1] via 209.165.200.234, 00:00:13, Serial0/0/1
     209.165.200.0/30 is subnetted, 2 subnets
C.
      209.165.200.228 is directly connected, Serial0/0/0
С
       209.165.200.232 is directly connected, Serial0/0/1
R2#
```

R1 still shows only its own subnets for the 172.30.0.0 network. R1 still does not have any routes for the 172.30.0.0 subnets on R3.

R1#show ip route

```
Rl#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
      D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
      N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
      E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
      i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
      P - periodic downloaded static route
Gateway of last resort is not set
R
     10.0.0.0/8 [120/1] via 209.165.200.229, 00:00:06, Serial0/0/0
    172.30.0.0/24 is subnetted, 2 subnets
С
       172.30.1.0 is directly connected, FastEthernet0/0
C
       172.30.2.0 is directly connected, FastEthernet0/1
     209.165.200.0/30 is subnetted, 2 subnets
C
       209.165.200.228 is directly connected, Serial0/0/0
R
       209.165.200.232 [120/1] via 209.165.200.229, 00:00:06, Serial0/0/0
R1#
```

Ctrl+F6 to exit CLI focus

R3 still only shows its own subnets for the 172.30.0.0 network. R3 still does not have any routes for the 172.30.0.0 subnets on R1.

## R3#show ip route

```
R3#
R3#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
* - candidate default, U - per-user static route, o - ODR
P - periodic downloaded static route

Gateway of last resort is not set

R 10.0.0.0/8 [120/1] via 209.165.200.233, 00:00:27, Serial0/0/1
172.30.0.0/16 is variably subnetted, 4 subnets, 2 masks
C 172.30.100.0/24 is directly connected, FastEthernet0/0
C 172.30.100.0/24 is directly connected, Loopback0
C 172.30.200.16/28 is directly connected, Loopback1
C 172.30.200.32/28 is directly connected, Loopback2
209.165.200.0/30 is subnetted, 2 subnets
R 209.165.200.228 [120/1] via 209.165.200.233, 00:00:27, Serial0/0/1
C 209.165.200.232 is directly connected, Serial0/0/1
```

## Use the output of the debug ip rip command to answer the following questions:

## What entries are included in the RIP updates sent out from R3?

```
RIP protocol debugging is on
R3#RIP: received v2 update from 209.165.200.233 on Serial0/0/1
10.0.0.0/8 via 0.0.0.0 in 1 hops
209.165.200.228/30 via 0.0.0.0 in 1 hops
RIP: sending v2 update to 224.0.0.9 via Loopback0 (172.30.110.1)
RIP: build update entries
10.0.0.0/8 via 0.0.0.0, metric 2, tag 0 \,
172.30.100.0/24 via 0.0.0.0, metric 1, tag 0
172.30.200.16/28 via 0.0.0.0, metric 1, tag 0
172.30.200.32/28 via 0.0.0.0, metric 1, tag 0
209.165.200.0/24 via 0.0.0.0, metric 1, tag 0
RIP: sending v2 update to 224.0.0.9 via Loopback1 (172.30.200.17)
RIP: build update entries
10.0.0.0/8 via 0.0.0.0, metric 2, tag 0
172.30.100.0/24 via 0.0.0.0, metric 1, tag 0
172.30.110.0/24 via 0.0.0.0, metric 1, tag 0
172.30.200.32/28 via 0.0.0.0, metric 1, tag 0
209.165.200.0/24 via 0.0.0.0, metric 1, tag 0
RIP: sending v2 update to 224.0.0.9 via Serial0/0/1 (209.165.200.234)
RIP: build update entries
172.30.0.0/16 via 0.0.0.0, metric 1, tag 0 \,
RIP: sending v2 update to 224.0.0.9 via Loopback2 (172.30.200.33)
RIP: build update entries
10.0.0.0/8 via 0.0.0.0, metric 2, tag 0
172.30.100.0/24 via 0.0.0.0, metric 1, tag 0
172.30.110.0/24 via 0.0.0.0, metric 1, tag 0
172.30.200.16/28 via 0.0.0.0, metric 1, tag 0
209.165.200.0/24 via 0.0.0.0, metric 1, tag 0
```

10.0.0.0/8

172.30.100.0/24

172.30.110.0/24

172.30.200.16/28

209.165.200.0/24

#### On R2, what routes are in the RIP updates that are received from R3?

```
RIP protocol debugging is on R2#RIP: sending v2 update to 224.0.0.9 via Serial0/0/1 (209.165.200.233) RIP: build update entries 10.0.0.0/8 via 0.0.0.0, metric 1, tag 0 209.165.200.228/30 via 0.0.0.0, metric 1, tag 0 RIP: sending v2 update to 224.0.0.9 via Serial0/0/0 (209.165.200.229) RIP: build update entries 10.0.0.0/8 via 0.0.0.0, metric 1, tag 0 209.165.200.232/30 via 0.0.0.0, metric 1, tag 0 RIP: received v2 update from 209.165.200.230 on Serial0/0/0 172.30.0.0/16 via 0.0.0.0 in 1 hops RIP: received v2 update from 209.165.200.234 on Serial0/0/1 172.30.0.0/16 via 0.0.0.0 in 1 hops
```

10.0.0.0/8

209.165.200.228/30

172.30.0.0/16

R3 is not sending any of the 172.30.0.0 subnets—only the summarized route of 172.30.0.0/16, including the subnet mask. This is why R2 and R1 are not seeing the 172.30.0.0 subnets on R3.

## Task 6: Disable Automatic Summarization.

The no auto-summary command is used to turn off automatic summarization in RIPv2. Disable auto summarization on all routers. The routers will no longer summarize routes at major network boundaries.

```
R2(config) #router rip
R2(config-router) #no auto-summary
   R2#enable
   R2#config t
   Enter configuration commands, one per line. End with CNTL/Z.
   R2(config) #router rip
   R2(config-router)#no auto-summary
   R2(config-router)#
  Ctrl+F6 to exit CLI focus
R1(config) #router rip
R1(config-router) #no auto-summary
  Rl#config t
  Enter configuration commands, one per line. End with CNTL/Z.
  R1(config) #router rip
  R1(config-router) #no auto-summary
  R1(config-router)#
  Ctrl+F6 to exit CLI focus
R3(config) #router rip
R3(config-router) #no auto-summary
   R3#config t
   Enter configuration commands, one per line. End with CNTL/Z.
   R3(config) #router rip
   R3(config-router) #no auto-summary
   R3(config-router)#
  Ctrl+F6 to exit CLI focus
```

The show ip route and ping commands can be used to verify that automatic summarization is off.

## Task 7: Examine the Routing Tables.

The LANs connected to R1 and R3 should now be included in all three routing tables.

```
R2#show ip route
```

```
R2#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
         E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
         i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
          * - candidate default, U - per-user static route, o - ODR
         P - periodic downloaded static route
Gateway of last resort is not set
      10.0.0.0/16 is subnetted, 1 subnets
          10.1.0.0 is directly connected, FastEthernet0/0
      172.30.0.0/16 is variably subnetted, 7 subnets, 3 masks
172.30.0.0/16 [120/1] via 209.165.200.230, 00:01:57, Serial0/0/0
                             is possibly down, routing via 209.165.200.234, Serial0/0/1
          172.30.1.0/24 [120/1] via 209.165.200.230, 00:00:01, Serial0/0/0 172.30.2.0/24 [120/1] via 209.165.200.230, 00:00:01, Serial0/0/0
          172.30.100.0/24 [120/1] via 209.165.200.234, 00:00:23, Seria10/0/1
          172.30.110.0/24 [120/1] via 209.165.200.234, 00:00:23, Serial0/0/1 172.30.200.16/28 [120/1] via 209.165.200.234, 00:00:23, Serial0/0/1
           172.30.200.32/28 [120/1] via 209.165.200.234, 00:00:23, Serial0/0/1
      209.165.200.0/30 is subnetted, 2 subnets
  --More--
```

Ctrl+F6 to exit CLI focus

#### R1#show ip route

```
R1#
Rl#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
        - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route
Gateway of last resort is not set
     10.0.0.0/8 is variably subnetted, 2 subnets, 2 masks
        10.0.0.0/8 [120/1] via 209.165.200.229, 00:02:57, Serial0/0/0
        10.1.0.0/16 [120/1] via 209.165.200.229, 00:00:10, Serial0/0/0
     172.30.0.0/16 is variably subnetted, 7 subnets, 3 masks
        172.30.0.0/16 [120/2] via 209.165.200.229, 00:02:57, Serial0/0/0
        172.30.1.0/24 is directly connected, FastEthernet0/0
        172.30.2.0/24 is directly connected, FastEthernet0/1
        172.30.100.0/24 [120/2] via 209.165.200.229, 00:00:10, Serial0/0/0
        172.30.110.0/24 [120/2] via 209.165.200.229, 00:00:10, Serial0/0/0
        172.30.200.16/28 [120/2] via 209.165.200.229, 00:00:10, Serial0/0/0
        172.30.200.32/28 [120/2] via 209.165.200.229, 00:00:10, Serial0/0/0
     209.165.200.0/30 is subnetted, 2 subnets
  -More--
```

Ctrl+F6 to exit CLI focus


### R3#show ip route

```
R3#
R3#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route
Gateway of last resort is not set
     10.0.0.0/8 is variably subnetted, 2 subnets, 2 masks
        10.0.0.0/8 is possibly down, routing via 209.165.200.233, Serial0/0/1
        10.1.0.0/16 [120/1] via 209.165.200.233, 00:00:00, Serial0/0/1
R
     172.30.0.0/16 is variably subnetted, 6 subnets, 2 masks
R
        172.30.1.0/24 [120/2] via 209.165.200.233, 00:00:00, Serial0/0/1
        172.30.2.0/24 [120/2] via 209.165.200.233, 00:00:00, Serial0/0/1
R
С
        172.30.100.0/24 is directly connected, FastEthernet0/0
        172.30.110.0/24 is directly connected, Loopback0
        172.30.200.16/28 is directly connected, Loopback1
        172.30.200.32/28 is directly connected, Loopback2
     209.165.200.0/30 is subnetted, 2 subnets
       209.165.200.228 [120/1] via 209.165.200.233, 00:00:00, Serial0/0/1
```

Ctrl+F6 to exit CLI focus


Use the output of the **debug** ip rip command to answer the following questions:

What entries are included in the RIP updates sent out from R1?



172.30.1.0/24 172.30.2.0/24

On R2, what routes are in the RIP updates that are received from R1?




172.30.1.0/24 172.30.2.0/24

Are the subnet masks now included in the routing updates? \_\_yes\_\_\_\_


## **Task 8: Verify Network Connectivity.**

Step 1: Check connectivity between R2 router and PCs.

From R2, how many ICMP messages are successful when pinging PC1? 5/5 messages



From R2, how many ICMP messages are successful when pinging PC4? 5/5 messages



## Step 2: Check the connectivity between the PCs.

From PC1, is it possible to ping PC2? yes

What is the success rate? 4/4

From PC1, is it possible to ping PC3? yes

What is the success rate? 4/4

## From PC1, is it possible to ping PC4? yes


What is the success rate? 4/4

From PC4, is it possible to ping PC2? yes

What is the success rate? 4/4

## From PC4, is it possible to ping PC3? yes

What is the success rate? 4/4



## **Task 9: Documentation**

On each router, capture the following command output to a text (.txt) file and save for future reference.

## Router - R1

#### show running-config

```
spanning-tree mode pvst
interface FastEthernet0/0
ip address 172.30.1.1 255.255.255.0
duplex auto
speed auto
interface FastEthernet0/1
ip address 172.30.2.1 255.255.255.0
duplex auto
speed auto
interface Serial0/0/0
ip address 209.165.200.230 255.255.255.252
interface Serial0/0/1
no ip address
clock rate 2000000
shutdown
interface Vlan1
no ip address
shutdown
router rip
version 2
passive-interface FastEthernet0/0
passive-interface FastEthernet0/1
network 172.30.0.0
network 209.165.200.0
no auto-summary
ip classless
ip flow-export version 9
line con 0
line aux 0
line vty 0 4
password cisco
login
end
```

## • show ip route

```
R1#sh ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
* - candidate default, U - per-user static route, o - ODR
P - periodic downloaded static route
Gateway of last resort is not set
10.0.0.0/16 is subnetted, 1 subnets
R 10.1.0.0 [120/1] via 209.165.200.229, 00:00:18, Serial0/0/0
172.30.0.0/16 is variably subnetted, 6 subnets, 2 masks
C 172.30.1.0/24 is directly connected, FastEthernet0/0 C 172.30.2.0/24 is directly connected, FastEthernet0/1
R 172.30.100.0/24 [120/2] via 209.165.200.229, 00:00:18, Serial0/0/0
R 172.30.110.0/24 [120/2] via 209.165.200.229, 00:00:18, Serial0/0/0
R 172.30.200.16/28 [120/2] via 209.165.200.229, 00:00:18, Serial0/0/0
R 172.30.200.32/28 [120/2] via 209.165.200.229, 00:00:18, Serial0/0/0
209.165.200.0/30 is subnetted, 2 subnets
C 209.165.200.228 is directly connected, Serial0/0/0 \,
R 209.165.200.232 [120/1] via 209.165.200.229, 00:00:18, Serial0/0/0
```

#### • show ip interface brief

R1#sh ip interface brief

Interface	IP-Address	OK?	Method	Status	Protocol
FastEthernet0/0	172.30.1.1	YES	manual	up	up
FastEthernet0/1	172.30.2.1	YES	manual	up	up
Serial0/0/0	209.165.200.230	)YES	manual	up	up
Serial0/0/1	unassigned	YES	NVRAM	administratively down	down

• Vlan1 unassigned YES unset administratively down down

#### show ip protocols

```
R1#sh ip protocols
Routing Protocol is "rip"
Sending updates every 30 seconds, next due in 24 seconds
Invalid after 180 seconds, hold down 180, flushed after 240
Outgoing update filter list for all interfaces is not set
Incoming update filter list for all interfaces is not set
Redistributing: rip
Default version control: send version 2, receive 2
Interface Send Recv Triggered RIP Key-chain
Serial0/0/0 2 2
Automatic network summarization is not in effect
Maximum path: 4
Routing for Networks:
172.30.0.0
209.165.200.0
Passive Interface(s):
FastEthernet0/0
FastEthernet0/1
Routing Information Sources:
Gateway Distance Last Update
209.165.200.229 120 00:00:03
Distance: (default is 120)
```

#### Router - R2

#### • show running-config

```
R2#sh running-config
Building configuration...

Current configuration : 867 bytes
!
version 12.4
no service timestamps log datetime msec
no service timestamps debug datetime msec
no service password-encryption
!
hostname R2
```

```
no ip cef
no ipv6 cef
spanning-tree mode pvst
\verb|interface| FastEthernet0/0|
ip address 10.1.0.1 255.255.0.0
duplex auto
speed auto
\verb|interface| FastEthernet0/1|
no ip address
duplex auto
speed auto
shutdown
interface Serial0/0/0
ip address 209.165.200.229 255.255.255.252
clock rate 2000000
interface Serial0/0/1
ip address 209.165.200.233 255.255.255.252
clock rate 64000
interface Vlan1
no ip address
shutdown
router rip
{\tt version}\ 2
passive-interface FastEthernet0/0
network 10.0.0.0
network 209.165.200.0
no auto-summary
ip classless
ip flow-export version 9
line con 0
line aux 0
line vty 0 4
password cisco
```

```
login!!
```

#### • show ip route

```
R2#sh ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
* - candidate default, U - per-user static route, o - ODR
P - periodic downloaded static route
Gateway of last resort is not set
10.0.0.0/16 is subnetted, 1 subnets
C 10.1.0.0 is directly connected, FastEthernet0/0
172.30.0.0/16 is variably subnetted, 6 subnets, 2 masks
R 172.30.1.0/24 [120/1] via 209.165.200.230, 00:00:10, Serial0/0/0
R 172.30.2.0/24 [120/1] via 209.165.200.230, 00:00:10, Serial0/0/0
R 172.30.100.0/24 [120/1] via 209.165.200.234, 00:00:19, Serial0/0/1
R 172.30.110.0/24 [120/1] via 209.165.200.234, 00:00:19, Serial0/0/1
R 172.30.200.16/28 [120/1] via 209.165.200.234, 00:00:19, Serial0/0/1
R 172.30.200.32/28 [120/1] via 209.165.200.234, 00:00:19, Serial0/0/1
209.165.200.0/30 is subnetted, 2 subnets
C 209.165.200.228 is directly connected, Serial0/0/0
C 209.165.200.232 is directly connected, Serial0/0/1
```

#### • show ip interface brief

R2#sh ip int brief

Interface	IP-Address	OK?	Method	Status		Protoc	ol
FastEthernet0/0	10.1.0.1	YES	manual	up		up	
FastEthernet0/1	unassigned	YES	NVRAM	administ	ratively down	down	
Serial0/0/0	209.165.200.229	YES	manual	up		up	
Serial0/0/1	209.165.200.233	YES	manual	up		up	
• Vlan1	unassign	ed	YES	unset a	administratively	down	dow

## • show ip protocols

```
R2#sh ip protocols
Routing Protocol is "rip"
Sending updates every 30 seconds, next due in 18 seconds
Invalid after 180 seconds, hold down 180, flushed after 240
Outgoing update filter list for all interfaces is not set
Incoming update filter list for all interfaces is not set
Redistributing: rip
Default version control: send version 2, receive 2
Interface Send Recv Triggered RIP Key-chain
Serial0/0/0 2 2
Serial0/0/1 2 2
Automatic network summarization is not in effect
Maximum path: 4
Routing for Networks:
10.0.0.0
209.165.200.0
Passive Interface(s):
FastEthernet0/0
Routing Information Sources:
Gateway Distance Last Update
209.165.200.230 120 00:00:09
209.165.200.234 120 00:00:13
Distance: (default is 120)
```

#### Router - R3

#### • show running-config

R3#sh running-config Building configuration...

```
Current configuration: 1027 bytes
version 12.4
no service timestamps log datetime msec
no service timestamps debug datetime msec
no service password-encryption
hostname R3
no ip cef
no ipv6 cef
spanning-tree mode pvst
interface Loopback0
ip address 172.30.110.1 255.255.255.0
interface Loopback1
ip address 172.30.200.17 255.255.255.240
interface Loopback2
ip address 172.30.200.33 255.255.255.240
interface FastEthernet0/0
ip address 172.30.100.1 255.255.255.0
duplex auto
speed auto
interface FastEthernet0/1
no ip address
duplex auto
speed auto
shutdown
interface Serial0/0/0
no ip address
clock rate 2000000
shutdown
interface Serial0/0/1
ip address 209.165.200.234 255.255.255.252
interface Vlan1
no ip address
shutdown
router rip
version 2
passive-interface FastEthernet0/0
network 172.30.0.0
network 209.165.200.0
no auto-summary
```

```
!
ip classless
!
ip flow-export version 9
!
!
!
!
!
!
!
!
line con 0
!
line aux 0
!
line vty 0 4
password cisco
login
!
!
!
end
```

#### • show ip route

```
R3#sh ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
* - candidate default, U - per-user static route, o - ODR
P - periodic downloaded static route
Gateway of last resort is not set
10.0.0.0/16 is subnetted, 1 subnets
R 10.1.0.0 [120/1] via 209.165.200.233, 00:00:04, Serial0/0/1
172.30.0.0/16 is variably subnetted, 6 subnets, 2 masks
R 172.30.1.0/24 [120/2] via 209.165.200.233, 00:00:04, Serial0/0/1
R 172.30.2.0/24 [120/2] via 209.165.200.233, 00:00:04, Serial0/0/1
C 172.30.100.0/24 is directly connected, FastEthernet0/0 \,
C 172.30.110.0/24 is directly connected, Loopback0
C 172.30.200.16/28 is directly connected, Loopback1
C 172.30.200.32/28 is directly connected, Loopback2
209.165.200.0/30 is subnetted, 2 subnets
R 209.165.200.228 [120/1] via 209.165.200.233, 00:00:04, Serial0/0/1
```

• C 209.165.200.232 is directly connected, Serial0/0/1

#### • show ip interface brief

R3#sh ip interface brief									
Interface	IP-Address	OK?	Method	Status		Protocol			
FastEthernet0/0	172.30.100.1	YES	manual	up		up			
FastEthernet0/1	unassigned	YES	NVRAM	administratively	down	down			
Serial0/0/0	unassigned	YES	NVRAM	administratively	down	down			
Serial0/0/1	209.165.200.234	YES	manual	up		up			
Loopback0	172.30.110.1	YES	manual	up		up			
Loopback1	172.30.200.17	YES	manual	up		up			
Loopback2	172.30.200.33	YES	manual	up		up			
Vlan1	unassigned	YES	unset	administratively	down	down			

#### • show ip protocols


```
R3#sh ip protocols
Routing Protocol is "rip"
Sending updates every 30 seconds, next due in 13 seconds
Invalid after 180 seconds, hold down 180, flushed after 240
Outgoing update filter list for all interfaces is not set
Incoming update filter list for all interfaces is not set
Redistributing: rip
Default version control: send version 2, receive 2
Interface Send Recv Triggered RIP Key-chain
Loopback0 2 2
```


```
Loopback1 2 2
Loopback2 2 2
Serial0/0/1 2 2
Automatic network summarization is not in effect
Maximum path: 4
Routing for Networks:
172.30.0.0
209.165.200.0
Passive Interface(s):
FastEthernet0/0
Routing Information Sources:
Gateway Distance Last Update
209.165.200.233 120 00:00:19
Distance: (default is 120)
```


## Task 10: Clean Up

Erase the configurations and reload the routers. Disconnect and store the cabling. For PC hosts that are normally connected to other networks (such as the school LAN or to the Internet), reconnect the appropriate cabling and restore the TCP/IP settings.

Since there is no PC host which are connected to other networks, we disconnect cabling and reload the routers after erasing the configurations







Hence, we have Erased all configurations and disconnected and stored the cables.