

## **PAM Administration**

Troubleshooting





## Agenda

By the end of this session, you will be able to:

- Describe the basic flow for troubleshooting issues in the CyberArk environment
- Describe, locate, and manage the log files generated by the Vault and various components
- Describe, configure and use the xRay agent

## Troubleshooting Flow

3

cyberark.com ——————————————

## Overview

The basic troubleshooting methodology for the PAM solution requires a thorough understanding of:

- Your system implementation
- How components communicate with each other in your environment
- What is the current behavior compared to the expected behavior?



This methodology is designed to provide guidance and might not apply to every scenario

It is important to write down any information gathered during this process and any tests performed, as all of this information will be required when opening a case with <a href="CyberArk">CyberArk</a> support


## Prerequisites

- Knowledge of the environment layout
- Access to the different servers
- Access to CyberArk Knowledgebase (Customer Community)
- Access to CyberArk documentation (publicly available online)


The latest version of the documentation will contain the most recent enhancements and notes.




## Troubleshooting Flow



## Understanding the Environment




## **Initial Questions**



Reproducible?

## Isolation and Reproduction



- Modify a variable and try to reproduce again.
- Repeat in different scenarios
- Write down each scenario and the outcome of the test
- Review the logs of reproduced scenarios (working and not working)

#### Not reproducible

Review the logs relevant for the reported flow


questions Check documentation and knowledgebase Contact Support

Follow-up


9



## Checking the Logs



- Log location
- Log types
- Log correlation




10




Follow-up


## Follow-Up Questions




## Documentations and Knowledge Base



## Contacting CyberArk Support



- User experience?
- Did it work in the past?
- Are there any error messages?
- Flow, current and expected behavior?
- Troubleshooting steps?
- Steps to reproduce this issue?
- All relevant logs, screenshots and configuration files




logs


# Troubleshooting Flow: Example




 A user is unable to login to the PrivateArk client using the administrator user.
 They see the following message.




#### Understand the Environment



## **Initial Questions**




## Isolation and Reproduction






## Checking the Logs



Trace.d0


## Check Messages and Responses

Try to identify the problem by searching in the **Messages and Responses** page in on the online documentation



## Check Messages and Responses

Messages displayed to end users are intentionally generic, listing many possible causes.



## Check Messages and Responses

Because the error message starts with ITA, we know that the Vault server originated this error.

- At this point we will go to the Vault server and inspect the ITA log.
- There may be multiple log entries for the same problem.
- Try to find the first entry related to this problem
- When looking at the ITA log, we see an error message ITATS528E with a code of 66
- When we search for that error, we see the exact cause of the problem and the solution.

12:42:26

ITATS528E athentication failure for user administrator from station: 10.10.10.10

ITAT\$528E Authentication failure for User <username> from station <station> (Code: <code>).


#### Recommended Action:

This authentication failure could be due to one of several reasons, depending on the code that is displayed:

- Code 66 The specified password is incorrect. Specify the correct password or change it using the Change Password option.
- Code 76 The server tried to send data to the client, but failed.
- Code 77 The server requires specific data from the client, but did not receive it
- Code 84 The NT Authentication ticket that was used to authenticate has expired. Verify that the times set on the Vault and the NT Authentication Agent machines are synchronized.
- Code 108 LDAP connection failed due to either the wrong user or password. Specify the correct credentials, then try to authenticate again.
- Code 109 The user's DN LDAP directory does not exist in the Vault. Verify that the directory is configured in the Vault server and has authentication usage.
- Code 110 The user was not found in the LDAP directory. Verify that the user exists in the directory under the directory base context that was configured in the directory configuration file.




## Solution





#### **Problem Not Resolved**





In this section we will discuss the logs generated by the various system components, how to set the debug mode, and the logs location







## Types of Logs

#### Log files are divided into several types:



Provides component-level entries such as service up or down



Provides detailed entries of workflows related to that component



Exists in some components, and will include only error entries



Those logs may come in different types, sometimes they will be the trace files, with additional information and sometimes they will come at a form of separate files depending on the component.



For the full list of log locations please see the implementation guide



27

## Understanding CyberArk Logs

The log message code is built from four segments

for example:

Firewall is open for client communication

**ITA** – The source component of the message is the **Vault** server

**FW** – The module with the message is the **Vault** FW

**001** – Message number

I – The message category

Error:

Log messages are separated into four major categories:

Informational:

**ITAFW001I** Firewall is open for client communication **ITATS691E** *LDAP* synchronization error

Warning: System:

**ITATS319W** Firewall contains external rules **ITADB367S** Server unable to communicate with firewall

See CyberArk Messages and Responses for additional information

## Reviewing the Logs

Once we get to a point where we need to go over log files, there are a number of questions to ask:

- Which log file do we need to review?
- What do we search for?
  - Keywords (Error, Failed, Failure...)
  - Timestamps
  - User name
  - Object name (Account name, safe name)
- Are there correlated entries in other logs?
  - Log events and time of the issue
  - Different components
  - CyberArk logs and OS logs




Debug Mode and Log Location



20

# Set the Debug Mode for the Vault ITAlog

- The Vault debug levels can be changed in the dbparmi.ini file (requires a restart)
- The Vault debug levels can be changed without a restart using the PARclient or Central Administration Station



```
C:\CyberArkInstallationFiles\Version 9.8\Remote Control Client>PARClient.

Cyber-Ark Remote Administration Client (9.80.3.0)


Working with agent on: 192.168.202.129

Loaded component from [C:\CyberArkInstallationFiles\Version 9.8\Remote CoLoaded component from [C:\CyberArkInstallationFiles\Ver
```



## Set the Debug Mode for the Components

Debug mode for components can be set in the configuration files stored on the **Vault** or via the **PVWA** Web UI



# Log Locations and Configuring the Debug Levels

- Detailed information about setting debug level for different components and location of the log files can be found in the online documentation
- Setting Vault log levels to Debug should only be done under the guidance of CyberArk Support

Home > Administration > References > Configure Debug Levels X Highlights Configure Debug Levels > Privileged Accounts The following tables list the configuration files per component of the Privileged Access Security > Components solution, specify how to set the debug mode, and give the location of the log files for each component. Monitor system health > Utilities ∨ References Digital Vault 🔗 > Configure the system through PVWA Vault Vault Specifications > PARAgent > Disaster Recovery Vault Vault Audit Action Codes > PAReplicate Safe Settings > PrivateArk Client Wildcard Definitions > Event Notification Engine > Configuration Files Cluster Vault (CVM) **Configure Debug Levels** ExportVaultData > Vault Activity Email Notification > Messages and Responses

## Cheat Sheet – Vault and Related Components

| Vault              | Changes Require a Vault Restart                    |                    |           | Ene                | Event Notification Engine   |
|--------------------|--|--------------------|-----------|--------------------|---|
| Configuration File | DBParm.ini   |                    |           | Configuration File | \Program Files\PrivateArk\Server\Event Notification Engine\ENEConf.ini  |
|                    | \Database\my.ini Database Configuration File       |                    |           |                    | Vault →Safe:"Notification Engine"→root\EventNotificationEngine.ini  |
|                    | , ,  |                    |           | Debug              | EventNotificationEngine.ini   |
| Debug              | DebugLevel=PE(1),PERF(1) - Detailed Vault services | debug              |           |                    | [Debug]   |
|                    | LDAP(14,15) - Detailed LDAP debug                  | Disaster Recover   | v         |                    | <ul> <li>ControllerDebugLevel=1,2,3,4</li> <li>CollectorDebugLevel=1,2</li> <li>ParserDebugLevel=1,2</li> </ul> |
| Logs               | Italog.log   | Configuration File | PADR.ini  |                    | <ul> <li>SMTPSenderDebugLevel=1,2</li> <li>ConfigurationManagerDebugLevel=1,2</li> </ul>                        |
|                    | Trace.dX (X is a number from 0 to 4)               | Debug              | EnableTra | ice=yes            | ProgramFiles\PrivateArk\Server\EventNotification Engine\Logs\ENEConsole.log                                     |
|                    | \Database\VaultDB.log - Database log               | Logs               | PADR.log  |                    | ProgramFiles\PrivateArk\Server\EventNotification Engine\Logs\ENETrace.log                                       |

|         | <u> </u> | 4      |     |
|---------|----------|--------|-----|
| IIC.    | Con      | taine  | יוב |
| <br>100 | 9011     | Callin | -   |

| File Name | LogicContainer.Log |
|-----------|--------------------|
|-----------|--------------------|

Logs C:\ProgramFiles (x86)\PrivateArk\Server|LogicContainer\LogicContainer.log

| PAReplicate | Backup and Restore  |
|-------------|---|
| Debug       | In the PAReplicate.exe command executed, add the following flag: /EnableTrace |
| Logs        | PAReplicate.log   |
|             |   |

| Client       | Run –PAInfo.exe   |
|--------------|---|
| Debug        | In the Client:  |
|              | Tools → Options → Advanced → Log Configuration  |
| Logs (Win XI | P and Win 2003  |
|              | \Documents and Settings\ <user>\Application Data\CyberArk\PrivateArk\PALog.txt</user> |
| Logs (Win7   | and Win 2008  |
|              | \Users\ <user>\AppData\Roaming\CyberArk\PrivateArk</user>                             |
|              |   |

## Cheat Sheet – Components

| СРМ                | Central Password Manager  |
|--------------------|---|
| Configuration File | Vault → Safe "Password Manager"→ root\policies\ <policy>.ini</policy>   |
| Debug              | PVWA → Administration Tab → CPM settings  |
|                    | CPMDebugLevels=2 (default)  0 – No messages will be written to the trace log.  1 – CPM exceptions will be written to the trace log (Default Level)  2 – CPM trace messages will be written to the trace log.  3 – CPM CASOS activities will be written to the trace log.  4 – CPM CASOS debug activities will be written to the trace log.  5 – CPM CASOS errors will be written to the trace log.  6 – All CPM CASOS activities and errors will be written to the trace log. |
| Logs - CPM         | \Program Files\CyberArk\PasswordManager\Logs\pm.log \Program Files\CyberArk\PasswordManager\Logs\pm-error.log\Program Files\CyberArk\PasswordManager\Logs\PMConsole.log\Program Files\CyberArk\PasswordManager\Logs\PMTrace.log   |
| Logs -Plug-ins     | \Program Files\CyberArk passwordManager\Logs\ThirdParty\*.log   |

| PSM                          | Privileged Session Manager   |
|------------------------------|--|
| Configuration File           | \Program Files\CyberArk\PSM\Basic_psm.ini  |
|                              | PVWA → Administration Tab → Options → Privileged Session Management  |
| Debug                        | PVWA → System tab → Options → Privileged Session Management → General Settings   |
|                              | Server Settings → TraceLevels=1,2,3,4,5,6,7  Recorder settings → TraceLevels=1,2  Connection Client Settings → TraceLevels=1,2   |
| Logs                         | <pre><installation folder="">\Logs (and subfolders) or according to parameter "LogsFolder" (located in Basic_psm.ini file)</installation></pre>  |
| PVWA                         | Password Vault Web Access  |
|                              | 1 d33Word Vadit Web Access   |
| Configuration File           | \www.root\PasswordVault\web.config   |
| Configuration                |  |
| Configuration                | \wwwroot\PasswordVault\web.config  |
| Configuration                | \www.root\PasswordVault\web.config  Vault → Safe "PVWAConfig" → root\PVConfiguration.xml   |
| Configuration<br>File        | \wwwroot\PasswordVault\web.config  Vault → Safe "PVWAConfig" → root\PVConfiguration.xml  Vault → Safe "PVWAConfig" → root\Policies.xml   |
| Configuration<br>File        | \wwwroot\PasswordVault\web.config  Vault → Safe "PVWAConfig" → root\PVConfiguration.xml  Vault → Safe "PVWAConfig" → root\Policies.xml  PVWA → Administration Tab →Options → Logging   |
| Configuration<br>File        | \wwwroot\PasswordVault\web.config  Vault → Safe "PVWAConfig" → root\PVConfiguration.xml  Vault → Safe "PVWAConfig" → root\Policies.xml  PVWA → Administration Tab →Options → Logging  DebugLevel=High (options are None/High/Low/Profiling)  |
| Configuration<br>File  Debug | \wwwroot\PasswordVault\web.config  Vault → Safe "PVWAConfig" → root\PVConfiguration.xml  Vault → Safe "PVWAConfig" → root\Policies.xml  PVWA → Administration Tab →Options → Logging  DebugLevel=High (options are None/High/Low/Profiling)  InformationLevel=High (options are None/High/Low/Profiling)                 |
| Configuration<br>File  Debug | \wwwroot\PasswordVault\web.config  Vault → Safe "PVWAConfig" → root\PVConfiguration.xml  Vault → Safe "PVWAConfig" → root\Policies.xml  PVWA → Administration Tab →Options → Logging  DebugLevel=High (options are None/High/Low/Profiling)  InformationLevel=High (options are None/High/Low/Profiling)  %windir%\temp\ |

## xRay Agent

In this section we will discuss the CyberArk xRay utility, which can be used to collect log and configuration files from the CyberArk components and share them with CyberArk or partner support


#### Overview

- CyberArk xRay collects logs and configuration files from PAM components in a simple, single-step process
- The utility can be run from a remote machine or on any of the CyberArk servers
- All data files are encrypted during collection, regardless of whether they are collected locally or remotely, and then transferred back to the xRay machine
- You can share the collected data with your partner or CyberArk, knowing that it is safely encrypted during transfer
- When sharing with CyberArk, shared data is linked to a case to allow Enterprise Support easy and secure access to the collected data
- The utility can be downloaded from the <u>CyberArk Marketplace</u>



## Agent Setup


- Select the component
- Select time frame for the collection and collection level.
- Select Collection scope
  - Logs from OS and the application
  - Logs from application only
- Optionally, enable and provide the Active Vault IP address and Administrative user credentials for configuration files collection
- Agree to the Terms of Use and click Start Collection





## **Monitor Collection Process**


You can monitor the collection process as it collects the component files





## Share the Collected Data


- Once the process is complete, you can select whether to:
  - Share the collected data with your Partner
  - Share the collected data with CyberArk
- You can also preview the data before sending
- When sharing information with CyberArk, make sure you have:
  - A Technical Community account
  - Case number





#### **Documentation**

#### Additional information can be found in the **CyberArk documentation**







42

## Summary

In this session we covered:



How locate and manage the log files generated by the Vault and various components

How to configure and use the xRay agent



## Additional Resources



#### **Utilities**

<u>xRay</u>

(login required)



#### **Community Resources**

CyberArk Customer Community (login required)

CyberArk Subreddit\*



#### **Online Training:**

Working with CyberArk Support:

https://training.cyberark.com/elearning/workingwith-cyberark-support

\* **Note:** The CyberArk subreddit is not hosted or moderated by CyberArk.

