# Programming Languages (8) Rust Memory Management

Kenjiro Taura

#### Contents

Overview

Rust basics

Owning pointers

Assignments of owning pointers Box<T> type

Borrowing pointers (&T)

Borrow checking details

Summary

#### Contents

#### Overview

Rust basics

Owning pointers
Assignments of owning pointers
Box<T> type

Borrowing pointers (&T)


Borrow checking details

Summary

## Rust's basic idea to memory management

- ▶ Rust maintains that, for any live object,
  - 1. there is one and only one pointer that "owns" it (the owner pointer)
  - 2. "multiple borrowers": there are arbitrary number of non-owning pointers (borrowing pointers) pointing to it, but they cannot be dereferenced after the owning pointer goes away
- ► ⇒ it can safely reclaim the data when the owning pointer goes away

"single-owner-multiple-borrowers rule"



## The rules are enforced statically

- ► Rust maintains the rule *statically* (as opposed to *dynamically*)
- equivalently,
  - ► compile-time rather than at runtime
  - before execution not during execution

called borrow checker

## Ways outside the basic rules

to be sure, there are some ways to get around the rules

- 1. reference counting pointers ( $\approx$  multiple owning pointers)
  - counts the number of owners *at runtime*, and reclaim the data when all these pointers are gone
- 2. unsafe/raw pointers ( $\approx$  totally up to you) they are not specific to Rust, and we'll not cover them in the rest of this slide deck

#### Contents

Overview

#### Rust basics

Owning pointers
Assignments of owning pointers
Box<T> type

Borrowing pointers (&T)

Borrow checking details

Summary

# Pointer-like data types in Rust

given a type T (i32, struct, enum, ...), below are types representing "references (pointers) to T" <sup>1</sup>

- 1. T: owning pointer to T
- 2. BoxT> (box T): owning pointer to T
- 3. &T (pronounced "ref T"): borrowing pointer to data of T (through which you cannot modify it)
- 4. Rc < T > and Arc < T >: shared (reference-counting) owning pointer to T
- 5. \*T: unsafe pointer to T

following discussions are focused on T, Box<T> and &T.



<sup>&</sup>lt;sup>1</sup>we use pointers and references interchangeably

## Pointer-making expressions

given an expression e of type T, below are expressions that make pointers to the value of e

- 1. e (of type T): an owning pointer
- 2. Box::new(e) (of type Box<T>): an owning pointer
- 3. &e (of type &T): a borrowing pointer

# An example

- ▶ note: type of variables can be omitted (spelled out for clarity)
- ▶ note: the above program violates several rules so it does not compile

#### Contents

Overview

Rust basics

Owning pointers
Assignments of owning pointers
Box<T> type

Borrowing pointers (&T)

Borrow checking details

Summary

```
x = y;
             // y can no longer be used
   e.g.,
fn foo() {
  let a = S\{x: ..., y: ...\};
  \dots a.x \dots; // OK, as expected
  ... a.y ...; // OK, as expected
  // the reference moves out from a
  let b = a;
```

```
x = y;
             // y can no longer be used
   e.g.,
fn foo() {
  let a = S\{x: ..., y: ...\};
  \dots a.x \dots; // OK, as expected
  ... a.y ...; // OK, as expected
  // the reference moves out from a
  let b = a;
  a.x; // NG, the value has moved out
  b.x; // OK
```

# Argument-passing also moves the reference

passing a value to a function also moves the reference out of the source

```
fn foo() {
  let a = S{x: ..., y: ...};
  ... a.x ...; // OK, as expected
  ... a.y ...; // OK, as expected
}
```

# Argument-passing also moves the reference

passing a value to a function also moves the reference out of the source

```
fn foo() {
  let a = S{x: ..., y: ...};
  ... a.x ...; // OK, as expected
  ... a.y ...; // OK, as expected
  // moves the reference out of a
  f(a);
  a.x; // NG, the reference has moved
}
```

# Note: exceptions to "assignment moves the reference"

```
> you may think the moving assignment
         x = y;
         // y can no longer be used
   contradicts what you have seen
▶ does it apply to a primitive type, say f64?
   fn foo() {
     let a = 123.456;
     // does the reference to 123.456 move out from a!?
     let b = a;
     a + 0.789; // if so, is this invalid!?
```

- answer: no, it does *not* apply to primitive types like i32, f64, etc.
- $\blacktriangleright$  a more general answer: it does not apply to data types that implement Copy trait

#### Copy trait

▶ define your struct with #[derive(Copy, Clone)] like

```
#[derive(Copy, Clone)]
struct S { ... }
```

▶ and assignment or argument-passing of S makes a copy of the righthand side

```
fn foo() {
  let a = S{x: ..., y: ...};
  a.x; // OK, as expected
  a.y; // OK, as expected
```


## Copy trait

▶ define your struct with #[derive(Copy, Clone)] like

```
#[derive(Copy, Clone)]
struct S { ... }
```

▶ and assignment or argument-passing of S makes a copy of the righthand side

```
fn foo() {
  let a = S{x: ..., y: ...};
  a.x; // OK, as expected
  a.y; // OK, as expected
  // the value is copied
  let b = a;
```




## Copy trait

▶ define your struct with #[derive(Copy, Clone)] like

```
#[derive(Copy, Clone)]
struct S { ... }
```

▶ and assignment or argument-passing of S makes a copy of the righthand side

```
fn foo() {
  let a = S{x: ..., y: ...};
  a.x; // OK, as expected
  a.y; // OK, as expected
  // the value is copied
  let b = a;
  a.x; // OK
  b.x; // OK, too
}
```



## Copy types and the single-owner rule

- ▶ when a copy is made on every assignment or argument passing, the single-owner rule is trivially maintained
- ▶ below, we will only discuss types not implementing Copy trait (non-Copy types)

```
fn foo() {
  let a = S{x: ..., y: ...};
  a.x; // OK, as expected
  a.y; // OK, as expected
```



```
fn foo() {
  let a = S{x: ..., y: ...};
  a.x; // OK, as expected
  a.y; // OK, now o is the owning pointer
  let b = Box::new(a)
```

```
fn foo() {
  let a = S{x: ..., y: ...};
  a.x; // OK, as expected
  a.y; // OK, as expected
  // OK, now o is the owning pointer
  let b = Box::new(a)
  a.x; // NG, the value has moved out
```

```
fn foo() {
  let a = S{x: ..., y: ...};
  a.x; // OK, as expected
  a.y; // OK, as expected
  // OK, now o is the owning pointer
  let b = Box::new(a)
  a.x; // NG, the value has moved out
  (*b).x; // OK
}
```

```
fn foo() {
  let a = S{x: ..., y: ...};
  a.x; // OK, as expected
  a.y; // OK, as expected
  // OK, now o is the owning pointer
  let b = Box::new(a)
  a.x; // NG, the value has moved out
  (*b).x; // OK
  b.x; // OK. abbreviation of (*b).x
}
```

#### Note: difference between T and Box<T>?

► as you have seen, the effect of


```
1 let b = a;
and
1 let b = Box::<T>::new(a);
```

look identical

- ▶ as far as data lifetime is concerned, it is in fact safe to think T and Box::< T> are identical
- ▶ Rust have the distinction for
  - specifying data layout
  - ▶ specifying where data are allocated (stack vs. heap)

## Data layout differences between T and Box::< T>


- ▶ S and U below have different data layouts
  - ightharpoonup struct S { ..., p:T, } "embeds" a T into S
  - ▶ struct U  $\{\ldots, p:Box::<T>, \}$  has p point to a separately allocated T



- ▶ in particular, Box::<T> is essential to define recursive data structures
  - ▶ struct S { ..., p:S, } is not allowed, whereas
  - ▶ struct U { ..., p:Box::<U>, } is

## Data layout differences between T and Box::< T>


➤ the distinction is insignificant when discussing lifetimes



- ▶ in both cases, p (yellow box) is gone exactly when the enclosing structure is gone
- ▶ Rust spec also says it allocates T on stack and move it to heap when Box<T> is made
- ightharpoonup again, it has nothing to do with lifetime (unlike C/C++)

# A (huge) implication of the single-owner rule

- $\blacktriangleright$  with only owning pointers (T and Box<T>),
  - ightharpoonup you can make a tree of T,
  - but you cannot make a general graph of T (acyclic or cyclic), where a node may be pointed to by multiple nodes
- ightharpoonup if you want to make a graph of T, you use either
  - ightharpoonup &T to represent edges, or
  - ► Vec<T> to represent nodes and Vec<(i32,i32)> to represent edges






# The (huge) implication to memory management

- assume there are only owning pointers for now (forget about borrowing pointers)
- when
  - ▶ a variable of owning pointer type goes out of scope or
  - ▶ a variable or field of owning pointer type is overwritten,

the entire tree rooted from the pointer can be safely reclaimed



#### Contents

Overview

Rust basics

Owning pointers
Assignments of owning pointers
Box<T> type

Borrowing pointers (&T)

Borrow checking details

Summary

#### Basics

- you can make a borrowing pointer to T (&T) from T or Box<T>
- ▶ both the owning pointer and borrowing pointers can be used

```
1 let a = S{x: ..., y: ...};
2 let b = &a;
3 ... a.x + b.x ... // OK
```

▶ the issue is how to prevent a program from dereferencing borrowing pointers after its owning pointer is gone

#### Borrowers rule in action

▶ a borrowing pointer cannot be dereferenced after its owning pointer is gone

```
fn foo() -> i32 {
  let c: &S; // a reference to S
  { // an inner block
```

```
}
```

c: &S

#### Borrowers rule in action

▶ a borrowing pointer cannot be dereferenced after its owning pointer is gone

```
fn foo() -> i32 {
  let c: &S; // a reference to S
  { // an inner block
   let b: &S; // another reference
```

```
}
}
```

c: &S

b: &S


▶ a borrowing pointer cannot be dereferenced after its owning pointer is gone

```
fn foo() -> i32 {
  let c: &S; // a reference to S
  { // an inner block
   let b: &S; // another reference
   let a = S{x: ...}; // allocate S
}
```


c : &S

b: &S

```
fn foo() -> i32 {
  let c: &S; // a reference to S
  { // an inner block
   let b: &S; // another reference
   let a = S{x: ...}; // allocate S
   // OK (both a and b live only until the end of the inner block)
   b = &a;
}
```



```
fn foo() -> i32 {
  let c: &S; // a reference to S
  { // an inner block
   let b: &S; // another reference
  let a = S{x: ...}; // allocate S
   // OK (both a and b live only until the end of the inner block)
  b = &a;
  c = b; // dangerous (c outlives a)
}
```



```
fn foo() -> i32 {
  let c: &S; // a reference to S
  { // an inner block
    let b: &S; // another reference
    let a = S{x: ...}; // allocate S
    // OK (both a and b live only until the end of the inner block)
    b = &a;
    c = b; // dangerous (c outlives a)
  } // a dies here, making c a dangling pointer
}
```



```
fn foo() -> i32 {
  let c: &S; // a reference to S
  { // an inner block
    let b: &S; // another reference
    let a = S{x: ...}; // allocate S
    // OK (both a and b live only until the end of the inner block)
    b = &a;
    c = b; // dangerous (c outlives a)
  } // a dies here, making c a dangling pointer
    c.x // NG (deref a dangling pointer)
}
```



## A mutable borrowing reference (&mut T)

▶ you cannot modify data of type T through ordinary borrowing references &T

```
1 let a : S = S{x: 10, y: 20};
2 let b : &S = &a;
b.x = 100; // NG
```

- ▶ they are *immutable* references
- ightharpoonup you can modify data through a mutable reference &mut T

```
1  let mut a : S = S{x: 10, y: 20};
2  let b : &mut S = &mut a;
3  b.x = 100; // OK
```

## Additional restrictions on &mut T

- ightharpoonup a stronger restriction is imposed on &mut T
  - you cannot use the originating (owning) pointer (T or Box < T >) or
  - ▶ derive other borrowing pointers (mutable or not) from a mutable borrowing reference (&mut T)

where a mutable borrowing reference is active in scope

ightharpoonup active  $\approx$  may be used in future (omitting details)

```
fn mut_ref() {
   let mut a = S{x: ...};
   let m = &mut a; // make a mutable ref to a

4    ... a.x ...; // NG: cannot use a (the originating pointer)
   let d = &a; // NG: cannot borrow from a either
   let c = m; // NG: cannot derive another reference
   m.x // --- m is active up to this point
   ... a.x ...; // OK: as m no longer active here
}
```

## Contents

Overview

Rust basics

Owning pointers

Assignments of owning pointers Box<T> type

Borrowing pointers (&T)

Borrow checking details

Summary

#### A technical remark about borrowers rule

- ▶ it's *not a creation* of a dangling pointer, *per se*, that is not allowed, but *dereferencing* of it
- ► a slightly modified code below compiles without an *error*, despite that c becomes a dangling pointer to a (as it is not dereferenced past a's lifetime) fn foo() -> i32 { let c: &S; // a reference to S { // an inner block let b: &S; // another reference let a =  $S\{x: \ldots\}$ ; // allocate S // OK (both a and b live only until the end of the inner block) b = &a;c = b; // dangerous (c outlives a) }// a dies here, making c a dangling pointer // c.x don't deref c

1. for each borrowing reference (&T or &mut T type), Rust compiler determines the lifetime of data it points to (referent lifetime) as part of its static type

```
fn foo() -> i32 { let c: &S; // \rightarrow ?? { let b: &S; // \rightarrow ?? let a = S{x: ...}; b = &a; c = b; } // a dies here (\alpha) c.x
```

- 1. for each borrowing reference (&T or &mut T type), Rust compiler determines the lifetime of data it points to (referent lifetime) as part of its static type
- 2. assignment between borrowing pointers (p = q) equate their referent lifetimes

```
fn foo() -> i32 {
  let c: &S; // \rightarrow ??
  {
    let b: &S; // \rightarrow ??
  let a = S{x: ...};
    b = &a;
    c = b;
  } // a dies here (\alpha)
  c.x
```

- 1. for each borrowing reference (&T or &mut T type), Rust compiler determines the lifetime of data it points to (referent lifetime) as part of its static type
- 2. assignment between borrowing pointers (p = q) equate their referent lifetimes

```
fn foo() -> i32 {
  let c: &S; // \rightarrow ??
  {
    let b: &S; // \rightarrow \alpha
    let a = S{x: ...}; // lives until \alpha
    b = &a; // b's referent lifetime = a's lifetime
    c = b;
  } // a dies here (\alpha)
    c.x
}
```

- 1. for each borrowing reference (&T or &mut T type), Rust compiler determines the lifetime of data it points to (referent lifetime) as part of its static type
- 2. assignment between borrowing pointers (p = q) equate their referent lifetimes

```
fn foo() -> i32 {
let c: &S; // \rightarrow \alpha
{
let b: &S; // \rightarrow \alpha
let a = S{x: ...}; // lives until \alpha
b = &a; // b's referent lifetime = a's lifetime
c = b; // c's referent lifetime = b's referent lifetime
} // a dies here (\alpha)
```

30 / 56

- 1. for each borrowing reference (&T or &mut T type), Rust compiler determines the lifetime of data it points to (referent lifetime) as part of its static type
- 2. assignment between borrowing pointers (p = q) equate their referent lifetimes
- 3. dereferencing a borrowing pointer p (e.g., p.x) is allowed only within the p's referent lifetime

```
fn foo() -> i32 {
 let c: &S; // \rightarrow \alpha
 {
 let b: &S; // \rightarrow \alpha
 let a = S{x: ...}; // lives until \alpha
 b = &a; // b's referent lifetime = a's lifetime
 c = b; // c's referent lifetime = b's referent lifetime
} // a dies here (\alpha)
c.x
```

30 / 56

- 1. for each borrowing reference (&T or &mut T type), Rust compiler determines the lifetime of data it points to (referent lifetime) as part of its static type
- 2. assignment between borrowing pointers (p = q) equate their referent lifetimes
- 3. dereferencing a borrowing pointer p (e.g., p.x) is allowed only within the p's referent lifetime

```
fn foo() -> i32 {
let c: &S; // \rightarrow \alpha
{
let b: &S; // \rightarrow \alpha
let a = S{x: ...}; // lives until \alpha
b = &a; // b's referent lifetime = a's lifetime
c = b; // c's referent lifetime = b's referent lifetime
} // a dies here (\alpha)
c.x // NG (deref outside c's referent lifetime = \alpha)
}
```

30 / 56

# Programming with borrowing references

- programs using borrowing references must help compilers track their referent lifetimes
- ▶ this must be done for functions called from unknown places, function calls to unknown functions and data structures
- ▶ to this end, the programmer sometimes must annotate reference types with their referent lifetimes

## References in function parameters

▶ problem: how to check the validity of functions taking references

```
fn p_points_q(p: &mut P, q: &Q) {
   p.x = q; // OK?
}
```

without knowing all its callers, and function calls passing references

```
1  let c = ...;
2  {
3  let a = Q{...};
4  let b = &a;
5  f(c, b);
6  }
7  ... c.x.y ... // OK?
```

without knowing the definition of f?

#### References in function return values

▶ problem: how to check the validity of functions returning references

```
fn return_ref(...) -> &P {
    ...
    let p: &P = ...
    ...
    p // OK?
}
```

without knowing its all callers, and function calls receiving references from function calls

```
fn receive_ref() {
    ...
    let p: &P = return_ref(...);
    ...
    p.x // OK?
}
```

#### References in data structures

▶ problem: how to check the validity of dereferencing a pointer obtained from a data structure

```
fn ref_from_struct() {
    ...
let p: &P = a.p;
    ...
p.x // OK?
}
```

▶ what about functions taking data structures containing references and returning another containing references, etc.?

## Reference type with a lifetime parameter


- ▶ to address this problem, Rust's borrowing reference types (&T or &mut T) carry lifetime parameter representing their referent lifetimes
- > syntax:
  - $\triangleright$  &'a T: reference to "T whose lifetime is 'a"
  - ▶ &'a mut T: ditto; except you can modify data through it

T lives until 'a

- every reference carries a lifetime parameter, though there are places you can omit them
- ▶ roughly, you must write them explicitly in function parameters, return types, and struct/enum fields; and can omit them for local variables

## Reference type with a lifetime parameter

- ▶ to address this problem, Rust's borrowing reference types (&T or &mut T) carry lifetime parameter representing their referent lifetimes
- > syntax:
  - $\triangleright$  &'a T: reference to "T whose lifetime is 'a"
  - ▶ &'a mut T: ditto; except you can modify data through it



- every reference carries a lifetime parameter, though there are places you can omit them
- ➤ roughly, you must write them explicitly in function parameters, return types, and struct/enum fields; and can omit them for local variables

## Attaching lifetime parameters to functions

➤ the following does not compile

```
fn foo(ra: &i32, rb: &i32, rc: &i32) -> &i32 {
   ra
}
```

with errors like

# Why do we need an annotation, fundamentally?

▶ without any annotation, how to know whether this is safe, without knowing the definition of foo?

► essentially, the compiler complains "tell me what kind of lifetime foo(&a, &b, &c) has"

# Attaching lifetime parameters to functions

syntax:

► f<'a,'b,'c,...> is a function that takes parameters of respective lifetimes

## One way to attach lifetime parameters

```
fn foo<'a>(ra: &'a i32, rb: &'a i32, rc: &'a i32) -> &'a i32
```

- effect: the return value is assumed to point to the shortest of the three
- why? generally, when Rust compiler finds foo(x, y, z), it tries to determine 'a so that it is contained in the lifetime of all (x, y and z)
- ▶ as a result, our program does not compile, even if foo(&a, &b, &c) in fact returns &a

```
let r: &i32;
       let a = 123:
         let b = 456;
 7
           let, c = 789:
           r = foo(&a, &b, &c); // 'a \leftarrow shortest of \{\alpha, \beta, \gamma\} = \gamma
           // and r's type becomes & 132
 9
10
         } // b's lifetime (= \beta) ends here
11
12
       *r // NG, as we are outside \gamma
     } // a's lifetime (= \alpha) ends here
13
```

## An alternative

```
fn foo<'a,'b,'c>(ra: &'a i32, rb: &'b i32, rc: &'c i32) -> &'a i32
```

- ▶ signifies that the return value points to data whose lifetime is ra's referent lifetime (and has nothing to do with rb's or rc's)
- for foo(x, y, z), Rust compiler tries to determine 'a so it is contained in the lifetime of x's referent (therefore 'a =  $\alpha$ )
- ▶ as a result, the program we are discussing compiles

```
let r: &i32;
        let a = 123:
           let b = 456;
 7
             let c = 789:
             r = foo(&a, &b, &c); // 'a \rightarrow shortest of \{\alpha\} = \alpha
 9
             // and r's type becomes & \alpha i32
10
           } // c's lifetime (= \gamma) ends here
        } // b's lifetime (= \beta) ends here
11
12
        *r // OK, as here is within a

    \( \lambda \) a's lifetime (= α) ends here

13
```

# Types with lifetime parameters capture/constrain the function's behavior

▶ what if you try to fool the compiler by

```
fn foo<'a,'b,'c>(ra: &'a i32, rb: &'b i32, rc: &'c i32) -> &'a i32
rb
}
```

- ► the compiler rejects returning rb (of type &'b) when the function's return type is &'a
- ▶ in general, the compiler allows assignments only between references having the same lifetime parameter

# Another example (make a reference between inputs)

▶ what if we rewrite

```
r = foo(&a, &b, &c);
into

bar(&mut r, &a, &b, &c);

with bar something like

fn bar(r: &mut &i32, a: &i32, b: &i32, c: &i32) {
   *r = a;
}
```

## Make a reference between inputs

- ▶ how to specify lifetime parameters so that
  - 1. \*r = a; in bar's definition is allowed, and
  - 2. we can dereference \*r at the end of the caller?

```
1 {
2    let a = 123;
3    let mut r = &0;
4    {
5        let b = 456;
6     {
7        let c = 789;
8        bar(&mut r, &a, &b, &c); // r → ???
9    } // c's lifetime (= γ) ends here
10    } // b's lifetime (= β) ends here
11    *r // OK???
12 } // a's lifetime (= α) ends here
```

#### Answer

- ▶ again, we need to signify r points to a (and not b or c after bar(&r, &a, &b, &c)
- ▶ a working lifetime parameter is the following

#### References in data structures

▶ problem: how to check the validity of programs using data structure containing a borrowing reference

```
1 struct R {
2 p: &i32
3 ...
4 }
```

and functions returning R

```
1 fn ret_r(a: &i32, b: &i32, c: &i32) -> R {
2    R{p: a}
3 }
```

or taking R (or reference to it)

```
fn take_r(r: &mut R, a: &i32, b: &i32, c: &i32) {
    r.p = a;
}
```

#### References in data structures

ightharpoonup you cannot simply have a field of type &T in struct/enum like this

```
1 struct R {
2 p: &i32 ...
4 }
```

you need to specify the lifetime parameter of p, and signifies that R takes a lifetime parameter

```
1 struct R<'a> {
2 p: &'a i32
3 ...
}
```

▶ R<'a> represents R whose p field points i32 whose lifetime is 'a

## Attaching lifetime parameters to data structure

say we like to have data structures

```
1 struct T { x: i32 } struct S { p: &T }
```

and a function

```
1 fn make_s(a: &T, b: &T) -> S { S{p: a} }
```

so that the following compiles

```
1 let s;
2 let a = T{...};
3 {
4 let b = T{...};
5 s = make_s(&a, &b);
6 }
7 s.p.x
```

- b the compiler needs to verify s.p points to a, not b
- we have to signify that by appropriate lifetime parameters

#### Answer

- ▶ define S<'a> so
  - ▶ its p's referent lifetime is 'a

```
1 struct S<'a> { p: &'a T }
```

▶ define make\_s so it returns S<'a> where 'a is the referent lifetime of its *first* parameter

```
fn make_s(a: &'a T, b: &'b T) -> S<'a> {
    S{p: a}
}
```

## A more complex example Rust cannot verify

say we now have data structures

#### and a function

```
1 fn make_s(a: &T, b: &T) -> S { S{p: a, q: b} }
```

#### so that the following compiles

```
1 let s;
2 let a = T{...};
3 {
4 let b = T{...};
5 s = make_s(&a, &b);
6 }
7 s.p.x
```

again, the compiler needs to verify s.p points to a, notb

# Answer that I thought should work but didn't

- ▶ define S so
  - its p points to T of lifetime 'a and
  - ▶ its q points to T of lifetime 'b

```
1 struct S<'a, 'b> {
2 p: &'a T,
3 q: &'b T
4 }
```

▶ define make\_s so it returns S<'a, 'b> where 'a is the lifetime of its first parameter, like

```
1 fn make_s(a: &'a T, b: &'b T) -> S<'a, 'b> {
2    S{p: a, q: b}
3 }
```

# The compiler complains

▶ I don't know what is the exact spec of Rust that rejects this program, but I hypothesize that to dereference **s** for any field (**p**), all fields must be alive

### Contents

Overview

Rust basics

Owning pointers
Assignments of owning pointers
Box<T> type


Borrowing pointers (&T)

Borrow checking details

Summary


 every language wants to prevent dereferencing a pointer to an already-reclaimed memory block (dangling pointer)

```
{
  let v = T{x: ...};
  ...
}
```



- every language wants to prevent dereferencing a pointer to an already-reclaimed memory block (dangling pointer)
- ► the problem would have been trivial if you could reclaim v's referent as soon as v goes out of scope

```
{
  let v = T{x: ...};
  ...
}
```



- every language wants to prevent dereferencing a pointer to an already-reclaimed memory block (dangling pointer)
- ► the problem would have been trivial if you could reclaim v's referent as soon as v goes out of scope

```
{
  let v = T{x: ...};
  ...
} // OK to drop v's referent here?
```

- every language wants to prevent dereferencing a pointer to an already-reclaimed memory block (dangling pointer)
- ► the problem would have been trivial if you could reclaim v's referent as soon as v goes out of scope
- ▶ this is not the case, as v's referent may still be reachable from other variables when v goes out of scope


```
{
  let v = T{x: ...};
  ...
}
```

- every language wants to prevent dereferencing a pointer to an already-reclaimed memory block (dangling pointer)
- ► the problem would have been trivial if you could reclaim v's referent as soon as v goes out of scope
- ► this is not the case, as v's referent may still be reachable from other variables when v goes out of scope

```
let p : &T;
{
    let v = T{x: ...};
    ...
    p = &v;
} // v never used below, but its referent is
... p.x ...
```


### C vs. GC vs. Rust

ightharpoonup C/C++: it's up to you




### C vs. GC vs. Rust

- $\triangleright$  C/C++: it's up to you
- ► GC : if it is reachable from other variables, I retain it for you




#### C vs. GC vs. Rust


- $\triangleright$  C/C++: it's up to you
- $\blacktriangleright$  GC : if it is reachable from other variables, I retain it for you
- $\triangleright$  Rust: when v goes out of scope,
  - 1. I reclaim  $T_v$ , all data reachable from v through owning pointers
  - 2.  $T_v$  may be reachable from other variables via borrowing references, but I nevertheless guarantees a reclaimed memory block is never accessed




recall the "single-owner rule," which guarantees there is only one owning pointer to any node




- recall the "single-owner rule," which guarantees there is only one owning pointer to any node
- ▶ ⇒ there can be no *owning* pointers from outside  $T_v$  to inside  $T_v$



- recall the "single-owner rule," which guarantees there is only one owning pointer to any node
- ▶ ⇒ there can be no *owning* pointers from outside  $T_v$  to inside  $T_v$
- $\triangleright$   $\Rightarrow$  any such pointer must be a borrowing pointer



- recall the "single-owner rule," which guarantees there is only one owning pointer to any node
- ▶ ⇒ there can be no *owning* pointers from outside  $T_v$  to inside  $T_v$
- $\triangleright$   $\Rightarrow$  any such pointer must be a borrowing pointer
- crucially, such a borrowing pointer must have a lifetime parameter of the referent



- recall the "single-owner rule," which guarantees there is only one owning pointer to any node
- ▶ ⇒ there can be no *owning* pointers from outside  $T_v$  to inside  $T_v$
- $\triangleright$   $\Rightarrow$  any such pointer must be a borrowing pointer
- crucially, such a borrowing pointer must have a lifetime parameter of the referent
- $\triangleright$  as a result, a pointer that can reach  $T_v$  cannot be dereferenced after v goes out of scope

