

Create and Mount Samba and CIFS Fileshares

# **Contents**

Install and Configure Samba Server	1
Create Samba User Accounts	4
Configure Client and Mount Shares	6

# **Lab Connection Information**

- Labs may take up to five minutes to build
- The IP address of your server is located on the Hands-on Lab page
- Username: linuxacademy
- Password: 123456
- Root Password: 123456

### Related Courses

<u>Linux Academy</u> <u>RHCSA Prep</u> <u>Course</u>

#### Related Videos

Mount and
Unmount CIFS and
NFS Network File
Systems

### Need Help?

Linux Academy
Community

... and you can always send in a support ticket on our website to talk to an instructor!

In this lab, we deploy a Samba share for exchanging and sharing files across multiple systems. Using two CentOS 7 servers we set up and configure the share, add a user, and then set up the client server so it can access the share.

# **Install and Configure Samba Server**

SSH into the first server and install the needed packages:

```
[linuxacademy@ip]$ sudo yum install samba samba-client samba-common
cifs-utils
```

Note that the Cifs-utils package may not be necessary if using Samba 3.

We now need to make edits to the Samba configuration file, which is located at /etc/samba.

Review the example configuration file, Smb.conf.example; as we can see, this is a large file containing a variety of options, and it would not necessarily be the best option to copy this file directly to create our own configuration. Instead, open Smb.conf in your chosen text editor.

This configuration is largely acceptable for most Samba installs. That said, we still have to make some changes and ensure we understand what our settings are doing.

Notice that each setting has its own section within the configuration file ([homes], [printers], etc.), with a global section at the top:

```
[global]
    workgroup = Samba
    security = user
    passdb backend = tdbsam
    printing = cups
    printcap name = cups
    load printers = yes
    cups options = raw
```

The workgroup line defines the name of the workgroup we are using.

**Security** denotes who is able to access what; **user** is the Samba user security system, but we can also use Active Directory or a domain controller. In this case, we are leaving it as **user**.

passdb backend is for security on the database-level and is very rarely changed – any other options for this setting are external to Samba.

The next segment – printing, printcap name, load printers, and cups options – lets us define what service we are using for printing. By default, we use CUPS. This can be left as-is.

Next, the [homes] portion denotes whether users can share their home directories over Samba. This makes it easy for users to share files, as needed.

[printers] defines which printers to use, with the path defining the cups spool for printing. Because CUPS is not installed on this system, /var/tmp is used instead.

[print\$] allows for printer drivers to be shared across accounts.

We can also build our own sections in the Samba configuration, which we want to do now. Add a new section, [myshare]. This allows us to create a Samba share and determine who has access to that share.

```
[myshare]
    comment = This is our test share
    path = /myshare
    guest ok = no
    writeable = yes
```

We first want to add a <code>comment</code>, which helps us identify this share. The <code>path</code> defines where the share is located, and <code>guest ok</code> determines whether guest accounts can be used. <code>writable</code> defines whether or not our share is read only for those who have access to the account.

Save and exit the file.

Create the Samba share:

```
[linuxacademy@ip]$ cd /
[linuxacademy@ip]$ sudo mkdir /myshare
[linuxacademy@ip]$ sudo chmod 777 /myshare
[linuxacademy@ip]$ echo "test file" > /myshare/testfile.txt
```

Notice that we set the permissions to 777, because we expect the Samba share to take care of any permissions issues.

Since we are using a CentOS 7 server, and SELinux is enabled by default, we want to set SELinux to permissive mode:

```
[linuxacademy@ip]$ sudo setenforce 0
```

In actual practice, properly configuring SELinux to work with the Samba share may be more appropriate;

however, this is out of scope for this lab.

With our share created, open up the Smb.conf file again, and edit the load printers directive, since our system does not have printers:

```
load printers = no
```

Save and exit the file.

Test the file to see if the configuration is accurate:

```
[linuxacademy@ip]$ testparm
Load smb config files from /etc/samba/smb.conf
rlimit_max: increasing rlimit_max (1024) to minimum Windows limit
(16384)
Processing section "[homes]"
Processing section "[printers]"
Processing section "[print$]"
Processing section "[myshare]"
Loaded services file OK.
Server role: ROLE_STANDALONE
Press enter to see a dump of your service definitions
```

Everything should be configured correctly.

Start the Samba and nmb services, nmb allows Windows user to access the share.

```
[linuxacademy@ip]$ sudo systemctl start smb
[linuxacademy@ip]$ sudo systemctl start nmb
```

Confirm that both services are ready:

```
starting up and ready to serve connections
[linuxacademy@ip]$ sudo systemctl status -l nmb
nmb.service — Samba NMB Daemon
   Loaded: loaded (/usr/lib/systemd/system/nmb.service; disabled; vendor
preset: disabled)
   Active: active (running) since Mon 2017-03-27 17:15:47 UTC; 27s ago
 Main PID: 9727 (nmbd)
   Status: "nmbd: ready to serve connections..."
   CGroup: /system.slice/nmb.service
           0 9727 /usr/sbin/nmbd
Mar 27 17:15:47 ip-10-0-1-92 systemd[1]: Starting Samba NMB Daemon...
Mar 27 17:15:47 ip-10-0-1-92 nmbd[9727]: [2017/03/27 17:15:47.873762,
0] ../lib/util/become_daemon.c:124(daemon_ready)
Mar 27 17:15:47 ip-10-0-1-92 nmbd[9727]:
                                           STATUS=daemon 'nmbd' finished
starting up and ready to serve connections
See what shares are available for the Samba workgroup:
[linuxacademy@ip]$ nmblookup Samba
```

The IP address returned should be the one for the lab server.

### **Create Samba User Accounts**

We want to be able to use user authentication to determine who has access to our Samba share. To do this, we cannot just use regular system accounts but instead need to create Samba accounts and passwords for our users or create a username map so users without system accounts can access the share. This is especially important for Windows users.

Use the Smbpasswd command to create a user, user:

```
[linuxacademy@ip]$ sudo smbpasswd -a user
```

When prompted, enter a password. The user *user* is now added to the Samba database.

Alternatively, we can create a usermap file. Navigate to the /etc/samba directory, and create the file usermap. This file uses a key/pair style of formatting.

Since *user* is already an available account, we can set it up so the Windows user, *jsmith*, can access the share:

```
jsmith = user
```

Save and exit the file. We want to reference this file in our configuration, so Samba knows to use it. Open smb.conf, and add the following to the [global] section of the configuration:

```
username map = /etc/samba/usermap
```

Save and exit the file. Test the configuration:

```
[linuxacademy@ip]$ testparm
Load smb config files from /etc/samba/smb.conf
rlimit_max: increasing rlimit_max (1024) to minimum Windows limit
(16384)
Processing section "[homes]"
Processing section "[printers]"
Processing section "[print$]"
Processing section "[myshare]"
Loaded services file OK.
Server role: ROLE_STANDALONE
```

Since we installed the client tools on this server, we can also practically test our Samba share. Retrieve your server's IP address (use ifconfig or pull it from the Hands-on Lab page), and test as the *user* user. Note that for the Hands-on Lab we want to use the server's private IP.

```
[linuxacademy@ip]$ smbclient -U user -L <PRIVATEIP>
Domain=[Samba] OS=[Windows 6.1] Server=[Samba 4.4.4]
    Sharename
                    Type
                               Comment
    print$
                               Printer Drivers
                    Disk
                               This is our test share
                    Disk
    myshare
                    IPC
                               IPC Service (Samba 4.4.4)
    IPC$
                    Disk
    user
                               Home Directories
Domain=[Samba] OS=[Windows 6.1] Server=[Samba 4.4.4]
    Server
                         Comment
    IP-10-0-1-94
                          Samba 4.4.4
    Workgroup
                          Master
    Samba
                          IP-10-0-1-94
```

Enter the password when prompted.

Here we can see our available shares. To further test and see if we can access the share itself:

```
[linuxacademy@ip]$ smbclient -U user //<PRIVATEIP>/myshare
Domain=[Samba] OS=[Windows 6.1] Server=[Samba 4.4.4]
smb: \>
```

Enter the password when prompted. This gives us a Samba prompt (Smb: \>), which allows us to access our share. Run the \( \)5 command to ensure the test file is there, then quit

Finally, run SmbStatus to see who is connected and what shares they are using.

```
[linuxacademy@ip]$ sudo smbstatus
```

This will output a mostly-blank response, since we have no connected clients and no users are on our share.

# **Configure Client and Mount Shares**

SSH into your second provided server. Install the needed utilities for using Samba:

```
[linuxacademy@ip2]$ sudo yum install samba samba-client samba-common
cifs-utils
```

Connect to the Samba share, using the IP address of the serving instance:

```
[linuxacademy@ip2]$ smbclient -U user -L <PRIVATEIP>
Domain=[Samba] OS=[Windows 6.1] Server=[Samba 4.4.4]
    Sharename
                      Type
                                 Comment
                                 Printer Drivers
    print$
                      Disk
                                 This is our test share IPC Service (Samba 4.4.4)
                      Disk
    myshare
                      IPC
    IPC$
                                 Home Directories
                      Disk -
Domain=[Samba] OS=[Windows 6.1] Server=[Samba 4.4.4]
                           Comment
    Server
    IP-10-0-1-94
                           Samba 4.4.4
    Workgroup
                           Master
    Samba
                           IP-10-0-1-94
```

Enter the password when prompted. The output should match the output from earlier in the lab. We can also view the share:

```
[linuxacademy@ip2]$ smbclient -U user //<PRIVATEIP>/myshare
Domain=[Samba] OS=[Windows 6.1] Server=[Samba 4.4.4]
smb: \>
```

quit the Samba prompt.

However, we want to mount the share to our system, not only access it through the Samba prompt.

To avoid SELinux issues, cd into the /mnt directory. Create a directory:

```
[linuxacademy@ip2]$ cd /mnt
```

```
[linuxacademy@ip2]$ sudo mkdir sambashare
```

Mount the file system:

```
[linuxacademy@ip2]$ sudo mount -t cifs -o username=user //IP/myshare /
mnt/sambashare
```

Note that for Samba 3, username=user should instead be user=user. Input your password when prompted. Confirm its mount:

```
[linuxacademy@ip2]$ df -h
                            Used Avail Use% Mounted on
Filesystem
                      Size
/dev/xvda1
                            1.5G 6.6G 19% /
                      8.0G
devtmpfs
                                          0% /dev
                      477M
                                   477M
                                   496M
                                          0% /dev/shm
tmpfs
                      496M
                                          3% /run
tmpfs
                      496M
                              13M
                                   483M
                      496M
                                   496M
                                          0% /sys/fs/cgroup
tmpfs
tmpfs
                      100M
                                0
                                  100M
                                          0% /run/user/0
                                          0% /run/user/1001
                      100M
                                0
                                   100M
tmpfs
//10.0.1.94/myshare
                            1.5G 6.6G
                                         19% /mnt/sambashare
                      8.0G
```

As a test, create a second file in the Samba share:

```
[linuxacademy@ip2]$ sudo sh -c "echo "Another file" > /mnt/sambashare/
another.txt"
```

Return to the base /mnt directory and unmount the share:

```
[linuxacademy@ip2]$ cd /mnt
[linuxacademy@ip2]$ sudo umount sambashare
```

But what if we want to mount the system on boot? Open /etc/fstab, and add the mount as you would another file system but with included username and password information.

```
# samba mount for share - using username and password
//<PRIVATEIP>/myshare /mnt/sambashare cifs
username=user.password=password 0 0
```

Save and edit.

Mount the file system with mount -a. Confirm:

```
477M
devtmpfs
                       477M
                                           0% /dev
tmpfs
                       496M
                                0
                                    496M
                                            0% /dev/shm
                                            3% /run
tmpfs
                       496M
                              13M
                                    483M
                                    496M
                                            0% /sys/fs/cgroup
                       496M
tmpfs
                                0
tmpfs
                       100M
                                    100M
                                            0% /run/user/0
tmpfs
                       100M
                                0
                                    100M
                                           0% /run/user/1001
//10.0.1.94/myshare
                      8.0G
                             1.5G
                                    6.6G
                                          19% /mnt/sambashare
```

#### Unmount the share:

```
[linuxacademy@ip2]$ sudo umount /mnt/sambashare
```

While this works, it is not the most secure option for mounting the system – notably, it involves inputting a password in plain text into our /etc/fstab file. Remove the line from /etc/fstab. Instead, we can to use a credentials file:

```
# samba mount for share — user credentials file
//ip/myshare /mnt/sambashare cifs credentials=/etc/samba/creds.txt
0 0
```

Save and exit, then create the creds.txt file in /etc/samba.

```
username=user
password=password
```

Save and exit.

Mount the file system:

```
[linuxacademy@ip2]$ mount -a
[linuxacademy@ip2]$ df -h
Filesystem
                            Used Avail Use% Mounted on
                      Size
/dev/xvda1
                             1.5G
                                   6.6G
                                          19% /
                      8.0G
devtmpfs
                      477M
                                   477M
                                           0% /dev
                                   496M
                                           0% /dev/shm
tmpfs
                      496M
                                           3% /run
                                   483M
                      496M
                              13M
tmpfs
                                           0% /sys/fs/cgroup
tmpfs
                      496M
                                   496M
tmpfs
                      100M
                                   100M
                                           0% /run/user/0
tmbfs
                      100M
                                0
                                   100M
                                           0% /run/user/1001
                                          19% /mnt/sambashare
//10.0.1.94/myshare
                      8.0G
                             1.5G
                                   6.6G
```

Return to the first server, and run Smbstatus.

```
[linuxacademy@ip]$ sudo smbstatus
```

Here we can see that we're connected from the second server. You can now complete the lab!