Safe module unloading

in the Oberon operating system

Andreas Pirklbauer

11.11.2019

Purpose

This technical note describes an experimental implementation of *safe* module unloading for the Oberon operating system, as realized in Experimental Oberon¹, a revision of FPGA Oberon².

Module unloading in the Oberon system

In the Oberon system, there exist several possible types of references to a loaded module M³:

- 1. Client references exist when other loaded modules import module M. Client modules may refer by name to exported constants, types, variables or procedures declared in module M.
- 2. Type references exist when type tags (addresses of type descriptors) in dynamic objects reachable by other loaded modules refer to descriptors of types declared in module M⁴.
- 3. Procedure variable references exist when procedure variables in static or dynamic objects reachable by other loaded modules refer to procedures declared in module M.
- 4. Pointer variable references to static module data exist when pointer variables in static or dynamic objects reachable by other loaded modules refer to static objects declared in module M. Such references can only be created by resorting to low-level facilities and should be avoided and, in fact, be disallowed (pointer variables should point exclusively to anonymous variables allocated in the *heap* when needed during program execution). But since they *can* (at least in theory) exist, we opted to also check for them⁵.

Note that *pointer variable references to dynamic objects* in the heap reachable by the modules to be unloaded are not considered as bona fide module references and therefore should not prevent module unloading, i.e. they must not be checked. Such references will be handled by the Oberon garbage collector during a future garbage collection cycle (heap objects that were reachable *only* by the just unloaded modules will be collected).

¹ http://www.github.com/andreaspirklbauer/Oberon-experimental

An Oberon module can be viewed as a container of types, variables and procedures, where variables may be procedure-typed. Global objects with an explicit name declared in a module are allocated in the module area when the module is loaded. If exported, such "static" objects may be referenced by name in client modules. Anonymous variables with no explicit name declared in a module are allocated in the dynamic space (heap) when needed during program execution using the predefined procedure NEW. Such "dynamic" objects may be "reachable" by multiple

a mounte are aurocated in the dynamic space (neap) when needed during program execution using the predefined procedure NEW. Such "dynamic" objects may be "reachable" by multiple named global pointer variables, possibly declared in different modules.

In the programming language Oberon, pointer types are "bound" to their base types, giving rise to additional (hidden) references from dynamic objects to descriptors of types declared in the loaded modules. The concept of "pointer binding", first implemented in the language Algol W and adopted in Pascal, Modula-2 and Oberon, is essential for guaranteeing type safety, as it permits the validation of pointer values at the time of compilation without loss of run-time efficiency and in addition enables run-time type e c h e c ks on dynamic objects.

However, if the referenced module is imported (typical in such a case), the check for pointer variable references is not actually performed, as client references are always checked first.

In most Oberon implementations, only *client* references are checked prior to module unloading. *Type*, *procedure* and *pointer variable* references to static module data are usually not checked, although various approaches are typically employed to address the case where such references do exist⁶. As a result, module unloading has traditionally left an Oberon system in an *unsafe* state, which will become *unstable* the moment another module loaded later *overwrites* a previously released module block and other modules or data elements still contain "dangling" references to its (now overwritten) *type descriptors*, *procedures* or *static objects*. In addition, unloading of module *groups* with references only among themselves is usually not supported.

Implementing safe module unloading

In order to make module unloading *safe*, *all* possible types of references to a loaded module or module group must be checked. In Experimental Oberon, this is done as follows (see Figure 1):

- If clients exist among other loaded modules, a module or module group is never unloaded.
- If no references to a given module or module group exist in the remaining modules and data structures, it is unloaded *and* its associated memory is released.
- If no clients, but type, procedure or pointer variable references to static module data of a module or module group exist, the module *unload* command takes no action and merely displays the names of the modules and the references that caused the removal to fail.
- If, however, the *force* option /f is specified in the module *unload* command⁷, the specified modules are initially removed only from the *list* of loaded modules, without releasing their associated memory. Such "hidden" modules can later be physically removed from *memory* using the command *Modules.Collect* (or the command *System.Collect* which also invokes *Modules.Collect*), as soon as no more references exist.




Figure 1: Safe module unloading in Experimental Oberon

Removing a module only from the module *list* amounts to *renaming* it, with the implication that a newer version of the same module (with the same name) can be reloaded again, without having to unload (from memory) earlier versions that are still referenced⁸.

⁶ See the appendix for historical notes on module unloading in the Oberon operating system.

The force option /f must be specified at the e n d of the list of modules to be unloaded, e.g., System.Free M1 M2 M3/f

⁸ Modules removed only from the list of loaded modules are marked with an asterisk in the output of the command System. ShowModules. Commands of such "hidden" modules can be accessed by either specifying their module number or their (modified) module name. In both cases, the corresponding command text must be enclosed in double quotes. Typical use cases include hidden modules that still have background tasks installed or unclosed viewers. If the command to close a viewer is displayed in the viewer's menu bar, the user can manually edit the command text (by clicking within its bottom two pixel lines), replace the module name by its module number and enclose the resulting (modified) command text in double quotes. An alternative (and more convenient) approach is to provide a "Close" command that also accepts the marked viewer as argument, using procedure Oberon.MarkedViewer.

By contrast, unloading a module from *memory* frees up the memory area previously occupied by the module block⁹. In Experimental Oberon, this is only possible when no references to the module exist from anywhere in the system.

To automate the process of unloading no longer referenced *hidden* module data from memory, the command *Modules.Collect* is included in the background task handling garbage collection. It checks all possible combinations of *k* modules chosen from *n* hidden modules for references to them, and removes those module subgroups from memory that are no longer referenced.

In sum, module unloading does not affect any past or future references, as module data is kept in memory for exactly as long as necessary and removed from it as soon as possible.

For example, older versions of a module's code can still be executed if they are referenced by static or dynamic procedure variables in other modules, even if a newer version of the same module has been reloaded in the meantime¹⁰. Type descriptors also remain accessible to other modules for exactly as long as needed. This covers the important case where a structure rooted in a variable of base type T declared in a base module M contains elements of an extension T' defined in a client module M', which is unloaded. Such elements typically contain both *type* references (type tags) and *procedure variable* references (installed handlers) referring to M'.

If a module *group* is to be unloaded and there exist references *only* within this group, the group is unloaded *as a whole*. This can be used to remove module groups with *cyclic* references¹¹. It is also possible to release *entire subsystems* of modules. The command *System.FreeImports* attempts to unload the specified modules and all their direct and indirect *imports*. It may be used for conventional module stacks with a single top module, for example a compiler. By contrast, the command *System.FreeClients* unloads the specified modules and all their direct and indirect *clients*. This variant may be used for module stacks written in the object-oriented programming style with their typically inverted module hierarchy, for example a graphics editor.

Note, however, that these unloading strategies amount to *heuristics* and may tend to unload rather large parts of the system, which may not be desired. Therefore, the recommended way to unload modules from the system is to use the base command *System.Free* with a *specific* set of modules provided as parameters. For added convenience, the commands *System.ShowRefs* and *System.ShowGroupRefs* can be used to help identify all modules containing references to a given module or module group.

Implementation aspects

To check for references, the module *unload* command first *selects* the modules to be unloaded using the auxiliary procedure *Modules.Select* and then invokes procedure *Modules.Check*. Client references are checked first. This is as simple as verifying whether *unselected* modules import *selected* modules¹²:

⁹ In FPGA Oberon and Experimental Oberon, the module block includes the module's type descriptors. In some other Oberon implementations, such as Ceres-Oberon, type descriptors are not stored in the module block, but are allocated in the heap at module load time in order to persist them beyond the lifetime of their associated modules. In Experimental Oberon, no such extra precaution is necessary, as module blocks that are still referenced are only removed from the module list, but not from memory.
¹⁰ If an older version of a module's code accesses global variables (of itself or of other modules), it will automatically access the "right" version of such variables.
¹¹ In Oberon, cyclic references can be created by pointers or procedure variables, whereas cyclic module imports are normally not allowed. However, through a tricky sequence of compilation

¹⁰ If an older version of a module's code accesses global variables (of itself or of other modules), it will automatically access the "right" version of such variables.
¹¹ In Oberon, cyclic references can be created by pointers or procedure variables, whereas cyclic module imports are normally not allowed. However, through a tricky sequence of compilation and editing steps, it is actually possible to c on struct cyclic module imports, which cannot be detected by the compiler. But even though they can be created, such modules are not allowed to be loaded, as the module loader of Experimental Oberon – adopting the approach chosen in Original Oberon and FPGA Oberon – would enter an endless recursion, eventually leading to a stack overflow or out-of-memory condition – a totally acceptable solution for such an artificially constructed case. But even if modules with cyclic module imports we r e allowed to be loaded, Experimental Oberon would handle them correctly upon unloading, i.e. if no external clients or references exist, such a module group would simply be unloaded as a w h o l e.
¹² Mem stands for the entire memory and assignments involving Mem are expressed as SYSTEM.GET(a, x) for x := Mem[a] and SYSTEM.PUT(a, x) for Mem[a] := x.

```
PROCEDURE FindClients*(client: ImpHandler; VAR res: INTEGER);
 2
     VAR mod, imp, m: Module; p, q: INTEGER; continue: BOOLEAN;
 3
    BEGIN res := noref; m := root; continue := client # NIL;
     WHILE continue & (m # NIL) DO
 4
      IF (m.name[0] # 0X) & m.selected & (m.refcnt > 0) THEN mod := root;
 5
 6
        WHILE continue & (mod # NIL) DO
 7
         IF (mod.name[0] # 0X) & ~mod.selected THEN p := mod.imp; q := mod.cmd;
 8
          WHILE p < q DO imp := Mem[p];
 9
           IF imp = m THEN INC(res, client(mod, imp, continue)); p := q ELSE INC(p, 4) END
10
          END
         END:
11
         mod := mod.next
12
13
        END
14
      END;
15
      m := m.next
16
     END
    END FindClients;
```

If clients exist among the *unselected* modules, no further action is taken and the module *unload* command exits. If no clients exist, *type*, *procedure* and *pointer variable* references from objects in the heap¹³ are checked next. This is accomplished using a conventional *mark-scan* scheme:

```
PROCEDURE FindDynamicRefs*(typ, ptr, pvr: RefHandler;
     VAR resTyp, resPtr, resPvr: INTEGER; all: BOOLEAN);
 2
 3
     VAR mod: Module;
    BEGIN mod := root;
 5
     WHILE mod # NIL DO
      IF (mod.name[0] # 0X) & ~mod.selected THEN Kernel.Mark(mod.ptr);
 7
        IF ~all THEN Kernel.Scan(typ, ptr, pvr, mod.name, resTyp, resPtr, resPvr) END
 8
      END;
      mod := mod.next
 9
10
     END;
     IF all THEN Kernel.Scan(typ, ptr, pvr, "", resTyp, resPtr, resPvr) END
11
    END FindDynamicRefs;
```

During the *mark* phase, heap objects reachable by all named global pointer variables of all *other* modules are marked (line 6), thereby excluding objects reachable *only* by the modules to be unloaded. This automatically recognizes module *groups* and ensures that when a module group is referenced *only* by itself, it can still be unloaded. The subsequent *scan* phase (lines 7 or 11), implemented as a separate procedure *Scan* in module *Kernel*¹⁴, scans the heap sequentially, unmarks all *marked* objects and checks whether their *type tags* point to descriptors of *types* and whether *procedure* or *pointer variables* declared in those same objects refer to *procedures* or *static objects* declared in the modules to be unloaded.

An additional boolean parameter *all* allows the caller to indicate whether the *mark* phase should first mark all heap objects reachable by *all* other modules before initiating the *scan* phase *once* (used for module unloading), or whether the *scan* phase should be initiated for *each* unselected module *individually* (can be used for identifying references from each unselected module).

Finally, the check for procedure and pointer variable references to static module data is also performed for all *global* procedure and pointer variables, whose offsets in the module's data section are obtained from two arrays in the module's *meta* data section in memory, headed by the links *mod.pvr* and *mod.ptr*, respectively:

13 In FPGA Oberon, only records can be allocated in the heap. In Experimental Oberon, fixed-length and open arrays can also be dynamically allocated.

¹⁴ The original procedure Kernel. Scan (implementing the scan phase of the Oberon garbage collector) has been renamed to Kernel. Collect – in analogy to procedure Modules. Collect.

```
PROCEDURE FindStaticRefs*(ptr. pvr: RefHandler; VAR resPtr, resPvr: INTEGER);
 2
     VAR mod: Module; pref, pvadr, r: LONGINT; continue: BOOLEAN;
 3
    BEGIN resPtr := noref; resPvr := noref; mod := root; continue := (ptr # NIL) OR (pvr # NIL);
     WHILE continue & (mod # NIL) DO
 4
       IF (mod.name[0] # 0X) & ~mod.selected THEN
 5
        IF ptr # NIL THEN pref := mod.ptr; pvadr := Mem[pref];
 6
 7
         WHILE continue & (pvadr # 0) DO r := Mem[pvadr];
 8
          INC(resPtr, ptr(pvadr, r, mod.name, continue));
 9
          INC(pref, 4); pvadr := Mem[pref]
10
         END
        END;
11
        IF pvr # NIL THEN pref := mod.pvr; pvadr := Mem[pref];
12
13
         WHILE continue & (pvadr # 0) DO r := Mem[pvadr];
          INC(resPvr, pvr(pvadr, r, mod.name, continue));
14
          INC(pref, 4); pvadr := Mem[pref]
15
         END
16
        END
17
18
       END:
19
      mod := mod.next
20
      END
    END FindStaticRefs:
```

Procedures FindClients, FindDynamicRefs and FindStaticRefs are expressed as generic object traversal schemes, which accept parametric handler procedures that are called for each encountered object with the source and destination of the potential reference itself passed as parameters. This allows these procedures to be used for other purposes as well, for example to enumerate all references to a given module group. In order to omit in module Kernel any reference to the list of modules rooted in module Modules, procedure Scan is also expressed as a generic procedure. The following is a simplified version of this scheme 15:

```
PROCEDURE Scan*(typ, ptr, pvr: Handler; s: ARRAY OF CHAR; VAR resTyp, resPtr, resPvr: INTEGER);
 2
      VAR offadr, offset, p, r, mark, tag, size, pos, len, elemsize, blktyp: LONGINT; continue: BOOLEAN;
 3
    BEGIN p := heapOrg; resTyp := 0; resPtr := 0; resPvr := 0; continue := (typ # NIL) OR (ptr # NIL) OR (pvr # NIL);
     REPEAT mark := Mem[p+4];
 5
       IF mark < 0 THEN (*free*) size := Mem[p]
       ELSE (*allocated*) tag := Mem[p]; size := Mem[tag];
        IF mark > 0 THEN (*marked*) Mem[p+4] := 0;
         IF continue THEN
 8
           IF typ # NIL THEN INC(resTyp, typ(p, tag, s, continue)) END;
 9
10
           IF continue & ((ptr # NIL)) OR (pvr # NIL)) THEN offadr := tag + 16; offset := Mem[offadr]
            WHILE continue & (offset # -1) DO (*pointers*)
11
             IF ptr # NIL THEN r := Mem[p+8+offset]; INC(resPtr, ptr(p+8+offset, r, s, continue)) END;
12
13
             INC(offadr, 4); offset := Mem[offadr]
14
            END:
15
            IF continue & (pvr # NIL) THEN INC(offadr, 4); offset := Mem[offadr]
16
             WHILE continue & (offset # -1) DO (*procedures*) r := Mem[p+8+offset];
              INC(resPvr, pvr(p+8+offset, r, s, continue));
17
18
              INC(offadr, 4); offset := Mem[offadr]
19
             END
20
            END
21
          END
22
         END
23
        END
24
       END:
25
       INC(p, size)
26
     UNTIL p >= heapLim
27
    END Scan;
```

__

¹⁵ The simplified version scans only record blocks allocated via NEW(p), where p is a POINTER TO RECORD. The full implementation also covers array blocks.

This scheme calls *parametric* handler procedures for individual elements of each marked *heap* object rather than directly checking whether it contains *type*, *procedure* or *pointer variable* references to static module data of the modules to be unloaded.

- Procedure typ is called with the address of (the type tag of) the heap object as the source of
 the potential reference to be checked, followed by the address of the referenced type
 descriptor as its destination (line 9).
- Procedure *ptr* is called for each *pointer variable* in the heap object with the address of the pointer variable, followed by the address of the referenced object (line 12).
- Procedure *pvr* is called for each *procedure variable* in the heap object with the address of the procedure variable, followed by the address of the referenced procedure (line 17).

The results of these handler calls are *separately* added up for each handler procedure and returned in the variable parameters *resTyp*, *resPtr* and *resPvr*. By convention, a result of zero indicates that no reference has been found. Apart from that, handler procedures are free to define the semantics of these parameters.

An additional boolean variable parameter *continue* allows a handler procedure to indicate to the caller that it is no longer to be called (lines 8, 10, 11, 15, 16). Note that the scan process itself continues, but only to *unmark* the remaining marked heap objects (line 7).

Procedure Modules. Check uses procedures FindClients, FindDynamicRefs and FindStaticRefs by passing its own private handler procedures HandleClient and HandleRef. These procedures merely set the parameter continue, depending on whether a reference has been found or not.

In passing we note that procedure *Modules.Check* is not only called when a module is unloaded by the *user*, but also by the Oberon *background task* that removes no longer referenced *hidden* module data from memory. Thus, it must be able to handle both visible *and* hidden modules in the data structure rooted in module *Modules*.

Implementation prerequisites

In order to make the outlined validation pass possible, type descriptors of dynamic objects in the heap¹⁶ and descriptors of global module data in the static module blocks contain the *locations of all procedure variables* (in addition to the locations of all *pointer* variables, which were already present in FPGA Oberon) within the described object, adopting an approach employed in one of the earlier implementations of the Oberon system (MacOberon)¹⁷.

The descriptors also contain the offsets of *hidden* (not exported) procedure variables, enabling the module *unload* command to check *all* static and dynamic procedure variable locations in the entire system for possible procedure variable references to the modules to be unloaded.

The resulting run-time representations of a heap record with its associated type descriptor and a module block are shown in Figure 2¹⁸ (the *method table* used to implement Oberon-2 style *type-bound procedures* is not discussed here).

¹⁶ See chapter 8.2 of the book Project Oberon 2013 Edition for a description of an Oberon type descriptor. In essence, it contains information that is s h a r e d by all dynamically allocated records of the same t y p e, such as its size, information about type extensions and the offsets of pointer and procedure variable fields.

| This is not provided in the same t y p e, such as its size, information about type extensions and the offsets of pointer and procedure variable fields.
| This is not provided in the same t y p e, such as its size, information about type extensions and the offsets of pointer and procedure variable fields.

¹⁶ If only procedures declared in the same module were allowed to be assigned to global procedure variables, the meta data section headed by the link mod.pvr would not be needed.




Figure 2: Run-time representation of a dynamic record with its type descriptor and a module block in Experimental Oberon

To make the offsets of hidden *procedure variables* in exported record types available to clients, symbol files also include them. An importing module may, for example, declare a variable of an imported record type, which contains *hidden* procedure variable fields, or declare a record type, which contains (or extends) an imported type. We recall that in FPGA Oberon, hidden *pointers*, although not exported and therefore invisible in client modules, are included in symbol files because their offsets are needed for garbage collection. Similarly, in Experimental Oberon, hidden *procedure variables* are included in symbol files because their offsets are needed for reference checking prior to module unloading, as illustrated in the following example:

```
MODULE MO:
     TYPE P* = PROCEDURE; R* = RECORD p: P END;
 2
                                                                       (*hidden record field p, visible only in M0*)
 3
     PROCEDURE Init*(VAR r: R; p: P); BEGIN r.p := p END Init;
                                                                       (*install procedure p in hidden field r.p*)
 4
    END M0.
 5
 6
    MODULE M1;
 7
     IMPORT M0;
 8
     VAR r: M0.R;
                                                                       (*global variable r with hidden field r.p*)
     PROCEDURE Init*(p: M0.P); BEGIN M0.Init(r, p) END Init;
 9
10
    END M1.
11
    MODULE M2;
12
13
     IMPORT M1;
     PROCEDURE P; BEGIN END P;
14
     PROCEDURE Clear*; BEGIN M1.Init(NIL) END Clear;
15
                                                                       (*clear reference from M1.r.p*)
     PROCEDURE Set*; BEGIN M1.Init(P) END Set;
16
                                                                       (*create reference from M1.r.p to M2.P*)
17
    END M2.
18
19
    M2.Clear
                System.Free M2 ~
                                      unloading sucessful (as no references to M2 exist)
20
    M2.Set
                System.Free M2 ~
                                      unloading failed (procedures of M2 in use in global procedure variables of M1)
```

Here the global record variable *r* declared in module *M1* (line 8) is of an imported record type *M0.R*, which contains a *hidden* procedure variable field *r.p*, directly visible only in M0. If another module *M2* installs a procedure *M2.P* in this field (line 16), a hidden global procedure variable reference from *M1.r.p* to *M2.P* is created, with the effect that *M2* can no longer be unloaded (line 20). In order to be able to check for such hidden references, the location of *M1.r.p* within the module block of *M1* must be known at run time. This is accomplished as follows:

- The offset of the *hidden* record field *p* of the record type *M0.R* is also included in the *symbol* file of *M0*, when M0 is compiled.
- The location of the procedure variable *M1.r.p* within the data section of *M1* (computed as the sum of the start address of the global record *M1.r* and the offset of the field *M0.R.p*) is included in the *object* file of *M1*, when M1 is compiled.
- The location of *M1.r.p* is transferred from the object file of *M1* to the corresponding array in the *meta* data section in the module block, headed by the link *mod.pvr*, when *M1* is loaded.

Hidden *pointers* are included in symbol files without their names, and their (imported) type in the symbol table is of the form *ORB.NilTyp* (as in FPGA Oberon). Hidden *procedure variables* are also included in symbol files without their names, but their (imported) type in the symbol table is of the form *ORB.NoTyp*¹⁹. This choice is reflected in the conditions used to find *all* pointers and procedure variables in various procedures of the compiler²⁰, as illustrated in the following code excerpt of its symbol table handler (module ORB):

```
TYPE Ptrs* = {Pointer, NilTyp};
                                                     (*NilTyp = hidden pointer variable*)
     Procs* = {Proc, NoTyp};
 2
                                                     (*NoTyp = hidden procedure variable*)
 3
    PROCEDURE FindHiddenFields(VAR R: Files.Rider; typ: Type; off: LONGINT);
 4
     VAR fld: Object; i, s: LONGINT;
 5
 6
 7
     IF typ.form IN Ptrs THEN Write(R, Fld); Write(R, 0); Files.WriteNum(R, off)
 8
     ELSIF typ.form IN Procs THEN Write(R, Fld); Write(R, 0); Files.WriteNum(R, -off-1)
 9
      ELSIF typ.form = Record THEN fld := typ.dsc;
10
       WHILE fld # NIL DO FindHiddenFields(R, fld.type, fld.val + off); fld := fld.next END
11
      ELSIF typ.form = Array THEN s := typ.base.size;
      FOR i := 0 TO typ.len-1 DO FindHiddenFields(R, typ.base, i*s + off) END
12
13
      END
    END FindHiddenFields;
```

Assessment of the outlined solution

An obvious shortcoming of the reference checking scheme outlined above is that it requires *additional* run-time information to be present in *all* type descriptors of *all* modules *solely* for the purpose of reference checking, which in turn is *only* needed in the relatively infrequent case of module releases. In addition, module blocks now also contain an *additional* meta data section containing the offsets of global procedure variables. However, since there exists only one type descriptor per declared record *type* rather than one per allocated heap *record*, and global procedure variables tend to be rare, the additional memory requirements are negligible²¹.

¹⁹ This is acceptable because for record fields, the types ORB. NilTyp and ORB.NoTyp are not used otherwise ²⁰ See procedures ORB.FindHiddenFields, ORG.FindRefFlds, ORG.NofRefs and ORG.FindRefs.

See procedures ORB.FindriddenFields, ORG.Norkers and ORG.Findrest.

Adding procedure variable offsets to type descriptors is, strictly speaking, not necessary, as the compiler can always rearrange the memory layout of a record such that all procedure variable fields are placed in a contiguous section at the beginning of it, making their offsets implicit. Thus, it is in principle possible to realize the reference checking scheme without any additional fields in type descriptors. We have refrained from implementing this refinement for two main reasons. First, it would increase the complexity of the compiler. At first glance, it might seem that in order to rearrange a record's field list, only a small change needs to be made to a single procedure in the compiler (ORP.RecordType in FPGA Oberon). However, a complication arises because records may recursively contain other records, each again containing procedure variables at arbitrary offsets. While it is always possible to "flatten" such recursive record structures, it would make other record operations more complex. For example, assignments to subrecords would become less natural, as their fields would no longer be placed in a contiguous section in memory. Second, the memory savings in type descriptors are marginal, given that there exists only one type descriptor per record type rather than one per allocated heap record. Most applications are (or should be) programmed in the conventional programming style, where installed procedures are rare. For example, in the Oberon system, the object-oriented programming style is restricted to the viewer system, which provides distributed control in the form of installed handlers – of which there is usually only one per type of viewer. In sum, the benefit obtained by saving a few fields in a relatively small number of type descriptors is negligible, and therefore the additional effort required to implement this refinement would be hard to justify.

Although the operation of *reference checking* may appear expensive at first, in practice there is no performance issue. It is comparable in complexity to garbage collection and therefore barely noticeable – at least on systems with small to medium sized heaps. This is in spite of the fact that for *each* heap object encountered during the *mark* phase *all* modules to be unloaded are checked for references during the *scan* phase. However, reference checking *stops* when the *first* reference is detected and module unloading is rare except, perhaps, during development.

Thus, the presented solution, which was mainly chosen for its simplicity, appears to be amply sufficient for most practical purposes. We have therefore resisted the temptation to introduce additional "optimizations", whose benefits are often questionable.

* * *

Appendix: Historical notes on module unloading in the Oberon operating system

As stated earlier, in most Oberon implementations, only *client* references are checked prior to module unloading. *Type*, *procedure* and *pointer variable* references to static module data are usually not checked, although various approaches are typically employed to address the case where such references do exist. These approaches can be broadly grouped into two main categories: (a) schemes that explicitly allow invalidating references, and (b) schemes where all past and future references must remain unaffected at all times.

a. Schemes that explicitly allow invalidating references

In such schemes, unloading a module from memory *may*, and in general *will*, lead to "dangling" *type*, *procedure* or *pointer variable* references pointing to no longer valid static module data²². This includes the important case where a structure rooted in a variable of base type T declared in a base module M contains elements of an extension T' defined in a client module M'. Such elements typically contain both *type* references (type tags) and *procedure variable* references (installed handlers) referring to module M'. This is common in the Oberon viewer system, where M is module *Viewers* and M' may be a graphics editor, for example. If the client module M' is unloaded and the module block previously occupied by it is overwritten by another module loaded later, any still existing references to M' become *invalid* at that moment.

Global procedure variables declared in other modules may also refer to procedures declared in module M', although this case is much less common (global procedure variables tend to be used mainly for procedures declared in the same module).

A variety of approaches have been employed in different implementations of the Oberon system to cope with the introduced "dangling" *type, procedure* or *pointer variable* references:

1. On systems that use a memory management unit to perform virtual memory management, such as Ceres-1 or Ceres-2, one approach is to unmap the module space of an unloaded module from virtual memory, thereby invalidating any future references to it. When this is done, any still existing type, procedure or pointer variable references to static module data point to a now unallocated page, and consequently any attempt to access such a page later will result in a system trap.

We consider this an unfortunate proposal for several reasons. First, users generally have no way of knowing *whether* it is in fact safe to unload a module, yet they are allowed to do so. Second, even after having unloaded it, they still don't know whether references from other loaded modules still exist or not — until a *trap* occurs. But then it is often too late. While the trap itself will *prevent* a system crash (as intended), the user may *still* need to restart the system in order to recover an environment without any "frozen" parts, for example displayed viewers that may have been opened by the unloaded module. Note also that this solution requires special hardware support, which may not be available on all systems.

If the *language* Oberon featured the concept of (module) *finalization*, a module could provide code that is executed prior to module *unloading*, similar to the module *initialization* code that is executed after it has been *loaded*. Such a mechanism could be used to close any still open viewers or delete any data elements that may have been created by a module to be unloaded. However, module *finalization* has, regrettably, never been introduced as a feature

10

²² If the programming language Oberon-2 is used, there can also be references to method tables (which however are typically allocated within type descriptors).

in the Oberon *language* (note, however, that it could also be realized at the *system* level by providing a procedure that allows any module to set a finalization routine).

- 2. On systems that do not use virtual memory, such as Ceres-3 or FPGA Oberon on RISC, the easiest way to cope with dangling references is to simply ignore them, i.e. to always release the memory associated with a module without any further precautions (unless, of course, clients exist). While an attempt to access an unloaded module goes undetected initially, the system is still left in an unsafe state, which will become unstable the moment another module loaded later overwrites the previously released module block and other modules or data elements still contain "dangling" references to its (now overwritten) type descriptors, procedures or static objects. This is of course undesirable.
- 3. Another approach, which however can be used only for procedure variable references, is to identify all such references and make them refer to a dummy procedure, thereby preventing a run-time error when such "fixed up" procedures are called later. This solution requires the system to know the locations of all procedure variables in all static and dynamically allocated objects at run time (which can be achieved by including them in symbol and object files). It was used in an earlier version of Experimental Oberon, but was later discarded, mainly because the resulting effect on the overall behavior of a running system is essentially impossible to predict (or even detect) by the user. The fact that some procedure variables somewhere in the system no longer refer to real but to dummy procedures typically becomes "visible" only through the absence of some action such as the absence of mouse tracking if the unloaded module contained a viewer handler, for instance.
- 4. On systems that use *indirection* for procedure calls via a so-called "link table" (where an "address" of a procedure is not a real memory address, but an *index* to this translation table, which the caller consults for every procedure *call* in order to obtain the actual memory location of the called procedure), the same effect can be achieved by setting the *link table entries* for all referenced *procedures* of the module to be unloaded to *dummy* entries, instead of locating and modifying each individual procedure *call* anywhere in the system.

However, using a *link table* to implement indirection for procedure calls is only viable on systems that provide *efficient* hardware support for it. It was used in some earlier versions of the Oberon system on Ceres-1 and Ceres-2 computers, which were based on the (now defunct) NS32000 processor. This processor featured a *call external procedure* instruction (CXP k, where k is the index of the link table entry of the called procedure), which sped up the process of calling external procedures significantly²³. Later versions of the NS processor, however, internally re-implemented the *same* instruction using microcode, which negatively impacted its performance²⁴. For this and a variety of other reasons, the *CXP k* instruction – and with it the *link table* – were no longer used in later versions of the Oberon system.

5. In passing we note that for *type* references, it is actually possible to determine at *compile* time, whether a module *may* lead to references from other loaded modules at *run* time. The criteria is the following: if a module M' does *not* declare record types which are extensions T' of an imported type T, then records declared in module M' *cannot* be inserted in a data structure rooted in a variable v of the imported type T – precisely *because* their types are not

²⁴ The internal re-implementation of the CXP instruction using microcode in later versions of the NS processor followed the general industry trend – starting in the mid 1980s – of implementing only frequent, simple instructions directly with hardware, while interpreting more complex instructions using internal microcode. In general, with the advent of highly regular reduced instruction set computers (RISCs) around that time, the trend towards offering microprocessors providing a smaller set of simple instructions, most of them executing in a single clock cycle, combined with fairly large banks of (fast) registers, continued – and does so to this date.

²³ The use of the link table also increased code density considerably (as only 8 bits for the index instead of 32 bits for the full address were needed to address a procedure in every procedure call). In addition, the link table used by the CXP instruction allowed for an expedient linking process at module load time (as there are far fewer conversions to be performed by the module loader – one for every referenced procedure instead of one for every procedure call) and also eliminated the need for a fixup list (list of the locations of all external procedure references to be fixed up by the module loader) in the object file. A disadvantage is, of course, the need for a (short) link table.

²⁴ The internal re-implementation of the CXP instruction using microcode in later versions of the NS processor followed the general industry trend – starting in the mid 1980s – of implementing the internal procedure in the result in the internal procedure in the processor of highly regular reduced instruction.

extensions of T (in the Oberon programming language, an assignment p := p' is allowed only if the type of p' is the same as the type of p or an extension of it). One *could* therefore introduce a rule that a module M' can be safely dispensed *only* if it does *not* declare record types, which are extensions T' of an imported type T. The flip side of such a rule, however, is that modules that actually *do* declare such types can *never* be unloaded – unless, of course, other ways to safely unload such modules are implemented. Also, *procedure variable* references are not covered by this rule.

Even though most of these approaches have actually been realized in various implementations of the Oberon system, we consider none of them truly satisfactory. In our view, these schemes appear to only tinker with the symptoms of a problem that would not exist, if only one adopted the rule to *disallow* the physical removal (from memory) of still referenced module data.

The main issue appears to be that the moment one *allows* modules to release their associated memory in spite of references to them from other loaded modules, the resulting *dangling* module references must be dealt with *somehow* in order to prevent an almost certain system *crash*. However, *fixing up* or *invalidating* references will *always* remove essential information from the system. As a result, the run-time behavior of the modified system becomes *essentially unpredictable*, as other loaded modules may *critically* depend on the removed functionality. For example, unloading a module that contains an installed handler procedure of a *contents frame* may render it impossible to *close* the enclosing *menu viewer* that contains it, thereby leading to a system with "frozen" parts. A similar problem may occur with references to *type descriptors*, if they are not persisted in memory *after* unloading their associated modules.

b. Schemes where all past and future references must remain unaffected at all times

The second possible interpretation of *unloading* a module consists of schemes where all past and future references *must* remain unaffected at all times. In such schemes, module unloading can be viewed as an implicit mandate to preserve "critical module data", as long as references to the unloaded module exist. Various possible ways to satisfy this requirement exist:

- 1. One could simply exit the module *unload* command with an error message, whenever such references are detected. The user, however, may then be "stuck" with modules that he can *never* unload because they are referenced by modules over which he has no explicit control.
- 2. But the mandate could also be fulfilled by persisting any still referenced module data to a "safe" location before unloading the associated module.

For *type descriptors* referenced by *type tags* in dynamic records a simple solution exists: allocate them *outside* their module blocks in order to persist them beyond the lifetime of their associated module. One possibility is to allocate them in the *heap* itself at load time²⁵. This approach has been implemented in Ceres-Oberon, for instance. It eliminates dangling *type* references altogether and therefore also the *need* to check for them at run time, because type descriptors are unaffected by module unloading. Such dynamically created type descriptors can be deallocated if (a) their associated module has already been unloaded and (b) no *regular* heap objects refer to them via their *type tags*.

For procedures referenced by procedure variables and static objects referenced by pointer variables, no such straightforward solution exists. The only way to "persist" referenced

²⁵ Note that one cannot simply move type descriptors around in memory, as their addresses are (typically) used to implement type tests and type guards. By allocating them in the heap at module I o a d time, one avoids the need to move them to a different location when a module is later unloaded.

procedures or static objects would be to persist the *entire* module (recall that procedures may *access* global module data or *call* other procedures declared in the same module).

We conclude that if one wants to handle type, procedure *and* pointer variable references to static objects, one *cannot* unload a module block from memory, as long as references to it still exist from anywhere in the system²⁶.

- 3. One way to automatically persist type descriptors, procedures and static objects consists of simply never releasing the module block of a module once it is loaded. Instead, when the user requests the "unloading" of a module, the module is only removed from the list of loaded modules, without releasing its associated memory. This amounts to renaming the module, with the implication that a newer version of the same module (with the same name) can be reloaded again. This method has been chosen in MacOberon²⁷. Since the associated memory of a module is never released, the issue of dangling type, procedure or pointer variable references is avoided altogether, as they simply cannot exist. However, it can also lead to higher-than-necessary memory usage if a module is repeatedly loaded and unloaded (typical during development). Nevertheless, such an approach may be viewed as adequate on production or server systems, where module unloading is rare.
- 4. A further *refinement* of the approach outlined above consists of *initially* removing a module only from the module list (as is done in MacOberon), but *in addition* releasing its associated memory *as soon as* there are no more *type, procedure* or *pointer variable* references to static module data. If this is done in an automatic fashion, for example as part of a background process, module data is truly "kept in memory for exactly as long as necessary and removed from it as soon as possible". This is the approach chosen in Experimental Oberon. A variation of it was used in some versions of SparcOberon²⁸.

In sum, module unloading schemes where references remain *unaffected* at all times avoid many of the complications that are inherent in schemes that explicitly *allow* invalidating references. A (small) price to pay is to keep modules loaded in memory, as long as references to them exist.

However, on *production* systems, there is typically no need to keep multiple copies (or versions) of the same module loaded in memory, while on *development* systems it is totally acceptable.

Finally, we note that on modern day computers the amount of available memory, and therefore also the amount of *dynamic* data that can be allocated by modules, typically far exceeds the size of the module blocks holding their program code and global variables. Hence, not releasing module blocks immediately after a module *unload* operation typically has a rather negligible impact on overall memory consumption.

* * *

²⁶ "Mixed" variants are also possible. For example, one could allocate type descriptors in the heap at module load time (as in Ceres-Oberon), and either fix up procedure variable references or prevent the release of a module block if such references still exist; however, most modules referenced by type tags are a l s o referenced by procedure variables – this is in fact the typical case for dynamic records containing installed handler procedures. Thus, it seems more natural to use the s a m e approach for both type and procedure variable references.

27 http://e-collection.library.ethz.ch/eserv/eth/3269/eth-3269-01.pdf (The Implementation of MacOberon, 1990)

http://e-collection.library.ethz.ch/eserv/eth:7103/eth-7103-01.pdf (SPARC-Oberon User's Guide and Implementation, 1990/1991)