Performance measurements





Overview

Roofline

- comparison between hardware configurations
- high-level overview of code performance
- general guidance for optimisation

Overview

Roofline

- comparison between hardware configurations
- high-level overview of code performance
- general guidance for optimisation

Measurements

- ▶ to get more information about bottleneck
- to confirm the hypothesis formed through roofline analysis

Performance measurements

Special purpose registers:

- common in modern hardware
- record low-level performance events
 - number of Flops of different type (scalar, sse, avx)
 - cache miss/hit counts at various levels
 - branch prediction success rate
 - **...**

Performance measurements

Special purpose registers:

- ► common in modern hardware
- record low-level performance events
 - number of Flops of different type (scalar, sse, avx)
 - cache miss/hit counts at various levels
 - branch prediction success rate
 - **...**
- can be overwhelming
- best used to confirm hypothesis from some model

Caveats

- ► Information about
 - the algorithm you implemented
 - ▶ the way you implemented it
 - the data moved in the measured run
- Does not consider
 - potentially better algorithms
 - potentially superior ways of implementing those
 - data you could have moved in a different run

Caveats

- ► Information about
 - the algorithm you implemented
 - ▶ the way you implemented it
 - the data moved in the measured run
- Does not consider
 - potentially better algorithms
 - potentially superior ways of implementing those
 - data you could have moved in a different run

Only meaningful as complements to models.

Granularity

- Direct read of low-level hardware counters
 - most detailed
 - hardware dependent
 - not portable
- Abstract metrics
 - groups of low-level counters
 - easier to compare across hardware
- "instructions" → "instructions per cycle"

How do we measure them?

- ► Use likwid-perfctr (installed on Hamilton via the likwid module).
- ▶ Offers a reasonably friendly command-line interface.
- Provides access both to counters directly, and many useful predefined "groups".
- ▶ Will use likwid-perfctr to measure memory references in different implementations of the same loop.

Example: STREAM

for i from 0 to n: load a[i:i+1] reg1 load b[i:i+1] reg2 load c[i:i+1] reg4 mul reg1 reg2 reg3 add reg4 reg3 reg4 store reg4 c[i:i+1]

AVX

```
for i from 0 to n by 4:
  vload a[i:i+4] vreg1
  vload b[i:i+4] vreg2
  vload c[i:i+4] vreg4
  vmul vreg1 vreg2 vreg3
  vadd reg4 reg3 reg4
  vstore reg4 c[i:i+4]
```

SSE

```
for i from 0 to n by 2:

vload a[i:i+2] vreg1

vload b[i:i+2] vreg2

vload c[i:i+2] vreg4

vmul vreg1 vreg2 vreg3

vadd reg4 reg3 reg4

vstore reg4 c[i:i+2]
```

AVX2

```
for i from 0 to n by 4:
  vload a[i:i+4] vreg1
  vload b[i:i+4] vreg2
  vload c[i:i+4] vreg3
  vfma vreg1 vreg2 vreg3
  vstore reg3 c[i:i+4]
```

Measurement

Model

For $N = 10^6$, how many loads and stores in each case?

Measurement

Model

For $N = 10^6$, how many loads and stores in each case?

Answer

Each loop iteration has 3 loads and 1 store.

With vector width W and N iterations we need:

- $ightharpoonup \frac{3N}{W}$ loads
- $ightharpoonup \frac{N}{W}$ stores

Exercise 5: Models and measurements

- 1. Split into small groups
- 2. Make sure one person per group has access to Hamilton
- 3. Download the STREAM TRIAD benchmark
- 4. Compile with likwid annotations
- 5. Measure loads and stores
- **6.** Ask questions!