Example 1: Basic Conversions

 $15\,\mathrm{kW}\,\mathrm{h} = 54\,\mathrm{MJ}$

We can use Ohm's law: $U = R \cdot I \Leftrightarrow I = \frac{U}{R}$. When applying 115 V on a 0.22 M Ω resistor, the current is 0.523 mA.

Example 2: Switching Converter

The Buck converter is defined by

- Input voltage is given as $V_I = 5 \,\mathrm{V}$
- Output voltage is given as $V_O=2.2\,\mathrm{V}$
- Therefore, the duty cycle can be calculated to D=0.44
- Switching frequency is determined by the controller which uses $f_S=300\,\mathrm{kHz}$
- Output current is given as $I=10\,\mathrm{A}$ and inductor current ripple ratio shall be $CR=30\,\%$
- Therefore, the current ripple can be calculated to $\Delta I_L=3\,\mathrm{A}$

With this information, we can calculate the inductor and output capacitor:

$$L = \frac{D(V_I - V_O)}{\Delta I_L f_S} = 1.369\,\mathrm{\mu H}$$

Now we require the output voltage ripple to be less than $\Delta V_O = 10\,\mathrm{mV}.$

$$C_O \geq \frac{\Delta I_L}{8f_S\Delta V_O} = 125\,\mathrm{\mu F}$$

Example 3: Stress Analysis




Figure 1: I-beam profile (simplified)

• Constant thickness $t = 8 \,\mathrm{mm} \ll H, W$

A very simple I beam is defined using

• Beam length $l = 3 \,\mathrm{m}$

• Height $H = 140 \,\mathrm{mm}$ • Width $W=120\,\mathrm{mm}$

• Applied force at the end $F=18\,\mathrm{kN}$

The area moment of inertia may be approximated in thin-walled profiles like this:

$$\begin{split} I_{yy} &= \int x^2 \, \mathrm{d} a = t \int x^2 \, \mathrm{d} s \\ &= 2t \int_{-\frac{W}{2}}^{+\frac{W}{2}} s^2 \, \mathrm{d} s = 2t \left[\frac{1}{3} s^3 \right]_{-\frac{W}{2}}^{+\frac{W}{2}} = 2t \cdot \frac{1}{3} \cdot 2 \cdot \frac{W^3}{8} = \frac{W^3 t}{\underline{\underline{6}}} \end{split}$$

As well as

$$I_{zz} = t \int y^2 \, \mathrm{d}s = t \left(\frac{WH^2}{2} + \frac{1}{3} \cdot 2 \cdot \frac{W^3}{8} \right) = \frac{WH^2t}{2} + \frac{W^3t}{12}$$

Using the specific sizes, we calculate $I_{yy}=2\,304\,000\,\mathrm{mm^4}$ and $I_{zz}=10\,560\,000\,\mathrm{mm^4}$.

The section modulus measures the resistance against a bending moment: $W_y = \frac{I_{yy}}{W/2} = 38\,400\,\mathrm{mm}^3$ and $W_z=\frac{I_{yy}}{H/2}=150\,857\,\mathrm{mm}^3.$

Now we can calculate the tension under a load.