

# **TABLE OF CONTENTS**

Cha	apter 1. Modules	. 1
1	.1. Mathematical Functions	. 1
1	.2. Single Precision Mathematical Functions	. 1
	acosf	. 2
	acoshf	. 2
	asinf	. 2
	asinhf	3
	atan2f	. 3
	atanf	. 4
	atanhf	. 4
	cbrtf	. 4
	ceilf	. 5
	copysignf	. 5
	cosf	. 5
	coshf	. 6
	cospif	6
	cyl_bessel_i0f	7
	cyl_bessel_i1f	7
	erfcf	. 7
	erfcinvf	. 8
	erfcxf	8
	erff	. 9
	erfinvf	9
	exp10f	9
	exp2f	10
	expf	10
	expm1f	11
	fabsf	11
	fdimf	11
	fdividef	12
	floorf	12
	fmaf	13
	fmaxf	13
	fminf	14
	fmodf	14
	frexpf	15
	hypotf	15
	ilogbf	16
	isfinite	16
	isinf	16

isnan	17
j0f	17
j1f	17
jnf	18
ldexpf	18
lgammaf	19
llrintf	19
llroundf	20
log10f	20
log1pf	20
log2f	21
logbf	21
logf	22
lrintf	22
lroundf	22
modff	23
nanf	23
nearbyintf	23
nextafterf	24
normcdff	24
normcdfinvf	25
powf	25
rcbrtf	26
remainderf	26
remquof	27
rhypotf	
rintf	28
roundf	28
rsqrtf	28
scalblnf	29
scalbnf	29
signbit	29
sincosf	30
sincospif	30
sinf	31
sinhf	31
sinpif	32
sqrtf	32
tanf	
tanhf	33
tgammaf	
truncf	
y0f	

	y1f	.34
	ynf	.35
1.	3. Double Precision Mathematical Functions	. 35
	acos	. 36
	acosh	
	asin	
	asinh	. 37
	atan	
	atan2	.38
	atanh	38
	cbrt	38
	ceil	. 39
	copysign	
	COS	39
	cosh	. 40
	cospi	. 40
	cyl_bessel_i0	4(
	cyl_bessel_i1	41
	erf	. 41
	erfc	42
	erfcinv	. 42
	erfcx	. 42
	erfinv	43
	exp	. 43
	exp10	. 44
	exp2	.44
	expm1	. 44
	fabs	45
	fdim	. 45
	floor	.45
	fma	.46
	fmax	46
	fmin	. 47
	fmod	. 47
	frexp	. 48
	hypot	.48
	ilogb	49
	isfinite	. 49
	isinf	. 50
	isnan	. 50
	j0	. 50
	j1	. 51
	in	. 51

	ldexp	52
	lgamma	52
	llrint	53
	llround	53
	log	53
	log10	54
	log1p	54
	log2	54
	logb	55
	lrint	55
	lround	.55
	modf	56
	nan	56
	nearbyint	57
	nextafter	57
	normcdf	
	normcdfinv	
	pow	
	rcbrt	
	remainder	
	remquo	
	rhypot	
	rint	
	round	
	rsqrt	
	scalbln	
	scalbn	
	signbit	
	sin	
	sincos	
	sincospi	
	sinh	
	sinpi	
	sqrtsqrt	
	tan	
	tanh	
	tgamma	
	trunc	
	y0	
	y1	
	yn	
1.	4. Single Precision Intrinsics	
	cosf	69

_	_exp10f	69
_	_expf	70
_	_fadd_rd	70
_	_fadd_rn	70
_	_fadd_ru	71
_	_fadd_rz	71
_	_fdiv_rd	71
_	_fdiv_rn	72
_	_fdiv_ru	72
_	_fdiv_rz	72
_	_fdividef	73
_	_fmaf_rd	. 73
_	_fmaf_rn	74
_	_fmaf_ru	74
_	_fmaf_rz	75
_	_fmul_rd	75
_	_fmul_rn	76
_	_fmul_ru	76
_	_fmul_rz	76
_	_frcp_rd	.77
_	_frcp_rn	.77
_	_frcp_ru	.77
_	_frcp_rz	. 78
_	_frsqrt_rn	. 78
_	_fsqrt_rd	. 79
_	_fsqrt_rn	. 79
_	_fsqrt_ru	. 79
_	_fsqrt_rz	80
_	_fsub_rd	80
_	_fsub_rn	80
_	_fsub_ru	81
_	_fsub_rz	. 81
_	_log10f	82
_	_log2f	82
_	_logf	82
_	_powf	.83
_	_saturatef	83
_	_sincosf	84
_	_sinf	84
_	_tanf	.84
1.5	. Double Precision Intrinsics	85
_	_dadd_rd	.85
	dadd rn	.85

dadd_ru	86
dadd_rz	86
ddiv_rd	86
ddiv_rn	87
ddiv_ru	87
ddiv_rz	88
dmul_rd	88
dmul_rn	88
dmul_ru	89
dmul_rz	89
drcp_rd	89
drcp_rn	90
drcp_ru	90
drcp_rz	91
dsqrt_rd	91
dsqrt_rn	91
dsqrt_ru	92
dsqrt_rz	92
dsub_rd	93
dsub_rn	93
dsub_ru	
 dsub_rz	94
 fma_rd	
 fma_rn	
 fma_ru	
 fma_rz	
brev	
 brevll	
 byte_perm	
clz	
 clzll	
 ffs	
— ffsll	
 hadd	
 mul24	
 mul64hi	
 mulhi	
popc	
popcil	
rhadd	
sad	
aaauhadd	

umul24	101
umul64hi	102
umulhi	102
urhadd	102
usad	103
1.7. Type Casting Intrinsics	103
double2float_rd	103
double2float_rn	103
double2float_ru	104
double2float_rz	104
double2hiint	104
double2int_rd	104
double2int_rn	105
double2int_ru	105
double2int_rz	105
double2ll_rd	106
double2ll_rn	106
double2ll_ru	106
double2ll_rz	106
double2loint	107
double2uint_rd	107
double2uint_rn	107
double2uint_ru	108
double2uint_rz	108
double2ull_rd	108
double2ull_rn	108
double2ull_ru	109
double2ull_rz	109
double_as_longlong	109
float2half_rn	110
float2int_rd	110
float2int_rn	110
float2int_ru	110
float2int_rz	111
float2ll_rd	111
float2ll_rn	111
float2ll_ru	112
float2ll_rz	112
float2uint_rd	112
float2uint_rn	112
float2uint_ru	113
float2uint_rz	113
float?ull_rd	113

	float2ull_rn	. 114
	float2ull_ru	. 114
	float2ull_rz	114
	float_as_int	.115
	half2float	115
	hiloint2double	.115
	int2double_rn	115
	int2float_rd	.116
	int2float_rn	.116
	int2float_ru	.116
	int2float_rz	. 116
	int_as_float	.117
	ll2double_rd	. 117
	ll2double_rn	. 117
	ll2double_ru	. 118
	ll2double_rz	118
	ll2float_rd	118
	 ll2float_rn	118
		.119
	 longlong_as_double	
	uint2float_rd	
	 uint2float_rn	
	uint2float_ru	
	uint2float_rz	
	ull2double_rd	
	ull2double_rn	
	ull2double_ru	
	ull2double_rz	
	ull2float_rn	
	 ull2float_ru	
	 ull2float_rz	
1.8	B. SIMD Intrinsics	
	vabs2	
	vabs4	
	vabsdiffs2	
	vabsdiffs4	
	vabsdiffu2	
	vabsdiffu4	
	vabsss2	
	vahsss4	

	140	٠,	2/
_	_vadd2		
_	_vadd4		
_	_vaddss2		
_	_vaddss4		
_	_vaddus2		
_	_vaddus4		
_	_vavgs2		
_	_vavgs4		
_	_vavgu2		
_	_vavgu4	1.	29
_	_vcmpeq2	1.	29
_	_vcmpeq4	1.	30
_	_vcmpges2	1.	30
_	_vcmpges4	1.	30
_	_vcmpgeu2	1.	31
_	_vcmpgeu4	1.	31
_	_vcmpgts2	1.	31
_	_vcmpgts4	1.	32
_	_vcmpgtu2	1	32
_	_vcmpgtu4	1	32
_	_vcmples2	1	33
_	_vcmples4	1	33
_	_vcmpleu2		
_	_vcmpleu4	1	34
	_vcmplts2	1	34
	vcmpltu4		
	vcmpne2		
	vcmpne4		
	vhaddu2		
_	vhaddu4		
	vmaxs4		
	_vmaxu2		
	vmaxu4		
_	_vmins2		
	_vmins4		
	_vminu2		
	_vminu4		
	_vneg2		
	_vneg2		
			<del>4</del> 0 40
	VIIE822	-14	40

140
140
141
141
141
142
142
142
143
143
143
144
144
144
145
145
145
146
146
146
147
147
147
148
148
148
149
149
149
150
150

# Chapter 1. MODULES

Here is a list of all modules:

- Mathematical Functions
- Single Precision Mathematical Functions
- Double Precision Mathematical Functions
- Single Precision Intrinsics
- Double Precision Intrinsics
- ► Integer Intrinsics
- Type Casting Intrinsics
- SIMD Intrinsics

### 1.1. Mathematical Functions

CUDA mathematical functions are always available in device code. Some functions are also available in host code as indicated.

Note that floating-point functions are overloaded for different argument types. For example, the log() function has the following prototypes:

```
f double log(double x);
    float log(float x);
    float logf(float x);
```

# 1.2. Single Precision Mathematical Functions

This section describes single precision mathematical functions.

# \_\_device\_\_ float acosf (float x)

Calculate the arc cosine of the input argument.

#### **Returns**

Result will be in radians, in the interval  $[0, \pi]$  for x inside [-1, +1].

- ightharpoonup acosf(1) returns +0.
- $a\cos f(x)$  returns NaN for x outside [-1, +1].

### Description

Calculate the principal value of the arc cosine of the input argument x.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

# \_device\_\_ float acoshf (float x)

Calculate the nonnegative arc hyperbolic cosine of the input argument.

#### Returns

Result will be in the interval  $[0, +\infty]$ .

- acoshf(1) returns 0.
- ▶  $a\cosh f(x)$  returns NaN for x in the interval  $[-\infty, 1)$ .

### Description

Calculate the nonnegative arc hyperbolic cosine of the input argument x.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

# \_device\_\_ float asinf (float x)

Calculate the arc sine of the input argument.

#### Returns

Result will be in radians, in the interval [- $\pi/2$ , + $\pi/2$ ] for x inside [-1, +1].

- asinf(0) returns +0.
- asinf(x) returns NaN for x outside [-1, +1].

Calculate the principal value of the arc sine of the input argument x.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

# \_device\_\_ float asinhf (float x)

Calculate the arc hyperbolic sine of the input argument.

#### **Returns**

asinhf(0) returns 1.

### Description

Calculate the arc hyperbolic sine of the input argument x.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

# \_\_device\_\_ float atan2f (float y, float x)

Calculate the arc tangent of the ratio of first and second input arguments.

### Returns

Result will be in radians, in the interval [-  $\pi$  , +  $\pi$  ].

▶ atan2f(0, 1) returns +0.

### **Description**

Calculate the principal value of the arc tangent of the ratio of first and second input arguments y / x. The quadrant of the result is determined by the signs of inputs y and x.



# \_\_device\_\_ float atanf (float x)

Calculate the arc tangent of the input argument.

#### **Returns**

Result will be in radians, in the interval  $[-\pi/2, +\pi/2]$ .

atanf(0) returns +0.

### Description

Calculate the principal value of the arc tangent of the input argument x.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

# \_\_device\_\_ float atanhf (float x)

Calculate the arc hyperbolic tangent of the input argument.

#### Returns

- atanhf(  $\pm 0$  ) returns  $\pm 0$ .
- ▶ atanhf(  $\pm 1$ ) returns  $\pm \infty$ .
- ▶ atanhf(x) returns NaN for x outside interval [-1, 1].

### Description

Calculate the arc hyperbolic tangent of the input argument x.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

# \_\_device\_\_ float cbrtf (float x)

Calculate the cube root of the input argument.

#### **Returns**

Returns  $x^{1/3}$ .

- cbrtf(  $\pm 0$  ) returns  $\pm 0$ .
- ▶ cbrtf(  $\pm \infty$ ) returns  $\pm \infty$ .

Calculate the cube root of x,  $x^{1/3}$ .



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

# \_device\_\_ float ceilf (float x)

Calculate ceiling of the input argument.

#### Returns

Returns  $\square x \square$  expressed as a floating-point number.

- ceilf(  $\pm 0$ ) returns  $\pm 0$ .
- ceilf(  $\pm \infty$  ) returns  $\pm \infty$ .

### Description

Compute the smallest integer value not less than x.

# \_\_device\_\_ float copysignf (float x, float y)

Create value with given magnitude, copying sign of second value.

#### **Returns**

Returns a value with the magnitude of x and the sign of y.

### Description

Create a floating-point value with the magnitude x and the sign of y.

### \_\_device\_\_ float cosf (float x)

Calculate the cosine of the input argument.

#### Returns

- ightharpoonup cosf(0) returns 1.
- ▶  $cosf(\pm \infty)$  returns NaN.

### **Description**

Calculate the cosine of the input argument x (measured in radians).



- For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.
- ► This function is affected by the --use\_fast\_math compiler flag. See the CUDA C Programming Guide, Appendix D.2, Table 8 for a complete list of functions affected.

# \_\_device\_\_ float coshf (float x)

Calculate the hyperbolic cosine of the input argument.

#### Returns

- ightharpoonup coshf(0) returns 1.
- ▶  $\cosh(\pm \infty)$  returns NaN.

### Description

Calculate the hyperbolic cosine of the input argument x.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

# \_device\_\_ float cospif (float x)

Calculate the cosine of the input argument  $\times \pi$ .

#### Returns

- cospif(  $\pm 0$ ) returns 1.
- ▶ cospif(  $\pm \infty$  ) returns NaN.

### Description

Calculate the cosine of  $x \times \pi$  (measured in radians), where x is the input argument.



# \_\_device\_\_ float cyl\_bessel\_i0f (float x)

Calculate the value of the regular modified cylindrical Bessel function of order 0 for the input argument.

#### Returns

Returns the value of the regular modified cylindrical Bessel function of order 0.

### Description

Calculate the value of the regular modified cylindrical Bessel function of order 0 for the input argument x,  $I_0(x)$ .



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

# \_\_device\_\_ float cyl\_bessel\_i1f (float x)

Calculate the value of the regular modified cylindrical Bessel function of order 1 for the input argument.

#### **Returns**

Returns the value of the regular modified cylindrical Bessel function of order 1.

### Description

Calculate the value of the regular modified cylindrical Bessel function of order 1 for the input argument x,  $I_1(x)$ .



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

# \_\_device\_\_ float erfcf (float x)

Calculate the complementary error function of the input argument.

#### Returns

- erfcf( $-\infty$ ) returns 2.
- erfcf(  $+ \infty$  ) returns +0.

Calculate the complementary error function of the input argument x, 1 - erf(x).



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

# \_device\_\_ float erfcinvf (float y)

Calculate the inverse complementary error function of the input argument.

#### **Returns**

- erfcinvf(0) returns  $+\infty$ .
- erfcinvf(2) returns  $-\infty$ .

### Description

Calculate the inverse complementary error function of the input argument y, for y in the interval [0, 2]. The inverse complementary error function find the value x that satisfies the equation  $y = \operatorname{erfc}(x)$ , for  $0 \le y \le 2$ , and  $-\infty \le x \le \infty$ .



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

# \_\_device\_\_ float erfcxf (float x)

Calculate the scaled complementary error function of the input argument.

#### Returns

- erfcxf( $-\infty$ ) returns  $+\infty$
- erfcxf(  $+ \infty$  ) returns +0
- erfcxf(x) returns  $+\infty$  if the correctly calculated value is outside the single floating point range.

### Description

Calculate the scaled complementary error function of the input argument x,  $e^{x^2} \cdot \operatorname{erfc}(x)$ .



# \_\_device\_\_ float erff (float x)

Calculate the error function of the input argument.

#### Returns

- erff(  $\pm 0$  ) returns  $\pm 0$ .
- erff(  $\pm \infty$  ) returns  $\pm 1$ .

### Description

Calculate the value of the error function for the input argument  $\times$ ,  $\frac{2}{\sqrt{\pi}} \int_{0}^{x} e^{-t^2} dt$ .



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

# \_\_device\_\_ float erfinvf (float y)

Calculate the inverse error function of the input argument.

### **Returns**

- erfinvf(1) returns  $+\infty$ .
- erfinvf(-1) returns  $-\infty$ .

### Description

Calculate the inverse error function of the input argument y, for y in the interval [-1, 1]. The inverse error function finds the value x that satisfies the equation y = erf(x), for  $-1 \le y \le 1$ , and  $-\infty \le x \le \infty$ .



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

# \_device\_\_ float exp10f (float x)

Calculate the base 10 exponential of the input argument.

#### Returns

Returns  $10^x$ .

Calculate the base 10 exponential of the input argument x.



- For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.
- ► This function is affected by the --use\_fast\_math compiler flag. See the CUDA C Programming Guide, Appendix D.2, Table 8 for a complete list of functions affected.

# \_\_device\_\_ float exp2f (float x)

Calculate the base 2 exponential of the input argument.

#### Returns

Returns  $2^x$ .

### Description

Calculate the base 2 exponential of the input argument x.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

# \_\_device\_\_ float expf (float x)

Calculate the base e exponential of the input argument.

#### Returns

Returns  $e^{x}$ .

### Description

Calculate the base e exponential of the input argument x,  $e^x$ .



- For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.
- ► This function is affected by the --use\_fast\_math compiler flag. See the CUDA C Programming Guide, Appendix D.2, Table 8 for a complete list of functions affected.

# \_\_device\_\_ float expm1f (float x)

Calculate the base *e* exponential of the input argument, minus 1.

#### Returns

Returns  $e^{x} - 1$ .

### Description

Calculate the base *e* exponential of the input argument x, minus 1.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

# \_\_device\_\_ float fabsf (float x)

Calculate the absolute value of its argument.

#### Returns

Returns the absolute value of its argument.

- ▶ fabs(  $\pm \infty$ ) returns  $+ \infty$ .
- fabs(  $\pm 0$ ) returns 0.

#### Description

Calculate the absolute value of the input argument x.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

# \_device\_\_ float fdimf (float x, float y)

Compute the positive difference between x and y.

#### Returns

Returns the positive difference between x and y.

- fdimf(x, y) returns x y if x > y.
- fdimf(x, y) returns +0 if  $x \le y$ .

Compute the positive difference between x and y. The positive difference is x - y when x > y and +0 otherwise.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

# \_\_device\_\_ float fdividef (float x, float y)

Divide two floating point values.

#### Returns

Returns x / y.

### Description

Compute x divided by y. If --use\_fast\_math is specified, use \_\_fdividef() for higher performance, otherwise use normal division.



- For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.
- ► This function is affected by the --use\_fast\_math compiler flag. See the CUDA C Programming Guide, Appendix D.2, Table 8 for a complete list of functions affected.

# \_\_device\_\_ float floorf (float x)

Calculate the largest integer less than or equal to x.

#### Returns

Returns  $log_o(1+x)$  expressed as a floating-point number.

- floorf(  $\pm \infty$  ) returns  $\pm \infty$ .
- floorf(  $\pm 0$ ) returns  $\pm 0$ .

### Description

Calculate the largest integer value which is less than or equal to x.



# \_\_device\_\_ float fmaf (float x, float y, float z)

Compute  $x \times y + z$  as a single operation.

#### **Returns**

Returns the rounded value of  $x \times y + z$  as a single operation.

- fmaf(  $\pm \infty$ ,  $\pm 0$ , z) returns NaN.
- fmaf(  $\pm 0$ ,  $\pm \infty$ , z) returns NaN.
- ▶ fmaf(x, y,  $-\infty$ ) returns NaN if  $x \times y$  is an exact  $+\infty$ .
- ▶ fmaf(x, y,  $+\infty$ ) returns NaN if  $x \times y$  is an exact  $-\infty$ .

### Description

Compute the value of  $x \times y + z$  as a single ternary operation. After computing the value to infinite precision, the value is rounded once.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

# \_\_device\_\_ float fmaxf (float x, float y)

Determine the maximum numeric value of the arguments.

#### Returns

Returns the maximum numeric values of the arguments x and y.

- If both arguments are NaN, returns NaN.
- ▶ If one argument is NaN, returns the numeric argument.

### Description

Determines the maximum numeric value of the arguments x and y. Treats NaN arguments as missing data. If one argument is a NaN and the other is legitimate numeric value, the numeric value is chosen.



# \_\_device\_\_ float fminf (float x, float y)

Determine the minimum numeric value of the arguments.

#### Returns

Returns the minimum numeric values of the arguments x and y.

- ▶ If both arguments are NaN, returns NaN.
- ▶ If one argument is NaN, returns the numeric argument.

### **Description**

Determines the minimum numeric value of the arguments x and y. Treats NaN arguments as missing data. If one argument is a NaN and the other is legitimate numeric value, the numeric value is chosen.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

# \_\_device\_\_ float fmodf (float x, float y)

Calculate the floating-point remainder of x / y.

#### Returns

- Returns the floating point remainder of x / y.
- fmodf(  $\pm 0$ , y) returns  $\pm 0$  if y is not zero.
- ▶ fmodf(x, y) returns NaN and raised an invalid floating point exception if x is  $\pm \infty$  or y is zero.
- fmodf(x, y) returns zero if y is zero or the result would overflow.
- fmodf(x,  $\pm \infty$ ) returns x if x is finite.
- fmodf(x, 0) returns NaN.

### Description

Calculate the floating-point remainder of x / y. The absolute value of the computed value is always less than y 's absolute value and will have the same sign as x.



# \_\_device\_\_ float frexpf (float x, int \*nptr)

Extract mantissa and exponent of a floating-point value.

#### Returns

Returns the fractional component m.

- frexp(0, nptr) returns 0 for the fractional component and zero for the integer component.
- frexp( $\pm 0$ , nptr) returns  $\pm 0$  and stores zero in the location pointed to by nptr.
- ▶ frexp(  $\pm \infty$ , nptr) returns  $\pm \infty$  and stores an unspecified value in the location to which nptr points.
- frexp(NaN, y) returns a NaN and stores an unspecified value in the location to which nptr points.

### Description

Decomposes the floating-point value x into a component m for the normalized fraction element and another term n for the exponent. The absolute value of m will be greater than or equal to 0.5 and less than 1.0 or it will be equal to 0;  $x = m \cdot 2^n$ . The integer exponent n will be stored in the location to which nptr points.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

# \_device\_\_ float hypotf (float x, float y)

Calculate the square root of the sum of squares of two arguments.

#### Returns

Returns the length of the hypotenuse  $\sqrt{x^2 + y^2}$ . If the correct value would overflow, returns  $+\infty$ . If the correct value would underflow, returns 0.

### Description

Calculates the length of the hypotenuse of a right triangle whose two sides have lengths x and y without undue overflow or underflow.



# \_\_device\_\_ int ilogbf (float x)

Compute the unbiased integer exponent of the argument.

#### **Returns**

- ▶ If successful, returns the unbiased exponent of the argument.
- ▶ ilogbf(0) returns INT MIN.
- ▶ ilogbf(NaN) returns NaN.
- ▶ ilogbf(x) returns INT MAX if x is  $\infty$  or the correct value is greater than INT MAX.
- ▶ ilogbf(x) return INT MIN if the correct value is less than INT MIN.

### Description

Calculates the unbiased integer exponent of the input argument x.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

# \_\_device\_\_ \_\_RETURN\_TYPE isfinite (float a)

Determine whether argument is finite.

#### Returns

- ▶ With Visual Studio 2013 host compiler: \_\_RETURN\_TYPE is 'bool'. Returns true if and only if a is a finite value.
- ▶ With other host compilers: \_\_RETURN\_TYPE is 'int'. Returns a nonzero value if and only if a is a finite value.

### Description

Determine whether the floating-point value a is a finite value (zero, subnormal, or normal and not infinity or NaN).

### \_\_device\_\_ \_\_RETURN\_TYPE isinf (float a)

Determine whether argument is infinite.

#### Returns

- ▶ With Visual Studio 2013 host compiler: \_\_RETURN\_TYPE is 'bool'. Returns true if and only if a is a infinite value.
- ▶ With other host compilers: \_\_RETURN\_TYPE is 'int'. Returns a nonzero value if and only if a is a infinite value.

Determine whether the floating-point value a is an infinite value (positive or negative).

# \_\_device\_\_ \_\_RETURN\_TYPE isnan (float a)

Determine whether argument is a NaN.

### Returns

- ▶ With Visual Studio 2013 host compiler: \_\_RETURN\_TYPE is 'bool'. Returns true if and only if a is a NaN value.
- ▶ With other host compilers: \_\_RETURN\_TYPE is 'int'. Returns a nonzero value if and only if a is a NaN value.

### Description

Determine whether the floating-point value a is a NaN.

# \_\_device\_\_ float j0f (float x)

Calculate the value of the Bessel function of the first kind of order 0 for the input argument.

#### Returns

Returns the value of the Bessel function of the first kind of order 0.

- ▶  $i0f(\pm \infty)$  returns +0.
- ▶ j0f(NaN) returns NaN.

### Description

Calculate the value of the Bessel function of the first kind of order 0 for the input argument x,  $J_0(x)$ .



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

# \_device\_\_ float j1f (float x)

Calculate the value of the Bessel function of the first kind of order 1 for the input argument.

#### **Returns**

Returns the value of the Bessel function of the first kind of order 1.

- $j1f(\pm 0)$  returns  $\pm 0$ .
- ▶  $i1f(\pm \infty)$  returns +0.
- ▶ j1f(NaN) returns NaN.

Calculate the value of the Bessel function of the first kind of order 1 for the input argument x,  $J_1(x)$ .



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

# \_device\_\_ float jnf (int n, float x)

Calculate the value of the Bessel function of the first kind of order n for the input argument.

#### **Returns**

Returns the value of the Bessel function of the first kind of order n.

- jnf(n, NaN) returns NaN.
- $\inf(n, x)$  returns NaN for n < 0.
- ▶  $\inf(n, +\infty)$  returns +0.

### Description

Calculate the value of the Bessel function of the first kind of order n for the input argument x,  $J_n(x)$ .



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

# \_\_device\_\_ float ldexpf (float x, int exp)

Calculate the value of  $x \cdot 2^{exp}$ .

#### **Returns**

▶ ldexpf(x) returns  $\pm \infty$  if the correctly calculated value is outside the single floating point range.

### Description

Calculate the value of  $x \cdot 2^{exp}$  of the input arguments x and exp.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

# \_device\_\_ float lgammaf (float x)

Calculate the natural logarithm of the absolute value of the gamma function of the input argument.

#### **Returns**

- ▶ lgammaf(1) returns +0.
- ▶ lgammaf(2) returns +0.
- ▶ lgammaf(x) returns  $\pm \infty$  if the correctly calculated value is outside the single floating point range.
- ▶ lgammaf(x) returns  $+\infty$  if  $x \le 0$ .
- ▶ lgammaf( $-\infty$ ) returns  $-\infty$ .
- ▶ lgammaf(  $+\infty$ ) returns  $+\infty$ .

### Description

Calculate the natural logarithm of the absolute value of the gamma function of the input argument x, namely the value of  $log_{e} \int_{0}^{\infty} e^{-t} t^{x-1} dt$ .



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

# \_\_device\_\_ long long int llrintf (float x)

Round input to nearest integer value.

#### Returns

Returns rounded integer value.

### Description

Round x to the nearest integer value, with halfway cases rounded towards zero. If the result is outside the range of the return type, the result is undefined.

# \_\_device\_\_ long long int llroundf (float x)

Round to nearest integer value.

#### Returns

Returns rounded integer value.

### Description

Round x to the nearest integer value, with halfway cases rounded away from zero. If the result is outside the range of the return type, the result is undefined.



This function may be slower than alternate rounding methods. See llrintf().

# \_\_device\_\_ float log10f (float x)

Calculate the base 10 logarithm of the input argument.

#### Returns

- ▶  $\log 10f(\pm 0)$  returns  $-\infty$ .
- ▶ log10f(1) returns +0.
- ▶ log10f(x) returns NaN for x < 0.
- ▶  $log10f(+\infty)$  returns  $+\infty$ .

### Description

Calculate the base 10 logarithm of the input argument x.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

# \_\_device\_\_ float log1pf (float x)

Calculate the value of  $log_o(1+x)$ .

#### Returns

- log1pf(  $\pm 0$  ) returns  $-\infty$ .
- $\blacktriangleright$  log1pf(-1) returns +0.
- ▶ log1pf(x) returns NaN for x < -1.
- ▶  $log1pf(+\infty)$  returns  $+\infty$ .

Calculate the value of  $log_a(1+x)$  of the input argument x.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

# \_device\_\_ float log2f (float x)

Calculate the base 2 logarithm of the input argument.

#### Returns

- ▶  $\log 2f(\pm 0)$  returns  $-\infty$ .
- ightharpoonup log2f(1) returns +0.
- ▶ log2f(x) returns NaN for x < 0.
- ▶  $\log 2f(+\infty)$  returns  $+\infty$ .

### Description

Calculate the base 2 logarithm of the input argument x.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

# \_\_device\_\_ float logbf (float x)

Calculate the floating point representation of the exponent of the input argument.

#### **Returns**

- ▶ logbf  $\pm 0$  returns  $-\infty$
- ▶  $logbf + \infty returns + \infty$

### Description

Calculate the floating point representation of the exponent of the input argument x.



# \_\_device\_\_ float logf (float x)

Calculate the natural logarithm of the input argument.

#### Returns

- ▶  $logf(\pm 0)$  returns  $-\infty$ .
- ▶ logf(1) returns +0.
- ▶ logf(x) returns NaN for x < 0.
- ▶  $logf(+\infty)$  returns  $+\infty$ .

### Description

Calculate the natural logarithm of the input argument x.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

# \_\_device\_\_ long int lrintf (float x)

Round input to nearest integer value.

#### Returns

Returns rounded integer value.

### Description

Round x to the nearest integer value, with halfway cases rounded towards zero. If the result is outside the range of the return type, the result is undefined.

# \_\_device\_\_ long int lroundf (float x)

Round to nearest integer value.

#### Returns

Returns rounded integer value.

### Description

Round x to the nearest integer value, with halfway cases rounded away from zero. If the result is outside the range of the return type, the result is undefined.



This function may be slower than alternate rounding methods. See lrintf().

# \_\_device\_\_ float modff (float x, float \*iptr)

Break down the input argument into fractional and integral parts.

#### Returns

- modff( $\pm x$ , iptr) returns a result with the same sign as x.
- ▶ modff(  $\pm \infty$ , iptr) returns  $\pm 0$  and stores  $\pm \infty$  in the object pointed to by iptr.
- modff(NaN, iptr) stores a NaN in the object pointed to by iptr and returns a NaN.

### Description

Break down the argument  $\times$  into fractional and integral parts. The integral part is stored in the argument <code>iptr</code>. Fractional and integral parts are given the same sign as the argument  $\times$ .



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

# \_\_device\_\_ float nanf (const char \*tagp)

Returns "Not a Number" value.

#### Returns

nanf(tagp) returns NaN.

### Description

Return a representation of a quiet NaN. Argument tagp selects one of the possible representations.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

# \_device\_\_ float nearbyintf (float x)

Round the input argument to the nearest integer.

### **Returns**

- nearbyintf(  $\pm 0$  ) returns  $\pm 0$ .
- ▶ nearbyintf(  $\pm \infty$ ) returns  $\pm \infty$ .

Round argument x to an integer value in single precision floating-point format.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

# \_device\_\_ float nextafterf (float x, float y)

Return next representable single-precision floating-point value afer argument.

### Returns

▶ nextafterf(  $\pm \infty$ , y) returns  $\pm \infty$ .

### Description

Calculate the next representable single-precision floating-point value following x in the direction of y. For example, if y is greater than x, nextafterf() returns the smallest representable number greater than x



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

# \_\_device\_\_ float normcdff (float y)

Calculate the standard normal cumulative distribution function.

### Returns

- ▶ normcdff(  $+\infty$ ) returns 1
- ▶ normcdff( $-\infty$ ) returns +0

### Description

Calculate the cumulative distribution function of the standard normal distribution for input argument y,  $\Phi(y)$ .



# \_\_device\_\_ float normcdfinvf (float y)

Calculate the inverse of the standard normal cumulative distribution function.

#### Returns

- ▶ normcdfinvf(0) returns  $-\infty$ .
- ▶ normcdfinvf(1) returns  $+\infty$ .
- normcdfinvf(x) returns NaN if x is not in the interval [0,1].

### Description

Calculate the inverse of the standard normal cumulative distribution function for input argument y,  $\Phi^{-1}(y)$ . The function is defined for input values in the interval (0, 1).



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

# \_device\_\_ float powf (float x, float y)

Calculate the value of first argument to the power of second argument.

- ▶ powf(  $\pm 0$ , y) returns  $\pm \infty$  for y an integer less than 0.
- powf(  $\pm 0$ , y) returns  $\pm 0$  for y an odd integer greater than 0.
- powf( $\pm 0$ , y) returns +0 for y > 0 and not and odd integer.
- ▶ powf(-1,  $\pm \infty$ ) returns 1.
- $\triangleright$  powf(+1, y) returns 1 for any y, even a NaN.
- powf(x,  $\pm 0$ ) returns 1 for any x, even a NaN.
- ightharpoonup powf(x, y) returns a NaN for finite x < 0 and finite non-integer y.
- ▶ powf(x,  $-\infty$ ) returns  $+\infty$  for |x| < 1.
- ▶ powf(x,  $-\infty$ ) returns +0 for |x| > 1.
- ▶ powf(x, +∞) returns +0 for |x| < 1.
- ▶ powf(x, +∞) returns +∞ for |x| > 1.
- ▶ powf( $-\infty$ , y) returns -0 for y an odd integer less than 0.
- ▶ powf( $-\infty$ , y) returns +0 for y < 0 and not an odd integer.
- ▶ powf( $-\infty$ , y) returns  $-\infty$  for y an odd integer greater than 0.
- ▶ powf( $-\infty$ , y) returns  $+\infty$  for y > 0 and not an odd integer.
- ▶ powf(  $+\infty$ , y) returns +0 for y < 0.
- ▶ powf(  $+\infty$ , y) returns  $+\infty$  for y > 0.

Calculate the value of x to the power of y.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

# \_device\_\_ float rcbrtf (float x)

Calculate reciprocal cube root function.

#### **Returns**

- rcbrt(  $\pm 0$ ) returns  $\pm \infty$ .
- rcbrt(  $\pm \infty$  ) returns  $\pm 0$ .

### Description

Calculate reciprocal cube root function of x



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

# \_device\_\_ float remainderf (float x, float y)

Compute single-precision floating-point remainder.

### **Returns**

- remainder f(x, 0) returns NaN.
- remainderf(  $\pm \infty$ , y) returns NaN.
- ▶ remainderf(x,  $\pm \infty$ ) returns x for finite x.

### Description

Compute single-precision floating-point remainder r of dividing x by y for nonzero y. Thus r = x - ny. The value n is the integer value nearest  $\frac{X}{y}$ . In the case when  $|n - \frac{X}{y}| = \frac{1}{2}$ , the even n value is chosen.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

# \_\_device\_\_ float remquof (float x, float y, int \*quo)

Compute single-precision floating-point remainder and part of quotient.

#### Returns

Returns the remainder.

- remquof(x, 0, quo) returns NaN.
- ▶ remquof(  $\pm \infty$ , y, quo) returns NaN.
- remquof(x,  $\pm \infty$ , quo) returns x.

### Description

Compute a double-precision floating-point remainder in the same way as the remainderf() function. Argument quo returns part of quotient upon division of x by y. Value quo has the same sign as  $\frac{X}{Y}$  and may not be the exact quotient but agrees with the exact quotient in the low order 3 bits.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

# \_\_device\_\_ float rhypotf (float x, float y)

Calculate one over the square root of the sum of squares of two arguments.

#### Returns

Returns one over the length of the hypotenuse  $\frac{1}{\sqrt{x^2+y^2}}$ . If the square root would overflow, returns 0. If the square root would underflow, returns  $+\infty$ .

### Description

Calculates one over the length of the hypotenuse of a right triangle whose two sides have lengths x and y without undue overflow or underflow.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

# \_\_device\_\_ float rintf (float x)

Round input to nearest integer value in floating-point.

#### Returns

Returns rounded integer value.

### Description

Round x to the nearest integer value in floating-point format, with halfway cases rounded towards zero.

# \_\_device\_\_ float roundf (float x)

Round to nearest integer value in floating-point.

#### Returns

Returns rounded integer value.

### Description

Round  $\times$  to the nearest integer value in floating-point format, with halfway cases rounded away from zero.



This function may be slower than alternate rounding methods. See rintf().

# \_\_device\_\_ float rsqrtf (float x)

Calculate the reciprocal of the square root of the input argument.

#### **Returns**

Returns  $1/\sqrt{x}$ .

- rsqrtf( + ∞) returns +0.
- rsqrtf(  $\pm 0$ ) returns  $\pm \infty$ .
- rsqrtf(x) returns NaN if x is less than 0.

### Description

Calculate the reciprocal of the nonnegative square root of  $\times$ ,  $1/\sqrt{x}$ .



# \_\_device\_\_ float scalblnf (float x, long int n)

Scale floating-point input by integer power of two.

#### Returns

Returns  $\times * 2^n$ .

- scalblnf(  $\pm 0$ , n) returns  $\pm 0$ .
- scalblnf(x, 0) returns x.
- ▶ scalblnf(  $\pm \infty$ , n) returns  $\pm \infty$ .

### Description

Scale  $\times$  by  $2^n$  by efficient manipulation of the floating-point exponent.

# \_\_device\_\_ float scalbnf (float x, int n)

Scale floating-point input by integer power of two.

### Returns

Returns  $x * 2^n$ .

- scalbnf(  $\pm 0$ , n) returns  $\pm 0$ .
- $\blacktriangleright$  scalbnf(x, 0) returns x.
- ▶ scalbnf(  $\pm \infty$ , n) returns  $\pm \infty$ .

#### Description

Scale  $\times$  by  $2^n$  by efficient manipulation of the floating-point exponent.

# \_\_device\_\_ \_\_RETURN\_TYPE signbit (float a)

Return the sign bit of the input.

#### **Returns**

Reports the sign bit of all values including infinities, zeros, and NaNs.

With Visual Studio 2013 host compiler: \_\_RETURN\_TYPE is 'bool'. Returns true if and only if a is negative. ▶ With other host compilers: \_\_RETURN\_TYPE is 'int'. Returns a nonzero value if and only if a is negative.

### Description

Determine whether the floating-point value a is negative.

# \_\_device\_\_ void sincosf (float x, float \*sptr, float \*cptr)

Calculate the sine and cosine of the first input argument.

#### Returns

none

### Description

Calculate the sine and cosine of the first input argument x (measured in radians). The results for sine and cosine are written into the second argument, sptr, and, respectively, third argument, cptr.

#### See also:

sinf() and cosf().



- For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.
- ► This function is affected by the --use\_fast\_math compiler flag. See the CUDA C Programming Guide, Appendix D.2, Table 8 for a complete list of functions affected.

# \_\_device\_\_ void sincospif (float x, float \*sptr, float \*cptr)

Calculate the sine and cosine of the first input argument  $\times \pi$ .

#### Returns

none

### Description

Calculate the sine and cosine of the first input argument, x (measured in radians), x  $\pi$ . The results for sine and cosine are written into the second argument, sptr, and, respectively, third argument, cptr.

### See also:

sinpif() and cospif().



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

# \_device\_\_ float sinf (float x)

Calculate the sine of the input argument.

#### Returns

- $sinf(\pm 0)$  returns  $\pm 0$ .
- ▶  $sinf(\pm \infty)$  returns NaN.

### Description

Calculate the sine of the input argument x (measured in radians).



- For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.
- ► This function is affected by the --use\_fast\_math compiler flag. See the CUDA C Programming Guide, Appendix D.2, Table 8 for a complete list of functions affected.

# \_\_device\_\_ float sinhf (float x)

Calculate the hyperbolic sine of the input argument.

#### Returns

- $\sinh(\pm 0)$  returns  $\pm 0$ .
- ▶  $\sinh(\pm \infty)$  returns NaN.

### Description

Calculate the hyperbolic sine of the input argument x.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

# \_\_device\_\_ float sinpif (float x)

Calculate the sine of the input argument  $\times \pi$ .

#### **Returns**

- sinpif(  $\pm 0$  ) returns  $\pm 0$ .
- ▶ sinpif(  $\pm \infty$ ) returns NaN.

### Description

Calculate the sine of  $x \times \pi$  (measured in radians), where x is the input argument.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

# \_device\_\_ float sqrtf (float x)

Calculate the square root of the input argument.

#### **Returns**

Returns  $\sqrt{x}$ .

- sqrtf(  $\pm 0$  ) returns  $\pm 0$ .
- ▶ sqrtf(  $+\infty$ ) returns  $+\infty$ .
- $\operatorname{sqrtf}(x)$  returns NaN if x is less than 0.

### Description

Calculate the nonnegative square root of x,  $\sqrt{x}$ .



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

# \_device\_\_ float tanf (float x)

Calculate the tangent of the input argument.

- $tanf(\pm 0)$  returns  $\pm 0$ .
- ▶  $tanf(\pm \infty)$  returns NaN.

Calculate the tangent of the input argument x (measured in radians).



- For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.
- ► This function is affected by the --use\_fast\_math compiler flag. See the CUDA C Programming Guide, Appendix D.2, Table 8 for a complete list of functions affected.

# \_\_device\_\_ float tanhf (float x)

Calculate the hyperbolic tangent of the input argument.

#### Returns

•  $\tanh(\pm 0)$  returns  $\pm 0$ .

### Description

Calculate the hyperbolic tangent of the input argument x.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

# \_\_device\_\_ float tgammaf (float x)

Calculate the gamma function of the input argument.

#### Returns

- ▶ tgammaf(  $\pm 0$ ) returns  $\pm \infty$ .
- tgammaf(2) returns +0.
- ▶ tgammaf(x) returns  $\pm \infty$  if the correctly calculated value is outside the single floating point range.
- tgammaf(x) returns NaN if x < 0.
- ▶ tgammaf( $-\infty$ ) returns NaN.
- ▶ tgammaf(  $+ \infty$ ) returns  $+ \infty$ .

### Description

Calculate the gamma function of the input argument x, namely the value of  $\int_0^\infty e^{-t} t^{x-1} dt$ .



# \_\_device\_\_ float truncf (float x)

Truncate input argument to the integral part.

#### Returns

Returns truncated integer value.

### Description

Round x to the nearest integer value that does not exceed x in magnitude.

# \_\_device\_\_ float y0f (float x)

Calculate the value of the Bessel function of the second kind of order 0 for the input argument.

#### **Returns**

Returns the value of the Bessel function of the second kind of order 0.

- ▶ y0f(0) returns  $-\infty$ .
- y0f(x) returns NaN for x < 0.
- ▶  $y0f(+\infty)$  returns +0.
- ▶ y0f(NaN) returns NaN.

#### Description

Calculate the value of the Bessel function of the second kind of order 0 for the input argument x,  $Y_0(x)$ .



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

# \_device\_\_ float y1f (float x)

Calculate the value of the Bessel function of the second kind of order 1 for the input argument.

#### **Returns**

Returns the value of the Bessel function of the second kind of order 1.

- ▶ y1f(0) returns  $-\infty$ .
- ▶ y1f(x) returns NaN for x < 0.
- ▶  $y1f(+\infty)$  returns +0.
- ▶ y1f(NaN) returns NaN.

Calculate the value of the Bessel function of the second kind of order 1 for the input argument x,  $Y_1(x)$ .



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

# \_\_device\_\_ float ynf (int n, float x)

Calculate the value of the Bessel function of the second kind of order n for the input argument.

#### Returns

Returns the value of the Bessel function of the second kind of order n.

- ynf(n, x) returns NaN for n < 0.
- ▶ ynf(n, 0) returns  $-\infty$ .
- ynf(n, x) returns NaN for x < 0.
- ▶  $ynf(n, +\infty)$  returns +0.
- ynf(n, NaN) returns NaN.

### Description

Calculate the value of the Bessel function of the second kind of order n for the input argument x,  $Y_n(x)$ .



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

# 1.3. Double Precision Mathematical Functions

This section describes double precision mathematical functions.

# \_\_device\_\_ double acos (double x)

Calculate the arc cosine of the input argument.

#### Returns

Result will be in radians, in the interval  $[0, \pi]$  for x inside [-1, +1].

- acos(1) returns +0.
- acos(x) returns NaN for x outside [-1, +1].

### Description

Calculate the principal value of the arc cosine of the input argument x.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

### \_device\_\_ double acosh (double x)

Calculate the nonnegative arc hyperbolic cosine of the input argument.

#### Returns

Result will be in the interval  $[0, +\infty]$ .

- acosh(1) returns 0.
- ▶  $a\cosh(x)$  returns NaN for x in the interval  $[-\infty, 1)$ .

### Description

Calculate the nonnegative arc hyperbolic cosine of the input argument x.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

# \_device\_\_ double asin (double x)

Calculate the arc sine of the input argument.

#### Returns

Result will be in radians, in the interval  $[-\pi/2, +\pi/2]$  for x inside [-1, +1].

- ightharpoonup asin(0) returns +0.
- asin(x) returns NaN for x outside [-1, +1].

Calculate the principal value of the arc sine of the input argument x.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

# \_device\_\_ double asinh (double x)

Calculate the arc hyperbolic sine of the input argument.

#### **Returns**

asinh(0) returns 1.

### Description

Calculate the arc hyperbolic sine of the input argument x.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

# \_\_device\_\_ double atan (double x)

Calculate the arc tangent of the input argument.

### Returns

Result will be in radians, in the interval  $[-\pi/2, +\pi/2]$ .

ightharpoonup atan(0) returns +0.

### **Description**

Calculate the principal value of the arc tangent of the input argument x.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

# \_\_device\_\_ double atan2 (double y, double x)

Calculate the arc tangent of the ratio of first and second input arguments.

#### **Returns**

Result will be in radians, in the interval  $[-\pi/, +\pi]$ .

▶ atan2(0, 1) returns +0.

### Description

Calculate the principal value of the arc tangent of the ratio of first and second input arguments y / x. The quadrant of the result is determined by the signs of inputs y and x.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

# \_\_device\_\_ double atanh (double x)

Calculate the arc hyperbolic tangent of the input argument.

#### **Returns**

- atanh(  $\pm 0$ ) returns  $\pm 0$ .
- ▶ atanh(  $\pm 1$ ) returns  $\pm \infty$ .
- atanh(x) returns NaN for x outside interval [-1, 1].

### Description

Calculate the arc hyperbolic tangent of the input argument x.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

# \_device\_\_ double cbrt (double x)

Calculate the cube root of the input argument.

### Returns

Returns  $x^{1/3}$ .

- cbrt(  $\pm 0$  ) returns  $\pm 0$ .
- ▶ cbrt(  $\pm \infty$ ) returns  $\pm \infty$ .

Calculate the cube root of x,  $x^{1/3}$ .



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

# \_\_device\_\_ double ceil (double x)

Calculate ceiling of the input argument.

#### Returns

Returns  $\Box x \Box$  expressed as a floating-point number.

- ceil(  $\pm 0$ ) returns  $\pm 0$ .
- ceil(  $\pm \infty$ ) returns  $\pm \infty$ .

### Description

Compute the smallest integer value not less than x.

# \_\_device\_\_ double copysign (double x, double y)

Create value with given magnitude, copying sign of second value.

#### **Returns**

Returns a value with the magnitude of x and the sign of y.

### Description

Create a floating-point value with the magnitude x and the sign of y.

# \_\_device\_\_ double cos (double x)

Calculate the cosine of the input argument.

#### Returns

- $\triangleright$  cos(  $\pm 0$  ) returns 1.
- ▶  $\cos(\pm \infty)$  returns NaN.

### Description

Calculate the cosine of the input argument x (measured in radians).



# \_device\_\_ double cosh (double x)

Calculate the hyperbolic cosine of the input argument.

#### Returns

- ightharpoonup cosh(0) returns 1.
- ▶  $\cosh(\pm \infty)$  returns  $+ \infty$ .

### Description

Calculate the hyperbolic cosine of the input argument x.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

# \_\_device\_\_ double cospi (double x)

Calculate the cosine of the input argument  $\times \pi$ .

#### Returns

- $cospi(\pm 0)$  returns 1.
- ▶ cospi(  $\pm \infty$ ) returns NaN.

#### Description

Calculate the cosine of  $x \times \pi$  (measured in radians), where x is the input argument.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

# \_device\_\_ double cyl\_bessel\_i0 (double x)

Calculate the value of the regular modified cylindrical Bessel function of order 0 for the input argument.

### **Returns**

Returns the value of the regular modified cylindrical Bessel function of order 0.

Calculate the value of the regular modified cylindrical Bessel function of order 0 for the input argument x,  $I_0(x)$ .



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

# \_\_device\_\_ double cyl\_bessel\_i1 (double x)

Calculate the value of the regular modified cylindrical Bessel function of order 1 for the input argument.

#### **Returns**

Returns the value of the regular modified cylindrical Bessel function of order 1.

### Description

Calculate the value of the regular modified cylindrical Bessel function of order 1 for the input argument  $\times$ ,  $I_1(x)$ .



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

# \_device\_\_ double erf (double x)

Calculate the error function of the input argument.

### Returns

- erf(  $\pm 0$  ) returns  $\pm 0$ .
- erf(  $\pm \infty$ ) returns  $\pm 1$ .

### Description

Calculate the value of the error function for the input argument  $\times$ ,  $\frac{2}{\sqrt{\pi}} \int_{0}^{\infty} e^{-t^2} dt$ .



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

# \_\_device\_\_ double erfc (double x)

Calculate the complementary error function of the input argument.

#### Returns

- erfc( $-\infty$ ) returns 2.
- erfc(  $+\infty$ ) returns +0.

### Description

Calculate the complementary error function of the input argument x, 1 - erf(x).



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

# \_\_device\_\_ double erfcinv (double y)

Calculate the inverse complementary error function of the input argument.

#### Returns

- erfcinv(0) returns  $+\infty$ .
- erfcinv(2) returns  $-\infty$ .

### Description

Calculate the inverse complementary error function of the input argument y, for y in the interval [0, 2]. The inverse complementary error function find the value x that satisfies the equation  $y = \operatorname{erfc}(x)$ , for  $0 \le y \le 2$ , and  $-\infty \le x \le \infty$ .



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

# \_\_device\_\_ double erfcx (double x)

Calculate the scaled complementary error function of the input argument.

- erfcx(  $-\infty$ ) returns  $+\infty$
- erfcx(  $+ \infty$  ) returns +0
- erfcx(x) returns  $+\infty$  if the correctly calculated value is outside the double floating point range.

Calculate the scaled complementary error function of the input argument x,  $e^{x^2} \cdot \operatorname{erfc}(x)$ .



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

# \_device\_ double erfinv (double y)

Calculate the inverse error function of the input argument.

#### **Returns**

- erfinv(1) returns  $+\infty$ .
- erfinv(-1) returns  $-\infty$ .

### Description

Calculate the inverse error function of the input argument y, for y in the interval [-1, 1]. The inverse error function finds the value x that satisfies the equation y = erf(x), for  $-1 \le y \le 1$ , and  $-\infty \le x \le \infty$ .



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

# \_\_device\_\_ double exp (double x)

Calculate the base *e* exponential of the input argument.

#### Returns

Returns  $e^{x}$ .

### Description

Calculate the base e exponential of the input argument x.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

# \_\_device\_\_ double exp10 (double x)

Calculate the base 10 exponential of the input argument.

#### Returns

Returns  $10^x$ .

### Description

Calculate the base 10 exponential of the input argument x.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

# \_\_device\_\_ double exp2 (double x)

Calculate the base 2 exponential of the input argument.

#### Returns

Returns  $2^{x}$ .

### Description

Calculate the base 2 exponential of the input argument x.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

# \_device\_\_ double expm1 (double x)

Calculate the base *e* exponential of the input argument, minus 1.

#### Returns

Returns  $e^{x} - 1$ .

### Description

Calculate the base *e* exponential of the input argument x, minus 1.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

# \_\_device\_\_ double fabs (double x)

Calculate the absolute value of the input argument.

#### **Returns**

Returns the absolute value of the input argument.

- fabs(  $\pm \infty$  ) returns  $+ \infty$ .
- fabs(  $\pm 0$ ) returns 0.

### Description

Calculate the absolute value of the input argument x.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

# \_device\_\_ double fdim (double x, double y)

Compute the positive difference between x and y.

#### Returns

Returns the positive difference between x and y.

- fdim(x, y) returns x y if x > y.
- fdim(x, y) returns +0 if  $x \le y$ .

### Description

Compute the positive difference between x and y. The positive difference is x - y when x > y and +0 otherwise.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

# \_device\_\_ double floor (double x)

Calculate the largest integer less than or equal to x.

#### Returns

Returns  $log_o(1+x)$  expressed as a floating-point number.

• floor(  $\pm \infty$  ) returns  $\pm \infty$ .

• floor(  $\pm 0$ ) returns  $\pm 0$ .

### Description

Calculates the largest integer value which is less than or equal to x.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

# \_\_device\_\_ double fma (double x, double y, double z)

Compute  $x \times y + z$  as a single operation.

#### Returns

Returns the rounded value of  $x \times y + z$  as a single operation.

- fma(  $\pm \infty$ ,  $\pm 0$ , z) returns NaN.
- fma(  $\pm 0$ ,  $\pm \infty$ , z) returns NaN.
- ▶ fma(x, y,  $-\infty$ ) returns NaN if  $x \times y$  is an exact  $+\infty$ .
- ▶ fma(x, y, +∞) returns NaN if  $x \times y$  is an exact -∞.

### Description

Compute the value of  $x \times y + z$  as a single ternary operation. After computing the value to infinite precision, the value is rounded once.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

# \_\_device\_\_ double fmax (double, double)

Determine the maximum numeric value of the arguments.

#### **Returns**

Returns the maximum numeric values of the arguments x and y.

- If both arguments are NaN, returns NaN.
- ▶ If one argument is NaN, returns the numeric argument.

### Description

Determines the maximum numeric value of the arguments  $\times$  and y. Treats NaN arguments as missing data. If one argument is a NaN and the other is legitimate numeric value, the numeric value is chosen.



# \_\_device\_\_ double fmin (double x, double y)

Determine the minimum numeric value of the arguments.

#### Returns

Returns the minimum numeric values of the arguments x and y.

- If both arguments are NaN, returns NaN.
- ▶ If one argument is NaN, returns the numeric argument.

### Description

Determines the minimum numeric value of the arguments x and y. Treats NaN arguments as missing data. If one argument is a NaN and the other is legitimate numeric value, the numeric value is chosen.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

# \_\_device\_\_ double fmod (double x, double y)

Calculate the floating-point remainder of x / y.

#### Returns

- Returns the floating point remainder of x / y.
- fmod(  $\pm 0$ , y) returns  $\pm 0$  if y is not zero.
- ▶ fmod(x, y) returns NaN and raised an invalid floating point exception if x is  $\pm \infty$  or y is zero.
- fmod(x, y) returns zero if y is zero or the result would overflow.
- ▶ fmod(x,  $\pm \infty$ ) returns x if x is finite.
- fmod(x, 0) returns NaN.

### Description

Calculate the floating-point remainder of x / y. The absolute value of the computed value is always less than y 's absolute value and will have the same sign as x.



# \_device\_\_ double frexp (double x, int \*nptr)

Extract mantissa and exponent of a floating-point value.

#### Returns

Returns the fractional component m.

- frexp(0, nptr) returns 0 for the fractional component and zero for the integer component.
- frexp( $\pm 0$ , nptr) returns  $\pm 0$  and stores zero in the location pointed to by nptr.
- ▶ frexp(  $\pm \infty$ , nptr) returns  $\pm \infty$  and stores an unspecified value in the location to which nptr points.
- frexp(NaN, y) returns a NaN and stores an unspecified value in the location to which nptr points.

### Description

Decompose the floating-point value x into a component m for the normalized fraction element and another term n for the exponent. The absolute value of m will be greater than or equal to 0.5 and less than 1.0 or it will be equal to 0;  $x = m \cdot 2^n$ . The integer exponent n will be stored in the location to which nptr points.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

# \_\_device\_\_ double hypot (double x, double y)

Calculate the square root of the sum of squares of two arguments.

### Returns

Returns the length of the hypotenuse  $\sqrt{x^2 + y^2}$ . If the correct value would overflow, returns  $+\infty$ . If the correct value would underflow, returns 0.

#### Description

Calculate the length of the hypotenuse of a right triangle whose two sides have lengths x and y without undue overflow or underflow.



# \_\_device\_\_ int ilogb (double x)

Compute the unbiased integer exponent of the argument.

#### **Returns**

- ▶ If successful, returns the unbiased exponent of the argument.
- ▶ ilogb(0) returns INT MIN.
- ▶ ilogb(NaN) returns NaN.
- ▶ ilogb(x) returns INT MAX if x is  $\infty$  or the correct value is greater than INT MAX.
- ▶ ilogb(x) return INT\_MIN if the correct value is less than INT\_MIN.

### Description

Calculates the unbiased integer exponent of the input argument x.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

# \_\_device\_\_ \_\_RETURN\_TYPE isfinite (double a)

Determine whether argument is finite.

#### Returns

- ▶ With Visual Studio 2013 host compiler: \_\_RETURN\_TYPE is 'bool'. Returns true if and only if a is a finite value.
- ▶ With other host compilers: \_\_RETURN\_TYPE is 'int'. Returns a nonzero value if and only if a is a finite value.

### Description

Determine whether the floating-point value a is a finite value (zero, subnormal, or normal and not infinity or NaN).

# \_\_device\_\_ \_\_RETURN\_TYPE isinf (double a)

Determine whether argument is infinite.

#### Returns

- With Visual Studio 2013 host compiler: Returns true if and only if a is a infinite value.
- ▶ With other host compilers: Returns a nonzero value if and only if a is a infinite value.

### Description

Determine whether the floating-point value a is an infinite value (positive or negative).

# \_\_device\_\_ \_\_RETURN\_TYPE isnan (double a)

Determine whether argument is a NaN.

#### Returns

- ▶ With Visual Studio 2013 host compiler: \_\_RETURN\_TYPE is 'bool'. Returns true if and only if a is a NaN value.
- ▶ With other host compilers: \_\_RETURN\_TYPE is 'int'. Returns a nonzero value if and only if a is a NaN value.

### Description

Determine whether the floating-point value a is a NaN.

# \_\_device\_\_ double j0 (double x)

Calculate the value of the Bessel function of the first kind of order 0 for the input argument.

#### Returns

Returns the value of the Bessel function of the first kind of order 0.

- ▶  $j0(\pm \infty)$  returns +0.
- ▶ j0(NaN) returns NaN.

### Description

Calculate the value of the Bessel function of the first kind of order 0 for the input argument x,  $J_0(x)$ .



# \_device\_\_ double j1 (double x)

Calculate the value of the Bessel function of the first kind of order 1 for the input argument.

#### **Returns**

Returns the value of the Bessel function of the first kind of order 1.

- $j1(\pm 0)$  returns  $\pm 0$ .
- ▶  $j1(\pm\infty)$  returns +0.
- ▶ j1(NaN) returns NaN.

### Description

Calculate the value of the Bessel function of the first kind of order 1 for the input argument x,  $J_1(x)$ .



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

# \_\_device\_\_ double jn (int n, double x)

Calculate the value of the Bessel function of the first kind of order n for the input argument.

#### **Returns**

Returns the value of the Bessel function of the first kind of order n.

- jn(n, NaN) returns NaN.
- jn(n, x) returns NaN for n < 0.
- ▶  $jn(n, +\infty)$  returns +0.

### Description

Calculate the value of the Bessel function of the first kind of order n for the input argument x,  $J_n(x)$ .



# \_\_device\_\_ double ldexp (double x, int exp)

Calculate the value of  $x \cdot 2^{exp}$ .

#### Returns

▶ ldexp(x) returns  $\pm \infty$  if the correctly calculated value is outside the double floating point range.

### Description

Calculate the value of  $x \cdot 2^{exp}$  of the input arguments x and exp.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

# \_\_device\_\_ double lgamma (double x)

Calculate the natural logarithm of the absolute value of the gamma function of the input argument.

#### **Returns**

- ▶ lgamma(1) returns +0.
- ▶ lgamma(2) returns +0.
- ▶ lgamma(x) returns  $\pm \infty$  if the correctly calculated value is outside the double floating point range.
- ▶ lgamma(x) returns  $+\infty$  if  $x \le 0$ .
- ▶ lgamma( $-\infty$ ) returns  $-\infty$ .
- ▶ lgamma(  $+ \infty$ ) returns  $+ \infty$ .

### Description

Calculate the natural logarithm of the absolute value of the gamma function of the input argument x, namely the value of  $\log_e \left| \int_0^\infty e^{-t} t^{x-1} dt \right|$ 



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

# \_\_device\_\_ long long int llrint (double x)

Round input to nearest integer value.

#### **Returns**

Returns rounded integer value.

### Description

Round  $\times$  to the nearest integer value, with halfway cases rounded towards zero. If the result is outside the range of the return type, the result is undefined.

# \_\_device\_\_ long long int llround (double x)

Round to nearest integer value.

#### Returns

Returns rounded integer value.

### Description

Round x to the nearest integer value, with halfway cases rounded away from zero. If the result is outside the range of the return type, the result is undefined.



This function may be slower than alternate rounding methods. See llrint().

# \_\_device\_\_ double log (double x)

Calculate the base *e* logarithm of the input argument.

#### **Returns**

- log(  $\pm 0$ ) returns  $-\infty$ .
- ightharpoonup log(1) returns +0.
- ▶ log(x) returns NaN for x < 0.
- ▶  $\log(+\infty)$  returns  $+\infty$

### Description

Calculate the base e logarithm of the input argument x.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

# \_\_device\_\_ double log10 (double x)

Calculate the base 10 logarithm of the input argument.

#### **Returns**

- ▶  $\log 10(\pm 0)$  returns  $-\infty$ .
- ▶ log10(1) returns +0.
- ▶ log10(x) returns NaN for x < 0.
- ▶  $\log 10(+\infty)$  returns  $+\infty$ .

### Description

Calculate the base 10 logarithm of the input argument x.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

# \_\_device\_\_ double log1p (double x)

Calculate the value of  $log_{\rho}(1+x)$ .

#### **Returns**

- log1p(  $\pm 0$  ) returns  $-\infty$ .
- log1p(-1) returns +0.
- ▶ log1p(x) returns NaN for x < -1.
- ▶  $log1p(+\infty)$  returns  $+\infty$ .

### Description

Calculate the value of  $log_{\rho}(1+x)$  of the input argument x.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

# \_device\_\_ double log2 (double x)

Calculate the base 2 logarithm of the input argument.

- ▶  $\log 2(\pm 0)$  returns  $-\infty$ .
- ightharpoonup log2(1) returns +0.

- ▶ log2(x) returns NaN for x < 0.
- ▶  $\log 2(+\infty)$  returns  $+\infty$ .

Calculate the base 2 logarithm of the input argument x.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

# \_device\_\_ double logb (double x)

Calculate the floating point representation of the exponent of the input argument.

#### Returns

- ▶ logb  $\pm 0$  returns  $-\infty$
- ▶ logb  $\pm \infty$  returns  $+ \infty$

### Description

Calculate the floating point representation of the exponent of the input argument x.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

# \_\_device\_\_ long int lrint (double x)

Round input to nearest integer value.

#### Returns

Returns rounded integer value.

### Description

Round  $\times$  to the nearest integer value, with halfway cases rounded towards zero. If the result is outside the range of the return type, the result is undefined.

# \_\_device\_\_ long int lround (double x)

Round to nearest integer value.

#### Returns

Returns rounded integer value.

Round x to the nearest integer value, with halfway cases rounded away from zero. If the result is outside the range of the return type, the result is undefined.



This function may be slower than alternate rounding methods. See lrint().

# \_device\_\_ double modf (double x, double \*iptr)

Break down the input argument into fractional and integral parts.

#### **Returns**

- modf( $\pm x$ , iptr) returns a result with the same sign as x.
- ▶ modf(  $\pm \infty$ , iptr) returns  $\pm 0$  and stores  $\pm \infty$  in the object pointed to by iptr.
- modf(NaN, iptr) stores a NaN in the object pointed to by iptr and returns a NaN.

### Description

Break down the argument x into fractional and integral parts. The integral part is stored in the argument iptr. Fractional and integral parts are given the same sign as the argument x.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

# \_\_device\_\_\_ double nan (const char \*tagp)

Returns "Not a Number" value.

#### Returns

nan(tagp) returns NaN.

### Description

Return a representation of a quiet NaN. Argument tagp selects one of the possible representations.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

# \_\_device\_\_ double nearbyint (double x)

Round the input argument to the nearest integer.

#### Returns

- nearbyint(  $\pm 0$ ) returns  $\pm 0$ .
- ▶ nearbyint(  $\pm \infty$ ) returns  $\pm \infty$ .

### Description

Round argument x to an integer value in double precision floating-point format.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

# \_device\_\_ double nextafter (double x, double y)

Return next representable double-precision floating-point value after argument.

### Returns

▶ nextafter(  $\pm \infty$ , y) returns  $\pm \infty$ .

### Description

Calculate the next representable double-precision floating-point value following x in the direction of y. For example, if y is greater than x, nextafter() returns the smallest representable number greater than x



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

# \_device\_\_ double normcdf (double y)

Calculate the standard normal cumulative distribution function.

- ▶ normcdf(  $+ \infty$ ) returns 1
- ▶ normcdf( $-\infty$ ) returns +0

Calculate the cumulative distribution function of the standard normal distribution for input argument y,  $\Phi(y)$ .



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

# \_\_device\_\_ double normcdfinv (double y)

Calculate the inverse of the standard normal cumulative distribution function.

#### **Returns**

- ▶ normcdfinv(0) returns  $-\infty$ .
- ▶ normcdfinv(1) returns  $+\infty$ .
- normcdfinv(x) returns NaN if x is not in the interval [0,1].

### Description

Calculate the inverse of the standard normal cumulative distribution function for input argument y,  $\Phi^{-1}(y)$ . The function is defined for input values in the interval (0, 1).



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

# \_\_device\_\_ double pow (double x, double y)

Calculate the value of first argument to the power of second argument.

- ▶ pow(  $\pm 0$ , y) returns  $\pm \infty$  for y an integer less than 0.
- pow( $\pm 0$ , y) returns  $\pm 0$  for y an odd integer greater than 0.
- pow( $\pm 0$ , y) returns +0 for y > 0 and not and odd integer.
- ▶ pow(-1,  $\pm \infty$ ) returns 1.
- pow(+1, y) returns 1 for any y, even a NaN.
- pow(x,  $\pm 0$ ) returns 1 for any x, even a NaN.
- ightharpoonup pow(x, y) returns a NaN for finite x < 0 and finite non-integer y.
- ▶ pow(x,  $-\infty$ ) returns  $+\infty$  for |x| < 1.
- ▶ pow(x,  $-\infty$ ) returns +0 for |x| > 1.
- ▶ pow(x, +∞) returns +0 for |x| < 1.
- ▶ pow(x, +∞) returns + ∞ for |x| > 1.

- ▶ pow( $-\infty$ , y) returns -0 for y an odd integer less than 0.
- ▶ pow( $-\infty$ , y) returns +0 for y < 0 and not an odd integer.
- ▶ pow( $-\infty$ , y) returns  $-\infty$  for y an odd integer greater than 0.
- ▶ pow( $-\infty$ , y) returns  $+\infty$  for y > 0 and not an odd integer.
- ▶ pow(  $+\infty$ , y) returns +0 for y < 0.
- ▶ pow(  $+\infty$ , y) returns  $+\infty$  for y > 0.

Calculate the value of x to the power of y



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

# \_device\_\_ double rcbrt (double x)

Calculate reciprocal cube root function.

#### Returns

- rcbrt( $\pm 0$ ) returns  $\pm \infty$ .
- ▶ rcbrt(  $\pm \infty$ ) returns  $\pm 0$ .

### Description

Calculate reciprocal cube root function of x



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

# \_\_device\_\_ double remainder (double x, double y)

Compute double-precision floating-point remainder.

- $\blacktriangleright$  remainder(x, 0) returns NaN.
- ▶ remainder(  $\pm \infty$ , y) returns NaN.
- ▶ remainder(x,  $\pm \infty$ ) returns x for finite x.

Compute double-precision floating-point remainder r of dividing x by y for nonzero y. Thus r = x - ny. The value n is the integer value nearest  $\frac{X}{y}$ . In the case when  $|n - \frac{X}{y}| = \frac{1}{2}$ , the even n value is chosen.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

# \_\_device\_\_ double remquo (double x, double y, int \*quo)

Compute double-precision floating-point remainder and part of quotient.

#### Returns

Returns the remainder.

- ▶ remquo(x, 0, quo) returns NaN.
- ▶ remquo(  $\pm \infty$ , y, quo) returns NaN.
- ▶ remquo(x,  $\pm \infty$ , quo) returns x.

### Description

Compute a double-precision floating-point remainder in the same way as the remainder() function. Argument quo returns part of quotient upon division of x by y. Value quo has the same sign as  $\frac{X}{Y}$  and may not be the exact quotient but agrees with the exact quotient in the low order 3 bits.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

# \_device\_\_ double rhypot (double x, double y)

Calculate one over the square root of the sum of squares of two arguments.

#### **Returns**

Returns one over the length of the hypotenuse  $\frac{1}{\sqrt{x^2+y^2}}$ . If the square root would overflow, returns 0. If the square root would underflow, returns  $+\infty$ .

Calculate one over the length of the hypotenuse of a right triangle whose two sides have lengths x and y without undue overflow or underflow.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

### \_\_device\_\_ double rint (double x)

Round to nearest integer value in floating-point.

#### Returns

Returns rounded integer value.

### Description

Round x to the nearest integer value in floating-point format, with halfway cases rounded to the nearest even integer value.

### \_\_device\_\_ double round (double x)

Round to nearest integer value in floating-point.

#### **Returns**

Returns rounded integer value.

### Description

Round  $\times$  to the nearest integer value in floating-point format, with halfway cases rounded away from zero.



This function may be slower than alternate rounding methods. See rint().

# \_\_device\_\_ double rsqrt (double x)

Calculate the reciprocal of the square root of the input argument.

### Returns

Returns  $1/\sqrt{x}$ .

- rsqrt( + ∞) returns +0.
- rsqrt(  $\pm 0$ ) returns  $\pm \infty$ .

• rsqrt(x) returns NaN if x is less than 0.

### Description

Calculate the reciprocal of the nonnegative square root of x,  $1/\sqrt{x}$ .



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

### \_\_device\_\_ double scalbln (double x, long int n)

Scale floating-point input by integer power of two.

#### Returns

Returns  $x * 2^n$ .

- scalbln(  $\pm 0$ , n) returns  $\pm 0$ .
- ightharpoonup scalbln(x, 0) returns x.
- ▶ scalbln(  $\pm \infty$ , n) returns  $\pm \infty$ .

### Description

Scale  $\times$  by  $2^n$  by efficient manipulation of the floating-point exponent.

# \_\_device\_\_ double scalbn (double x, int n)

Scale floating-point input by integer power of two.

### **Returns**

Returns  $x * 2^n$ .

- scalbn(  $\pm 0$ , n) returns  $\pm 0$ .
- $\triangleright$  scalbn(x, 0) returns x.
- ▶ scalbn(  $\pm \infty$ , n) returns  $\pm \infty$ .

### Description

Scale  $\times$  by  $2^n$  by efficient manipulation of the floating-point exponent.

### \_\_device\_\_ \_\_RETURN\_TYPE signbit (double a)

Return the sign bit of the input.

#### Returns

Reports the sign bit of all values including infinities, zeros, and NaNs.

- ▶ With Visual Studio 2013 host compiler: \_\_RETURN\_TYPE is 'bool'. Returns true if and only if a is negative.
- ▶ With other host compilers: \_\_RETURN\_TYPE is 'int'. Returns a nonzero value if and only if a is negative.

### Description

Determine whether the floating-point value a is negative.

### \_\_device\_\_ double sin (double x)

Calculate the sine of the input argument.

#### Returns

- $\blacktriangleright$  sin(  $\pm 0$  ) returns  $\pm 0$ .
- ▶  $\sin(\pm \infty)$  returns NaN.

### Description

Calculate the sine of the input argument x (measured in radians).



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

# \_\_device\_\_ void sincos (double x, double \*sptr, double \*cptr)

Calculate the sine and cosine of the first input argument.

#### Returns

none

Calculate the sine and cosine of the first input argument x (measured in radians). The results for sine and cosine are written into the second argument, sptr, and, respectively, third argument, cptr.

### See also:

sin() and cos().



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

# \_\_device\_\_ void sincospi (double x, double \*sptr, double \*cptr)

Calculate the sine and cosine of the first input argument  $\times \pi$ .

### Returns

none

### Description

Calculate the sine and cosine of the first input argument, x (measured in radians), x  $\pi$ . The results for sine and cosine are written into the second argument, sptr, and, respectively, third argument, cptr.

### See also:

sinpi() and cospi().



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

### \_device\_\_ double sinh (double x)

Calculate the hyperbolic sine of the input argument.

### Returns

•  $\sinh(\pm 0)$  returns  $\pm 0$ .

### Description

Calculate the hyperbolic sine of the input argument x.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

### \_device\_ double sinpi (double x)

Calculate the sine of the input argument  $\times \pi$ .

### Returns

- $sinpi(\pm 0)$  returns  $\pm 0$ .
- ▶  $sinpi(\pm \infty)$  returns NaN.

### Description

Calculate the sine of  $x \times \pi$  (measured in radians), where x is the input argument.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

# \_device\_\_ double sqrt (double x)

Calculate the square root of the input argument.

### **Returns**

Returns  $\sqrt{x}$ .

- sqrt(  $\pm 0$  ) returns  $\pm 0$ .
- sqrt(  $+ \infty$  ) returns  $+ \infty$ .
- $\operatorname{sqrt}(x)$  returns NaN if x is less than 0.

### Description

Calculate the nonnegative square root of x,  $\sqrt{x}$ .



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

### \_\_device\_\_ double tan (double x)

Calculate the tangent of the input argument.

#### **Returns**

- $\tan(\pm 0)$  returns  $\pm 0$ .
- ▶  $tan(\pm \infty)$  returns NaN.

### Description

Calculate the tangent of the input argument x (measured in radians).



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

### \_\_device\_\_ double tanh (double x)

Calculate the hyperbolic tangent of the input argument.

#### Returns

•  $\tanh(\pm 0)$  returns  $\pm 0$ .

### Description

Calculate the hyperbolic tangent of the input argument x.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

### \_device\_\_ double tgamma (double x)

Calculate the gamma function of the input argument.

#### Returns

- ▶ tgamma(  $\pm 0$ ) returns  $\pm \infty$ .
- ▶ tgamma(2) returns +0.
- tgamma(x) returns  $\pm \infty$  if the correctly calculated value is outside the double floating point range.
- tgamma(x) returns NaN if x < 0.
- ▶ tgamma( $-\infty$ ) returns NaN.
- ▶ tgamma(  $+ \infty$ ) returns  $+ \infty$ .

Calculate the gamma function of the input argument x, namely the value of  $\int_{0}^{\infty} e^{-t} t^{x-1} dt$ .



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

### \_\_device\_\_ double trunc (double x)

Truncate input argument to the integral part.

#### Returns

Returns truncated integer value.

### Description

Round x to the nearest integer value that does not exceed x in magnitude.

### \_\_device\_\_ double y0 (double x)

Calculate the value of the Bessel function of the second kind of order 0 for the input argument.

#### Returns

Returns the value of the Bessel function of the second kind of order 0.

- ▶ y0(0) returns  $-\infty$ .
- y0(x) returns NaN for x < 0.
- ▶  $y0(+\infty)$  returns +0.
- ▶ y0(NaN) returns NaN.

### Description

Calculate the value of the Bessel function of the second kind of order 0 for the input argument  $\times$ ,  $Y_0(x)$ .



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

# \_\_device\_\_ double y1 (double x)

Calculate the value of the Bessel function of the second kind of order 1 for the input argument.

### **Returns**

Returns the value of the Bessel function of the second kind of order 1.

- ▶ y1(0) returns  $-\infty$ .
- y1(x) returns NaN for x < 0.
- ▶  $y1(+\infty)$  returns +0.
- ▶ y1(NaN) returns NaN.

### Description

Calculate the value of the Bessel function of the second kind of order 1 for the input argument x,  $Y_1(x)$ .



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

### \_\_device\_\_ double yn (int n, double x)

Calculate the value of the Bessel function of the second kind of order n for the input argument.

### **Returns**

Returns the value of the Bessel function of the second kind of order n.

- yn(n, x) returns NaN for n < 0.
- ▶ yn(n, 0) returns  $-\infty$ .
- yn(n, x) returns NaN for x < 0.
- ▶  $yn(n, +\infty)$  returns +0.
- yn(n, NaN) returns NaN.

### Description

Calculate the value of the Bessel function of the second kind of order n for the input argument x,  $Y_n(x)$ .



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

# 1.4. Single Precision Intrinsics

This section describes single precision intrinsic functions that are only supported in device code.

\_\_device\_\_ \_\_cudart\_builtin\_\_ float \_\_cosf (float x)

Calculate the fast approximate cosine of the input argument.

#### Returns

Returns the approximate cosine of x.

### Description

Calculate the fast approximate cosine of the input argument x, measured in radians.



- For accuracy information for this function see the CUDA C Programming Guide, Appendix D.2, Table 9.
- Input and output in the denormal range is flushed to sign preserving 0.0.

\_\_device\_\_ \_\_cudart\_builtin\_\_ float \_\_exp10f (float x)

Calculate the fast approximate base 10 exponential of the input argument.

#### Returns

Returns an approximation to  $10^x$ .

### **Description**

Calculate the fast approximate base 10 exponential of the input argument x,  $10^x$ .



- For accuracy information for this function see the CUDA C Programming Guide, Appendix D.2, Table 9.
- Most input and output values around denormal range are flushed to sign preserving 0.0.

# \_\_device\_\_ \_\_cudart\_builtin\_\_ float \_\_expf (float x)

Calculate the fast approximate base e exponential of the input argument.

#### Returns

Returns an approximation to  $e^{x}$ .

### Description

Calculate the fast approximate base e exponential of the input argument x,  $e^x$ .



- For accuracy information for this function see the CUDA C Programming Guide, Appendix D.2, Table 9.
- Most input and output values around denormal range are flushed to sign preserving 0.0.

### \_\_device\_\_ float \_\_fadd\_rd (float x, float y)

Add two floating point values in round-down mode.

### **Returns**

Returns x + y.

### Description

Compute the sum of x and y in round-down (to negative infinity) mode.



- For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.
- ▶ This operation will never be merged into a single multiply-add instruction.

### \_\_device\_\_ float \_\_fadd\_rn (float x, float y)

Add two floating point values in round-to-nearest-even mode.

### Returns

Returns x + y.

### Description

Compute the sum of x and y in round-to-nearest-even rounding mode.



- For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.
- This operation will never be merged into a single multiply-add instruction.

### \_\_device\_\_ float \_\_fadd\_ru (float x, float y)

Add two floating point values in round-up mode.

### Returns

Returns x + y.

### Description

Compute the sum of x and y in round-up (to positive infinity) mode.



- For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.
- ▶ This operation will never be merged into a single multiply-add instruction.

# \_\_device\_\_ float \_\_fadd\_rz (float x, float y)

Add two floating point values in round-towards-zero mode.

### Returns

Returns x + y.

### Description

Compute the sum of x and y in round-towards-zero mode.



- For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.
- ▶ This operation will never be merged into a single multiply-add instruction.

### \_\_device\_\_ float \_\_fdiv\_rd (float x, float y)

Divide two floating point values in round-down mode.

#### Returns

Returns x / y.

Divide two floating point values x by y in round-down (to negative infinity) mode.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

### \_device\_\_ float \_\_fdiv\_rn (float x, float y)

Divide two floating point values in round-to-nearest-even mode.

### **Returns**

Returns x / y.

### Description

Divide two floating point values x by y in round-to-nearest-even mode.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

# \_\_device\_\_ float \_\_fdiv\_ru (float x, float y)

Divide two floating point values in round-up mode.

### Returns

Returns x / y.

### Description

Divide two floating point values x by y in round-up (to positive infinity) mode.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

### \_device\_\_ float \_\_fdiv\_rz (float x, float y)

Divide two floating point values in round-towards-zero mode.

### Returns

Returns x / y.

Divide two floating point values x by y in round-towards-zero mode.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

### \_device\_\_ float \_\_fdividef (float x, float y)

Calculate the fast approximate division of the input arguments.

### Returns

Returns x / y.

- fdividef( $\infty$ , y) returns NaN for  $2^{126} < y < 2^{128}$ .
- fdividef(x, y) returns 0 for  $2^{126} < y < 2^{128}$  and x ≠ ∞.

### Description

Calculate the fast approximate division of x by y.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.2, Table 9.

### \_\_device\_\_ float \_\_fmaf\_rd (float x, float y, float z)

Compute  $x \times y + z$  as a single operation, in round-down mode.

### Returns

Returns the rounded value of  $x \times y + z$  as a single operation.

- fmaf(  $\pm \infty$ ,  $\pm 0$ , z) returns NaN.
- ▶ fmaf(  $\pm 0$ ,  $\pm \infty$ , z) returns NaN.
- ▶ fmaf(x, y,  $-\infty$ ) returns NaN if  $x \times y$  is an exact  $+\infty$ .
- ▶ fmaf(x, y,  $+\infty$ ) returns NaN if  $x \times y$  is an exact  $-\infty$ .

### Description

Computes the value of  $x \times y + z$  as a single ternary operation, rounding the result once in round-down (to negative infinity) mode.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

### \_\_device\_\_ float \_\_fmaf\_rn (float x, float y, float z)

Compute  $x \times y + z$  as a single operation, in round-to-nearest-even mode.

#### Returns

Returns the rounded value of  $x \times y + z$  as a single operation.

- fmaf(  $\pm \infty$ ,  $\pm 0$ , z) returns NaN.
- fmaf(  $\pm 0$ ,  $\pm \infty$ , z) returns NaN.
- ▶ fmaf(x, y,  $-\infty$ ) returns NaN if  $x \times y$  is an exact  $+\infty$ .
- ▶ fmaf(x, y, +∞) returns NaN if  $x \times y$  is an exact  $-\infty$ .

### Description

Computes the value of  $x \times y + z$  as a single ternary operation, rounding the result once in round-to-nearest-even mode.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

### \_\_device\_\_ float \_\_fmaf\_ru (float x, float y, float z)

Compute  $x \times y + z$  as a single operation, in round-up mode.

#### Returns

Returns the rounded value of  $x \times y + z$  as a single operation.

- fmaf(  $\pm \infty$ ,  $\pm 0$ , z) returns NaN.
- ▶ fmaf(  $\pm 0$ ,  $\pm \infty$ , z) returns NaN.
- ▶ fmaf(x, y,  $-\infty$ ) returns NaN if  $x \times y$  is an exact  $+\infty$ .
- ▶ fmaf(x, y, +∞) returns NaN if  $x \times y$  is an exact -∞.

### Description

Computes the value of  $x \times y + z$  as a single ternary operation, rounding the result once in round-up (to positive infinity) mode.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

### \_\_device\_\_ float \_\_fmaf\_rz (float x, float y, float z)

Compute  $x \times y + z$  as a single operation, in round-towards-zero mode.

#### Returns

Returns the rounded value of  $x \times y + z$  as a single operation.

- fmaf(  $\pm \infty$ ,  $\pm 0$ , z) returns NaN.
- ▶ fmaf(  $\pm 0$ ,  $\pm \infty$ , z) returns NaN.
- ▶ fmaf(x, y,  $-\infty$ ) returns NaN if  $x \times y$  is an exact  $+\infty$ .
- ▶ fmaf(x, y, +∞) returns NaN if  $x \times y$  is an exact  $-\infty$ .

### Description

Computes the value of  $x \times y + z$  as a single ternary operation, rounding the result once in round-towards-zero mode.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

# \_\_device\_\_ float \_\_fmul\_rd (float x, float y)

Multiply two floating point values in round-down mode.

### Returns

Returns x \* y.

### Description

Compute the product of x and y in round-down (to negative infinity) mode.



- For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.
- This operation will never be merged into a single multiply-add instruction.

### \_\_device\_\_ float \_\_fmul\_rn (float x, float y)

Multiply two floating point values in round-to-nearest-even mode.

#### Returns

Returns x \* y.

### Description

Compute the product of x and y in round-to-nearest-even mode.



- For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.
- This operation will never be merged into a single multiply-add instruction.

### \_\_device\_\_ float \_\_fmul\_ru (float x, float y)

Multiply two floating point values in round-up mode.

#### Returns

Returns x \* y.

### **Description**

Compute the product of x and y in round-up (to positive infinity) mode.



- For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.
- This operation will never be merged into a single multiply-add instruction.

### \_\_device\_\_ float \_\_fmul\_rz (float x, float y)

Multiply two floating point values in round-towards-zero mode.

### Returns

Returns x \* y.

### Description

Compute the product of x and y in round-towards-zero mode.



- For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.
- This operation will never be merged into a single multiply-add instruction.

Compute  $\frac{1}{X}$  in round-down mode.

### Returns

Returns  $\frac{1}{X}$ .

### Description

Compute the reciprocal of x in round-down (to negative infinity) mode.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

Compute  $\frac{1}{X}$  in round-to-nearest-even mode.

#### Returns

Returns  $\frac{1}{X}$ .

### Description

Compute the reciprocal of x in round-to-nearest-even mode.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

Compute  $\frac{1}{x}$  in round-up mode.

### **Returns**

Returns  $\frac{1}{X}$ .

Compute the reciprocal of x in round-up (to positive infinity) mode.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

\_\_device\_\_ float \_\_\_frcp\_rz (float x)

Compute  $\frac{1}{X}$  in round-towards-zero mode.

### **Returns**

Returns  $\frac{1}{X}$ .

### Description

Compute the reciprocal of x in round-towards-zero mode.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

\_\_device\_\_ float \_\_frsqrt\_rn (float x)

Compute  $1/\sqrt{x}$  in round-to-nearest-even mode.

### **Returns**

Returns  $1/\sqrt{x}$ .

### **Description**

Compute the reciprocal square root of x in round-to-nearest-even mode.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

### \_\_device\_\_ float \_\_fsqrt\_rd (float x)

Compute  $\sqrt{x}$  in round-down mode.

#### Returns

Returns  $\sqrt{x}$ .

### Description

Compute the square root of x in round-down (to negative infinity) mode.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

### \_\_device\_\_\_ float \_\_\_fsqrt\_rn (float x)

Compute  $\sqrt{x}$  in round-to-nearest-even mode.

### Returns

Returns  $\sqrt{x}$ .

### Description

Compute the square root of x in round-to-nearest-even mode.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

# \_\_device\_\_ float \_\_fsqrt\_ru (float x)

Compute  $\sqrt{x}$  in round-up mode.

### Returns

Returns  $\sqrt{x}$ .

### Description

Compute the square root of x in round-up (to positive infinity) mode.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

### \_\_device\_\_ float \_\_\_fsqrt\_rz (float x)

Compute  $\sqrt{x}$  in round-towards-zero mode.

### Returns

Returns  $\sqrt{x}$ .

### Description

Compute the square root of x in round-towards-zero mode.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.

### \_\_device\_\_ float \_\_fsub\_rd (float x, float y)

Subtract two floating point values in round-down mode.

#### Returns

Returns x - y.

### Description

Compute the difference of x and y in round-down (to negative infinity) mode.



- For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.
- ▶ This operation will never be merged into a single multiply-add instruction.

# \_device\_\_ float \_\_fsub\_rn (float x, float y)

Subtract two floating point values in round-to-nearest-even mode.

### **Returns**

Returns x - y.

Compute the difference of x and y in round-to-nearest-even rounding mode.



- For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.
- ▶ This operation will never be merged into a single multiply-add instruction.

### \_\_device\_\_ float \_\_fsub\_ru (float x, float y)

Subtract two floating point values in round-up mode.

### Returns

Returns x - y.

### Description

Compute the difference of x and y in round-up (to positive infinity) mode.



- For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.
- ▶ This operation will never be merged into a single multiply-add instruction.

# \_\_device\_\_ float \_\_fsub\_rz (float x, float y)

Subtract two floating point values in round-towards-zero mode.

### **Returns**

Returns x - y.

### Description

Compute the difference of x and y in round-towards-zero mode.



- For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 6.
- This operation will never be merged into a single multiply-add instruction.

### \_\_device\_\_ \_\_cudart\_builtin\_\_ float \_\_log10f (float x)

Calculate the fast approximate base 10 logarithm of the input argument.

#### **Returns**

Returns an approximation to  $\log_{10}(x)$ .

### Description

Calculate the fast approximate base 10 logarithm of the input argument x.



- For accuracy information for this function see the CUDA C Programming Guide, Appendix D.2, Table 9.
- Most input and output values around denormal range are flushed to sign preserving 0.0.

\_\_device\_\_ \_\_cudart\_builtin\_\_ float \_\_log2f (float x)

Calculate the fast approximate base 2 logarithm of the input argument.

### Returns

Returns an approximation to  $\log_2(x)$ .

### **Description**

Calculate the fast approximate base 2 logarithm of the input argument x.



- For accuracy information for this function see the CUDA C Programming Guide, Appendix D.2, Table 9.
- Input and output in the denormal range is flushed to sign preserving 0.0.

\_\_device\_\_ \_\_cudart\_builtin\_\_ float \_\_logf (float x)

Calculate the fast approximate base *e* logarithm of the input argument.

### Returns

Returns an approximation to  $\log_{\rho}(x)$ .

### Description

Calculate the fast approximate base e logarithm of the input argument x.



- For accuracy information for this function see the CUDA C Programming Guide, Appendix D.2, Table 9.
- Most input and output values around denormal range are flushed to sign preserving 0.0.

# \_\_device\_\_ \_\_cudart\_builtin\_\_ float \_\_powf (float x, float y)

Calculate the fast approximate of  $x^y$ .

#### Returns

Returns an approximation to  $x^y$ .

### Description

Calculate the fast approximate of x, the first input argument, raised to the power of y, the second input argument,  $x^y$ .



- For accuracy information for this function see the CUDA C Programming Guide, Appendix D.2, Table 9.
- Most input and output values around denormal range are flushed to sign preserving 0.0.

### \_\_device\_\_ float \_\_saturatef (float x)

Clamp the input argument to [+0.0, 1.0].

#### Returns

- ► \_\_saturatef(x) returns 0 if x < 0.
- ▶ \_\_saturatef(x) returns 1 if x > 1.
- ▶ \_\_saturatef(x) returns x if  $0 \le x \le 1$ .
- \_\_saturatef(NaN) returns 0.

### Description

Clamp the input argument x to be within the interval [+0.0, 1.0].

device	cudart_	builtin	void _	_sincosf	(float x,
float *sptr,	float *cptr	)			

Calculate the fast approximate of sine and cosine of the first input argument.

### Returns

none

### Description

Calculate the fast approximate of sine and cosine of the first input argument x (measured in radians). The results for sine and cosine are written into the second argument, sptr, and, respectively, third argument, cptr.



- For accuracy information for this function see the CUDA C Programming Guide, Appendix D.2, Table 9.
- Denorm input/output is flushed to sign preserving 0.0.

Calculate the fast approximate sine of the input argument.

#### Returns

Returns the approximate sine of x.

### Description

Calculate the fast approximate sine of the input argument x, measured in radians.



- For accuracy information for this function see the CUDA C Programming Guide, Appendix D.2, Table 9.
- Input and output in the denormal range is flushed to sign preserving 0.0.

\_\_device\_\_ \_\_cudart\_builtin\_\_ float \_\_tanf (float x)

Calculate the fast approximate tangent of the input argument.

### Returns

Returns the approximate tangent of x.

Calculate the fast approximate tangent of the input argument x, measured in radians.



- For accuracy information for this function see the CUDA C Programming Guide, Appendix D.2, Table 9.
- ► The result is computed as the fast divide of \_\_sinf() by \_\_cosf(). Denormal input and output are flushed to sign-preserving 0.0 at each step of the computation.

### 1.5. Double Precision Intrinsics

This section describes double precision intrinsic functions that are only supported in device code.

\_\_device\_\_ double \_\_dadd\_rd (double x, double y)

Add two floating point values in round-down mode.

#### **Returns**

Returns x + y.

### Description

Adds two floating point values x and y in round-down (to negative infinity) mode.



- For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.
- ▶ This operation will never be merged into a single multiply-add instruction.

\_\_device\_\_ double \_\_dadd\_rn (double x, double y)

Add two floating point values in round-to-nearest-even mode.

### Returns

Returns x + y.

### Description

Adds two floating point values x and y in round-to-nearest-even mode.



- For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.
- ▶ This operation will never be merged into a single multiply-add instruction.

### \_\_device\_\_ double \_\_dadd\_ru (double x, double y)

Add two floating point values in round-up mode.

### Returns

Returns x + y.

### Description

Adds two floating point values x and y in round-up (to positive infinity) mode.



- For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.
- ▶ This operation will never be merged into a single multiply-add instruction.

### \_\_device\_\_ double \_\_dadd\_rz (double x, double y)

Add two floating point values in round-towards-zero mode.

#### Returns

Returns x + y.

### Description

Adds two floating point values x and y in round-towards-zero mode.



- For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.
- ▶ This operation will never be merged into a single multiply-add instruction.

### \_\_device\_\_ double \_\_ddiv\_rd (double x, double y)

Divide two floating point values in round-down mode.

#### Returns

Returns x / y.

Divides two floating point values x by y in round-down (to negative infinity) mode.



- For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.
- ► Requires compute capability >= 2.0.

### \_\_device\_\_ double \_\_ddiv\_rn (double x, double y)

Divide two floating point values in round-to-nearest-even mode.

### Returns

Returns x / y.

### **Description**

Divides two floating point values x by y in round-to-nearest-even mode.



- For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.
- ► Requires compute capability >= 2.0.

# \_\_device\_\_ double \_\_ddiv\_ru (double x, double y)

Divide two floating point values in round-up mode.

### **Returns**

Returns x / y.

### Description

Divides two floating point values x by y in round-up (to positive infinity) mode.



- For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.
- ► Requires compute capability >= 2.0.

# \_\_device\_\_ double \_\_ddiv\_rz (double x, double y)

Divide two floating point values in round-towards-zero mode.

#### Returns

Returns x / y.

### Description

Divides two floating point values x by y in round-towards-zero mode.



- For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.
- Requires compute capability >= 2.0.

### \_\_device\_\_ double \_\_dmul\_rd (double x, double y)

Multiply two floating point values in round-down mode.

#### Returns

Returns x \* y.

### Description

Multiplies two floating point values x and y in round-down (to negative infinity) mode.



- For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.
- ▶ This operation will never be merged into a single multiply-add instruction.

### \_\_device\_\_ double \_\_dmul\_rn (double x, double y)

Multiply two floating point values in round-to-nearest-even mode.

### Returns

Returns x \* y.

### Description

Multiplies two floating point values x and y in round-to-nearest-even mode.



- For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.
- This operation will never be merged into a single multiply-add instruction.

### \_\_device\_\_ double \_\_dmul\_ru (double x, double y)

Multiply two floating point values in round-up mode.

### Returns

Returns x \* y.

### Description

Multiplies two floating point values x and y in round-up (to positive infinity) mode.



- For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.
- ▶ This operation will never be merged into a single multiply-add instruction.

# \_\_device\_\_ double \_\_dmul\_rz (double x, double y)

Multiply two floating point values in round-towards-zero mode.

#### Returns

Returns x \* y.

### Description

Multiplies two floating point values x and y in round-towards-zero mode.



- For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.
- ▶ This operation will never be merged into a single multiply-add instruction.

### \_\_device\_\_ double \_\_drcp\_rd (double x)

Compute  $\frac{1}{X}$  in round-down mode.

#### Returns

Returns  $\frac{1}{X}$ .

Compute the reciprocal of x in round-down (to negative infinity) mode.



- For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.
- ► Requires compute capability >= 2.0.

# \_\_device\_\_ double \_\_drcp\_rn (double x)

Compute  $\frac{1}{X}$  in round-to-nearest-even mode.

### **Returns**

Returns  $\frac{1}{x}$ .

### Description

Compute the reciprocal of x in round-to-nearest-even mode.



- For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.
- Requires compute capability >= 2.0.

# \_\_device\_\_ double \_\_drcp\_ru (double x)

Compute  $\frac{1}{X}$  in round-up mode.

### **Returns**

Returns  $\frac{1}{x}$ .

### **Description**

Compute the reciprocal of x in round-up (to positive infinity) mode.



- For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.
- ► Requires compute capability >= 2.0.

### \_\_device\_\_ double \_\_drcp\_rz (double x)

Compute  $\frac{1}{X}$  in round-towards-zero mode.

#### Returns

Returns  $\frac{1}{X}$ .

### Description

Compute the reciprocal of x in round-towards-zero mode.



- For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.
- ► Requires compute capability >= 2.0.

# \_\_device\_\_ double \_\_dsqrt\_rd (double x)

Compute  $\sqrt{x}$  in round-down mode.

### Returns

Returns  $\sqrt{x}$ .

### Description

Compute the square root of x in round-down (to negative infinity) mode.



- For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.
- ▶ Requires compute capability >= 2.0.

# \_\_device\_\_ double \_\_dsqrt\_rn (double x)

Compute  $\sqrt{x}$  in round-to-nearest-even mode.

### **Returns**

Returns  $\sqrt{x}$ .

### Description

Compute the square root of x in round-to-nearest-even mode.



- For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.
- ► Requires compute capability >= 2.0.

### \_\_device\_\_ double \_\_dsqrt\_ru (double x)

Compute  $\sqrt{x}$  in round-up mode.

### **Returns**

Returns  $\sqrt{x}$ .

### Description

Compute the square root of x in round-up (to positive infinity) mode.



- For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.
- Requires compute capability >= 2.0.

### \_\_device\_\_ double \_\_dsqrt\_rz (double x)

Compute  $\sqrt{x}$  in round-towards-zero mode.

#### **Returns**

Returns  $\sqrt{x}$ .

### Description

Compute the square root of x in round-towards-zero mode.



- For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.
- ▶ Requires compute capability >= 2.0.

# \_\_device\_\_ double \_\_dsub\_rd (double x, double y)

Subtract two floating point values in round-down mode.

### Returns

Returns x - y.

### Description

Subtracts two floating point values x and y in round-down (to negative infinity) mode.



- For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.
- This operation will never be merged into a single multiply-add instruction.

### \_\_device\_\_ double \_\_dsub\_rn (double x, double y)

Subtract two floating point values in round-to-nearest-even mode.

#### **Returns**

Returns x - y.

### Description

Subtracts two floating point values x and y in round-to-nearest-even mode.



- For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.
- ▶ This operation will never be merged into a single multiply-add instruction.

# \_\_device\_\_ double \_\_dsub\_ru (double x, double y)

Subtract two floating point values in round-up mode.

#### Returns

Returns x - y.

### Description

Subtracts two floating point values x and y in round-up (to positive infinity) mode.



- For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.
- This operation will never be merged into a single multiply-add instruction.

### \_\_device\_\_ double \_\_dsub\_rz (double x, double y)

Subtract two floating point values in round-towards-zero mode.

### Returns

Returns x - y.

### Description

Subtracts two floating point values x and y in round-towards-zero mode.



- For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.
- ▶ This operation will never be merged into a single multiply-add instruction.

# \_\_device\_\_ double \_\_fma\_rd (double x, double y, double z)

Compute  $x \times y + z$  as a single operation in round-down mode.

### Returns

Returns the rounded value of  $x \times y + z$  as a single operation.

- fmaf(  $\pm \infty$ ,  $\pm 0$ , z) returns NaN.
- fmaf(  $\pm 0$ ,  $\pm \infty$ , z) returns NaN.
- ▶ fmaf(x, y,  $-\infty$ ) returns NaN if  $x \times y$  is an exact  $+\infty$
- ▶ fmaf(x, y, +∞) returns NaN if  $x \times y$  is an exact  $-\infty$

### Description

Computes the value of  $x \times y + z$  as a single ternary operation, rounding the result once in round-down (to negative infinity) mode.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

# \_\_device\_\_ double \_\_fma\_rn (double x, double y, double z)

Compute  $x \times y + z$  as a single operation in round-to-nearest-even mode.

### Returns

Returns the rounded value of  $x \times y + z$  as a single operation.

- fmaf(  $\pm \infty$ ,  $\pm 0$ , z) returns NaN.
- fmaf(  $\pm 0$ ,  $\pm \infty$ , z) returns NaN.
- ▶ fmaf(x, y,  $-\infty$ ) returns NaN if  $x \times y$  is an exact  $+\infty$
- ▶ fmaf(x, y, +∞) returns NaN if  $x \times y$  is an exact -∞

### Description

Computes the value of  $x \times y + z$  as a single ternary operation, rounding the result once in round-to-nearest-even mode.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

# \_\_device\_\_ double \_\_fma\_ru (double x, double y, double z)

Compute  $x \times y + z$  as a single operation in round-up mode.

#### Returns

Returns the rounded value of  $x \times y + z$  as a single operation.

- fmaf(  $\pm \infty$ ,  $\pm 0$ , z) returns NaN.
- ▶ fmaf(  $\pm 0$ ,  $\pm \infty$ , z) returns NaN.
- ▶ fmaf(x, y,  $-\infty$ ) returns NaN if  $x \times y$  is an exact  $+\infty$
- ▶ fmaf(x, y, +∞) returns NaN if  $x \times y$  is an exact  $-\infty$

### Description

Computes the value of  $x \times y + z$  as a single ternary operation, rounding the result once in round-up (to positive infinity) mode.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

# \_\_device\_\_ double \_\_fma\_rz (double x, double y, double z)

Compute  $x \times y + z$  as a single operation in round-towards-zero mode.

### Returns

Returns the rounded value of  $x \times y + z$  as a single operation.

- fmaf(  $\pm \infty$ ,  $\pm 0$ , z) returns NaN.
- fmaf(  $\pm 0$ ,  $\pm \infty$ , z) returns NaN.
- ▶ fmaf(x, y,  $-\infty$ ) returns NaN if  $x \times y$  is an exact  $+\infty$
- ▶ fmaf(x, y, +∞) returns NaN if  $x \times y$  is an exact  $-\infty$

### Description

Computes the value of  $x \times y + z$  as a single ternary operation, rounding the result once in round-towards-zero mode.



For accuracy information for this function see the CUDA C Programming Guide, Appendix D.1, Table 7.

# 1.6. Integer Intrinsics

This section describes integer intrinsic functions that are only supported in device code.

\_\_device\_\_ unsigned int \_\_brev (unsigned int x)

Reverse the bit order of a 32 bit unsigned integer.

### Returns

Returns the bit-reversed value of x. i.e. bit N of the return value corresponds to bit 31-N of x.

### Description

Reverses the bit order of the 32 bit unsigned integer x.

# \_\_device\_\_ unsigned long long int \_\_brevll (unsigned long long int x)

Reverse the bit order of a 64 bit unsigned integer.

#### Returns

Returns the bit-reversed value of x. i.e. bit N of the return value corresponds to bit 63-N of x.

## Description

Reverses the bit order of the 64 bit unsigned integer x.

# \_\_device\_\_ unsigned int \_\_byte\_perm (unsigned int x, unsigned int y, unsigned int s)

Return selected bytes from two 32 bit unsigned integers.

#### Returns

The returned value r is computed to be: result[n] := input[selector[n]] where result[n] is the nth byte of r.

## Description

byte\_perm(x,y,s) returns a 32-bit integer consisting of four bytes from eight input bytes provided in the two input integers x and y, as specified by a selector, s.

The input bytes are indexed as follows: input[0] = x<7:0> input[1] = x<15:8> input[2] = x<23:16> input[3] = x<31:24> input[4] = y<7:0> input[5] = y<15:8> input[6] = y<23:16> input[7] = y<31:24> The selector indices are as follows (the upper 16-bits of the selector are not used): selector[0] = x<10:8> selector[3] = x<10:8

# \_\_device\_\_ int \_\_clz (int x)

Return the number of consecutive high-order zero bits in a 32 bit integer.

#### Returns

Returns a value between 0 and 32 inclusive representing the number of zero bits.

### Description

Count the number of consecutive leading zero bits, starting at the most significant bit (bit 31) of x.

# \_\_device\_\_ int \_\_clzll (long long int x)

Count the number of consecutive high-order zero bits in a 64 bit integer.

#### Returns

Returns a value between 0 and 64 inclusive representing the number of zero bits.

## Description

Count the number of consecutive leading zero bits, starting at the most significant bit (bit 63) of x.

Find the position of the least significant bit set to 1 in a 32 bit integer.

#### **Returns**

Returns a value between 0 and 32 inclusive representing the position of the first bit set.

► \_\_ffs(0) returns 0.

## Description

Find the position of the first (least significant) bit set to 1 in x, where the least significant bit position is 1.

# \_\_device\_\_ int \_\_ffsll (long long int x)

Find the position of the least significant bit set to 1 in a 64 bit integer.

#### Returns

Returns a value between 0 and 64 inclusive representing the position of the first bit set.

\_\_ffsll(0) returns 0.

#### Description

Find the position of the first (least significant) bit set to 1 in x, where the least significant bit position is 1.

# \_\_device\_\_ int \_\_hadd (int, int)

Compute average of signed input arguments, avoiding overflow in the intermediate sum.

#### **Returns**

Returns a signed integer value representing the signed average value of the two inputs.

## **Description**

Compute average of signed input arguments x and y as (x + y) >> 1, avoiding overflow in the intermediate sum.

# \_\_device\_\_ int \_\_mul24 (int x, int y)

Calculate the least significant 32 bits of the product of the least significant 24 bits of two integers.

#### **Returns**

Returns the least significant 32 bits of the product x \* y.

# Description

Calculate the least significant 32 bits of the product of the least significant 24 bits of x and y. The high order 8 bits of x and y are ignored.

# \_\_device\_\_ long long int \_\_mul64hi (long long int x, long long int y)

Calculate the most significant 64 bits of the product of the two 64 bit integers.

#### **Returns**

Returns the most significant 64 bits of the product x \* y.

### Description

Calculate the most significant 64 bits of the 128-bit product x \* y, where x \* y are 64-bit integers.

# \_\_device\_\_ int \_\_mulhi (int x, int y)

Calculate the most significant 32 bits of the product of the two 32 bit integers.

#### **Returns**

Returns the most significant 32 bits of the product x \* y.

## Description

Calculate the most significant 32 bits of the 64-bit product x \* y, where x and y are 32-bit integers.

# \_\_device\_\_ int \_\_popc (unsigned int x)

Count the number of bits that are set to 1 in a 32 bit integer.

#### **Returns**

Returns a value between 0 and 32 inclusive representing the number of set bits.

## Description

Count the number of bits that are set to 1 in x.

# \_\_device\_\_ int \_\_popcll (unsigned long long int x)

Count the number of bits that are set to 1 in a 64 bit integer.

#### **Returns**

Returns a value between 0 and 64 inclusive representing the number of set bits.

## Description

Count the number of bits that are set to 1 in x.

# \_\_device\_\_ int \_\_rhadd (int, int)

Compute rounded average of signed input arguments, avoiding overflow in the intermediate sum.

## Returns

Returns a signed integer value representing the signed rounded average value of the two inputs.

Compute average of signed input arguments x and y as (x + y + 1) >> 1, avoiding overflow in the intermediate sum.

\_\_device\_\_ unsigned int \_\_sad (int x, int y, unsigned int
z)

Calculate |x - y| + z, the sum of absolute difference.

#### Returns

Returns |x - y| + z.

## Description

Calculate |x-y|+z, the 32-bit sum of the third argument z plus and the absolute value of the difference between the first argument, x, and second argument, y.

Inputs x and y are signed 32-bit integers, input z is a 32-bit unsigned integer.

# \_\_device\_\_ unsigned int \_\_uhadd (unsigned int, unsigned int)

Compute average of unsigned input arguments, avoiding overflow in the intermediate sum.

### **Returns**

Returns an unsigned integer value representing the unsigned average value of the two inputs.

## Description

Compute average of unsigned input arguments x and y as (x + y) >> 1, avoiding overflow in the intermediate sum.

\_\_device\_\_ unsigned int \_\_umul24 (unsigned int x,
unsigned int y)

Calculate the least significant 32 bits of the product of the least significant 24 bits of two unsigned integers.

#### **Returns**

Returns the least significant 32 bits of the product x \* y.

Calculate the least significant 32 bits of the product of the least significant 24 bits of x and y. The high order 8 bits of x and y are ignored.

# \_\_device\_\_ unsigned long long int \_\_umul64hi (unsigned long long int x, unsigned long long int y)

Calculate the most significant 64 bits of the product of the two 64 unsigned bit integers.

#### Returns

Returns the most significant 64 bits of the product x \* y.

## Description

Calculate the most significant 64 bits of the 128-bit product x \* y, where x and y are 64-bit unsigned integers.

# \_\_device\_\_ unsigned int \_\_umulhi (unsigned int x, unsigned int y)

Calculate the most significant 32 bits of the product of the two 32 bit unsigned integers.

## Returns

Returns the most significant 32 bits of the product x \* y.

### Description

Calculate the most significant 32 bits of the 64-bit product x \* y, where x and y are 32-bit unsigned integers.

# \_\_device\_\_ unsigned int \_\_urhadd (unsigned int, unsigned int)

Compute rounded average of unsigned input arguments, avoiding overflow in the intermediate sum.

## Returns

Returns an unsigned integer value representing the unsigned rounded average value of the two inputs.

### Description

Compute average of unsigned input arguments x and y as (x + y + 1) >> 1, avoiding overflow in the intermediate sum.

# \_\_device\_\_ unsigned int \_\_usad (unsigned int x, unsigned int y, unsigned int z)

Calculate |x-y|+z, the sum of absolute difference.

#### Returns

Returns |x - y| + z.

## Description

Calculate |x - y| + z, the 32-bit sum of the third argument z plus and the absolute value of the difference between the first argument, x, and second argument, y.

Inputs x, y, and z are unsigned 32-bit integers.

# 1.7. Type Casting Intrinsics

This section describes type casting intrinsic functions that are only supported in device code.

Convert a double to a float in round-down mode.

#### **Returns**

Returns converted value.

## Description

Convert the double-precision floating point value  $\times$  to a single-precision floating point value in round-down (to negative infinity) mode.

# \_\_device\_\_ float \_\_double2float\_rn (double x)

Convert a double to a float in round-to-nearest-even mode.

## Returns

Returns converted value.

## Description

Convert the double-precision floating point value x to a single-precision floating point value in round-to-nearest-even mode.

# \_\_device\_\_ float \_\_double2float\_ru (double x)

Convert a double to a float in round-up mode.

#### Returns

Returns converted value.

# Description

Convert the double-precision floating point value x to a single-precision floating point value in round-up (to positive infinity) mode.

# \_\_device\_\_ float \_\_double2float\_rz (double x)

Convert a double to a float in round-towards-zero mode.

#### **Returns**

Returns converted value.

# Description

Convert the double-precision floating point value x to a single-precision floating point value in round-towards-zero mode.

# \_\_device\_\_ int \_\_double2hiint (double x)

Reinterpret high 32 bits in a double as a signed integer.

#### Returns

Returns reinterpreted value.

#### Description

Reinterpret the high 32 bits in the double-precision floating point value x as a signed integer.

# \_\_device\_\_ int \_\_double2int\_rd (double x)

Convert a double to a signed int in round-down mode.

#### Returns

Convert the double-precision floating point value x to a signed integer value in round-down (to negative infinity) mode.

# \_\_device\_\_ int \_\_double2int\_rn (double x)

Convert a double to a signed int in round-to-nearest-even mode.

#### **Returns**

Returns converted value.

## Description

Convert the double-precision floating point value x to a signed integer value in round-to-nearest-even mode.

# \_\_device\_\_ int \_\_double2int\_ru (double x)

Convert a double to a signed int in round-up mode.

#### Returns

Returns converted value.

## Description

Convert the double-precision floating point value x to a signed integer value in round-up (to positive infinity) mode.

# \_\_device\_\_ int \_\_double2int\_rz (double)

Convert a double to a signed int in round-towards-zero mode.

#### Returns

Returns converted value.

### Description

Convert the double-precision floating point value x to a signed integer value in round-towards-zero mode.

# \_\_device\_\_ long long int \_\_double2ll\_rd (double x)

Convert a double to a signed 64-bit int in round-down mode.

#### Returns

Returns converted value.

## Description

Convert the double-precision floating point value x to a signed 64-bit integer value in round-down (to negative infinity) mode.

# \_\_device\_\_ long long int \_\_double2ll\_rn (double x)

Convert a double to a signed 64-bit int in round-to-nearest-even mode.

#### Returns

Returns converted value.

## Description

Convert the double-precision floating point value  $\times$  to a signed 64-bit integer value in round-to-nearest-even mode.

# \_\_device\_\_ long long int \_\_double2ll\_ru (double x)

Convert a double to a signed 64-bit int in round-up mode.

#### Returns

Returns converted value.

#### Description

Convert the double-precision floating point value  $\times$  to a signed 64-bit integer value in round-up (to positive infinity) mode.

# \_\_device\_\_ long long int \_\_double2ll\_rz (double)

Convert a double to a signed 64-bit int in round-towards-zero mode.

#### Returns

Convert the double-precision floating point value  $\times$  to a signed 64-bit integer value in round-towards-zero mode.

# \_\_device\_\_ int \_\_double2loint (double x)

Reinterpret low 32 bits in a double as a signed integer.

#### Returns

Returns reinterpreted value.

## Description

Reinterpret the low 32 bits in the double-precision floating point value x as a signed integer.

# \_\_device\_\_ unsigned int \_\_double2uint\_rd (double x)

Convert a double to an unsigned int in round-down mode.

### **Returns**

Returns converted value.

## Description

Convert the double-precision floating point value  $\times$  to an unsigned integer value in round-down (to negative infinity) mode.

# \_\_device\_\_ unsigned int \_\_double2uint\_rn (double x)

Convert a double to an unsigned int in round-to-nearest-even mode.

#### Returns

Returns converted value.

### Description

Convert the double-precision floating point value x to an unsigned integer value in round-to-nearest-even mode.

# \_\_device\_\_ unsigned int \_\_double2uint\_ru (double x)

Convert a double to an unsigned int in round-up mode.

#### Returns

Returns converted value.

## Description

Convert the double-precision floating point value x to an unsigned integer value in round-up (to positive infinity) mode.

# \_\_device\_\_ unsigned int \_\_double2uint\_rz (double)

Convert a double to an unsigned int in round-towards-zero mode.

#### Returns

Returns converted value.

## Description

Convert the double-precision floating point value  $\times$  to an unsigned integer value in round-towards-zero mode.

# \_\_device\_\_ unsigned long long int \_\_double2ull\_rd (double x)

Convert a double to an unsigned 64-bit int in round-down mode.

#### Returns

Returns converted value.

## Description

Convert the double-precision floating point value  $\times$  to an unsigned 64-bit integer value in round-down (to negative infinity) mode.

# \_\_device\_\_ unsigned long long int \_\_double2ull\_rn (double x)

Convert a double to an unsigned 64-bit int in round-to-nearest-even mode.

#### Returns

Convert the double-precision floating point value x to an unsigned 64-bit integer value in round-to-nearest-even mode.

# \_\_device\_\_ unsigned long long int \_\_double2ull\_ru (double x)

Convert a double to an unsigned 64-bit int in round-up mode.

#### Returns

Returns converted value.

## Description

Convert the double-precision floating point value x to an unsigned 64-bit integer value in round-up (to positive infinity) mode.

# \_\_device\_\_ unsigned long long int \_\_double2ull\_rz (double)

Convert a double to an unsigned 64-bit int in round-towards-zero mode.

#### Returns

Returns converted value.

### Description

Convert the double-precision floating point value x to an unsigned 64-bit integer value in round-towards-zero mode.

# \_\_device\_\_ long long int \_\_double\_as\_longlong (double x)

Reinterpret bits in a double as a 64-bit signed integer.

#### **Returns**

Returns reinterpreted value.

### Description

Reinterpret the bits in the double-precision floating point value  $\times$  as a signed 64-bit integer.

# \_\_device\_\_ unsigned short \_\_float2half\_rn (float x)

Convert a single-precision float to a half-precision float in round-to-nearest-even mode.

#### Returns

Returns converted value.

## Description

Convert the single-precision float value x to a half-precision floating point value represented in unsigned short format, in round-to-nearest-even mode.

# \_\_device\_\_ int \_\_float2int\_rd (float x)

Convert a float to a signed integer in round-down mode.

#### Returns

Returns converted value.

## Description

Convert the single-precision floating point value x to a signed integer in round-down (to negative infinity) mode.

# \_\_device\_\_ int \_\_float2int\_rn (float x)

Convert a float to a signed integer in round-to-nearest-even mode.

## Returns

Returns converted value.

#### Description

Convert the single-precision floating point value x to a signed integer in round-to-nearest-even mode.

# \_\_device\_\_ int \_\_float2int\_ru (float)

Convert a float to a signed integer in round-up mode.

#### Returns

Convert the single-precision floating point value  $\times$  to a signed integer in round-up (to positive infinity) mode.

# \_\_device\_\_ int \_\_float2int\_rz (float x)

Convert a float to a signed integer in round-towards-zero mode.

#### **Returns**

Returns converted value.

## Description

Convert the single-precision floating point value x to a signed integer in round-towards-zero mode.

# \_\_device\_\_ long long int \_\_float2ll\_rd (float x)

Convert a float to a signed 64-bit integer in round-down mode.

#### Returns

Returns converted value.

## Description

Convert the single-precision floating point value  $\times$  to a signed 64-bit integer in round-down (to negative infinity) mode.

# \_\_device\_\_ long long int \_\_float2ll\_rn (float x)

Convert a float to a signed 64-bit integer in round-to-nearest-even mode.

#### Returns

Returns converted value.

### Description

Convert the single-precision floating point value x to a signed 64-bit integer in round-to-nearest-even mode.

# \_\_device\_\_ long long int \_\_float2ll\_ru (float x)

Convert a float to a signed 64-bit integer in round-up mode.

#### Returns

Returns converted value.

# Description

Convert the single-precision floating point value  $\times$  to a signed 64-bit integer in round-up (to positive infinity) mode.

# \_\_device\_\_ long long int \_\_float2ll\_rz (float x)

Convert a float to a signed 64-bit integer in round-towards-zero mode.

#### Returns

Returns converted value.

## Description

Convert the single-precision floating point value  $\times$  to a signed 64-bit integer in round-towards-zero mode.

# \_\_device\_\_ unsigned int \_\_float2uint\_rd (float x)

Convert a float to an unsigned integer in round-down mode.

#### Returns

Returns converted value.

#### Description

Convert the single-precision floating point value  $\times$  to an unsigned integer in round-down (to negative infinity) mode.

# \_\_device\_\_ unsigned int \_\_float2uint\_rn (float x)

Convert a float to an unsigned integer in round-to-nearest-even mode.

#### Returns

Convert the single-precision floating point value  $\times$  to an unsigned integer in round-to-nearest-even mode.

# \_\_device\_\_ unsigned int \_\_float2uint\_ru (float x)

Convert a float to an unsigned integer in round-up mode.

#### **Returns**

Returns converted value.

## Description

Convert the single-precision floating point value x to an unsigned integer in round-up (to positive infinity) mode.

# \_\_device\_\_ unsigned int \_\_float2uint\_rz (float x)

Convert a float to an unsigned integer in round-towards-zero mode.

#### Returns

Returns converted value.

## Description

Convert the single-precision floating point value  $\times$  to an unsigned integer in round-towards-zero mode.

# \_\_device\_\_ unsigned long long int \_\_float2ull\_rd (float x)

Convert a float to an unsigned 64-bit integer in round-down mode.

## Returns

Returns converted value.

### Description

Convert the single-precision floating point value x to an unsigned 64-bit integer in round-down (to negative infinity) mode.



Convert a float to an unsigned 64-bit integer in round-to-nearest-even mode.

#### Returns

Returns converted value.

## Description

Convert the single-precision floating point value x to an unsigned 64-bit integer in round-to-nearest-even mode.

# \_\_device\_\_ unsigned long long int \_\_float2ull\_ru (float x)

Convert a float to an unsigned 64-bit integer in round-up mode.

#### Returns

Returns converted value.

# Description

Convert the single-precision floating point value x to an unsigned 64-bit integer in round-up (to positive infinity) mode.

# \_\_device\_\_ unsigned long long int \_\_float2ull\_rz (float x)

Convert a float to an unsigned 64-bit integer in round-towards-zero mode.

#### Returns

Returns converted value.

# Description

Convert the single-precision floating point value x to an unsigned 64-bit integer in round-towards\_zero mode.



Reinterpret bits in a float as a signed integer.

#### Returns

Returns reinterpreted value.

## **Description**

Reinterpret the bits in the single-precision floating point value x as a signed integer.

# \_\_device\_\_ float \_\_half2float (unsigned short x)

Convert a half-precision float to a single-precision float in round-to-nearest-even mode.

#### Returns

Returns converted value.

## Description

Convert the half-precision floating point value x represented in unsigned short format to a single-precision floating point value.

# \_\_device\_\_ double \_\_hiloint2double (int hi, int lo)

Reinterpret high and low 32-bit integer values as a double.

#### Returns

Returns reinterpreted value.

## Description

Reinterpret the integer value of hi as the high 32 bits of a double-precision floating point value and the integer value of lo as the low 32 bits of the same double-precision floating point value.

\_\_device\_\_ double \_\_int2double\_rn (int x)

Convert a signed int to a double.

#### Returns

Convert the signed integer value x to a double-precision floating point value.

Convert a signed integer to a float in round-down mode.

#### Returns

Returns converted value.

# Description

Convert the signed integer value x to a single-precision floating point value in round-down (to negative infinity) mode.

Convert a signed integer to a float in round-to-nearest-even mode.

#### **Returns**

Returns converted value.

## Description

Convert the signed integer value  $\times$  to a single-precision floating point value in round-to-nearest-even mode.

Convert a signed integer to a float in round-up mode.

#### Returns

Returns converted value.

#### Description

Convert the signed integer value  $\times$  to a single-precision floating point value in round-up (to positive infinity) mode.

# \_\_device\_\_ float \_\_int2float\_rz (int x)

Convert a signed integer to a float in round-towards-zero mode.

#### Returns

Convert the signed integer value  $\times$  to a single-precision floating point value in round-towards-zero mode.

\_\_device\_\_ float \_\_int\_as\_float (int x)

Reinterpret bits in an integer as a float.

#### **Returns**

Returns reinterpreted value.

# Description

Reinterpret the bits in the signed integer value  $\times$  as a single-precision floating point value.

\_\_device\_\_ double \_\_ll2double\_rd (long long int x)

Convert a signed 64-bit int to a double in round-down mode.

#### Returns

Returns converted value.

## Description

Convert the signed 64-bit integer value x to a double-precision floating point value in round-down (to negative infinity) mode.

\_\_device\_\_ double \_\_ll2double\_rn (long long int x)

Convert a signed 64-bit int to a double in round-to-nearest-even mode.

#### Returns

Returns converted value.

### Description

Convert the signed 64-bit integer value  $\times$  to a double-precision floating point value in round-to-nearest-even mode.

# \_\_device\_\_ double \_\_ll2double\_ru (long long int x)

Convert a signed 64-bit int to a double in round-up mode.

#### Returns

Returns converted value.

## Description

Convert the signed 64-bit integer value  $\times$  to a double-precision floating point value in round-up (to positive infinity) mode.

Convert a signed 64-bit int to a double in round-towards-zero mode.

#### Returns

Returns converted value.

# Description

Convert the signed 64-bit integer value  $\times$  to a double-precision floating point value in round-towards-zero mode.

Convert a signed integer to a float in round-down mode.

#### Returns

Returns converted value.

### Description

Convert the signed integer value x to a single-precision floating point value in round-down (to negative infinity) mode.

# \_\_device\_\_ float \_\_ll2float\_rn (long long int x)

Convert a signed 64-bit integer to a float in round-to-nearest-even mode.

#### Returns

Convert the signed 64-bit integer value x to a single-precision floating point value in round-to-nearest-even mode.

# \_\_device\_\_ float \_\_ll2float\_ru (long long int x)

Convert a signed integer to a float in round-up mode.

#### **Returns**

Returns converted value.

## Description

Convert the signed integer value x to a single-precision floating point value in round-up (to positive infinity) mode.

# \_\_device\_\_ float \_\_ll2float\_rz (long long int x)

Convert a signed integer to a float in round-towards-zero mode.

#### Returns

Returns converted value.

## Description

Convert the signed integer value  $\times$  to a single-precision floating point value in round-towards-zero mode.

# \_\_device\_\_ double \_\_longlong\_as\_double (long long int x)

Reinterpret bits in a 64-bit signed integer as a double.

## Returns

Returns reinterpreted value.

## Description

Reinterpret the bits in the 64-bit signed integer value x as a double-precision floating point value.

# \_\_device\_\_ double \_\_uint2double\_rn (unsigned int x)

Convert an unsigned int to a double.

#### Returns

Returns converted value.

# Description

Convert the unsigned integer value x to a double-precision floating point value.

# \_\_device\_\_ float \_\_uint2float\_rd (unsigned int x)

Convert an unsigned integer to a float in round-down mode.

#### Returns

Returns converted value.

## Description

Convert the unsigned integer value x to a single-precision floating point value in round-down (to negative infinity) mode.

# \_\_device\_\_ float \_\_uint2float\_rn (unsigned int x)

Convert an unsigned integer to a float in round-to-nearest-even mode.

#### **Returns**

Returns converted value.

## Description

Convert the unsigned integer value x to a single-precision floating point value in round-to-nearest-even mode.

# \_\_device\_\_ float \_\_uint2float\_ru (unsigned int x)

Convert an unsigned integer to a float in round-up mode.

#### Returns

Convert the unsigned integer value x to a single-precision floating point value in round-up (to positive infinity) mode.

# \_\_device\_\_ float \_\_uint2float\_rz (unsigned int x)

Convert an unsigned integer to a float in round-towards-zero mode.

#### **Returns**

Returns converted value.

## Description

Convert the unsigned integer value x to a single-precision floating point value in round-towards-zero mode.

# \_\_device\_\_ double \_\_ull2double\_rd (unsigned long long int x)

Convert an unsigned 64-bit int to a double in round-down mode.

### Returns

Returns converted value.

## Description

Convert the unsigned 64-bit integer value  $\times$  to a double-precision floating point value in round-down (to negative infinity) mode.

# \_\_device\_\_ double \_\_ull2double\_rn (unsigned long long int x)


Convert an unsigned 64-bit int to a double in round-to-nearest-even mode.

#### Returns

Returns converted value.

### Description

Convert the unsigned 64-bit integer value x to a double-precision floating point value in round-to-nearest-even mode.



Convert an unsigned 64-bit int to a double in round-up mode.

#### Returns

Returns converted value.

## Description

Convert the unsigned 64-bit integer value  $\times$  to a double-precision floating point value in round-up (to positive infinity) mode.

# \_\_device\_\_ double \_\_ull2double\_rz (unsigned long long int x)

Convert an unsigned 64-bit int to a double in round-towards-zero mode.

#### Returns

Returns converted value.

# Description

Convert the unsigned 64-bit integer value  $\times$  to a double-precision floating point value in round-towards-zero mode.

Convert an unsigned integer to a float in round-down mode.

#### Returns

Returns converted value.

# Description

Convert the unsigned integer value x to a single-precision floating point value in round-down (to negative infinity) mode.



Convert an unsigned integer to a float in round-to-nearest-even mode.

#### **Returns**

Returns converted value.

## Description

Convert the unsigned integer value x to a single-precision floating point value in round-to-nearest-even mode.

Convert an unsigned integer to a float in round-up mode.

#### Returns

Returns converted value.

## Description

Convert the unsigned integer value x to a single-precision floating point value in round-up (to positive infinity) mode.

Convert an unsigned integer to a float in round-towards-zero mode.

### Returns

Returns converted value.

# Description

Convert the unsigned integer value x to a single-precision floating point value in round-towards-zero mode.

# 1.8. SIMD Intrinsics

This section describes SIMD intrinsic functions that are only supported in device code.

# \_\_device\_\_ unsigned int \_\_vabs2 (unsigned int a)

Computes per-halfword absolute value.

#### Returns

Returns computed value.

## Description

Splits 4 bytes of argument into 2 parts, each consisting of 2 bytes, then computes absolute value for each of parts. Result is stored as unsigned int and returned.

\_\_device\_\_ unsigned int \_\_vabs4 (unsigned int a)

Computes per-byte absolute value.

#### Returns

Returns computed value.

## Description

Splits argument by bytes. Computes absolute value of each byte. Result is stored as unsigned int.

# \_\_device\_\_ unsigned int \_\_vabsdiffs2 (unsigned int a, unsigned int b)

Computes per-halfword sum of absolute difference of signed integer.

#### Returns

Returns computed value.

## Description

Splits 4 bytes of each into 2 parts, each consisting of 2 bytes. For corresponding parts function computes absolute difference. Result is stored as unsigned int and returned.

# \_\_device\_\_ unsigned int \_\_vabsdiffs4 (unsigned int a, unsigned int b)

Computes per-byte absolute difference of signed integer.

#### Returns

Returns computed value.

Splits 4 bytes of each into 4 parts, each consisting of 1 byte. For corresponding parts function computes absolute difference. Result is stored as unsigned int and returned.

# \_\_device\_\_ unsigned int \_\_vabsdiffu2 (unsigned int a, unsigned int b)

Performs per-halfword absolute difference of unsigned integer computation: |a - b|.

#### Returns

Returns computed value.

## Description

Splits 4 bytes of each argument into 2 parts, each consisting of 2 bytes. For corresponding parts function computes absolute difference. Result is stored as unsigned int and returned.

# \_\_device\_\_ unsigned int \_\_vabsdiffu4 (unsigned int a, unsigned int b)

Computes per-byte absolute difference of unsigned integer.

#### Returns

Returns computed value.

# Description

Splits 4 bytes of each argument into 4 parts, each consisting of 1 byte. For corresponding parts function computes absolute difference. Result is stored as unsigned int and returned.

# \_\_device\_\_ unsigned int \_\_vabsss2 (unsigned int a)

Computes per-halfword absolute value with signed saturation.

#### Returns

Returns computed value.

# Description

Splits 4 bytes of argument into 2 parts, each consisting of 2 bytes, then computes absolute value with signed saturation for each of parts. Result is stored as unsigned int and returned.

# \_\_device\_\_ unsigned int \_\_vabsss4 (unsigned int a)

Computes per-byte absolute value with signed saturation.

#### Returns

Returns computed value.

## Description

Splits 4 bytes of argument into 4 parts, each consisting of 1 byte, then computes absolute value with signed saturation for each of parts. Result is stored as unsigned int and returned.

# \_\_device\_\_ unsigned int \_\_vadd2 (unsigned int a, unsigned int b)

Performs per-halfword (un)signed addition, with wrap-around: a + b.

#### **Returns**

Returns computed value.

## Description

Splits 4 bytes of each argument into 2 parts, each consisting of 2 bytes, then performs unsigned addition on corresponding parts. Result is stored as unsigned int and returned.

# \_\_device\_\_ unsigned int \_\_vadd4 (unsigned int a, unsigned int b)

Performs per-byte (un)signed addition.

#### Returns

Returns computed value.

#### Description

Splits 4 bytes of each argument into 4 parts, each consisting of 1 byte, then performs unsigned addition on corresponding parts. Result is stored as unsigned int and returned.

# \_\_device\_\_ unsigned int \_\_vaddss2 (unsigned int a, unsigned int b)

Performs per-halfword addition with signed saturation.

#### **Returns**

Returns computed value.

## Description

Splits 4 bytes of each argument into 2 parts, each consisting of 2 bytes, then performs addition with signed saturation on corresponding parts. Result is stored as unsigned int and returned.

# \_\_device\_\_ unsigned int \_\_vaddss4 (unsigned int a, unsigned int b)

Performs per-byte addition with signed saturation.

## Returns

Returns computed value.

## Description

Splits 4 bytes of each argument into 4 parts, each consisting of 1 byte, then performs addition with signed saturation on corresponding parts. Result is stored as unsigned int and returned.

# \_\_device\_\_ unsigned int \_\_vaddus2 (unsigned int a, unsigned int b)

Performs per-halfword addition with unsigned saturation.

#### Returns

Returns computed value.

## Description

Splits 4 bytes of each argument into 2 parts, each consisting of 2 bytes, then performs addition with unsigned saturation on corresponding parts.

# \_\_device\_\_ unsigned int \_\_vaddus4 (unsigned int a, unsigned int b)

Performs per-byte unaddition with signed saturation.

#### **Returns**

Returns computed value.

## Description

Splits 4 bytes of each argument into 4 parts, each consisting of 1 byte, then performs addition with unsigned saturation on corresponding parts.

# \_\_device\_\_ unsigned int \_\_vavgs2 (unsigned int a, unsigned int b)

Performs per-halfword signed rounded average computation.

#### Returns

Returns computed value.

## Description

Splits 4 bytes of each argument into 2 parts, each consisting of 2 bytes. then computes signed rounded avarege of corresponding parts. Result is stored as unsigned int and returned.

# \_\_device\_\_ unsigned int \_\_vavgs4 (unsigned int a, unsigned int b)

Computes per-byte signed rounder average.

#### Returns

Returns computed value.

## Description

Splits 4 bytes of each argument into 4 parts, each consisting of 1 byte. then computes signed rounded avarege of corresponding parts. Result is stored as unsigned int and returned.

# \_\_device\_\_ unsigned int \_\_vavgu2 (unsigned int a, unsigned int b)

Performs per-halfword unsigned rounded average computation.

#### **Returns**

Returns computed value.

## Description

Splits 4 bytes of each argument into 2 parts, each consisting of 2 bytes. then computes unsigned rounded avarege of corresponding parts. Result is stored as unsigned int and returned.

# \_\_device\_\_ unsigned int \_\_vavgu4 (unsigned int a, unsigned int b)

Performs per-byte unsigned rounded average.

#### Returns

Returns computed value.

## Description

Splits 4 bytes of each argument into 4 parts, each consisting of 1 byte. then computes unsigned rounded avarege of corresponding parts. Result is stored as unsigned int and returned.

# \_\_device\_\_ unsigned int \_\_vcmpeq2 (unsigned int a, unsigned int b)

Performs per-halfword (un)signed comparison.

#### Returns

Returns 0xffff computed value.

## Description

Splits 4 bytes of each argument into 2 parts, each consisting of 2 bytes. For corresponding parts result is ffff if they are equal, and 0000 otherwise. For example \_\_vcmpeq2(0x1234aba5, 0x1234aba6) returns 0xffff0000.

# \_\_device\_\_ unsigned int \_\_vcmpeq4 (unsigned int a, unsigned int b)

Performs per-byte (un)signed comparison.

#### **Returns**

Returns 0xff if a = b, else returns 0.

## Description

Splits 4 bytes of each argument into 4 parts, each consisting of 1 byte. For corresponding parts result is ff if they are equal, and 00 otherwise. For example \_\_vcmpeq4(0x1234aba5, 0x1234aba6) returns 0xffffff00.

# \_\_device\_\_ unsigned int \_\_vcmpges2 (unsigned int a, unsigned int b)

Performs per-halfword signed comparison:  $a \ge b$ ? 0xffff : 0.

#### Returns

Returns 0xffff if  $a \ge b$ , else returns 0.

## Description

Splits 4 bytes of each argument into 2 parts, each consisting of 2 bytes. For corresponding parts result is ffff if 'a' part >= 'b' part, and 0000 otherwise. For example \_\_vcmpges2(0x1234aba5, 0x1234aba6) returns 0xffff0000.

# \_\_device\_\_ unsigned int \_\_vcmpges4 (unsigned int a, unsigned int b)

Performs per-byte signed comparison.

#### Returns

Returns 0xff if  $a \ge b$ , else returns 0.

# Description

Splits 4 bytes of each argument into 4 parts, each consisting of 1 byte. For corresponding parts result is ff if 'a' part >= 'b' part, and 00 otherwise. For example \_\_vcmpges4(0x1234aba5, 0x1234aba6) returns 0xffffff00.

# \_\_device\_\_ unsigned int \_\_vcmpgeu2 (unsigned int a, unsigned int b)

Performs per-halfword unsigned comparison:  $a \ge b$ ? 0xffff : 0.

#### **Returns**

Returns 0xffff if  $a \ge b$ , else returns 0.

## Description

Splits 4 bytes of each argument into 2 parts, each consisting of 2 bytes. For corresponding parts result is ffff if 'a' part >= 'b' part, and 0000 otherwise. For example \_\_vcmpgeu2(0x1234aba5, 0x1234aba6) returns 0xffff0000.

# \_\_device\_\_ unsigned int \_\_vcmpgeu4 (unsigned int a, unsigned int b)

Performs per-byte unsigned comparison.

#### Returns

Returns 0xff if a = b, else returns 0.

## Description

Splits 4 bytes of each argument into 4 parts, each consisting of 1 byte. For corresponding parts result is ff if 'a' part >= 'b' part, and 00 otherwise. For example \_\_vcmpgeu4(0x1234aba5, 0x1234aba6) returns 0xffffff00.

# \_\_device\_\_ unsigned int \_\_vcmpgts2 (unsigned int a, unsigned int b)

Performs per-halfword signed comparison: a > b ? 0xffff : 0.

#### Returns

Returns 0xffff if a > b, else returns 0.

## Description

Splits 4 bytes of each argument into 2 parts, each consisting of 2 bytes. For corresponding parts result is ffff if 'a' part > 'b' part, and 0000 otherwise. For example \_\_vcmpgts2(0x1234aba5, 0x1234aba6) returns 0x00000000.

# \_\_device\_\_ unsigned int \_\_vcmpgts4 (unsigned int a, unsigned int b)

Performs per-byte signed comparison.

#### **Returns**

Returns 0xff if a > b, else returns 0.

## Description

Splits 4 bytes of each argument into 4 parts, each consisting of 1 byte. For corresponding parts result is ff if 'a' part > 'b' part, and 00 otherwise. For example \_\_vcmpgts4(0x1234aba5, 0x1234aba6) returns 0x00000000.

# \_\_device\_\_ unsigned int \_\_vcmpgtu2 (unsigned int a, unsigned int b)

Performs per-halfword unsigned comparison: a > b ? 0xffff : 0.

#### Returns

Returns 0xffff if a > b, else returns 0.

## Description

Splits 4 bytes of each argument into 2 parts, each consisting of 2 bytes. For corresponding parts result is ffff if 'a' part > 'b' part, and 0000 otherwise. For example \_\_vcmpgtu2(0x1234aba5, 0x1234aba6) returns 0x00000000.

# \_\_device\_\_ unsigned int \_\_vcmpgtu4 (unsigned int a, unsigned int b)

Performs per-byte unsigned comparison.

#### Returns

Returns 0xff if a > b, else returns 0.

## Description

Splits 4 bytes of each argument into 4 parts, each consisting of 1 byte. For corresponding parts result is ff if 'a' part > 'b' part, and 00 otherwise. For example \_\_vcmpgtu4(0x1234aba5, 0x1234aba6) returns 0x00000000.

# \_\_device\_\_ unsigned int \_\_vcmples2 (unsigned int a, unsigned int b)

Performs per-halfword signed comparison:  $a \le b$ ? 0xffff : 0.

#### **Returns**

Returns 0xffff if a <= b, else returns 0.

### Description

Splits 4 bytes of each argument into 2 parts, each consisting of 2 bytes. For corresponding parts result is ffff if 'a' part <= 'b' part, and 0000 otherwise. For example \_\_vcmples2(0x1234aba5, 0x1234aba6) returns 0xffffffff.

# \_\_device\_\_ unsigned int \_\_vcmples4 (unsigned int a, unsigned int b)

Performs per-byte signed comparison.

#### Returns

Returns 0xff if a <= b, else returns 0.

### Description

Splits 4 bytes of each argument into 4 parts, each consisting of 1 byte. For corresponding parts result is ff if 'a' part <= 'b' part, and 00 otherwise. For example \_\_vcmples4(0x1234aba5, 0x1234aba6) returns 0xfffffff.

# \_\_device\_\_ unsigned int \_\_vcmpleu2 (unsigned int a, unsigned int b)

Performs per-halfword unsigned comparison: a <= b ? 0xffff : 0.

#### Returns

Returns 0xffff if a <= b, else returns 0.

### Description

Splits 4 bytes of each argument into 2 parts, each consisting of 2 bytes. For corresponding parts result is ffff if 'a' part <= 'b' part, and 0000 otherwise. For example \_\_vcmpleu2(0x1234aba5, 0x1234aba6) returns 0xffffffff.

# \_\_device\_\_ unsigned int \_\_vcmpleu4 (unsigned int a, unsigned int b)

Performs per-byte unsigned comparison.

#### **Returns**

Returns 0xff if a  $\leq$  b, else returns 0.

### Description

Splits 4 bytes of each argument into 4 parts, each consisting of 1 byte. For corresponding parts result is ff if 'a' part <= 'b' part, and 00 otherwise. For example \_\_vcmpleu4(0x1234aba5, 0x1234aba6) returns 0xffffffff.

# \_\_device\_\_ unsigned int \_\_vcmplts2 (unsigned int a, unsigned int b)

Performs per-halfword signed comparison: a < b ? 0xffff : 0.

### Returns

Returns 0xffff if a < b, else returns 0.

### Description

Splits 4 bytes of each argument into 2 parts, each consisting of 2 bytes. For corresponding parts result is ffff if 'a' part < 'b' part, and 0000 otherwise. For example \_\_vcmplts2(0x1234aba5, 0x1234aba6) returns 0x0000ffff.

# \_\_device\_\_ unsigned int \_\_vcmplts4 (unsigned int a, unsigned int b)

Performs per-byte signed comparison.

#### Returns

Returns 0xff if a < b, else returns 0.

### Description

Splits 4 bytes of each argument into 4 parts, each consisting of 1 byte. For corresponding parts result is ff if 'a' part < 'b' part, and 00 otherwise. For example \_\_vcmplts4(0x1234aba5, 0x1234aba6) returns 0x000000ff.

# \_\_device\_\_ unsigned int \_\_vcmpltu2 (unsigned int a, unsigned int b)

Performs per-halfword unsigned comparison: a < b ? 0xffff : 0.

#### Returns

Returns 0xffff if a < b, else returns 0.

### Description

Splits 4 bytes of each argument into 2 parts, each consisting of 2 bytes. For corresponding parts result is ffff if 'a' part < 'b' part, and 0000 otherwise. For example \_\_vcmpltu2(0x1234aba5, 0x1234aba6) returns 0x0000ffff.

# \_\_device\_\_ unsigned int \_\_vcmpltu4 (unsigned int a, unsigned int b)

Performs per-byte unsigned comparison.

#### Returns

Returns 0xff if a < b, else returns 0.

### Description

Splits 4 bytes of each argument into 4 parts, each consisting of 1 byte. For corresponding parts result is ff if 'a' part < 'b' part, and 00 otherwise. For example \_\_vcmpltu4(0x1234aba5, 0x1234aba6) returns 0x000000ff.

# \_\_device\_\_ unsigned int \_\_vcmpne2 (unsigned int a, unsigned int b)

Performs per-halfword (un)signed comparison: a != b ? 0xffff : 0.

#### Returns

Returns 0xffff if a != b, else returns 0.

### Description

Splits 4 bytes of each argument into 2 parts, each consisting of 2 bytes. For corresponding parts result is ffff if 'a' part != 'b' part, and 0000 otherwise. For example \_\_vcmplts2(0x1234aba5, 0x1234aba6) returns 0x0000ffff.

# \_\_device\_\_ unsigned int \_\_vcmpne4 (unsigned int a, unsigned int b)

Performs per-byte (un)signed comparison.

#### **Returns**

Returns 0xff if a != b, else returns 0.

### Description

Splits 4 bytes of each argument into 4 parts, each consisting of 1 byte. For corresponding parts result is ff if 'a' part != 'b' part, and 00 otherwise. For example \_\_vcmplts4(0x1234aba5, 0x1234aba6) returns 0x000000ff.

# \_\_device\_\_ unsigned int \_\_vhaddu2 (unsigned int a, unsigned int b)

Performs per-halfword unsigned average computation.

### Returns

Returns computed value.

### Description

Splits 4 bytes of each argument into 2 parts, each consisting of 2 bytes. then computes unsigned avarege of corresponding parts. Result is stored as unsigned int and returned.

# \_\_device\_\_ unsigned int \_\_vhaddu4 (unsigned int a, unsigned int b)

Computes per-byte unsigned average.

#### Returns

Returns computed value.

### Description

Splits 4 bytes of each argument into 4 parts, each consisting of 1 byte. then computes unsigned avarege of corresponding parts. Result is stored as unsigned int and returned.

# \_\_device\_\_ unsigned int \_\_vmaxs2 (unsigned int a, unsigned int b)

Performs per-halfword signed maximum computation.

#### **Returns**

Returns computed value.

### Description

Splits 4 bytes of each argument into 2 parts, each consisting of 2 bytes. For corresponding parts function computes signed maximum. Result is stored as unsigned int and returned.

# \_\_device\_\_ unsigned int \_\_vmaxs4 (unsigned int a, unsigned int b)

Computes per-byte signed maximum.

### Returns

Returns computed value.

### Description

Splits 4 bytes of each argument into 4 parts, each consisting of 1 byte. For corresponding parts function computes signed maximum. Result is stored as unsigned int and returned.

# \_\_device\_\_ unsigned int \_\_vmaxu2 (unsigned int a, unsigned int b)

Performs per-halfword unsigned maximum computation.

#### Returns

Returns computed value.

### Description

Splits 4 bytes of each argument into 2 parts, each consisting of 2 bytes. For corresponding parts function computes unsigned maximum. Result is stored as unsigned int and returned.

# \_\_device\_\_ unsigned int \_\_vmaxu4 (unsigned int a, unsigned int b)

Computes per-byte unsigned maximum.

#### **Returns**

Returns computed value.

### Description

Splits 4 bytes of each argument into 4 parts, each consisting of 1 byte. For corresponding parts function computes unsigned maximum. Result is stored as unsigned int and returned.

# \_\_device\_\_ unsigned int \_\_vmins2 (unsigned int a, unsigned int b)

Performs per-halfword signed minimum computation.

#### Returns

Returns computed value.

### Description

Splits 4 bytes of each argument into 2 parts, each consisting of 2 bytes. For corresponding parts function computes signed minimum. Result is stored as unsigned int and returned.

# \_\_device\_\_ unsigned int \_\_vmins4 (unsigned int a, unsigned int b)

Computes per-byte signed minimum.

#### Returns

Returns computed value.

### Description

Splits 4 bytes of each argument into 4 parts, each consisting of 1 byte. For corresponding parts function computes signed minimum. Result is stored as unsigned int and returned.

# \_\_device\_\_ unsigned int \_\_vminu2 (unsigned int a, unsigned int b)

Performs per-halfword unsigned minimum computation.

#### Returns

Returns computed value.

### Description

Splits 4 bytes of each argument into 2 parts, each consisting of 2 bytes. For corresponding parts function computes unsigned minimum. Result is stored as unsigned int and returned.

# \_\_device\_\_ unsigned int \_\_vminu4 (unsigned int a, unsigned int b)

Computes per-byte unsigned minimum.

#### Returns

Returns computed value.

### Description

Splits 4 bytes of each argument into 4 parts, each consisting of 1 byte. For corresponding parts function computes unsigned minimum. Result is stored as unsigned int and returned.

\_\_device\_\_ unsigned int \_\_vneg2 (unsigned int a)

Computes per-halfword negation.

#### Returns

Returns computed value.

### Description

Splits 4 bytes of argument into 2 parts, each consisting of 2 bytes. For each part function computes negation. Result is stored as unsigned int and returned.

# \_\_device\_\_ unsigned int \_\_vneg4 (unsigned int a)

Performs per-byte negation.

#### Returns

Returns computed value.

# Description

Splits 4 bytes of argument into 4 parts, each consisting of 1 byte. For each part function computes negation. Result is stored as unsigned int and returned.

# \_\_device\_\_ unsigned int \_\_vnegss2 (unsigned int a)

Computes per-halfword negation with signed saturation.

#### **Returns**

Returns computed value.

## Description

Splits 4 bytes of argument into 2 parts, each consisting of 2 bytes. For each part function computes negation. Result is stored as unsigned int and returned.

# \_\_device\_\_ unsigned int \_\_vnegss4 (unsigned int a)

Performs per-byte negation with signed saturation.

#### Returns

Returns computed value.

#### Description

Splits 4 bytes of argument into 4 parts, each consisting of 1 byte. For each part function computes negation. Result is stored as unsigned int and returned.

# \_\_device\_\_ unsigned int \_\_vsads2 (unsigned int a, unsigned int b)

Performs per-halfword sum of absolute difference of signed.

#### Returns

Splits 4 bytes of each argument into 2 parts, each consisting of 2 bytes. For corresponding parts functions computes absolute difference and sum it up. Result is stored as unsigned int and returned.

# \_\_device\_\_ unsigned int \_\_vsads4 (unsigned int a, unsigned int b)

Computes per-byte sum of abs difference of signed.

#### Returns

Returns computed value.

## Description

Splits 4 bytes of each argument into 4 parts, each consisting of 1 byte. For corresponding parts functions computes absolute difference and sum it up. Result is stored as unsigned int and returned.

# \_\_device\_\_ unsigned int \_\_vsadu2 (unsigned int a, unsigned int b)

Computes per-halfword sum of abs diff of unsigned.

#### Returns

Returns computed value.

# Description

Splits 4 bytes of each argument into 2 parts, each consisting of 2 bytes. For corresponding parts function computes absolute differences, and returns sum of those differences.

# \_\_device\_\_ unsigned int \_\_vsadu4 (unsigned int a, unsigned int b)

Computes per-byte sum af abs difference of unsigned.

#### **Returns**

Splits 4 bytes of each argument into 2 parts, each consisting of 2 bytes. For corresponding parts function computes absolute differences, and returns sum of those differences.

# \_\_device\_\_ unsigned int \_\_vseteq2 (unsigned int a, unsigned int b)

Performs per-halfword (un)signed comparison.

#### Returns

Returns 1 if a = b, else returns 0.

## Description

Splits 4 bytes of each argument into 2 parts, each consisting of 2 bytes. For corresponding parts function performs comparison 'a' part == 'b' part. If both equalities are satisfied, function returns 1.

# \_\_device\_\_ unsigned int \_\_vseteq4 (unsigned int a, unsigned int b)

Performs per-byte (un)signed comparison.

#### **Returns**

Returns 1 if a = b, else returns 0.

### Description

Splits 4 bytes of each argument into 4 parts, each consisting of 1 byte. For corresponding parts function performs comparison 'a' part == 'b' part. If both equalities are satisfiad, function returns 1.

# \_\_device\_\_ unsigned int \_\_vsetges2 (unsigned int a, unsigned int b)

Performs per-halfword signed comparison.

#### **Returns**

Returns 1 if  $a \ge b$ , else returns 0.

Splits 4 bytes of each argument into 2 parts, each consisting of 2 bytes. For corresponding parts function performs comparison 'a' part >= 'b' part. If both inequalities are satisfied, function returns 1.

# \_\_device\_\_ unsigned int \_\_vsetges4 (unsigned int a, unsigned int b)

Performs per-byte signed comparison.

#### Returns

Returns 1 if  $a \ge b$ , else returns 0.

## Description

Splits 4 bytes of each argument into 4 parts, each consisting of 1 byte. For corresponding parts function performs comparison 'a' part >= 'b' part. If both inequalities are satisfied, function returns 1.

# \_\_device\_\_ unsigned int \_\_vsetgeu2 (unsigned int a, unsigned int b)

Performs per-halfword unsigned minimum unsigned comparison.

#### **Returns**

Returns 1 if  $a \ge b$ , else returns 0.

# Description

Splits 4 bytes of each argument into 2 parts, each consisting of 2 bytes. For corresponding parts function performs comparison 'a' part >= 'b' part. If both inequalities are satisfied, function returns 1.

# \_\_device\_\_ unsigned int \_\_vsetgeu4 (unsigned int a, unsigned int b)

Performs per-byte unsigned comparison.

#### **Returns**

Returns 1 if  $a \ge b$ , else returns 0.

Splits 4 bytes of each argument into 4 parts, each consisting of 1 byte. For corresponding parts function performs comparison 'a' part >= 'b' part. If both inequalities are satisfied, function returns 1.

# \_\_device\_\_ unsigned int \_\_vsetgts2 (unsigned int a, unsigned int b)

Performs per-halfword signed comparison.

#### Returns

Returns 1 if a > b, else returns 0.

## Description

Splits 4 bytes of each argument into 2 parts, each consisting of 2 bytes. For corresponding parts function performs comparison 'a' part > 'b' part. If both inequalities are satisfied, function returns 1.

# \_\_device\_\_ unsigned int \_\_vsetgts4 (unsigned int a, unsigned int b)

Performs per-byte signed comparison.

#### **Returns**

Returns 1 if a > b, else returns 0.

### Description

Splits 4 bytes of each argument into 4 parts, each consisting of 1 byte. For corresponding parts function performs comparison 'a' part > 'b' part. If both inequalities are satisfied, function returns 1.

# \_\_device\_\_ unsigned int \_\_vsetgtu2 (unsigned int a, unsigned int b)

Performs per-halfword unsigned comparison.

#### **Returns**

Returns 1 if a > b, else returns 0.

Splits 4 bytes of each argument into 2 parts, each consisting of 2 bytes. For corresponding parts function performs comparison 'a' part > 'b' part. If both inequalities are satisfied, function returns 1.

# \_\_device\_\_ unsigned int \_\_vsetgtu4 (unsigned int a, unsigned int b)

Performs per-byte unsigned comparison.

#### Returns

Returns 1 if a > b, else returns 0.

## Description

Splits 4 bytes of each argument into 4 parts, each consisting of 1 byte. For corresponding parts function performs comparison 'a' part > 'b' part. If both inequalities are satisfied, function returns 1.

# \_\_device\_\_ unsigned int \_\_vsetles2 (unsigned int a, unsigned int b)

Performs per-halfword unsigned minimum computation.

#### **Returns**

Returns 1 if a  $\leq$  b, else returns 0.

### Description

Splits 4 bytes of each argument into 2 parts, each consisting of 2 bytes. For corresponding parts function performs comparison 'a' part <= 'b' part. If both inequalities are satisfied, function returns 1.

# \_\_device\_\_ unsigned int \_\_vsetles4 (unsigned int a, unsigned int b)

Performs per-byte signed comparison.

#### **Returns**

Returns 1 if a <= b, else returns 0.

Splits 4 bytes of each argument into 4 parts, each consisting of 1 byte. For corresponding parts function performs comparison 'a' part <= 'b' part. If both inequalities are satisfied, function returns 1.

# \_\_device\_\_ unsigned int \_\_vsetleu2 (unsigned int a, unsigned int b)

Performs per-halfword signed comparison.

#### Returns

Returns 1 if  $a \le b$ , else returns 0.

## Description

Splits 4 bytes of each argument into 2 parts, each consisting of 2 bytes. For corresponding parts function performs comparison 'a' part <= 'b' part. If both inequalities are satisfied, function returns 1.

# \_\_device\_\_ unsigned int \_\_vsetleu4 (unsigned int a, unsigned int b)

Performs per-byte unsigned comparison.

#### **Returns**

Returns 1 if a  $\leq$  b, else returns 0.

### Description

Splits 4 bytes of each argument into 4 part, each consisting of 1 byte. For corresponding parts function performs comparison 'a' part <= 'b' part. If both inequalities are satisfied, function returns 1.

# \_\_device\_\_ unsigned int \_\_vsetlts2 (unsigned int a, unsigned int b)

Performs per-halfword signed comparison.

#### **Returns**

Returns 1 if a < b, else returns 0.

Splits 4 bytes of each argument into 2 parts, each consisting of 2 bytes. For corresponding parts function performs comparison 'a' part <= 'b' part. If both inequalities are satisfied, function returns 1.

# \_\_device\_\_ unsigned int \_\_vsetlts4 (unsigned int a, unsigned int b)

Performs per-byte signed comparison.

#### Returns

Returns 1 if a < b, else returns 0.

## Description

Splits 4 bytes of each argument into 4 parts, each consisting of 1 byte. For corresponding parts function performs comparison 'a' part <= 'b' part. If both inequalities are satisfied, function returns 1.

# \_\_device\_\_ unsigned int \_\_vsetltu2 (unsigned int a, unsigned int b)

Performs per-halfword unsigned comparison.

#### **Returns**

Returns 1 if a < b, else returns 0.

# Description

Splits 4 bytes of each argument into 2 parts, each consisting of 2 bytes. For corresponding parts function performs comparison 'a' part <= 'b' part. If both inequalities are satisfied, function returns 1.

# \_\_device\_\_ unsigned int \_\_vsetltu4 (unsigned int a, unsigned int b)

Performs per-byte unsigned comparison.

#### **Returns**

Returns 1 if a < b, else returns 0.

Splits 4 bytes of each argument into 4 parts, each consisting of 1 byte. For corresponding parts function performs comparison 'a' part <= 'b' part. If both inequalities are satisfied, function returns 1.

# \_\_device\_\_ unsigned int \_\_vsetne2 (unsigned int a, unsigned int b)

Performs per-halfword (un)signed comparison.

#### Returns

Returns 1 if a != b, else returns 0.

## Description

Splits 4 bytes of each argument into 2 parts, each consisting of 2 bytes. For corresponding parts function performs comparison 'a' part != 'b' part. If both conditions are satisfied, function returns 1.

# \_\_device\_\_ unsigned int \_\_vsetne4 (unsigned int a, unsigned int b)

Performs per-byte (un)signed comparison.

#### **Returns**

Returns 1 if a != b, else returns 0.

# Description

Splits 4 bytes of each argument into 4 parts, each consisting of 1 bytes. For corresponding parts function performs comparison 'a' part != 'b' part. If both conditions are satisfied, function returns 1.

# \_\_device\_\_ unsigned int \_\_vsub2 (unsigned int a, unsigned int b)

Performs per-halfword (un)signed substraction, with wrap-around.

#### **Returns**

Splits 4 bytes of each argument into 2 parts, each consisting of 2 bytes. For corresponding parts functions performs substraction. Result is stored as unsigned int and returned.

# \_\_device\_\_ unsigned int \_\_vsub4 (unsigned int a, unsigned int b)

Performs per-byte substraction.

#### Returns

Returns computed value.

## Description

Splits 4 bytes of each argument into 4 parts, each consisting of 1 bytes. For corresponding parts functions performs substraction. Result is stored as unsigned int and returned.

# \_\_device\_\_ unsigned int \_\_vsubss2 (unsigned int a, unsigned int b)

Performs per-halfword (un)signed substraction, with signed saturation.

#### Returns

Returns computed value.

### Description

Splits 4 bytes of each argument into 2 parts, each consisting of 2 bytes. For corresponding parts functions performs substraction with signed saturation. Result is stored as unsigned int and returned.

# \_\_device\_\_ unsigned int \_\_vsubss4 (unsigned int a, unsigned int b)

Performs per-byte substraction with signed saturation.

#### **Returns**

Splits 4 bytes of each argument into 4 parts, each consisting of 1 byte. For corresponding parts functions performs substraction with signed saturation. Result is stored as unsigned int and returned.

# \_\_device\_\_ unsigned int \_\_vsubus2 (unsigned int a, unsigned int b)

Performs per-halfword substraction with unsigned saturation.

#### Returns

Returns computed value.

## Description

Splits 4 bytes of each argument into 2 parts, each consisting of 2 bytes. For corresponding parts functions performs substraction with unsigned saturation. Result is stored as unsigned int and returned.

# \_\_device\_\_ unsigned int \_\_vsubus4 (unsigned int a, unsigned int b)

Performs per-byte substraction with unsigned saturation.

#### Returns

Returns computed value.

### Description

Splits 4 bytes of each argument into 4 parts, each consisting of 1 byte. For corresponding parts functions performs substraction with unsigned saturation. Result is stored as unsigned int and returned.

#### Notice

ALL NVIDIA DESIGN SPECIFICATIONS, REFERENCE BOARDS, FILES, DRAWINGS, DIAGNOSTICS, LISTS, AND OTHER DOCUMENTS (TOGETHER AND SEPARATELY, "MATERIALS") ARE BEING PROVIDED "AS IS." NVIDIA MAKES NO WARRANTIES, EXPRESSED, IMPLIED, STATUTORY, OR OTHERWISE WITH RESPECT TO THE MATERIALS, AND EXPRESSLY DISCLAIMS ALL IMPLIED WARRANTIES OF NONINFRINGEMENT, MERCHANTABILITY, AND FITNESS FOR A PARTICULAR PURPOSE.

Information furnished is believed to be accurate and reliable. However, NVIDIA Corporation assumes no responsibility for the consequences of use of such information or for any infringement of patents or other rights of third parties that may result from its use. No license is granted by implication of otherwise under any patent rights of NVIDIA Corporation. Specifications mentioned in this publication are subject to change without notice. This publication supersedes and replaces all other information previously supplied. NVIDIA Corporation products are not authorized as critical components in life support devices or systems without express written approval of NVIDIA Corporation.

## Trademarks

NVIDIA and the NVIDIA logo are trademarks or registered trademarks of NVIDIA Corporation in the U.S. and other countries. Other company and product names may be trademarks of the respective companies with which they are associated.

### Copyright

© 2007-2014 NVIDIA Corporation. All rights reserved.

