

Steven Labalme

February 5, 2025

Weeks

1	1D NMR Principles and Practices						
	1.1	Underlying Principles of NMR	1				

List of Figures

1.1	Chemical shift	ranges of common	nuclei.	 	 	 	2

Week 1

1/4:

1D NMR Principles and Practices

1.1 Underlying Principles of NMR

- Philosophy: NMR is a complicated and useful set of tool for chemists.
 - Background on Walt.
 - Training: Masters, PhD, Postdoc, and 5 jobs in NMR.
 - 20 years industry experience, 10 years academia experience, some small company experience.
 - Considers himself somewhere in the middle between knowing nothing and everything about NMR.
 - Experience in natural products discovery, drug discovery, biological NMR, etc.
 - Goal of the class: Distill what's most important for us to know.
 - Announcements.
 - Syllabus now posted on Canvas!
 - Everything important will be posted on Canvas.
 - MestReNova is what we should use; TopSpin is what Walt is more comfortable with.
 - Slides posted to Canvas at the end of the day.
 - This week: The fundamentals.
 - Chemical shift, coupling constants, correlations (new), NMR relaxation
 - The NMR periodic table.
 - ¹H has almost 100% spin 1/2.
 - ¹²C is 99% abundant and has spin 0.
 - Thus, we can only do NMR with 13 C.
 - The resonant frequency depends on an absolutely fundamental physical property called the **gyromagnetic ratio** (γ).
 - Highest gyromagnetic ratio is tritium (³H), then fluorine, then a whole bunch, then phosphorus, carbon, nitrogen (with a bunch in between these three as well).
 - Higher magnetic field gives more signal.
 - But 1/4 as much for 13 C as for 1 H, because γ for 13 C is 1/4 what it is for 1 H.
 - The highest field NMR systems commercially available are at 1.2 GHz.
 - Walt will typically only go up to 600 MHz in this class, corresponding to a 14.1 T magnet.

• Range of chemical shifts.



Figure 1.1: Chemical shift ranges of common nuclei.

- The range of chemical signals we'll see is tiny, though; only about 6000 Hz if we're talking about a 10 ppm window.
- Different nuclei appear in different windows and with different ranges (think of how carbon is 0-200 ppm vs. proton -5-15!!).
- Note that the ranges in Figure 1.1 are to scale relative to each other, but have been scaled up absolutely by 10 times.
- All atoms' spins are active as soon as we magnetize the sample in the magnet bore. Differentiating between them is now an electronics problem.
- α and β -D-glucose's anomeric protons have significantly different chemical shifts (4.6 ppm vs. 5.1 ppm, roughly).
- Oxygen is virtually all spin 0 ¹⁶O, but protons will couple to each other and to ¹³C (giving carbon satellites).
 - -1% of the time, the proton is coupled to 13 C, and gets massively split.
 - All couplings exist; it's just a question of whether we can see them!
 - 170 Hz coupling for the 1-bond carbon-to-proton coupling.
 - 2-bond connection is then expected to be much smaller, maybe 25-30 Hz.
 - Protons are present in much higher concentration, though, so we see their splitting much more (but it's also smaller because they're farther away!). This is why vicinal protons couple in 4-8 Hz instead of 200 Hz.
- Sergei: Why no coupling to the alcohol protons?
 - Because the sample is in D_2O , we get exchange everywhere to OD.
 - Since deuterium is spin 1, it should split the spin 1/2 nucleus into a triplet. But it also has 1/6 the gyromagnetic ratio. Additionally, fast exchange prevents any meaningful coupling from developing.
 - Dissolving the sample in (very dry) DMSO-d₆ will *not* lead to proton exchange, and we *can* observe the couplings to the hydroxyl protons!
- Equations.
 - -5/2 exponent for gyromagnetic ratio means it *really* matters for sensitivity.
- 600 MHz denotes the resonance for protons at the set magnetic field.
 - Carbon would be at 150 MHz in this case (because 1/4 gyromagnetic ratio)!
 - 140-150 A of current in the magnetic.
- A 4 Hz coupling is on the order of parts per billion, so to discern it, we need parts per billion homogeneity in the magnetic field. This is why we need shimming.
 - Shimming is done with additional coils that impart additional magnetism to parts of the sample.

- Shimming is done for all of the few dozen coils every once in a while, and then with some of the coils for each particular sample.
- To shim, you measure the deuterium lock signal and how broad or narrow/high the peak is and then you fiddle with the coils!
- All you really have to look at is the height because the area is the same, so the height of the lock signal correlates to how good the shimming is.
- Today, we do **radian shimming**, which tells us how to change the current in the coils to make the shimming better.
- Shim coils can only be adjusted so far; if there's no sample below the coil, the shimming likely can't compensate enough to get a good spectrum.

• Administrivia.

- There will be some kind of group project.
- Final project is for us to use our skills to do something useful.
- Write up our PSets independently, but we can work together on them.