
CSS3 Flexbox



Learn CSS3 Flexbox The Right Way



Siavash Sattari Front-end Developer







Section 1:

Getting Started With Flexbox

Lecture 1.3:

Introduction

Get started with FLEXBOX:

- What is Flexbox?
- Browser Support for Flexbox
- Setup Starter Files
- Our First Flexbox Layout

Section 1:

Getting Started With Flexbox

Lecture 2.3:

What is Flexbox?


What Is Flexbox?

- Flexbox is a new layout module in CSS3 designed to help us create CSS layouts much easier.
- Flexbox layout model provides a more efficient way to layout, align and distribute space among elements within our document even when the viewport and the size of our elements is dynamic or unknown.
- The main idea behind the flex layout is to give the container the ability to change it's elements width, height and order to best fill the available free space.
- A flex container expands elements to fill available free space or shrink them to prevent overflow.
- Flexbox is a one-dimensional layout model which controls the layout based on a row or on a column but not together at the same time .
- Flexbox really makes it easier to create flexible responsive layouts without using float or positioning.
- Flexbox is the Future!

- Flexbox is the tool that let's us forgot about using :
 - Table layouts
 - Floats
 - Clearfix hacks
 - Positioning
- With new CSS3 Flexbox model, we can now write more less and maintainable code for various common layout tasks such as:
 - Vertical centering
 - Equal height columns
 - Take up the whole space
 - Simpler grids

Flexbox consists of two main components:

- Flex Container: The parent element in which Flex items are contained.
- Flex Items: The direct child elements within a Flex container.




Flexbox is a set of properties:

Flex Container Properties

- 1. flex-direction
- 2. flex-wrap
- 3. flex-flow
- 4. justify-content
- 5. align-items
- 6. align-content

Flex Item Properties

- 1. order
- 2. align-self
- 3. flex-grow
- 4. flex-shrink
- 5. flex-basis
- 6. flex



Section 1:

Getting Started With Flexbox

Lecture 3.3:

Browser Support For Flexbox

Browser Support For Flexbox:



CSS Flexbox is supported in all the modern browsers

Section 2:

Working On Flex Container

Lecture 1.10:

Introduction

Working on Flex Container:

- display display : flex ; **VS** display : inline-flex
- main-axis and Cross-axis
- flex-direction
- flex-wrap
- The shorthand 'flex-flow' property
- justify-content
- align-items
- align-content
- Flex container properties overview

Section 2:

Working On Flex Container

Lecture 2.10:

display: flex VS display: inline-flex

Creating a Flex Container:


Flexbox layout activated by declaring the **display** property:

- display: flex; The element becomes a block-level flex container.
- display: inline-flex; The element becomes an inline-level flex container.

display: flex



Note: Both flex containers take 100% width of screen.



Note: Inline flex containers do not take 100% width of screen.

Section 2:


Working On Flex Container

Lecture 3.10:


Main-Axis & Cross-Axis

The Two Axis Of Flexbox:


- 1. Main-axis: This is the primary axis along which flex items are laid out. This will change depending upon the value of flex-direction property.
- 2. Cross-axis: This is the axis that is perpendicular to the main axis. The direction depends on the main axis direction.




By default, Flex items laid out horizontally.





Flex items laid out vertically.




Flex items laid out horizontally.







(Right to Left, Top to Bottom)



(Bottom to Top, Left to Right)

Section 2:

Working On Flex Container

Lecture 4.10:

flex-direction Property

- The flex-direction allows to set the direction that how flex items are placed within flex container.
- It establishes the main-axis which determines the direction that flex items are laid out in .


flex-direction:

• The **flex-direction** property sets direction for flex items within flex container . It accepts 4 values :

- row (Default) : Main-axis runs from left to right .
- column Main-axis runs from top to bottom .
- row-reverse Main-axis runs from right to left .
- column-reverse Main-axis runs from bottom to top.
- Syntax for **flex-direction** property:

```
flex-direction: row | row-reverse | column | column-reverse;
```

flex-direction: row;




Main-axis runs from left to right

flex-direction: row-reverse;




Main-axis runs from right to left

flex-direction: column;




Main-axis runs from top to bottom


flex-direction: column-reverse;




Main-axis runs from bottom to top


Normal





Reverse





Section 2:

Working On Flex Container

Lecture 5.10:

flex-wrap Property

• The flex-wrap defines whether the flex container is **single-line** or **multi-line**, and it also defines the direction of the cross-axis, which determines the direction new lines are stacked in .

flex-wrap:


- The **flex-wrap** property specifies whether the flex items should wrap or not . It accepts 3 values :
 - nowrap This is the default. The flex container creates only one row or column.
 - wrap The flex container is multi-line & Flex items will wrap onto multiple lines.
 - wrap-reverse Same as wrap; but in opposite direction .
- Syntax for flex **flex-wrap** property:

```
flex-wrap : nowrap | wrap | wrap-reverse ;
```

flex-wrap: nowrap;




No-wrap may cause flex container to overflow, breaking the layout




Flex items wrapped on the new next line / row along the cross axis

flex-wrap: wrap;



Flex items wrapped on the new next line / column along the cross axis

flex-wrap: wrap-reverse;



Flex items wrapped on the new next line / row but in the reverse / opposite direction of the the cross axis

Section 2:

Working On Flex Container

Lecture 6.10:

The Shorthand 'flex-flow 'Property

The shorthand 'flex-flow' Property:


• The **flex-flow** property is a shorthand for flex-direction and flex-wrap, in allows us to specify both of them using just one property name:

row nowrap – This is the default.

• Syntax for **flex-flow** property:

flex-flow: row nowrap [flex-direction flex-wrap]

The shorthand 'flex-flow' Property:



Section 2:

Working On Flex Container

Lecture 7.10:

Justify-content Property


- The justify-content Property aligns the flex items along the main-axis, the direction in which flex-direction has set the flow.
- Typically it helps to distribute extra free space leftover between and around the flex items along the main-axis of a flex container.

justify-content:

- The **justify-content** property is used to align the flex items along the main-axis . It accepts 6 values :
 - flex-start Aligns the flex items at the start of the flex container . This is default .
 - flex-end Aligns the Flex items at the end of the flex container.
 - center Aligns the flex items in the middle of the flex container.
 - space-between Aligns the flex items with equal spacing between them.
 - space-around Aligns the flex items with equal spacing around them .
 - space-evenly Aligns the flex items with equal spacing between any two flex items.
- Syntax for **justify-content** property:


```
justify-content: flex-start | flex-end | center | space-between | ...;
```

Main-axis & Cross-axis :




Flex items laid out horizontally.

Main-axis




Note: justify-content positions flex-items along the Main-axis

justify-content: flex-start;




All flex items are placed at the start of main-axis. This is default

justify-content: flex-end;




All flex items are placed at the end of main-axis

justify-content : center ;




All flex items are placed at the center of main-axis

justify-content: space-between;




Flex items are evenly distributed along the main-axis, first item is on the main-start and last item is on the main-end

justify-content: space-between;




Same spacing between flex-items

justify-content: space-around;




Flex items are evenly distributed along the main-axis with equal space around them

justify-content : space-around ;



Same spacing around flex-items


justify-content: space-evenly;



Flex items are distributed so that the spacing between any two flex items is equal .

And also the space to the edges is equal too

justify-content: space-evenly;



Same spacing between flex-items, And also the space to the edges is equal too

justify-content – row : ----

flex-start

1 2 3

flex-end



space-around



center




space-between



space-evenly



justify-content – column :



Section 2:

Working On Flex Container

Lecture 8.10:

align-items Property


• The align-items allows to align flex items along the cross-axis on the current row/column.

align-items Properties:

- The align-items property is used to align the flex items along the cross-axis. It accepts 5 values:
 - stretch Stretches the flex items to fill the flex container. This is default.
 - flex-start Aligns the flex items at the top of the flex container.
 - center Aligns the flex items in the middle of the flex container.
 - flex-end Aligns the flex items at the bottom of the flex container.
 - baseline Aligns the flex items along their baselines .
- Syntax for align-items property:


```
align-items: stretch | flex-start | center | flex-end | baseline;
```

Main-axis & Cross-axis :




Flex items laid out horizontally.

Cross-axis:




Note: align-items positions flex-items along the Cross-axi

align-items: stretch;




All flex items stretch along the cross-axis to fill the flex container. This is default.

align-items: flex-start;




All flex items are placed at the start of the cross-axis.

align-items : center ;




All flex items are placed in the middle of the cross-axis.

align-items: flex-end;




All flex items are placed at the end of cross-axis.

align-items : baseline ;




All flex items are aligned in such a way that the baseline are equal .

align-items – row : →



align-items – column:



Section 2:

Working On Flex Container

Lecture 9.10:

align-content Property


- The align-content aligns flex lines within the flex container when there is an extra space along the cross-axis.
- It has no effect on single line flex containers.

Flex lines:

• Flex items in a flex container are laid out and aligned within flex lines. A flex container can be either single-line or multi-line depending on the flex-wrap property.


- A **single-line** flex container lays out all of its flex items in a single line, even if that would cause its contents to overflow.
- A multi-line flex container breaks its flex items across multiple lines. When additional lines are created, they are stacked in the flex container along the cross-axis according to the flex-wrap property.

flex-wrap: wrap;



Flex items wrapped on the new next line / row along the cross-axis

flex-wrap: wrap;




Flex items wrapped on the new next line / column along the cross-axis

align-content:

- The align-content property is used to align the flex lines along the cross-axis. It accepts 6 values:
 - stretch Stretches the flex lines to take up the remaining space . This is default.
 - flex-start Displays the flex lines at the start of the flex container.
 - center Displays the flex lines in the middle of the flex container.
 - flex-end Displays the flex lines at the end of the container.
 - Space-between Displays the flex lines with equal space between them .
 - Space-around Displays the flex lines with equal space around each line.
- Syntax for *align-content* property :


```
align-content: stretch | flex-start | center | flex-end | space-between | space-around;
```

align-content: stretch;




All flex lines stretch to take up the remaining space in flex container. This is default.

align-content: flex-start;




All flex lines are placed at the start of the flex container.

align-content : center ;




All flex lines are placed in the middle of the flex container.

align-content: flex-end;




All flex lines are placed at the end of the flex container.

align-content: space-between;




Flex lines are evenly distributed the first line is at the start of the flex container while the last one is at the end

align-content: space-around;




Flex lines evenly distributed with equal space before and after each flex line.


align-content: space-around;



Flex lines evenly distributed with equal space around each line.

align-content:





Section 2:

Working On Flex Container

Lecture 10.10:

Flex Container Properties Overview

Flex Container Properties Overview:

1. flex-direction : row row-reverse column column-reverse 2. flex-wrap: nowrap wrap wrap-reverse 3. flex-flow: row nowrap flex-direction flex-wrap 4. justify-content: flex-start flex-end center space-between space-around space-evenly 5. Align-items: stretch flex-start flex-end center baseline align-content

Section 3:

Working On Flex Items

Lecture 1.8:

Introduction

Working on Flex Items:

- order
- align-self
- flex-grow
- flex-shrink
- flex-basis
- The Shorthand 'flex' Property
- Flex Item properties overview

Section 3:

Working On Flex Items

Lecture 2.8:

order Property

The flexbox ordering controls the order in which flex items of a flex container appear inside the flex container. By default they are ordered as initially added in the flex container.

order Property:


• The **order** property specifies the order of a flex item relative to the rest of flexible items inside the same flex container. It accepts positive or negative integer as a value.

```
    0 - This is default.
```


<integer> - A positive or negative integer value .

• Syntax for **order** property:


```
order: 0 | <integer>;
```





Note: order positions flex-items along the Main-axis





By default, flex items are laid out in the order in which they appear.

















Section 3:

Working On Flex Items

Lecture 3.8:

align-self Property

• The align-self defines the alignment of individual flex item along the cross-axis .


align-self:

- The align-self property specifies the alignment for the selected flex item inside the flex container. It accepts 6 values:
 - auto Selected flex item inherits it's flex container's align-items property. This is default.
 - stretch Stretches the selected flex item to fill the flex container.
 - flex-start Aligns the selected flex item at the top of the flex container.
 - center Aligns the selected flex item in the middle of the flex container.
 - flex-end Aligns the selected flex item at the bottom of the flex container .
 - baseline Aligns the selected flex item at the baseline of the flex container.

Syntax for align-self property :


```
align-self: auto | stretch | flex-start | center | flex-end | baseline ;
```

Cross-axis:




Note: align-self aligns the selected flex-item along the Cross-a

align-self : auto ;




By default, all flex items inherit their flex container's align-items property so therefore stretched.

align-self: stretch;




The selected flex item is stretched to fill the flex container.

align-self : flex-start ;




The selected flex item is positioned at the top of the flex container .

align-self : center ;



The selected flex item is positioned in middle of the flex container.

align-self : baseline ;



The selected flex item is positioned at the baseline of the flex container.

Section 3:

Working On Flex Items


Lecture 4.8:

flex-grow Property

The Superpower of Flex Items;

- 1. flex-grow: Decides how much a flex item should grow, if there is extra space.
- 2. flex-shrink: Decides how much a flex item should shrink, if there is no extra space.
- 3. flex-basis: Defines the initial main-size of a flex item.

order:



Note: flex-grow, flex-shrink & flex-basis, all three act along the Main-axis

What is flex-grow?;

• The flex-grow defines how much a flex item should grow relative to other flex items if there is an extra space available .

flex-grow


• The flex-grow property specifies how much a flex item can grow relative to the other flex items . It accepts a unitless positive number as a value . Negative numbers are invalid .

```
• 0 - This is default.
```


• <number> - Any unitless positive number.

• Syntax for **flex-grow** property:


```
flex-grow : 0 | <number> ;
```



By default, flex items are with flex-grow set to zero, which means, they take **only** as much space as it is necessary to display their content.




The flex-grow allows us to increase the width of flex-item, so it nicely expand & take all the available extra space of it's flex container.




If all flex-items have same grow factor, we get flex-items that grow equally and fill up the entire flex container.

flex-grow:



If one of the flex-item has grow factor of 2, that would mean, that flex-item will take twice as much space as the ones that have grow factor set to 1.

flex-grow Calculation:



Section 3:

Working On Flex Items

Lecture 5.8:

flex-shrink Property

What is flex-shrink?;

- The flex-shrink defines how much a flex item should shrink relative to other flex items if there is not enough space available.
- The flex-shrink is only important if the flex container has the **nowrap** setting, so that all of the flex items sit next to each other in a single row.

flex-shrink Property:


• The flex-shrink property specifies how much a flex item can shrink relative to the other flex items. It accepts a unitless positive number as a value. Negative numbers are invalid.

```
• 1 - This is default.
```


• <number> - Any unitless positive number.

• Syntax for **flex-shrink** property:


```
flex-shrink: 1 | <number>;
```




Note: flex-shrink acts along the Main-axis




flex-wrap: nowrap




By default, all flex items have flex-shrink set to 1, which means, they are allowed to shrink equally if there is not enough space to accommodate.




flex-wrap: nowrap



If all flex items have flex-shrink set to zero (don't shrink), they will simply overflow their flex-container if there is not enough space.



flex-wrap: nowrap



flex-wrap: nowrap

Setting one flex-item with flex-shrink of 2 would mean that , that flex-item will shrink 2 times more as compare to others .

Section 3:

Working On Flex Items

Lecture 6.8:

flex-basis Property

What is flex-basis?;

• It specifies the **initial main size** of the flex-item , before any available space is distributed according to the flex factors (flex-grow & flex-shrink).


• The **flex-basis** property specifies the initial main size of the flex-item , before any available space is distributed. It takes any CSS size .

```
    auto - This is default .
```


<length> - Any CSS size - percentage | em | rem | pixel etc .

• Syntax for flex-basis property:

```
flex-shrink : auto | <length> ;
```




Note: flex-basis acts along the Main-axis




By default, the flex-basis property is set to auto, which means, the flex-basis falls back to the flex item's width property.




If the flex-items have flex-basis property set to zero, that means, they will take up only the necessary space to display their content.



By default, the flex-basis property is set to auto, which means, the flex-basis falls back to the flex item's width property.





The flex-basis specifies the initial main size of a flex-item, before any free space is distributed according to the flex factors. It takes any CSS size in %, rem, em, px, etc.

flex-basis VS widths:

```
.child {
   flex-basis: 500px;
                                       500px
   width: 100px;
.child {
   flex-basis: 100px;
                            100рх
   min-width: 500px;
.child {
   flex-basis: 100px;
                                                700px
   max-width: 700px;
```

Section 3:

Working On Flex Items

Lecture 7.8:

The Shorthand 'flex' Property


flex Property:

• The flex property is a shorthand for the flex-grow, flex-shrink and flex-basis properties

```
• 0 1 auto - This is default .
```

• flex: 0 1 auto;

flex:



Section 3:

Working On Flex Items

Lecture 8.8:

Flex Item Properties Overview

Flex Item Properties Overview:

```
1. oredr: 0 <integer>
2. align-self: auto stretch flex-start flex-end center baseline
3. flex-grow: 0 <integer>
4. flex-shrink: 1 <integer>
5. flex-basis: auto <length>
6. flex: 0 1 auto flex-grow flex-shrink flex-basis
```

The End:) Hope you enjoy it

Email: siavash.sattari.dev@gmail.com