Programming Shared Address Space Platforms

Dr B Krishna Priya

Topic Overview

- Thread Basics
- The POSIX Thread API
- Synchronization Primitives in Pthreads
- Controlling Thread and Synchronization Attributes
- Composite Synchronization Constructs
- OpenMP: a Standard for Directive Based Parallel Programming

Overview of Programming Models

- Programming models provide support for expressing concurrency and synchronization.
- Process based models assume that all data associated with a process is private, by default, unless otherwise specified.
- Lightweight processes and threads assume that all memory is global.
- Directive based programming models extend the threaded model by facilitating creation and synchronization of threads.

Overview of Programming Models

A thread is a single stream of control in the flow of a program.
 A program like:


can be transformed to:

In this case, one may think of the thread as an instance of a function that returns before the function has finished executing.

Thread Basics

- All memory in the logical machine model of a thread is globally accessible to every thread.
- The stack corresponding to the function call is generally treated as being local to the thread for liveness reasons.
- This implies a logical machine model with both global memory (default) and local memory (stacks).
- It is important to note that such a flat model may result in very poor performance since memory is physically distributed in typical machines.

Thread Basics



The logical machine model of a thread-based programming paradigm.

Thread Basics

- Threads provide software portability.
- Inherent support for latency hiding.
- Scheduling and load balancing.
- Ease of programming and widespread use.

The POSIX Thread API

- Commonly referred to as Pthreads, POSIX has emerged as the standard threads API, supported by most vendors.
- The concepts discussed here are largely independent of the API and can be used for programming with other thread APIs (NT threads, Solaris threads, Java threads, etc.) as well.

Thread Basics: Creation and Termination

 Pthreads provides two basic functions for specifying concurrency in a program:

```
#include <pthread.h>
int pthread_create (
    pthread_t    *thread_handle,
    const pthread_attr_t    *attribute,
    void * (*thread_function)(void *),
    void *arg);

int pthread_join (
    pthread_t    thread,
    void    **ptr);
```

• The function pthread_create invokes function thread_function as a thread.

Thread Basics: Creation and Termination (Example)

```
#include <pthread.h>
#include <stdlib.h>
#define MAX_THREADS
                      512
void *compute_pi (void *);
. . . .
main() {
    pthread_t p_threads[MAX_THREADS];
    pthread_attr_t attr;
    pthread_attr_init (&attr);
    for (i=0; i< num_threads; i++) {</pre>
        hits[i] = i;
        pthread_create(&p_threads[i], &attr, compute_pi,
            (void *) &hits[i]);
    for (i=0; i< num_threads; i++) {</pre>
        pthread_join(p_threads[i], NULL);
        total_hits += hits[i];
```


Thread Basics: Creation and Termination (Example)

```
void *compute_pi (void *s) {
    int seed, i, *hit pointer;
    double rand_no_x, rand_no_y;
    int local_hits;
    hit pointer = (int *) s;
    seed = *hit_pointer;
    local_hits = 0;
    for (i = 0; i < sample_points_per_thread; i++) {</pre>
        rand_no_x = (double) (rand_r(\&seed)) / (double) ((2 << 14) -1);
        rand_no_y = (double) (rand_r(\&seed)) / (double) ((2 << 14) -1);
        if (((rand_no_x - 0.5) * (rand_no_x - 0.5) +
            (rand_no_y - 0.5) * (rand_no_y - 0.5)) < 0.25)
            local hits ++;
        seed *= i;
    *hit_pointer = local_hits;
    pthread_exit(0);
```

Programming and Performance Notes

- Note the use of the function rand_r (instead of superior random number generators such as drand48).
- Executing this on a 4-processor SGI Origin, we observe a 3.91 fold speedup at 32 threads. This corresponds to a parallel efficiency of 0.98!
- We can also modify the program slightly to observe the effect of false-sharing.
- The program can also be used to assess the secondary cache line size.

Programming and Performance Notes



Execution time of the compute_pi program.

Synchronization Primitives in Pthreads

 When multiple threads attempt to manipulate the same data item, the results can often be incoherent if proper care is not taken to synchronize them.

• Consider:

```
/* each thread tries to update variable best_cost as follows */
if (my_cost < best_cost)
   best_cost = my_cost;</pre>
```

- Assume that there are two threads, the initial value of best_cost is 100, and the values of my_cost are 50 and 75 at threads t1 and t2.
- Depending on the schedule of the threads, the value of best_cost could be 50 or 75!
- The value 75 does not correspond to any serialization of the threads.

Mutual Exclusion

- The code in the previous example corresponds to a critical segment; i.e., a segment that must be executed by only one thread at any time.
- Critical segments in Pthreads are implemented using mutex locks.
- Mutex-locks have two states: locked and unlocked. At any point of time, only one thread can lock a mutex lock. A lock is an atomic operation.
- A thread entering a critical segment first tries to get a lock. It goes ahead when the lock is granted.

Mutual Exclusion

The Pthreads API provides the following functions for handling mutex-locks:

```
int pthread_mutex_lock (
    pthread_mutex_t *mutex_lock);

int pthread_mutex_unlock (
    pthread_mutex_t *mutex_lock);

int pthread_mutex_init (
    pthread_mutex_t *mutex_lock,
    const pthread_mutexattr_t *lock_attr);
```

Mutual Exclusion

We can now write our previously incorrect code segment as:

```
pthread mutex t minimum value lock;
main() {
    pthread_mutex_init(&minimum_value_lock, NULL);
void *find_min(void *list_ptr) {
    pthread_mutex_lock(&minimum_value_lock);
    if (my_min < minimum_value)</pre>
        minimum_value = my_min;
    /* and unlock the mutex */
    pthread_mutex_unlock(&minimum_value_lock);
```

Producer-Consumer Using Locks

The producer-consumer scenario imposes the following constraints:

- The producer thread must not overwrite the shared buffer when the previous task has not been picked up by a consumer thread.
- The consumer threads must not pick up tasks until there is something present in the shared data structure.
- Individual consumer threads should pick up tasks one at a time.

Producer-Consumer Using Locks

```
pthread_mutex_t task_queue_lock;
int task_available;
main() {
    task_available = 0;
    pthread_mutex_init(&task_queue_lock, NULL);
    . . . .
void *producer(void *producer_thread_data) {
    while (!done()) {
        inserted = 0;
        create_task(&my_task);
        while (inserted == 0) {
            pthread_mutex_lock(&task_queue_lock);
            if (task_available == 0) {
                insert_into_queue(my_task);
                task_available = 1;
                inserted = 1;
            pthread_mutex_unlock(&task_queue_lock);
```

Producer-Consumer Using Locks

```
void *consumer(void *consumer_thread_data) {
    int extracted;
    struct task my_task;
    /* local data structure declarations */
    while (!done()) {
        extracted = 0;
        while (extracted == 0) {
            pthread_mutex_lock(&task_queue_lock);
            if (task_available == 1) {
                extract_from_queue(&my_task);
                task_available = 0;
                extracted = 1;
            pthread_mutex_unlock(&task_queue_lock);
        process_task(my_task);
```

Types of Mutexes

- Pthreads supports three types of mutexes normal, recursive, and error-check.
- A normal mutex deadlocks if a thread that already has a lock tries a second lock on it.
- A recursive mutex allows a single thread to lock a mutex as many times as it wants. It simply increments a count on the number of locks. A lock is relinquished by a thread when the count becomes zero.
- An error check mutex reports an error when a thread with a lock tries to lock it again (as opposed to deadlocking in the first case, or granting the lock, as in the second case).
- The type of the mutex can be set in the attributes object before it is passed at time of initialization.

Overheads of Locking

- Locks represent serialization points since critical sections must be executed by threads one after the other.
- Encapsulating large segments of the program within locks can lead to significant performance degradation.
- It is often possible to reduce the idling overhead associated with locks using an alternate function, pthread_mutex_trylock.

```
int pthread_mutex_trylock (
    pthread_mutex_t *mutex_lock);
```

pthread_mutex_trylock is typically much faster than pthread_mutex.
 on typical systems since it does not have to deal with queues associated with locks for multiple threads waiting on the lock.

Alleviating Locking Overhead (Example)

```
/* Finding k matches in a list */
void *find entries(void *start pointer) {
    /* This is the thread function */
    struct database_record *next_record;
    int count;
    current_pointer = start_pointer;
    do {
        next_record = find_next_entry(current_pointer);
        count = output_record(next_record);
    } while (count < requested_number_of_records);</pre>
int output_record(struct database_record *record_ptr) {
    int count;
    pthread_mutex_lock(&output_count_lock);
    output_count ++;
    count = output_count;
    pthread mutex_unlock(&output_count_lock);
    if (count <= requested_number_of_records)</pre>
        print_record(record_ptr);
    return (count);
```

Alleviating Locking Overhead (Example)

```
/* rewritten output_record function */
int output_record(struct database_record *record_ptr) {
    int count;
    int lock_status;
    lock_status = pthread_mutex_trylock(&output_count_lock);
    if (lock_status == EBUSY) {
        insert_into_local_list(record_ptr);
        return(0);
    else {
        count = output_count;
        output_count += number_on_local_list + 1;
        pthread_mutex_unlock(&output_count_lock);
        print_records(record_ptr, local_list,
              requested_number_of_records - count);
        return(count + number_on_local_list + 1);
```

Condition Variables for Synchronization

- A condition variable allows a thread to block itself until specified data reaches a predefined state.
- A condition variable is associated with this predicate. When the predicate becomes true, the condition variable is used to signal one or more threads waiting on the condition.
- A single condition variable may be associated with more than one predicate.
- A condition variable always has a mutex associated with it. A thread locks this mutex and tests the predicate defined on the shared variable.
- If the predicate is not true, the thread waits on the condition variable associated with the predicate using the function pthread_cond_wait.

Condition Variables for Synchronization

Pthreads provides the following functions for condition variables:

```
int pthread_cond_wait(pthread_cond_t *cond,
    pthread_mutex_t *mutex);
int pthread_cond_signal(pthread_cond_t *cond);
int pthread_cond_broadcast(pthread_cond_t *cond);
int pthread_cond_init(pthread_cond_t *cond,
    const pthread_condattr_t *attr);
int pthread_cond_destroy(pthread_cond_t *cond);
```

Producer-Consumer Using Condition Variables

```
pthread_cond_t cond_queue_empty, cond_queue_full;
pthread_mutex_t task_queue_cond_lock;
int task_available;

/* other data structures here */

main() {
    /* declarations and initializations */
    task_available = 0;
    pthread_init();
    pthread_cond_init(&cond_queue_empty, NULL);
    pthread_cond_init(&cond_queue_full, NULL);
    pthread_mutex_init(&task_queue_cond_lock, NULL);
    /* create and join producer and consumer threads */
}
```

Producer-Consumer Using Condition Variables

Producer-Consumer Using Condition Variables

Controlling Thread and Synchronization Attributes

- The Pthreads API allows a programmer to change the default attributes of entities using attributes objects.
- An attributes object is a data-structure that describes entity (thread, mutex, condition variable) properties.
- Once these properties are set, the attributes object can be passed to the method initializing the entity.
- Enhances modularity, readability, and ease of modification.

Attributes Objects for Threads

- Use pthread_attr_init to create an attributes object.
- Individual properties associated with the attributes object can be changed using the following functions:

```
pthread_attr_setdetachstate,
pthread_attr_setguardsize_np,
pthread_attr_setstacksize,
pthread_attr_setinheritsched,
pthread_attr_setschedpolicy, and
pthread_attr_setschedparam.
```

Attributes Objects for Mutexes

- Initialize the attributes object using function: pthread_mutexattr_init.
- The function pthread_mutexattr_settype_np can be used for setting the type of mutex specified by the mutex attributes object.

```
pthread_mutexattr_settype_np (
    pthread_mutexattr_t *attr,
    int type);
```

Here, type specifies the type of the mutex and can take one of:

- PTHREAD_MUTEX_NORMAL_NP
- PTHREAD_MUTEX_RECURSIVE_NP
- PTHREAD_MUTEX_ERRORCHECK_NP

Composite Synchronization Constructs

- By design, Pthreads provide support for a basic set of operations.
- Higher level constructs can be built using basic synchronization constructs.
- We discuss two such constructs read-write locks and barriers.

- In many applications, a data structure is read frequently but written infrequently. For such applications, we should use readwrite locks.
- A read lock is granted when there are other threads that may already have read locks.
- If there is a write lock on the data (or if there are queued write locks), the thread performs a condition wait.
- If there are multiple threads requesting a write lock, they must perform a condition wait.
- With this description, we can design functions for read locks mylib_rwlock_rlock, write locks mylib_rwlock_wlock, and unlocking mylib_rwlock_unlock.

- The lock data type mylib_rwlock_t holds the following:
 - a count of the number of readers,
 - the writer (a 0/1 integer specifying whether a writer is present),
 - a condition variable readers_proceed that is signaled when readers can proceed,
 - a condition variable writer_proceed that is signaled when one of the writers can proceed,
 - a count pending_writers of pending writers, and
 - a mutex read_write_lock associated with the shared data structure.

```
typedef struct {
    int readers;
    int writer;
    pthread_cond_t readers_proceed;
    pthread_cond_t writer_proceed;
    int pending_writers;
    pthread_mutex_t read_write_lock;
} mylib_rwlock_t;

void mylib_rwlock_init (mylib_rwlock_t *1) {
    1 -> readers = 1 -> writer = 1 -> pending_writers = 0;
    pthread_mutex_init(&(1 -> read_write_lock), NULL);
    pthread_cond_init(&(1 -> readers_proceed), NULL);
    pthread_cond_init(&(1 -> writer_proceed), NULL);
}
```

```
void mylib_rwlock_unlock(mylib_rwlock_t *1) {
    /* if there is a write lock then unlock, else if there are
    read locks, decrement count of read locks. If the count
    is 0 and there is a pending writer, let it through, else
    if there are pending readers, let them all go through */


    pthread_mutex_lock(&(l -> read_write_lock));
    if (l -> writer > 0)
        l -> writer = 0;
    else if (l -> readers > 0)
        l -> readers --;
    pthread_mutex_unlock(&(l -> read_write_lock));
    if ((l -> readers == 0) && (l -> pending_writers > 0))
        pthread_cond_signal(&(l -> writer_proceed));
    else if (l -> readers > 0)
        pthread_cond_broadcast(&(l -> readers_proceed));
}
```

- As in MPI, a barrier holds a thread until all threads participating in the barrier have reached it.
- Barriers can be implemented using a counter, a mutex and a condition variable.
- A single integer is used to keep track of the number of threads that have reached the barrier.
- If the count is less than the total number of threads, the threads execute a condition wait.
- The last thread entering (and setting the count to the number of threads) wakes up all the threads using a condition broadcast.

```
typedef struct {
    pthread_mutex_t count_lock;
    pthread_cond_t ok_to_proceed;
    int count;
} mylib_barrier_t;

void mylib_init_barrier(mylib_barrier_t *b) {
    b -> count = 0;
    pthread_mutex_init(&(b -> count_lock), NULL);
    pthread_cond_init(&(b -> ok_to_proceed), NULL);
}
```

- The barrier described above is called a linear barrier.
- The trivial lower bound on execution time of this function is therefore O(n) for n threads.
- This implementation of a barrier can be speeded up using multiple barrier variables organized in a tree.
- We use n/2 condition variable-mutex pairs for implementing a barrier for n threads.
- At the lowest level, threads are paired up and each pair of threads shares a single condition variable-mutex pair.
- Once both threads arrive, one of the two moves on, the other one waits.
- This process repeats up the tree.
- This is also called a log barrier and its runtime grows as $O(\log p)$.



Execution time of 1000 sequential and logarithmic barriers as a function of number of threads on a 32 processor SGI Origin 2000.

Tips for Designing Asynchronous Programs

- Never rely on scheduling assumptions when exchanging data.
- Never rely on liveness of data resulting from assumptions on scheduling.
- Do not rely on scheduling as a means of synchronization.
- Where possible, define and use group synchronizations and data replication.